



# **Digital Photo Professional**

Ver. 3.5

## **Instruction Manual**

- Content of this Instruction Manual
  - DPP is used for Digital Photo Professional.
  - In this manual, the windows used in the examples are from Mac OS X 10.4.
  - ▶ indicates the selection procedure of the menu. Example: [Digital Photo Professional] menu ▶ [Quit Digital Photo Professional].
  - Square brackets are used to indicate items such as menu names, button names and window names that appear on the computer screen.
  - Text inside < > indicates a key on the keyboard.
  - \*\* indicates a reference page. Click to move to the relevant page.
  - ? : Marks helpful information when a problem arises.
  - $\frac{1}{2}$  : Marks tips for using the software skillfully.
  - (!) : Marks information that should be read before use.
  - Marks additional information you may find helpful.

- Switching Between Pages
  - Click on arrows on the bottom right of the screen.
    - 🜔 : next page
    - I previous page
    - I return to a page you had previously displayed
  - Click on the chapter headings on the right side of the screen to switch to the contents page of that chapter. Also, click the item you want to read about on the table of contents to move to the relevant page.
- Help and Shortcut Keys
  - For information about using DPP, refer to Help from the [Help] menu.
  - Refer to the "Shortcut Key List" in the Help for a list of shortcut keys which are helpful for quick operation.

Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Editing JPEG/TIFF Images

of Images

Reference

Index



Macintosh

## **READ CAREFULLY BEFORE USING!**

#### CANON SOFTWARE LICENSE AGREEMENT

IMPORTANT - READ THIS AGREEMENT BEFORE USING THE SOFTWARE ON THE CD-ROM IN THIS BOX. BY USING THE SOFTWARE, YOU AGREE TO BE BOUND BY THE TERMS OF THIS AGREEMENT.

This is a license agreement (the [Agreement]) between you and Canon Inc. ([Canon]).

IF YOU DO NOT AGREE TO THE TERMS AND CONDITIONS OF THIS AGREEMENT, DO NOT USE THE SOFTWARE PROGRAM ON THE CD-ROM AND THE USER MANUAL IN THIS BOX (COLLECTIVELY, THE [SOFTWARE]) AND RETURN THE SOFTWARE WITHIN 30 DAYS FROM THE DATE OF PURCHASE TO YOUR POINT OF PURCHASE FOR A REFUND.

In consideration of the right to use the SOFTWARE, you agree to abide by the terms and conditions of this Agreement.

 LICENSE: Canon grants you the non-exclusive right to use the SOFTWARE only on a single computer. You may physically transfer the SOFTWARE from one computer to another provided that the SOFTWARE is used on only one computer at a time. You shall not install or use the SOFTWARE on a network, multiple CPU, multiple site arrangement, or any other hardware configuration where the SOFTWARE is accessible to more than one CPU or to more than one user.

YOU SHALL NOT ASSIGN, SUBLICENSE, RENT, LEASE, LOAN, CONVEY OR OTHERWISE USE, TRANSFER, COPY, TRANSLATE, CONVERT TO ANOTHER PROGRAMMING LANGUAGE, ALTER, MODIFY, DECOMPILE OR DISASSEMBLE THE SOFTWARE, IN WHOLE OR IN PART, EXCEPT AS EXPRESSLY PROVIDED IN THIS AGREEMENT.

- BACK-UP COPY: You may make one copy of the SOFTWARE solely for back-up purposes, or copy the SOFTWARE onto the permanent storage device (e.g. a hard disk) of your computer and retain the original for back-up purposes. Any other copying of the SOFTWARE is a violation of this Agreement. You must reproduce and include the copyright notice on the back-up copy.
- SUPPORT AND UPDATES: Canon is not responsible for providing maintenance or support for use of the SOFTWARE. No updates, fixes or support will be made available for the SOFTWARE.
- 4. LIMITED WARRANTY AND LIMITATION OF LIABILITY: It is your responsibility to choose, maintain and match the hardware and software components of your computer system. Thus Canon does not guarantee uninterrupted service or correction of errors or that the functions or performance of the SOFTWARE will meet your requirements. THE SOFTWARE IS LICENSED ON AN [AS IS] BASIS AND WITHOUT WARRANTY OF ANY KIND. The CD-ROM storing the SOFTWARE is warranted only against defective material under normal use for a period of ninety (90) days after purchase from an authorized Canon dealer as evidenced by your sales receipt. Your sole remedy for a defective CD-ROM shall be replacement of the same without charge when returned by you at your expense to your point of purchase and proven to be defective upon inspection. The replacement CD-ROM will be warranted for the remainder of the original ninety (90) day warranty period of the defective CD-ROM. The limited warranty does not apply if the failure of the CD-ROM resulted from accident, abuse or misapplication of the SOFTWARE and shall not extend to anyone other than the original user of the SOFTWARE.

EXCEPT AS SPECIFICALLY SET FORTH IN THIS PARAGRAPH 4, CANON, CANON'S SUBSIDIARIES, DISTRIBUTORS AND DEALERS DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE, WITH RESPECT TO THE SOFTWARE.

NEITHER CANON NOR ANY OF CANON'S SUBSIDIARIES, DISTRIBUTORS OR DEALERS IS LIABLE FOR ANY DAMAGES HOWSOEVER CAUSED, INCLUDING WITHOUT LIMITATION, DIRECT, CONSEQUENTIAL OR INCIDENTAL LOSS OR DAMAGE INCLUDING LOSS OF PROFITS, EXPENSE OR INCONVENIENCE HOWSOEVER CAUSED OR ARISING OUT OF THE SOFTWARE OR THE USE THEREOF.

NEITHER CANON, NOR ANY OF CANON'S SUBSIDIARIES, DISTRIBUTORS OR DEALERS SHALL HAVE ANY OBLIGATION TO INDEMNIFY YOU AGAINST ANY CLAIM OR SUIT BROUGHT BY A THIRD PARTY ALLEGING THAT THE SOFTWARE OR THE USE THEREOF INFRINGES ANY INTELLECTUAL PROPERTY OF SUCH THIRD PARTY.

- 5. TERM: This Agreement is effective upon your using the SOFTWARE and remains in effect until expiration of all copyright interests in the SOFTWARE unless earlier terminated. You may terminate this Agreement by destroying the SOFTWARE. This Agreement will also terminate without notice to you if you fail to comply with any of the terms of this Agreement and you must then promptly return the SOFTWARE. In addition, Canon may enforce its other legal rights.
- 6. U.S. GOVERNMENT RESTRICTED RIGHTS NOTICE: The SOFTWARE is provided with restricted rights. Use, duplication or disclosure is subject to restrictions as set forth in either subparagraph (c) (1) (ii) of the Rights in Technical Data and Computer software clause at DFARs 252.227-7013 or subparagraph (c) (1) and (2) of the Commercial Computer Software Restricted Rights Clause at FAR 52.227-19, as applicable.
- 7. SEVERABILITY: In the event that any provision of this Agreement is declared or found to be illegal by any court or tribunal of competent jurisdiction, such provision shall be null and void with respect to the jurisdiction of that court or tribunal and all the remaining provisions of this Agreement shall remain in full force and effect.
- 8. CONTROLLING LAW: The terms of this Agreement as it relates to purchases of the Software in the United States of America shall be governed and construed in all respects in accordance with the laws and regulations of the State of New York, without reference to choice of law principles. The terms of this Agreement as it relates to purchases of the Software in Canada shall be governed by the laws of the province of Ontario.
- 9. OWNERSHIP: All rights, including but not limited to copyrights and trade secret rights, to the SOFTWARE belong to Canon, its affiliated corporations and third party licensors. Your use of the SOFTWARE is subject to the United States, Canada and other applicable copyright and trademark laws and nothing in this Agreement constitutes a waiver of the rights of Canon, its affiliated corporations and third party licensors under such laws. Nothing contained in Paragraph 1 shall be construed to give Canon any ownership rights in any images, graphics or textual material that you save in connection with the Software.
- 10.ACKNOWLEDGEMENT: BY USING THE SOFTWARE, YOU ACKNOWLEDGE THAT YOU HAVE READ THIS AGREEMENT, UNDERSTOOD IT, AND AGREE TO BE BOUND BY ITS TERMS AND CONDITIONS. YOU ALSO AGREE THAT THIS AGREEMENT IS THE COMPLETE AND EXCLUSIVE STATEMENT OF AGREEMENT BETWEEN YOU AND CANON CONCERNING THE SUBJECT MATTER HEREOF AND SUPERSEDES ALL PROPOSALS OR PRIOR AGREEMENTS, VERBAL OR WRITTEN, AND ANY OTHER COMMUNICATIONS BETWEEN THE PARTIES RELATING TO THE SUBJECT MATTER HEREOF. NO AMENDMENT TO THIS AGREEMENT SHALL BE EFFECTIVE UNLESS SIGNED BY A DULY AUTHORIZED OFFICER OF CANON.

Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



## Introduction

Digital Photo Professional (hereinafter, "DPP") is high-performance RAW image processing, viewing and editing software for EOS DIGITAL cameras. It is often thought that RAW images are difficult to handle compared with ordinary JPEG images, but using DPP, you can perform advanced edits and print RAW images with ease.

## **RAW Images and Their Features**

## What is a RAW Image?

A RAW image is image data that has recorded output data of imaging sensor. Because image processing does not occur inside the camera when a photo is taken and the photo has been recorded in the special form of "RAW image data + Image processing conditions information at the time of shooting", special software is needed to view or edit the image.

\* "RAW" means "in a natural condition" or "not processed or refined".

## What is RAW Development?

If described in terms of film, the concept of a RAW image is a shot image not yet developed (latent image).

With film, the image appears for the first time when it is developed. And as for the RAW image too, you cannot view it as an image on your computer unless you perform subsequent image signal processing. Therefore, even though it is digital, this processing is called "development" and with EOS DIGITAL is performed using DPP. With DPP, you can view, edit and print RAW images without having to be particularly conscious of the development processing.

## What Advantages Does a RAW Image Have?

RAW images are recorded in the format "RAW image data + Image processing conditions information at the time of shooting". When you open an image in DPP, the image is instantly developed and you can view the image as an image to which image processing conditions at the time of shooting have been applied.

Even if you perform various adjustments to the image you have opened (it undergoes automatic development processing each time), only the image processing conditions (development conditions) change and the "original image data itself" remains unaffected. Consequently, image deterioration is not a problem and it is the perfect image data for users who want to get creative with their images after they have been shot. In DPP, the "Image processing conditions information" that can be adjusted is called a "Recipe".



Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editina JPEG/TIFF Images Reference Index

## Main Features of DPP

Following are the main tasks you can perform with images you have downloaded to your computer.

## View and organize RAW images

## Real-time adjustment of a RAW image

- Various image adjustments while maintaining the original image
- Freely apply a Picture Style
- View your image before and after adjustment in the same window

## Trim an image and change its size

**Correction of lens aberration** 

## Automatic/manual dust erasure processing

### Convert from a RAW image to a JPEG or **TIFF** image and save

Process large numbers of RAW images in batches

Transfer the image to image editing software

## Print a RAW image

View and organize JPEG and TIFF images

## Real-time adjustment of JPEG and TIFF images

Various image adjustments while maintaining the original image

## **Print JPEG and TIFF images**

## Color management compatibility

CMYK simulation for commercial printing

## **System Requirements**

OS	Mac OS X 10.4 to 10.5	
Computer	Macintosh with one of the above OS installed	$\left[ \right]$
CPU*	PowerPC G4, G5 or Intel processor	
RAM	Minimum 1GB	
Display	Resolution : 1024 × 768 or more Colors : Thousands or more	

- \* Core2 Duo or higher is recommended
- This software program is not compatible with UFS (UNIX File System) formatted disks.

## **Supported Images**

This software supports the following image types.

	Extension	
RAW images	RAW images <sup>*1</sup> shot with EOS DIGITAL cameras, excluding EOS DCS1 and EOS DCS3 RAW images <sup>*2</sup> shot with PowerShot cameras	.CR2 .TIF .CRW
JPEG images	Exif 2.2 or 2.21-compatible JPEG images	.JPG, .JPEG
TIFF images	Exif-compatible TIFF images	.TIF, .TIFF

- Editing Images Reference Index × j 3
- \*1 Compatible with RAW images shot with EOS D6000 or EOS D2000 that have been converted to RAW images using the CR2 Converter and have the ".CR2" extension.

For information on CR2 Converter, refer to Canon's web site.

- \*2 Only models where Digital Photo Professional is listed in the "Data Type" item in the "Specifications" section near the end of the Camera User Guide.
  - Use the dedicated CameraWindow application to download images from a PowerShot camera to a computer. See the Software Starter Guide for details.
  - ① Registering Picture Styles to a camera, ② Lens aberration correction, ③ Automatic dust erasure processing and other EOS DIGITAL specific functions cannot be used.

Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Processing Large Numbers of Images

JPEG/TIFF

## Contents at a Glance

### **Downloading Images to Your Computer**

<ul> <li>Download images by connecting your camera and computer</li> </ul>	<b>→</b> p.7
Download images using a card reader	→ p.9

#### **Viewing and Checking RAW Images**

Quickly enlarge parts of an image	→ p.11
<ul> <li>Sort images (check marks)</li> </ul>	→ p.17, p.18
<ul> <li>Display an image shot simultaneously as a RAW image and JPEG image as a single image</li> </ul>	→ p.20
<ul> <li>Display the images in the thumbnail list display at high resolution</li> </ul>	→ p.21

• Check shooting information such as the shooting date  $\rightarrow$  p.10, p.21

#### **Editing RAW Images (Adjusting)**

<ul> <li>Adjust brightness/darkness</li> <li>Use automatic adjustment</li> <li>Change the Picture Style</li> </ul>	<ul> <li>→ p.12, p.24</li> <li>→ p.30</li> <li>→ p.24</li> </ul>
<ul> <li>Sharpen the modulation and contrast of colors (contrast)</li> </ul>	→ p.27
Make skin tone look healthier (color tone)	→ p.27
<ul> <li>Make the image colors more vivid (color saturation)</li> </ul>	→ p.27
<ul> <li>Make an image sharp (sharpness)</li> </ul>	→ p.29
<ul> <li>Adjust an image to make color tone more natural (white balance)</li> </ul>	→ p.25
<ul> <li>Change an image to black-and-white or sepia tones (monochrome)</li> </ul>	→ p.28
<ul> <li>Trim parts of an image (trimming)</li> </ul>	→ p.35
<ul> <li>Specify an aspect ratio that matches the size of the paper on which an image is to be printed</li> </ul>	→ p.35

Erase dust shot with the image	-	→ p.62, p.64
<ul> <li>Erase unwanted parts of an image</li> </ul>	-	<b>→</b> p.66
Auto correct RAW images with the Auto Lighting Optimized in the Auto Content of the	mizer -	<b>→</b> p.56
<ul> <li>Reduce image noise</li> </ul>	-	<b>→</b> p.57
<ul> <li>Correct lens aberration</li> </ul>	-	<b>→</b> p.58
<ul> <li>Use a Picture Style file</li> </ul>	-	<b>→</b> p.53
<ul> <li>Edit efficiently</li> </ul>	-	<b>→</b> p.31
<ul> <li>Edit an image while comparing the image before after adjustment</li> </ul>	and	<b>→</b> p.49
<ul> <li>Synchronize multiple images</li> </ul>	-	<b>→</b> p.50
<ul> <li>Display an area beyond the set range as a warning indicator (Highlight/Shadow warning)</li> </ul>	ng	<b>→</b> p.51
<ul> <li>Restore an adjusted image to its condition at the of shooting</li> </ul>	time	<b>→</b> p.39
Printing		
<ul> <li>Print well on a Canon printer</li> </ul>	→ p.39	), p.69, p.70
<ul> <li>Faithfully reproduce the color of the subject when printing</li> </ul>	→ p.39	), p.69, p.70
<ul> <li>Print with the shooting information</li> </ul>	→ p.67	,
<ul> <li>Print a thumbnail list of images</li> </ul>	→ p.68	3
<ul> <li>Approximate the color seen on screen with your printing results</li> </ul>	→ p.75	;
Conversion of Images		
Convert a RAW image to a JPEG image	-	▶ p.38, p.81
<ul> <li>Edit in Photoshop</li> </ul>	-	▶ p.66, p.82
<ul> <li>Perform batch processing</li> </ul>	-	<b>→</b> p.81
<ul> <li>Edit (adjust) a JPEG image</li> </ul>	-	<b>→</b> p.85

Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



# **1** Basic Operation



The basic operational flow – from how to download to your computer images shot with a camera to checking, editing, saving and printing a downloaded RAW image – is explained here.

Starting up DPP6	
Main Window Display 6	
Downloading an Image to Your Computer 7	
Downloading Images Using Your Card Reader	
Viewing an Image 10	
View Images as Thumbnails in the Main Window 10	
Changing the Size of Thumbnail Images 10	
Enlarge and View an Image in the Edit Window 11	
Enlarging and Viewing a Specific Area 11	
Adjusting an Image 12	
About the Tool Palette 12	
About Recipes 12	
Saving an Image 13	
Saving 13	
Printing an Image 14	
Printing 14	
Quitting DPP 14	



Introduction

Contents at

a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index

## **Starting up DPP**

#### Click the Dock icon.



→ DPP starts up and the main window ([Folder] window) appears.



#### Main window ([Folder] window)

No.         No. <th>Cigital Photo Profession</th> <th>al file Edit Vew Bo</th> <th>s Window Help al - [ MacOSX/Users/Kanon/Deskt</th> <th>1 ( <del>1</del></th> <th></th> <th></th> <th>med 3-08 PM</th>	Cigital Photo Profession	al file Edit Vew Bo	s Window Help al - [ MacOSX/Users/Kanon/Deskt	1 ( <del>1</del>			med 3-08 PM
	Image: Control of the contro	2.0/	al - [ MacOlX/Users/Canon/Deski		0	-	
	19 11 12 14 15						

## Main Window Display

In the main window, you can use tabs to select either the [Folder] window or the [Collection] window. The [Folder] window displays the images in folders on your computer, while the [Collection] window (p.33) displays images selected randomly by the user from one or more folders and gathered together.

Unless noted otherwise, the [Folder] window will be described as the main window from this point on.

#### [Folder] window



#### [Collection] window



## Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editina JPEG/TIFF Images Reference Index

## **Downloading an Image to Your Computer**

Connect the camera and computer with the cable provided and download the images saved on the memory card inserted in the camera. For downloading images, start up the camera software "EOS Utility" from DPP and use.

### Select the save destination for the images.

- Select the save destination in the folder area on the left of the main window.
- When creating a folder, refer to p.45.



- Start up EOS Utility.
- Select the [Tools] menu ▶ [Start EOS Utility].

#### Tools

Start EOS Utility	~ιπε
Transfer to Photoshop	Σ%P
Start Quick check tool	∖CℋF
Start Trimming tool	∖жт
Start Stamp tool	\7₩S
Start Rename tool	\%R

→ EOS Utility starts up.

#### **EOS Utility**



Introduction
Contents at a Glance
Basic Operation
Advanced Operation
Advanced Image Editing and Printing
Processing Large Numbers of Images
Editing JPEG/TIFF Images
Reference
Index

## Connect your camera and computer and turn the camera on.

- Connect the camera and your computer with the interface cable provided with the camera and turn the camera on.
- For detailed instructions on connecting your camera and computer, refer to the "EOS Utility Instruction Manual" (PDF electronic manual).



#### Download images.



Advantages of using EOS Utility to download images

Using EOS Utility to download images makes it easier to organize your images as they are downloaded, sorted and saved into folders by date.

- You cannot start up EOS Utility in the [Collection] window (p.6, p.33).
  - When EOS Utility has been started up from DPP, you cannot use the following functions.
    - Quick check window view (p.16)
    - Trimming images (p.35, p.93)
    - Dust erasure processing (copy stamp function) (p.62 to p.66, p.95 to p.99)
    - Batch change file names (rename function) (p.83)
    - Printing with shooting information (p.67)
    - Printing a thumbnail list (contact sheet printing) (p.68)
    - Printing using Easy-PhotoPrint EX or Easy-PhotoPrint (Plug-in printing) (p.39, p.42)
    - Transferring images to Photoshop (p.66)
    - Batch saving images (batch processing) (p.81)



- → Downloading of images begins.
- The downloaded images are saved in the folder selected in step 1 and are displayed in the main window of DPP.
- The downloaded images are sorted by date into folders and saved.

## **Downloading Images Using Your Card Reader**

You can also download images to the computer using a third-party card reader.

## Load the memory card into the card reader.



Open a removable disk icon in the folder area and move the [DCIM] folder inside to a suitable place such as to the [Desktop].



- → The [DCIM] folder is downloaded to your computer.
- All images are saved in folder units inside the [DCIM] folder.

- Display the images downloaded to your computer.
- In the [DCIM] folder copied to your desktop, select the folder where the shot images are saved.



→ Images in the folder are displayed in the main window of DPP.



Checking before downloading images

By selecting the memory card folder directly in DPP, the images in the folder are displayed in DPP and you can check the shot images.

- Copying to your computer may take time when there is a large number of shot images saved in the memory card.
  - For details on the [DCIM] folder structure and the file names of shot images, refer to "Folder Structure and File Names in the Memory Card" in the "EOS Utility Instruction Manual" (PDF electronic manual).

## Viewing an Image

Images downloaded to your computer are displayed as a thumbnails list in the main window. You can double-click an image to open the edit window and display the image at large size.

## View Images as Thumbnails in the Main Window



Click to select the image

Display thumbnails of all the images inside the folder selected in the folder area on the left

Images displayed with the [ ] icon are movie files and cannot be played back in DPP. Please use "ImageBrowser", which is compatible with EOS DIGITAL movie files.

 $\equiv$ When aspect ratio information is attached to the shot image with the EOS-1Ds Mark III or EOS-1D Mark III, the image is displayed as a trimmed image (p.35, p.93).

#### • For a list of main window functions, refer to p.104.

## Changing the Size of Thumbnail Images

You can change the size of the thumbnail images displayed in the main window and display them with shooting information attached.

### Select the [View] menu ▶ desired item.

Folders Toolbar Tool palette %T Large thumbnail %1 Medium thumbnail %2 Small thumbnail %3 Thumbnail with information %4 Sort	Folders Toolbar Tool palette %T Large thumbnail %1 Medium thumbnail %2 Small thumbnail %3 Thumbnail with information %4 Sort	Folders Toolbar Tool palette %T Large thumbnail %1 Medium thumbnail %2 Small thumbnail %3 Thumbnail with information %4	<mark>fiew</mark> Edit in Edit image window View collections	#→ ∖~#G
Medium thumbnail9€ 2Small thumbnail9€ 3Thumbnail with information9€ 4Sort►	Medium thumbnail#2Small thumbnail#3Thumbnail with information#4Sort	Medium thumbnail#2Small thumbnail#3Thumbnail with information#4Sort	/ Tab / Folders / Toolbar Tool palette	жт
	Sort		/ Medium thumbnail Small thumbnail	ж2 ж3
The display changes to the selected item.				to the



## Introduction

Contents at a Glance

### Enlarge and View an Image in the Edit Window

**Tool palette** 



→ The edit window appears.





- → It may take time for the image to redraw itself.
- Click the [] in the upper left of the window to close the edit window.
- By selecting the [View] menu ▶ [AF Point] in the edit window, you can display the AF points selected in the camera at the time of shooting. However, AF points are not displayed for images which have had their image size changed and then been converted and saved (p.38, p.112).
- For a list of edit window functions, refer to p.107.

## **Enlarging and Viewing a Specific Area**

#### Double-click the area you want to enlarge.



– Double-click

- The area you double-clicked is enlarged to 100% (actual pixel size). If you wait for a while, it changes to a clearer display.
- Double-click again to revert to the full view.
- To change the display position, drag on the image or drag the enlargement display position of the tool palette.

#### Tool palette enlargement display position



Change the enlargement display position by dragging

Reference
Index

#### To display an image in an enlargement ratio other than 100%

Select the [View] menu ▶ [200% view] or [50% view].

You can change the enlargement ratio when you double-click (p.73).

## Introduction

a Glance

Contents at

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images



## Adjusting an Image

You can perform a variety of image adjustments, such as adjusting the brightness or changing the Picture Style of an image using the tool palette of the edit window. You can easily restore an image to its original settings with the [ ] button even if you have made the wrong adjustment. Try out the various adjustments.

As an example, the procedure to adjust the brightness of an image is explained here.

#### **Tool palette**



The image brightness changes in real time according to the amount of adjustments.

### ? The tool palette does not display

Select the [View] menu ▶ [Tool palette].

## About the Tool Palette

You can adjust images with the tool palette by switching between the [RAW], [RGB] and [NR/Lens/ALO] tab sheets according to your editing requirements.

Because adjustment made with the tool palette (it undergoes automatic development processing each time) only changes the image processing conditions, the "original image data itself" remains unaffected.

Therefore, there are no problems with image deterioration that arise with editing and you can readjust your images any number of times. See Chapter 2 onwards for more detailed information on the various functions of the tool palette.

## **About Recipes**

In DPP, all the adjustment contents (image processing conditions information) made with the tool palette is saved to an image as data called a "Recipe" (p.78).



## Saving an Image

If you perform the save operation described here, you can save all the adjustment contents (recipe) made with the tool palette to the RAW image.

### Select the [File] menu ▶ [Save].

			-	
FILE .		Ie.	г	

Close window	жw
Save	ЖS
Save As	û₩S
Convert and save	ЖD
Page setup	ŵжР
Print	ЖP
Print with detailed setting	企業D
Contact Sheet Prints	^%₽
Plug-in printing	•
Info	жı

→ Your adjustment contents (recipe) are saved to the image.

## Saving

With DPP, you can perform the following types of saving according to your requirements. For detailed information on each saving method, refer to Chapter 2 onwards.

#### • Save (p.37)

Add adjustment contents (recipe) made with the tool palette to a RAW image and save.

#### Save as (p.37)

Add adjustment contents (recipe) made with the tool palette to a RAW image and save as a separate RAW image. The original RAW image remains unaffected.

#### Add thumbnail to image and save\* (p.21)

Create a new thumbnail image for the main window and save to each image.

The quality of images in the main window improves and images redraw themselves more quickly.

#### Convert and save (p.38)

Convert adjusted RAW image to a JPEG or TIFF image and save. The original RAW image remains unaffected.

#### Batch process\* (p.81)

Convert in batches adjusted multiple RAW images to JPEG or TIFF images and save.

The original RAW images remain unaffected.

\* You can save these images in the main window.



Introduction

Contents at

JPEG/TIFF Images

Reference

Index



## **Printing an Image**

You can print images with a printer. As an example, the procedure to print one image on one sheet of paper is described here.

### Select the [File] menu ▶ [Print].

File	
Close window	жw
Save	жs
Save As	ΰЖS
Convert and save	ЖD
Page setup	ûЖР
Print	ЖP
Print with detailed setting	ûЖD
Contact Sheet Prints	^ ℋP
Plug-in printing	•
Info	жı

→ The [Print] dialog box appears.

### Print.

- Specify the optimum settings for photograph printing in the printer's print settings dialog box and click the [Print] button.
- → Printing begins.

### To change the paper size

To set the paper size etc., select the [File] menu > [Page setup].

## Printing

With DPP, you can perform the following types of printing according to your requirements. For detailed information on each printing method, refer to Chapter 2 onwards.

- Print one image (p.44)
- Print using a Canon inkjet printer (p.39, p.42)
- Print with a high-end Canon printer (p.69)
- Print with shooting information (p.67)
- Printing a thumbnail list (contact sheet printing) (p.68)

## **Quitting DPP**

In the main window, select the [Digital Photo Professional] menu ▶ [Quit Digital Photo Professionall.

Digital Photo Professional	
About Digital Photo Professional	
Preferences	ж,
Services	•
Hide Digital Photo Professional	жн
Hide Others	∕жн
Show All	
Quit Digital Photo Professional	жQ

→ DPP quits.

adjusted.



# **Advanced Operation**

A more advanced operation - from efficiently checking images, to various ways of editing an image, printing a RAW image using a Canon printer and sorting images - is explained here.

Efficiently Checking/Sorting Images1	16
Sorting Images 1	17
Sorting Images in the Main Window 1	8
Arranging Images in the Main Window 1	18
Arranging by Type 1	18
Arranging Freely 1	19
Displaying a RAW Image and JPEG Image as a Single	)
Image 2	<u>2</u> C
Improving the Quality of an Image in the Main Window 2	21
Checking Image Information 2	21
Editing an Image 2	23
About the RAW Tool Palette	
Editing with the Tool Palette in the Main Window. 2	23
Adjusting Brightness 2	
Changing a Picture Style 2	
Picture Style File	25
Adjusting Color Tone by Changing White Balance 2	25
Adjusting Color Tone Using Click White Balance 2	26
Adjusting Contrast 2	
Changing Color Tone and Color Saturation	
Adjusting Monochrome 2	
Adjusting Sharpness 2	
Automatically Adjusting Brightness and Color (Tone	
	<b>3C</b>

Editing Efficiently 31	
Editing in the Edit Image Window	Contents at
Changing the Thumbnail Display Position to a Horizontal	a Glance
Position	
Gathering and Editing Images in the Collection Window 33	Basic Operation
Trimming an Image 35	
Applying Adjustment Contents to Other Images 37	Advanced
Saving Editing Results	Operation
Saving Editing Contents to a RAW Image	Advanced
Saving as a JPEG or TIFF Image	Image Editing and Printing
Re-Editing an Image 39	and Printing
Printing an Image 39	Processing Large Numbers
Printing Photographs with Canon Inkjet Printers	of Images
Compatible with Easy-PhotoPrint EX	Editing
Printing Photographs with Canon Inkjet Printers	Editing JPEG/TIFF
Compatible with Easy-PhotoPrint42	Images
Printing Photographs with a Printer other than the Canon	
Inkjet Printers 44	Reference
Organizing Images 45	
Deleting an Unwanted Image45	Index
Creating a Folder for Saving Images	
Moving Images 46	
Moving Images in Folders 46	
Registering Frequent-Use Folders (Bookmark	
Registration) 47	$(\mathbf{b})$
Organizing Bookmarks 47	•

## **Efficiently Checking/Sorting Images**

You can enlarge images displayed as thumbnails in the main window and efficiently check each image. You can attach check marks and sort images into three groups.

### Display the quick check window.

● Select the [Tools] menu ▶ [Start Quick check tool].

#### Tools

<b>℃#E</b> ∖₹#P
₹₩F
T#J
\C₩S
∖∵≋R
ility

→ The quick check window appears.

#### Click the [Next] or [Previous] button to switch between images to be checked.

#### Quick check window



 All the images displayed in the main window can be checked in the quick check window. Double-click the area you want to enlarge. 50% view Full screen Double-click Al Point → The area you double-clicked is enlarged to 50% view. Double-click again to revert to the full view. To change the display position, drag on the image. To quit, click the [OK] button.

Introduction

Contents at a Glance

Basic

Operation

Advanced Operation

Advanced Image Editing

and Printing

Processing

Large Numbers of Images

Editing

JPEG/TIFF

Images

Reference

Index

When [AF Point] is checkmarked, you can display the AF points selected in the camera at the time of shooting. However, AF points are not displayed for images which have had their image size changed and then been converted and saved (p.38, p.112).

### 🔆 Convenient functions of the quick check window

#### To check only selected images

You can use the quick check window to check only selected images by selecting the desired images from those displayed in the main window and then performing step 1.

#### Switch between images using the keyboard

You can also switch between images by pressing the  $< \Re > + < \rightarrow >$  or  $< \Re > + < \leftarrow >$  keys.

#### Switch between screens using the keyboard

You can also switch between full screen display/normal screen display by pressing the  $< \Re > + <$ F11> keys.

#### Operate using the menu

Each operation can also be performed with the menu which appears by clicking on the image while holding down the <control> key.

- The enlargement ratio when an image is enlarged is half (50%) of the 100% (actual pixel size).
  - You can change the enlargement ratio to 100%, when an image is enlarged (p.73).
  - For a list of quick check window functions, refer to p.110.

## Sorting Images

You can sort images by attaching three types of check marks for each subject or theme.

#### Attach check marks for sorting.





The selected check mark appears in the upper left of the window.
Click the [Clear] button to remove the check marks.



## Sorting Images in the Main Window

You can sort images by attaching three types of check marks in the main window.

# In the main window, select the images you want to sort and attach a check mark for sorting.



- The selected check mark appears in the upper left of the image frame.
- Click the [Clear check] button to remove the check marks.

## Arranging Images in the Main Window

You can arrange images in the order of the types of check marks you have attached to images, or in the order of date and time at which the images were shot. You can also freely arrange images by moving them individually.

## Arranging by Type

Select the [View] menu ▶ [Sort] ▶ desired item.

View Edit in Edit image window View collections	#→ ۲#G		Advanced Operation
<ul> <li>✓ Tab</li> <li>✓ Folders</li> <li>✓ Toolbar Tool palette</li> <li>Large thumbnail</li> </ul>	ЖT Ж1		Advanced Image Editing and Printing
<ul> <li>Medium thumbnail</li> <li>Small thumbnail</li> <li>Thumbnail with information</li> </ul>	策2 策3		Processing Large Numbers
Sort		<ul> <li>✓ File name RAW priority</li> <li>Check mark1</li> <li>Check mark2</li> <li>Check mark3</li> </ul>	of Images Editing JPEG/TIFF Images
The images are arra item.	inged i	Shooting Date/Time	Reference
			Index

#### 🤄 To select multiple images in the main window

Click on desired images while holding down the  $< \Re >$  key. To select multiple consecutive images, click on the first image, and then click on the last image while holding down the <shift> key.

Introduction

Contents at

a Glance

Basic

Operation

Sort item	Description
Check mark1 - Check mark3	Images with check marks take priority and are sorted in number order.
Shooting Date/Time	Images are sorted by shooting date and time from the earliest.
File name	Images are sorted by file name in alphanumeric order (0 to $9 \rightarrow A$ to Z).
RAW priority	Images are sorted in the following order: RAW images $\rightarrow$ JPEG images $\rightarrow$ TIFF images.
	· · ·

#### Check mark order

When you assign check marks 1 to 3, the images are sorted as follows: 1 selected:  $1 \rightarrow 2 \rightarrow 3$ 

- 2 selected:  $2 \rightarrow 1 \rightarrow 3$
- 3 selected: 3→2→1

## Arranging Freely

Drag and drop the image to the desired location.



- → The image moves to the desired location.
- You can also select multiple images (p.18) and move them.
- The order of rearranged images is maintained until you quit DPF or select another folder in the folder area.
- Select the [View] menu ▶ [Sort] ▶ [File name] to revert to the order before the images were rearranged.



#### Maintaining the order of rearranged images

You can maintain the order of rearranged images even if you quit DPP or select another folder in the folder area.

#### Maintain order without changing image file names

You can use the [View settings] tab sheet in Preferences to maintain the order of images without changing the image file names (p.73).

### Maintain order and change image file names You can use the rename function to maintain the order of images and change the image file names all at once in the order they were rearranged (p.83).

	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
P	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
D	Index
n	

### Displaying a RAW Image and JPEG Image as a Single Image

You can display and handle a RAW image and JPEG image shot simultaneously as a single image. In particular, you can halve the number of images displayed in the main window and you can streamline the checking of a large number of images shot simultaneously.

Select the [Digital Photo Professional] menu
[Preferences].

Select the [View settings] tab sheet and checkmark [Display only CR2 images for CR2 and JPEG files of the same name].

Preferences					
General settings	View settings	Tool palette	Color management		
General settings	view settings	Tool palette	Color management		
Grid pitch					
64 Pixels(8-256)					
Locking selected image					
🗹 Images opened in Edit windo	w remain selected	in main window			
Magnification in Edit windo	w				
• Fit to window 50%	G C	100%	○ 200%		
Magnification when the Edi	t/Edit image wi	ndow is doub	le-clicked		
○ 50% ● 100% ○ 200%					
RAW and IPEG					
Display only CR2 images for	CR2 and JPEG files	of the same nar	ne		
Sort order in main window					
Retain sort order					
Highlight/shadow warning					
Highlight 192	(192-255)				
Shadow 0	(0-64)				
Quick check tool display					
• 50%	🔵 100% (moiré re	duction off)			
			Cancel OK		

The main window display updates and the simultaneously shot RAW image and JPEG image are displayed as a single image with the [R+J] mark (p.106).

#### ? RAW images with the extension ".CR2" can be displayed as a single image

Images that can be displayed as a single image are images shot with a camera that shoots RAW images with the extension ".CR2" and JPEG images simultaneously. Images that have been simultaneously shot with a camera that shoots RAW images with the extension ".CRW" or ".TIF" cannot be displayed as a single image.

When a single image is displayed	Advanced
Image displayed	Operation
The RAW image is displayed in all windows.  Edited image	Advanced
The content which has been adjusted with any of DPP's functions (the tool palette etc.) will be applied to the RAW image only.	Image Editing and Printing
<ul> <li>However, if you have used the following functions, the adjustments will be applied to both the RAW image and the JPEG image.</li> <li>Deleting an image (p.45)</li> <li>Moving or copying an image (p.46)</li> </ul>	Processing Large Numbers of Images
<ul> <li>Checkmarks (p.17, p.18)</li> <li>Rotating an image (p.104, p.110, p.111)</li> <li>Attaching a thumbnail to an image and saving (p.21)</li> </ul>	Editing JPEG/TIFF Images
Images added to the [Collection] window	
When you add a RAW image and JPEG image displayed as a single image to the [Collection] window, the single image is marked with the	Reference
[R+J] mark. However, because the RAW and JPEG images are	
actually added individually, the number of images shown on the [Collection] tab sheet increases by 2 (p.105).	Index
In step 2, if you uncheck [Display only CR2 images for CR2 and IDEC image	
JPEG files of the same name], the RAW image and JPEG image are displayed as separate images.	

Introduction

Contents at

a Glance

Basic

Operation

### Improving the Quality of an Image in the Main Window

Create a new thumbnail image for the main window and save to each image.

The quality of images in the main window improves and images redraw themselves more quickly.

# With all the images selected, select the [File] menu ▶ [Add thumbnail to image and save].

File	
Open in Edit window	жо
Open in Edit window (enlarged)	
Close all	
Open window	ЖN
Close window	жw
Save	жs
Save As	ûЖS
Add thumbnail to image and save	企業T
Convert and save	ЖD
Batch process	ЖB
Create new folder	企業N
Page setup	ûжР
Print	ЖP
Print with detailed setting	企業D
Contact Sheet Prints	^쁐P
Plug-in printing	•
Add to collection	ЖG
Remove from collection	企業G

#### $\frac{1}{2}$ The extent of the improvement in quality

The quality is improved for any RAW, JPEG or TIFF image. While the image quality improves regardless of the thumbnail size (p.10), selecting [Large thumbnail], with its larger display size, shows the improvement more clearly than [Medium thumbnail] and [Small thumbnail].

• A large number of images may take some time to add.

• You can specify a presetting for JPEG images to improve the quality of all main window thumbnails (p.71, p.72).

### **Checking Image Information**

Select the image for which you want to check the image information.

Select the [File] menu ▶ [Info].

File	
Open in Edit window	жо
Open in Edit window (enlarged)	
Close all	
Open window	ЖN
Close window	жw
Save	ЖS
Save As	ΰ₩S
Add thumbnail to image and save	企ℋT
Convert and save	ЖD
Batch process	₩В
Create new folder	企業N
Page setup	ûжР
Print	ЖP
Print with detailed setting	企業D
Contact Sheet Prints	^%₽
Plug-in printing	•
Add to collection	ЖG
Remove from collection	ûЖG
Delete	<b>#</b> (X)
Info	жı

→ The image information window appears (p.22).

Contents at a Glance
Basic Operation
Advanced Operation
Advanced Image Editing and Printing
Processing Large Numbers of Images
Editing JPEG/TIFF Images
Reference
Index



· · ·	mation] tab sheet	[Metadata] tab sheet	tab sheet, while IPTC* information appended to the image Photoshop CS3 after shooting is displayed in the [Metadata sheet. IPTC* information provides additional comments on
tem Name ile Name camera Model irmware hooting Date/Time uthor copyright Notice hooting Mode V(Shutter Speed ) V(Aperture Value ) Aetering Mode V(Shutter Speed ) V(Aperture Value ) Aetering Mode V(Shutter Speed ) Uto ISO Speed uto ISO Speed ens ocal Length mage Size mage Quality lash E lock Vhite Balance Mode GF Mode Color Style harpness Contrast aturation Color Space ong exposure noise red iigh ISO speed noise re iigh Sposure noise red iigh Sposure noise red iigh Speed noise re iigh Speed noise re iigh Speed noise re iigh Sposure noise red iigh Speed noise re iigh Speed Sp	Value IMG_0001.CR2 Canon EOS XXXX Firmware Version XXXX XX/XX/XX XX:XX Photographer:XXX Copyright:XXX Photographer:XXX Copyright:XXX Program AE 1/40 5.6 Evaluative Metering 0 3200 OFF Evaluative Metering 0 3200 OFF EF-S18-S5mm f/3.5-5 55.0mm XXXXxXXX RAW O O FF Auto O O O FF Auto O O SRGB 0:Off 2:Strong 0:Disable 0:Standard Enable XXXXKB No Low-speed continuous s OFF X	Description         [Document Title]         xxxxxxxx         [Author]         xxxxxxxxx         [Author]         xxxxxxxx         [Description]         xxxxxxxx         [Description]         xxxxxxxx         [Description]         xxxxxxxx         [Copyright Status]         Public domain         [Copyright Notice]         xxxxxxxx         [Copyright info URL]         xxxxxxxx	<ul> <li>images, such as captions, credits and the shooting location information is sorted into 5 different categories and can be viewed by selecting [Description], [IPTC Contact], [IPTC Im [IPTC Content] or [IPTC Status] from the list box in the [Metadata] tab sheet.</li> <li>* International Press Telecommunications Council (IPTC)</li> <li>The contents of the [Shooting Information] tab sheet will va depending on the camera model.</li> </ul>



#### Convenient uses in the main window

#### Difference with the [Thumbnail with information]

Detailed shooting information for each image is displayed in the image information window. However, if you want to only check the main shooting information, you can check it for each image in [Thumbnail with information] (p.10).

Y)

Introduction

Contents at a Glance

Basic

Operation

Advanced

Operation

Advanced

Image Editing

and Printing

Processing

Large Numbers of Images

Editing

JPEG/TIFF

Images

Reference

Index

## **Editing an Image**

This section explains how to adjust an image using the tool palette in the edit window.

You can easily restore an image to its original condition with the [[]] button even if you have made the wrong adjustment. Try out the various adjustments.

How to make adjustments using the [RAW] tool palette functions, and how to adjust automatically with the [RGB] tool palette are explained in this section.



- The image changes in real time according to adjustments performed with the tool palette.
- To revert to the condition before the last operation performed on the tool palette, select [Undo] in the [Edit] menu or press <\mathcal{H}> + <Z> keys.
- You can rotate an image in the [Adjustment] menu.

- You can adjust an image while comparing the image before and after adjustment (p.49).
- You can synchronize multiple images and edit while comparing them (p.50).
- Refer to p.107 for a list of edit window functions, and p.108 for a list of tool palette functions.

## About the RAW Tool Palette

You can adjust images with the tool palette by switching between the [RAW], [RGB] and [NR/Lens/ALO] tab sheets according to your editing requirements.

Adjustments similar to those that can be performed with the functions of your camera can be performed using the functions of the [RAW] tool palette. When the camera settings were incorrect during shooting, or when the shooting result is not what you visualized, you can get closer to what you envisaged with the [RAW] tool palette which is similar to the camera.

All functions other than [RGB] tool palette automatic adjustment, and each function of the [NR/Lens/ALO] tool palette are explained in Chapter 3.

## Editing with the Tool Palette in the Main Window

By clicking the [Tools] button (p.104) in the toolbar on the main window, the same tool palette that appears in the edit window is displayed and you can edit images.

	Introduction
e ing	Contents at a Glance
s of I r ser	Basic Operation
the d	Advanced Operation
OW	Advanced Image Editing and Printing
low, nd	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

## **Adjusting Brightness**

The brightness of an image can be adjusted. Move the slider to the right to make the image brighter and to the left to make the image darker.



## **Changing a Picture Style**

If the image you shot is different to what you visualized, you can change the Picture Style to get closer to what you envisaged. Even if you have saved the image (p.37) with [Monochrome] (p.28)selected, you can still change to another Picture Style at any point by simply selecting a Picture Style other than [Monochrome].



Index

Introduction

Contents at

a Glance

Basic

The adjustment range is –2.0 to +2.0 (in 0.01-stop increments when entering a value).

- Picture Style settings, you can still set a Picture Style as long as the RAW image is compatible with DPP (p.3).
  You can retain the [Color tone], [Color saturation], [Contrast] and
- You can retain the [Color tone], [Color saturation], [Contrast] and [Sharpness] settings, even if you change the Picture Style (p.74).

Even if the RAW image is from a camera that does not have

Picture Style	Description
Standard	The image looks vivid. Ordinarily, this setting is suitable for most images.
Portrait	For nice skin tones. Effective for close-ups of women and children. By changing the [Color tone], you can adjust the skin tone (p.27).
Landscape	For vivid blues and greens. Effective for making images of landscapes impressive.
Neutral	For natural colors and subdued images. Effective for base images which are to undergo adjustment.
Faithful	When the subject is photographed under a color temperature of 5200K, the color is adjusted colorimetrically to match the subject's color. Effective for base images which are to undergo adjustment.
Monochrome	For black and white images. You can also adjust with [Filter effect] or [Toning effect] (p.28).
(Picture Style file registered in the camera)	Displayed when selecting an image shot with the Picture Style file registered in the camera. In the list, the name of the Picture Style file is displayed in ().
[Picture Style file applied in DPP]	The name of the Picture Style file applied in DPP is displayed in [].

## **Picture Style File**

A Picture Style file is an extended function file of Picture Style. Refer to p.53 for how to use Picture Style files.

## Adjusting Color Tone by Changing White Balance

If the color tone of the photographed image does not appear natural, change the white balance to make it appear natural. You can make the color tone natural by setting the light source at the time of shooting an image of, for example, pale-colored flowers.



Introduction

Contents at

a Glance

## Adjusting Color Tone Using Click White Balance

You can adjust white balance using a selected part of an image as the standard for white to make the image appear natural. Using click white balance is effective when using it in parts of an image where white color tone has changed under the influence of a light source.

	RAW RGB	NR/Lens/ALO	]	
Brightness ad	justment		5	
	0			
111111111111	Y	0.00		
White balance	adjustment	0.00	•	
White balance	adjustment		pister	Clic

### Click on a point that is to be the standard for white.



Click The coordinates of the cursor position and the RGB values (8-bit conversion)

Reverts the image to the original settings 2

- → The color of the image is adjusted with the point you selected as the standard for white.
- If you click on another point in the image, the white balance is adjusted again.
- To finish click white balance, click the [7] button again.



Introduction

The image is adjusted based on the average value of  $5 \times 5$  pixel range from the clicked point.

When there are no white areas in your image

same adjustment result as selecting a white point.

## **Adjusting Contrast**

Modulation and degree of contrast can be adjusted. Move the slider to the right to make contrast stronger and to the left to make contrast weaker.



Display the value of the setting

## **Changing Color Tone and Color Saturation**

Skin tone and overall color saturation can be adjusted. If Picture Style (p.24) is set to [Monochrome], [Color tone] and [Color saturation] switch to [Filter effect] and [Toning effect] (p.28).





#### [Linear] - A function for advanced adjustment

Use [Linear] when you will be adjusting separately using image editing software that has advanced editing functions. Note that when [Linear] is checkmarked, the image will become dim.

Introduction

Contents at

a Glance

## **Adjusting Monochrome**

When the Picture Style (p.24) is set to [Monochrome], you can create monochrome photographs with effects similar to filtering and with the look of a single-color photograph.



Display the values of the settings

• Filter effect: Creates an image where the white of clouds and the green of trees are emphasized in the same monochrome photograph.

		Contents at
Filter	Example of effect	a Glance
None	Ordinary monochrome image without filter effect.	
Yellow	Blue sky is reproduced more naturally and white clouds emerge clearly.	Basic Operation
Orange	Blue sky becomes somewhat darker. The brightness of the setting sun increases further.	Advanced Operation
Red	Blue sky becomes quite dark. Autumn leaves become clear and bright.	
Green	Human skin tones and lips become softer. The green leaves of trees become clear and bright.	Advanced Image Editing and Printing
Toning effect	You can create a monochrome photograph to which a single color has been added. You can choose from [None], [Sepia], [Blue], [Purple]	Processing Large Numbers of Images
	and [Green].	Editing JPEG/TIFF Images
		Reference



Index

## **Adjusting Sharpness**

You can make the overall atmosphere of an image harder or softer. Move the slider to the right to make an image harder and to the left to make an image softer.



Display the value of the setting

#### **?** Sharpness is unnatural

Adjust sharpness with the window view set to [100% view], [50% view] or [200% view]. If the view is set to [Fit to window] (full view), the sharpness may seem unnatural.

The adjustment range is 0 to 10 (in 1-stop increments).



### Automatically Adjusting Brightness and Color (Tone Curve Assist)

In order to make the image a desirable standard image, automatically adjust the image tone curve (p.118). You can select the degree of automatic adjustment from "Standard" and "High".

## Click on the [RGB] tab sheet and click the desired automatic adjustment button.

- Standard: Standard automatic adjustment. Suitable for most images.
- **High:** Use when the effect achieved in standard automatic adjustment is not strong enough.



→ The tone curve changes as adjusted.

Images not suitable for automatic adjustment (tone curve assist)

The result of automatic adjustment (tone curve assist) may not be as expected with the following images:

- · Images which have been shot with the proper exposure
- Images where the brightness is unbalanced
- Images which are too dark
- Images which have extreme backlighting
- If you click the [25] button, the tone curve as well as the [Hue] and [Saturation] revert to the default settings. Take care when adjusting the [Hue] and [Saturation] individually (p.89).



## **Editing Efficiently**

## **Editing in the Edit Image Window**

The thumbnail display and the edit window are combined and images can be edited efficiently while quickly switching between images to be edited. Images to be edited are selected beforehand in the main window.

In the main window, select the images you want to edit.



→ The main window switches to the edit image window.

### Edit the image.

#### Edit image window



- → It may take time for the image to redraw itself.
- The same tool palette as in the edit window is displayed and y can edit the image.
- To revert to the condition before the last operation performed the tool palette, select [Undo] in the [Edit] menu or press  $< \Re$ : <Z> keys.

then been converted and saved (p.38, p.112).

Edit the image.	Introduction
Change the size Edit image window  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres President I's Edit Ver Adjustment Total Window Help  Deput Pres Pres Pres Pres Pres Pres Pres Pres	Contents at a Glance
Yer     Name     Yer     Name     Name     Name     Name     Name     Name       Image:	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
Select the image to be edited	Processing Large Numbers of Images
The selected image is displayed as an enlargement in the middle of the window → It may take time for the image to redraw itself.	Editing JPEG/TIFF Images
<ul> <li>The same tool palette as in the edit window is displayed and you can edit the image.</li> <li>To revert to the condition before the last operation performed on the tool palette, select [Undo] in the [Edit] menu or press &lt; \% &gt; +</li> </ul>	Reference
<z> keys.</z>	Index
By selecting the [View] menu ▶ [AF Point] in the edit window or edit image window, you can display the AF points selected in the camera at the time of shooting. However, AF points are not displayed for images which have had their image size changed and	



- The area you double-clicked is enlarged to 100% (actual pixel size). If you wait for a while, it changes to a clearer display.
- Double-click again to revert to the full view ([Fit to window]).
- To change the display position, drag on the image or drag the enlargement display position (p.108) of the tool palette.
- To return to the main window, click the [Main Window] button on the toolbar.

 $\frac{1}{2}$  To display an image in an enlargement ratio other than 100%

Click the [50% view] or [200% view] on the toolbar.

- You can change the way the tool palette is displayed (p.74).
  - You can change the enlargement ratio when you double-click (p.73).
  - With the edit image window, you can only select images from one folder. To gather images from several folders for editing, refer to "Gathering and Editing Images in the Collection Window" (p.33).
  - For a list of edit image window functions, refer to p.111.



Changing the Thumbnail Display Position to a Horizontal Position

Select the [View] menu ▶ [Change thumbnail position].



If you select [Change thumbnail position] again, the thumbnail display reverts to the vertical position.

### Gathering and Editing Images in the Collection Window

You can gather any randomly selected images together in the [Collection] window for viewing, comparison and editing. You c images from several folders as well as from only one folder, a you to work with them efficiently.

• •	-	Basic Operatio	older] window in the main
ndow, and select the [Fi	ile] me	n].	ile] menu ▶ [Add to collection]
e		Advance	
Open in Edit window	жо	Operatio	жо
Open in Edit window (enlarged)			
Close all			
Open window	ЖN	Advance	₩N
Close window	жw	Image Edi	жw
ave	жs	and Print	жs
ave As	ŵ業S		<del></del> û
Add thumbnail to image and save	ûЖТ	Processi	Ώжт
Convert and save	ЖD	Large Num	жD
Batch process	₩В	of Image	жв
Create new folder	ΰжN		û <mark>ዤ</mark> N
age setup	ûжр	Editing	ΏжР
Print	жP	JPEG/TI	жР
rint with detailed setting	ûжD	Images	仓 第D
Contact Sheet Prints	^쁐P		^ <b>ℋ</b> P
Plug-in printing	•		•
Add to collection	ЖG	Referen	жG
Remove from collection	企₩G		ΩжG
Ũ			led to the [Collection] window and the
number of selected images is	s shown	et. Index	s shown on the [Collection] tab sheet.
•			EG images displayed as a single

- You can select several images and add them to the [Collection] window.
- You can also add images to the [Collection] window by selecting images, clicking on the image while holding down the <control> key, and selecting [Add to collection] from the menu that appears.
- You can add up to 1,000 images to the [Collection] window.

#### Select the [Collection] tab sheet.



→ The selected images are displayed in the [Collection] window.

#### Check displayed images in the [Collection] window.



#### Edit the images.

You can now edit the images displayed in the [Collection] window.

### To remove images from the [Collection] window

Select the images to be removed in the [Collection] window and then select [Remove from collection] in the [File] menu. (You can also remove images from the [Collection] window by selecting the images, clicking on the image while holding down the <control> key, and selecting [Remove from collection] from the menu that appears.)

Note that even if you remove an image from the [Collection] window, the original image remains unaffected.

- Advanced Images brought together in the [Collection] window are Operation retained until you guit DPP When you guit DPP, the gathered images disappear from the Advanced [Collection] window, but this removal from the [Collection] window **Image Editing** does not mean that the original images themselves have been and Printing deleted. Modifications to the image are applied to the original image Processing Modifications made to images added to the [Collection] window Large Numbers are all applied to the original image. of Images Editina You cannot use the following functions in the [Collection] window. JPEG/TIFF Images • Starting of EOS Utility (p.7), or synchronizing of folders with EOS
- Batch change the file name of images (p.83)

Utility



Contents at

a Glance

Introduction

\_\_\_\_

Operation

34

Reference

Index

## **Trimming an Image**

You can trim only the part of an image you need, or change the composition of an image where an image shot horizontally becomes vertical.

Also, when aspect ratio information is attached to an image shot with the EOS-1Ds Mark III or EOS-1D Mark III, the trimming range based on the aspect ratio information is displayed.

#### Select the image to be trimmed.

#### Open the trimming window.

● Select the [Tools] menu ▶ [Start Trimming tool].

#### Tools

10015	
Start EOS Utility	∕C₩E
Transfer to Photoshop	Σ₩P
Start Quick check tool	τæF
Start Trimming tool	∖тжт
Chavet Chaven to al	32996
Start Stamp tool	\C₩S

→ The trimming window appears.

# When the image has redrawn itself, select a ratio and drag the trimming range.

#### **Trimming window**



- The trimming range can be moved by dragging.
- You can enlarge or reduce the size of the trimming range by dragging the four corners of the trimming range.
- List of aspect ratios (width : height)



[Free]: You can trim an image to any size, regardless of the selectable ratio.

[Custom]: You can trim an image at the specified ratio.

### Click the [OK] button to return to the main window.

The trimming range frame is displayed in the trimmed image (p.106).

When the trimmed image is displayed in an edit window or the edit image window, it is displayed in its trimmed form.

	Introduction
ру	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
of the	Processing Large Numbers of Images
ow.	Editing JPEG/TIFF Images
ge · the	Reference
	Index
### About trimmed images

 The trimmed range can be reverted to its original condition at any time

A trimmed image is displayed or printed as a trimmed image. However, since the image is not actually trimmed, you can always revert to the original image by clicking the [Reset] button in the trimming window or performing the "Re-Editing an Image" procedure (p.39).

#### Display of the trimmed image in each window

- Main window: The frame showing the trimming range is displayed on the image (p.106).
- Edit window: The image is displayed in its trimmed condition.
- Edit image window: The thumbnail image is the same as the main window display, and the enlarged image is the same as the edit window display.

#### Printing a trimmed image

You can print as a trimmed image by printing it in DPP.

- The image becomes a trimmed image when converted and saved The trimmed RAW image actually becomes a trimmed image when converted to a JPEG or TIFF image and saved (p.38).
- Images that have aspect ratio set will be displayed as trimmed images

When aspect ratio information is attached to an image shot with EOS-1Ds Mark III or EOS-1D Mark III, the set trimming range based on the aspect ratio information is displayed. However, since the image is not actually trimmed, you can change the trimming range or revert to the condition before trimming.

When reverting to the condition before trimming is performed based on the aspect ratio information at the time of shooting, click the [Reset] button. Also, if you want to cancel all the trimming range, click the [Clear] button (p.113).  $\in$  Convenient functions of the trimming window

#### Switch between screens using the keyboard

You can also switch between full screen display/normal screen display by pressing the  $< \Re > + < F11 > keys$ .

#### Operate using the menu

Each operation can also be performed with the menu which appears by clicking on the image while holding down the <control> key.

Apply the trimmed range to another image

You can apply the trimmed range to another image by clicking the [Copy] button to copy the trimmed range, displaying another image and then clicking the [Paste] button.

To batch apply a copied trimming range to multiple images, select the trimmed image and the multiple images to which you want to apply the trimmed range in the main window, and display the trimming window. With the trimmed image displayed, click the [Copy] button and then click the [Apply All] button. This will apply the trimming range to all the images selected when the trimming window is displayed.

For a list of the trimming window functions, refer to p.113.

Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editing JPEG/TIFF Images Reference Index

Introduction

# Applying Adjustment Contents to Other Images

You can copy the image adjustment contents (recipe) adjusted with the tool palette and apply it to other images.

You can efficiently adjust multiple images by adjusting one image and applying the results of this to multiple images shot in similar shooting environment.

### Select the adjusted image and then select the [Edit] menu ▶ [Copy recipe to clipboard].

→ The recipe is copied.

Select the image to which the recipe is to be applied
 and then select the [Edit] menu ▶ [Paste recipe to selected image].

→ The recipe is applied to the image.

# **Saving Editing Results**

# Saving Editing Contents to a RAW Image

All the contents (recipe) adjusted with the tool palette as well as the trimmed (p.35) range information can be saved to a RAW image or to a separate RAW image.

The adjustments made with the tool palette (p.52 to p.61) and the dust erase processing explained in Chapter 3 (p.62 to p.66) can also be saved in a RAW image.

### Select the [File] menu ▶ desired item.

File	
Open in Edit window Open in Edit window (enlarged) Close all	жо
Open window	ЖN
Close window	жw
Save	жs
Save As	ĉ₩S
Add thumbnail to image and save	ûЖТ
Convert and save	ЖD
Batch process	ЖB
Create new folder	û₩Ν
Page setup	企ℋP
Print	ЖP
Print with detailed setting	企業D
Contact Sheet Prints	^%₽
Plug-in printing	•
Add to collection	ЖG
Remove from collection	ŵЖG
Delete	¥≪
Info	жı

→ Your adjustments are saved to the image.

à	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

Introduction



The recipe (p.78) can be saved as a separate file from the image and loaded and applied to another image (p.79).

# Saving as a JPEG or TIFF Image

To view, edit and print a RAW image with software other than DPP, convert to a more versatile JPEG or TIFF image and save. The image is saved as a separate image, so the RAW image remains unaffected.

Select the image to be converted.

### Select the [File] menu ▶ [Convert and save].

File	
Open in Edit window	жо
Open in Edit window (enlarged)	
Close all	
Open window	ЖN
Close window	жw
Save	жs
Save As	企業S
Add thumbnail to image and save	ûЖТ
Convert and save	ЖD
Batch process	₩В
Create new folder	ΰжN
Page setup	ûжР
Print	ЖP
Print with detailed setting	企業D
Contact Sheet Prints	^ ፝ # P
Plug-in printing	•
Add to collection	жG
Remove from collection	ûЖG
Delete	¥≪
Info	жı

→ The [Convert and save] window appears.

# Specify the necessary settings, and then click the [Save] button.

 By default, the image is converted and saved to a JPEG image with the highest image quality, without changing the image size. Change the settings according to your requirements.



# **Re-Editing an Image**

Only the image processing conditions are changed in images adjusted with the tool palette (p.23), so the "original image data itself" remains unaffected.

Also, the trimming range information of a trimmed image (p.35) is simply saved to the image.

For this reason, you can undo any adjustments saved (p.37) to the image, trimming information, and revert to the condition when last saved, or when the image was shot.

### Select the image that is to be re-edited.

# Select the [Adjustment] menu > desired item.

#### Adjustment

Rotate Left	ℋL
Rotate Right	ЖR
Add check mark1	ℋF1
Add check mark2	ℋF2
Add check mark3	ℋF3
Clear check mark	ℋF4
Apply Dust Delete Data	
Work color space	•
Tone curve assist - Standard	1
Tone curve assist - High	
Revert to last saved settings	τ#Z
Revert to shot settings	^%Z

→ The image reverts to the conditions of the selected item.

# **Printing an Image**

This section explains how to print high-resolution photographs easily with the Canon inkjet printers compatible with the Canon printing software, Easy-PhotoPrint EX or Easy-PhotoPrint. It also explains how to print photographs using other printers.

Proceed to the page for the printer you are using.

- Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint EX (Same page)
- Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint (p.42)
- Printing Photographs with a Printer other than the Canon Inkjet Printers (p.44)

# Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint EX

You can perform the following types of photograph printing with the Canon inkjet printers compatible with Easy-PhotoPrint EX (hereinafter, "EPP EX") :

- Simple printing of RAW images
- Printing with faithful colors
- High quality printing using the color reproduction range of Adobe RGB and a Canon inkjet printer

To perform this printing, it is necessary to first install EPP EX version 1.1 or later on your computer.

Basic Operation Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images Editing JPEG/TIFF Images Reference

Index



Introduction

Contents at a Glance

### Select the image to be printed.

### Start up EPP EX.

 Select the [File] menu ▶ [Plug-in printing] ▶ [Print with Easy-PhotoPrint EX].

#### File

Close all		
Open window	ЖN	
Close window	жw	
Save	жs	
Save As	企業S	
Add thumbnail to image and save	ΰЖT	
Convert and save	ЖD	
Batch process	₩В	
Create new folder	企業N	
Page setup	ΰжР	
Print	ЖP	
Print with detailed setting	企業D	
Contact Sheet Prints	^ ፝ # P	
Plug-in printing	•	Print with Easy-PhotoPrin
Add to collection	жG	Print with Easy-PhotoPrin

ЖE

→ EPP EX starts up.

### In the EPP EX window, select the [File] menu ▶ [Preferences].

### File

Open My Recent Files	жо ►
Previous Step Next Step	
Save	жs
Save As Preferences	企業S
Print	ЖΡ

→ The [Preferences] window appears.



### Select the paper type, and then click the [Layout/ Print] button.



Click



# Specify the layout, and then click the [Print] button.

Click to print

→ Printing begins.

### Additional information

#### Print up to 1000 images at a time

You can print up to 1000 images selected in DPP at a time. When printing more than 1000 images, divide the printing into several jobs.

### The printed image's color is not what you expected

In the EPP EX window, select [Preferences] in the [File] menu and then click the [Advanced] tab in the [Preferences] window to display the [Advanced] tab sheet. In the [Advanced] tab sheet, select [Enable ICC Profile] in [Color correction for printing] and print using the [Perceptual] setting (p.119).

### Advantages of printing using EPP EX

### Printing with faithful colors

When the color space (p.119) is set to sRGB or Adobe RGB (p.66, p.75), this color space is automatically transmitted from DPP to EPP EX, allowing you to print with faithful colors.

If you set Apple RGB, ColorMatch RGB or Wide Gamut RGB, the image is printed with Adobe RGB color space.

### Printing with a wide color reproduction

When the color space (p.66, p.75) is set to Adobe RGB and the image is printed with the Canon inkjet printer, the color reproduction area widens, and green and blue in particular are reproduced vividly.

DPP is also compatible for printing with Easy-PhotoPrint Pro (p.69).



Introduction

Contents at

a Glance

Basic

Operation

Advanced

Operation

41

# Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint

You can perform the following types of photograph printing with the Canon inkjet printers compatible with Easy-PhotoPrint (hereinafter, "EPP"):

- Simple printing of RAW images
- Printing with faithful colors
- High quality printing using the color reproduction range of Adobe RGB and a Canon inkjet printer

To perform this printing, it is necessary to first install EPP version 3.5 or later on your computer.

### Select the image to be printed.

### Start up EPP.

 Select the [File] menu > [Plug-in printing] > [Print with Easy-PhotoPrint].

#### File

Open in Edit window Open in Edit window (enlarged) Close all	жо	
Open window	ЖN	
Close window	жw	
Save	жs	
Save As	企業S	
Add thumbnail to image and save	ûЖΤ	
Convert and save	ЖD	
Batch process	₩В	
Create new folder	企業N	
Page setup	ûжР	
Print	ЖP	
Print with detailed setting	企業D	
Contact Sheet Prints	^%P	
Plug-in printing	▶	Print with Easy-PhotoPri
Add to collection	ЖG	
Remove from collection	ûЖG	

In the EPP window, select the [Easy-PhotoPrint] menu ▶ [Preferences].

About Easy-PhotoPrin	nt
Preferences	¥,
Services	•
Hide Easy-PhotoPrint	жн
Hide Others	₹ЖН
Show All	
Quit Easy-PhotoPrint	жQ

→ The [Preferences] window appears.

# 📶 In [Print Quality], select [Quality Priority].



I	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
ct ity ity	Editing JPEG/TIFF Images
	Reference
	Index

Introduction

# Select the [Advanced] tab sheet and check that the EPP image compensation function is disabled.

 If not disabled, the operation of the EPP image compensation function may prevent images being printed with faithful color reproduction.



Specify the number of sheets to be printed, and then click [Next].



# Check that the image compensation function is disabled, select the paper type and then click [Next].



Specify the layout, and then click [Print].



→ Printing begins.



### Additional information

#### Print up to 1000 images at a time

You can print up to 1000 images selected in DPP at a time. When printing more than 1000 images, divide the printing into several jobs.

#### The printed image's color is not what you expected

Change the [Rendering intents when using Easy-PhotoPrint] (p.75) to [Perceptual] (p.119) and print.

### Advantages of printing using EPP

#### Printing with faithful colors

When the color space (p.119) is set to sRGB or Adobe RGB (p.66, p.75), this color space is automatically transmitted from DPP to EPP, allowing you to print with faithful colors.

If you set Apple RGB, ColorMatch RGB or Wide Gamut RGB, the image is printed with Adobe RGB color space.

#### Printing with a wide color reproduction

When the color space (p.66, p.75) is set to Adobe RGB and the image is printed with the Canon inkjet printer, the color reproduction area widens, and green and blue in particular are reproduced vividly.

DPP is also compatible for printing with Easy-PhotoPrint Pro (p.69).

### Printing Photographs with a Printer other than the Canon Inkjet Printers

You can print one image on one sheet of paper.

### Select the image to be printed.

### Select the [File] menu ▶ [Print].

File	
Open in Edit window	жо
Open in Edit window (enlarged)	
Close all	
Open window	ЖN
Close window	жw
Save	ЖS
Save As	企₩S
Add thumbnail to image and save	企業T
Convert and save	жD
Batch process	ЖB
Create new folder	ΰ₩N
Page setup	ûжР
Print	ЖP
Print with detailed setting	û μD
Contact Sheet Prints	^ ፝ # P
Plug-in printing	•
Add to collection	ЖG
Remove from collection	ûЖG
Delete	ж«
Info	жı

→ The [Print] dialog box appears.

### Set to photograph printing and print.

 Specify the optimum settings for photograph printing in the printer's print settings dialog box and click the [Print] button.
 Printing begins.

	Introduction
-	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

# **Organizing Images**

This section explains how to delete unwanted images, create folders for saving images, move or copy images, etc., and organize your images.

# **Deleting an Unwanted Image**

Be aware that you cannot recover deleted images.

### Select an unwanted image in the main window.

# Select the [File] menu ▶ [Delete].

File	
Open in Edit window	жо
Open in Edit window (enlarged)	
Close all	
Open window	ЖN
Close window	жw
Save	жs
Save As	企業S
Add thumbnail to image and save	ûЖΤ
Convert and save	жD
Batch process	жв
Create new folder	企業N
Page setup	企ℋP
Print	ЖP
Print with detailed setting	企業D
Contact Sheet Prints	^ ፝ ЖР
Plug-in printing	•
Add to collection	ЖG
Remove from collection	ûЖG
Delete	ж«
Info	жı

→ The image is moved to the [Trash] and is deleted from DPP.

• The images are deleted completely from your computer by selecting the [Finder] menu ▶ [Empty Trash] on the desktop.

# **Creating a Folder for Saving Images**

You can create a folder for sorting images.

In the folder area, select the location where the new folder is to be created.





Open in Edit window	жо
Open in Edit window (enlarged)	
Close all	
Open window	ЖN
Close window	жw
Save	ЖS
Save As	ŵжs
Add thumbnail to image and save	ûЖТ
Convert and save	жD
Batch process	ЖB
Create new folder	企ℋN
Page setup	ŵжР
Print	ЖP
Print with detailed setting	ûжD



# Enter a folder name and click the [OK] button.

→ The new folder is created in the folder selected in step 1.

# **Moving Images**

You can move or copy images to a separate folder and sort by shooting date or themes.

### Drag the image to be moved or copied.

- To move: Drag the image and release when the image is in the destination folder.
- **To copy:** Drag the image while holding down the <option> key and release when the image is in the destination folder.



The images are moved or copied to the destination folder.

# **Moving Images in Folders**

Collection((

by folders.

Folder

Temporary Items

Travel ·

▶ m Documents

▶ 🚺 Library

Movies

🚺 Music

Dicto

▶ 🗾 Sites

▶ 📁 Shared

🔻 📁 Photo

▶ 🚺 Public \*\* \*\* \*\*

▼ 📕 MacOSX ▶ 🛃 Applications

V I Users

🔻 🏦 canon 🔻 🔝 Desktop



Index

Introduction

# **Registering Frequent-Use Folders (Bookmark Registration)**

You can register frequently used folders in bookmarks. Registered folders appear by clicking the [Bookmark] menu.





## Select the [Bookmark] menu ▶ [Add].

- The folder selected in step 1 is registered in the [Bookmark] menu.
- Select a registered folder from the [Bookmark] menu to display images in the selected folder in the main window.

# **Organizing Bookmarks**

You can change a folder name or delete a folder registered in [Bookmark].

### Select the [Bookmark] menu ▶ [Organize].

The [Sort bookmarks] window appears and you can change folder names or delete folders.



Introduction

### 3 **Advanced Image Editing and Printing**

Various preferences including advanced image adjustment, automatic dust erasure processing, various printing functions for printing out work, and color management are explained here, geared to the user who is competent in the handling of third-party image editing software.

Adjusting While Comparing with the Original Image Changing How the Window is Split	
Adjusting by Comparing Multiple Images	
Displaying an Area Beyond the Set Range as a	
Warning Indicator (Highlight/Shadow Warning)	51
Performing Advanced Editing	52
Adjusting White Balance with Color Temperature	52
Tuning White Balance with Color Wheel	52
Adjusting Dynamic Range	53
Using a Picture Style File	53
Tone Curve Adjustment	54
Example of a Tone Curve Operation	55
About the RGB Tool Palette	55
Using the Auto Lighting Optimizer	56
Reducing Noise	57
Correcting Lens Aberration	58
Compatible Cameras	
Compatible Lenses	58
Making Corrections	60
About Shooting Distance Information Slider	<mark>61</mark>
Correcting Multiple Images at a Time	<mark>61</mark>

Compatible Cameras62Contents at a GlanceAutomatic Dust Erasure Processing in the Main Window63Manually Erasing Dust (Repair Function)64Erasing Unwanted Parts of an Image (Copy Stamp Function)66Transferring a RAW Image to Photoshop66Setting Work Color Space66Printing with Shooting Information67Printing a Thumbnail List (Contact Sheet Printing)68Printing RAW Images on a High-End Canon Printer69Printing with a High-End Canon Inkjet Printer69Printing with a Large-Format Canon Printer70Specifying Preferences71General Settings73Tool Palette74Color Management75	Performing Automatic Dust Erasure Processing 62	
Automatic Dust Erasure Processing in the Main Window63a GlanceManually Erasing Dust (Repair Function)	Compatible Cameras 62	Contents at
Erasing Unwanted Parts of an Image (Copy Stamp Function)	Automatic Dust Erasure Processing in the Main Window 63	
Setting Work Color Space66Printing with Shooting Information67Printing a Thumbnail List (Contact Sheet Printing)68Printing RAW Images on a High-End Canon Printer69Printing with a High-End Canon Inkjet Printer69Printing with a Large-Format Canon Printer70Specifying Preferences71General Settings71View Settings73Tool Palette74	Erasing Unwanted Parts of an Image (Copy Stamp	
Setting Work Color Space66Printing with Shooting Information67Printing a Thumbnail List (Contact Sheet Printing)68Printing RAW Images on a High-End Canon Printer69Printing with a High-End Canon Inkjet Printer69Printing with a Large-Format Canon Printer69Specifying Preferences71General Settings71View Settings73Tool Palette74	Transferring a RAW Image to Photoshop	Advanced
Printing a Thumbnail List (Contact Sheet Printing)68Printing RAW Images on a High-End Canon Printer69Printing with a High-End Canon Inkjet Printer69Printing with a Large-Format Canon Printer69Specifying Preferences	Setting Work Color Space 66	Operation
Printing a Thumbnail List (Contact Sheet Printing)68Image Editing and PrintingPrinting RAW Images on a High-End Canon Printer69Processing Printing with a High-End Canon Inkjet Printer69Printing with a Large-Format Canon Printer	Printing with Shooting Information	Advanced
Printing RAW Images on a High-End Canon Printer       69         Printing with a High-End Canon Inkjet Printer       69         Printing with a Large-Format Canon Printer       70         Specifying Preferences       71         General Settings       71         View Settings       73         Tool Palette       74	Printing a Thumbnail List (Contact Sheet Printing) 68	Image Editing
Printing with a High-End Canon Inkjet Printer       09         Printing with a Large-Format Canon Printer       70         Specifying Preferences       71         General Settings       71         View Settings       73         Tool Palette       74	Printing RAW Images on a High-End Canon Printer 69	
Printing with a Large-Format Canon Printer70of ImagesSpecifying Preferences71EditingGeneral Settings71Tool PaletteView Settings7374Reference74	Printing with a High-End Canon Inkjet Printer	
General Settings       71         View Settings       73         Tool Palette       74         Reference	Printing with a Large-Format Canon Printer	
General Settings       71         View Settings       73         Tool Palette       74         Reference	Specifying Preferences	Editing
View Settings		JPEG/TIFF
Tool Palette	View Settings73	integee
	-	Peference
	Color Management75	Kelelelice

Introduction

Index

S,

# Adjusting While Comparing with the Original Image

You can display before and after versions of an adjusted image in the same window and adjust while checking the adjustment results.

## In the edit window, select the [View] menu ▶ [Before/ after comparison].



- → The image divides into a left and right window.
- The window on the right shows the image after editing.

## Change the image display.

 Select the [View] menu ▶ [Change up/down/left/right] ▶ [Up/ down].



- → The layout of the two images changes to top and bottom.
- The bottom window shows the image after editing.

Images can also be displayed in the edit image window by the same operation.

# Changing How the Window is Split

You can change the display of the image to a single image split in two.

In the edit window, select the [View] menu ▶ [Display mode] ▶ [Split single image].





- One image is divided and displayed on the left and right or top and bottom.
- To switch between top and bottom, and left and right, perform the same operation as step 2 on the left page.



Introduction

Contents at

a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing

Reference

Index



49

# Adjusting by Comparing Multiple Images

You can synchronize the display position of multiple edit windows and adjust images while comparing them with each other.

In the edit window, display the multiple images to be compared.

### Align the images.

- Align the images for easy comparison.
- Select the [Window] menu ▶ [Synchronize].

### Enlarge the image.

Enlarge and display any of the edit windows.



- The other edit windows will also be displayed in the same position/enlargement ratio.
- Introduction Move the display position. → If you move the enlargement display position in one of the edit windows, the enlargement display position will also change in the Contents at other edit windows. To cancel synchronization, select the [Window] menu > [Synchronize] again. Image Editing and Printing Processing Large Numbers



a Glance

Basic

Operation

Advanced Operation

Advanced

of Images

Editing JPEG/TIFF Images

Reference

Index

Synchronization only applies to the enlargement display position and the enlargement ratio. Adjustments to the images are not synchronized.

# Displaying an Area Beyond the Set Range as a Warning Indicator (Highlight/Shadow Warning)

You can set up a warning indicator in both the highlighted part and the shaded part, which is effective for checking the light and dark areas and preventing excessive adjustment of an image. Where the area on the image has exceeded that set range, you can display the highlighted part in red and the shaded part in blue.

Select the [Digital Photo Professional] menu
[Preferences].

Select the [View settings] tab sheet.

# Enter the warning value for [Highlight] and [Shadow].

		Prefe	rences	
General set	tings Viev	/ settings	Tool palette	Color management
Grid pitch				
64 Pixels(8-256)				
Locking selected ima	ge			
🗹 Images opened in Edit	window rema	in selected	in main window	/
Magnification in Edit	window			
• Fit to window	0 50%	0	0 100%	○ 200%
Magnification when t	he Edit/Edit	image wi	ndow is doub	le-clicked
○ 50%	• 100%	C	200%	
RAW and JPEG				
Display only CR2 imag	es for CR2 an	d JPEG files	of the same na	me
Sort order in main wi	ndow			
Retain sort order				
Highlight/shadow wa	rning			
Highlight	192 (1	92-255)		
Shadow		-64)		
Quick check tool disp	olay			
<ul> <li>50%</li> </ul>	O 10	0% (moiré r	eduction off)	
			C	Cancel OK

Click the [OK] button to close the window.

Display the edit window.

Select the [View] menu > [Highlight]. Similarly, select [Shadow].

On the opened image, if there is an area that exceeds the value entered in step 3, the highlighted part of that area is displayed in red and the shaded part is displayed in blue.



51

Introduction

# **Performing Advanced Editing**

This section explains how to use the advanced adjustment function on the tool palette in the edit window.

Adjustments made using the high-level functions of the [RAW] and [RGB] tool palettes, as well as the functions of the [NR/Lens/ALO] tool palette are explained in this section.

# Adjusting White Balance with Color Temperature

White balance can be adjusted by setting a numerical value for color temperature.

Select [Color temperature] from the [White balance adjustment] list box.

### Set the color temperature.





#### Tune by dragging a point. You can also fine-tune your adjustment by directly entering the



The adjustment range of color tone is 0 to 359 (1 unit in numerical value input), and the adjustment range of color saturation is 0 to 255 (1 unit in numerical value input).

Introduction

Contents at

a Glance

Basic

Operation

Editing

Images

Index

# **Adjusting Dynamic Range**

Dynamic range (width of gradation expression) from dark points to bright points in an image can be adjusted.



Move to the left or right Input shadow points

 The horizontal axis shows the input level and the vertical axis shows the output level.

# Using a Picture Style File

A Picture Style file is an extended function file of a Picture Style. With DPP, you can apply to RAW images Picture Style files that you have downloaded from Canon's web site effective for various scenes of Picture Style files created with "Picture Style Editor". When using a Picture Style file, save it to your computer beforehand.

- Display the image to which the Picture Style file is the applied in the edit window (p.11).
  - Select the [RAW] tab sheet in the tool palette, and click the [Browse] button.

Standa	rd		•	Browse.
-	h 1	1 1	NI /	
			X	

→ The [Open] dialog box appears.

# Select a Picture Style file saved on your computer, and click the [Open] button.

- → The Picture Style file you selected is applied to an image.
- To apply a different Picture Style file, follow the procedure from step 2 again.

	Introduction
s or	Contents at a Glance
to	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
,	Reference
m	Index
vith	00

The Picture Style files that you can apply to the camera are files with the ".PF2" extension only. Furthermore, you cannot apply Picture Style files with the extension ".PSE" to an image; however if such a file is registered in the camera and the image is shot, the image will display correctly.

# **Tone Curve Adjustment**

You can adjust the brightness, contrast and color of a specific area by changing the tone curve (p.118).

- In the tool palette, select the [RGB] tab sheet.
- 2 Select the tone curve mode and interpolation method.





### **Example of a Tone Curve Operation**

Makes medium tones brighter

Makes medium tones darker



#### Makes tones harder

#### Makes tones softer



# About the RGB Tool Palette

You can adjust images with the tool palette by switching between the [RAW], [RGB] and [NR/Lens/ALO] tab sheets according to your editing requirements.

The [RGB] tool palette functions are the same as ordinary image editing software, such as tone curve adjustment that is explained here, with which you can adjust RAW images.

However, because the adjustment width of the adjustment functions in the [RGB] tool palette is wider than the [RAW] tool palette, the image color may be saturated, or the image quality may deteriorate if you adjust too much. Therefore we recommend for functions other than tone curve adjustment and automatic adjustment (p.30), that you adjust images using the same functions available in the [RAW] tool palette. Refer to Chapter 5 for explanations on functions of the [RGB] tool palette other than tone curve adjustment.



#### Using the tool palette

We recommend that as a general principle you edit RAW images using the [RAW] tool palette. However, where the adjustment width with the [RAW] tool palette is not wide enough and you wish to use the special functions in the [RGB] tool palette, we recommend that you adjust your images at the necessary lowest limit with the [RGB] tool palette after having completed basic adjustment with the [RAW] tool palette. Use the adjustment function of the [NR/Lens/ALO] tool palette (p.109) when applying the Auto Lighting Optimizer (p.56), reducing noise (p.57) or correcting aberration (p.58) after you have made any required adjustments with the [RAW] and [RGB] tool palettes.

Contents at

a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



# **Using the Auto Lighting Optimizer**

If the shooting result is dark or the contrast is low, using the Auto Lighting Optimizer will auto-correct the brightness or contrast to provide the desirable image.

You can also change the settings of the image shot with the camera's Auto Lighting Optimizer function.

This function is compatible only with RAW images shot with EOS 5D Mark II and EOS 50D.

\* ALO stands for Auto Lighting Optimizer.

Select the [NR/Lens/ALO] tab sheet from the tool
palette in the edit window or edit image window.

Auto Lighting Optim	Izer			
۲	.ow	<b>Standard</b>	Strong	
NR			Apply	/
RAW				
Luminance noise (7)	0			20
Chrominance nois (8)	e 0	<b>-</b>		20
TIFF/JPEG				
Luminance noise (0)	0	0	ana ang ang ang ang ang ang ang ang ang	20
Chrominance nois (0)	e 0	0		20
ens aberration corr	ection	8	Tune.	
Peripheral illumina	ation		OFF	
Distortion			OFF	
Chromatic aberrat	ion		OFF	

Checkmark the checkbox.	Introductio
Auto Lighting Optimizer	Contents a a Glance
<ul> <li>For images shot with the camera's Auto Lighting Optimizer function, the checkbox is already checked.</li> </ul>	Basic Operation
Change the settings according to your preferences.	Advance Operatio
Auto Lighting Optimizer  Select from three levels: Low/Standard/Strong	Advance Image Edit and Printi
<ul> <li>Auto correction is applied to the image to match the settings.</li> <li>For images shot with the camera's Auto Lighting Optimizer function, the settings at the time of shooting are applied as the default values.</li> </ul>	Processir Large Numb of Image
<ul> <li>default values.</li> <li>To cancel the Auto Lighting Optimizer, remove the check mark from the checkbox.</li> </ul>	Editing JPEG/TIF Images
	Referenc
	Index

# **Reducing Noise**

You can reduce noise that arises in RAW images that have been shot at night or with a high ISO speed.

NR is an abbreviation for "noise reduction".

### Select the [NR/Lens/ALO] tab sheet from the tool palette in the edit window or edit image window.

### Adjust an image.



• You can set a noise reduction level from within a range of 0 to 20. The larger the setting, the larger the noise reduction effect.

# Click the [Apply] button.

→ Noise reduction is applied to the image and the image is redisplayed.

# Display the image in the [100% view] or [200% view].

You can check the noise reduction effect.

In the [50% view] or [Fit to window] display, it may be difficult to check the noise reduction effect

### Additional information



Index

Introduction

Contents at

a Glance

Basic

Operation

# **Correcting Lens Aberration**

You can easily make corrections to drops in peripheral illumination, distortions in the subject, and color blur which occur by the physical characteristics of the lens or slightly remaining aberration.

Please note that you can only correct RAW images which have been taken with the compatible cameras and lenses listed below. JPEG or TIFF images cannot be corrected.

# **Compatible Cameras**

EOS-1Ds Mark III	EOS-1D Mark III	EOS-1D Mark II N
EOS-1Ds Mark II	EOS-1D Mark II	EOS-1Ds
EOS-1D	EOS 5D Mark II	EOS 5D*1
EOS 50D	EOS 40D	EOS 30D*2
EOS DIGITAL REBEL XSi/450D	EOS DIGITAL REBEL XTi/400D DIGITAL	

\*1 Requires firmware version 1.1.1

\*2 Requires firmware version 1.0.6

# **Compatible Lenses**

EF 85mm f/1.8 USM

Ultra wide and wide lenses				
EF 14mm f/2.8L USM	EF 14mm f/2.8L II USM* <sup>3</sup>			
EF 20mm f/2.8 USM	EF 24mm f/1.4L USM			
EF 24mm f/1.4L II USM* <sup>3</sup>	EF 24mm f/2.8			
EF 28mm f/1.8 USM	EF 28mm f/2.8			
EF 35mm f/1.4L USM	EF 35mm f/2			
Standard and medium telephoto lenses				
EF 50mm f/1.2L USM*4	EF 50mm f/1.4 USM			
EF 50mm f/1.8	EF 50mm f/1.8 II			
EF 85mm f/1.2L USM	EF 85mm f/1.2L II USM* <sup>5</sup>			

Telephoto lenses			
EF 135mm f/2L USM	EF 135mm f/2.8 (with Softfocus mechanism)		
EF 200mm f/2L IS USM*3	EF 200mm f/2.8L USM		
EF 200mm f/2.8L II USM	EF 300mm f/2.8L IS USM		
EF 300mm f/4L IS USM	EF 400mm f/2.8L IS USM		
EF 400mm f/5.6L USM	EF 400mm f/4 DO IS USM		
EF 500mm f/4L IS USM	EF 600mm f/4L IS USM		
EF 800mm f/5.6L IS USM*3	—		

EF 100mm f/2 USM



Basic Operation
Advanced Operation
Advanced Image Editing and Printing
Processing Large Numbers of Images

Introduction

Contents at

a Glance

Editing JPEG/TIFF Images

Reference

Index



Zoom lenses				
EF 16-35mm f/2.8L USM	EF 16-35mm f/2.8L II USM* <sup>3</sup>			
EF 17-35mm f/2.8L USM	EF 17-40mm f/4L USM			
EF 20-35mm f/3.5-4.5 USM	EF 24-70mm f/2.8L USM			
EF 24-85mm f/3.5-4.5 USM	EF 24-105mm f/4L IS USM			
EF 28-70mm f/2.8L USM	EF 28-90mm f/4-5.6 USM			
EF 28-90mm f/4-5.6 II USM	EF 28-90mm f/4-5.6			
EF 28-90mm f/4-5.6 II	EF 28-90mm f/4-5.6 III			
EF 28-105mm f/3.5-4.5 USM	EF 28-105mm f/3.5-4.5 II USM			
EF 28-105mm f/4-5.6 USM	EF 28-105mm f/4-5.6			
EF 28-135mm f/3.5-5.6 IS USM	EF 28-200mm f/3.5-5.6			
EF 28-200mm f/3.5-5.6 USM	EF 28-300mm f/3.5-5.6L IS USM			
EF 55-200mm f/4.5-5.6 II USM	EF 55-200mm f/4-5.6 USM			
EF 70-200mm f/2.8L USM	EF 70-200mm f/4L USM			
EF 70-200mm f/2.8L IS USM	EF 70-200mm f/4L IS USM*4			
EF 70-300mm f/4-5.6 IS USM	EF 70-300mm f/4.5-5.6 DO IS USM			
EF 75-300mm f/4-5.6 II* <sup>3</sup>	EF 75-300mm f/4-5.6 III* <sup>3</sup>			
EF 75-300mm f/4-5.6 USM	EF 75-300mm f/4-5.6 II USM			
EF 75-300mm f/4-5.6 III USM	EF 90-300mm f/4.5-5.6			
EF 90-300mm f/4.5-5.6 USM	EF 100-300mm f/4.5-5.6 USM			
EF 100-400mm f/4.5-5.6L IS USM				

EF-S lenses			
EF-S 60mm f/2.8 Macro USM	EF-S 10-22mm f/3.5-4.5 USM		
EF-S 17-55mm f/2.8 IS USM	EF-S 17-85mm f/4-5.6 IS USM		
EF-S 18-55mm f/3.5-5.6	EF-S 18-55mm f/3.5-5.6 II		
EF-S 18-55mm f/3.5-5.6 USM	EF-S 18-55mm f/3.5-5.6 II USM		
EF-S 18-55mm f/3.5-5.6 IS*3	EF-S 18-200mm f/3.5-5.6 IS* <sup>3</sup>		
EF-S 55-250mm f/4-5.6 IS* <sup>3</sup>			

Aberration correction will not apply to images shot with a combination of lenses  $^{*3}$   $^{*4}$   $^{*5}$  and EOS 5D or EOS 30D with the firmware versions below.

- \* You cannot attach an EF-S lens to EOS 5D.
- \*3 EOS 5D with firmware version 1.1.0 or earlier, EOS 30D with firmware version 1.0.5 or earlier
- \*4 EOS 5D with firmware version 1.1.0 or earlier, EOS 30D with firmware version 1.0.4 or earlier
- \*5 EOS 5D with firmware version 1.0.5 or earlier, EOS 30D with firmware version 1.0.4 or earlier
- Contents at a Glance Basic Operation Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images Editing JPEG/TIFF Images Reference Index

Introduction

- You can also correct RAW images taken with the compatible lens even when the extender is attached.
- The aberration correction function is not available for images shot with combinations of camera/lens other than those given under "Compatible Cameras" and "Compatible Lenses". They are therefore not displayed and cannot be used.

# **Making Corrections**

You can make corrections to any of the four aberrations as below, either one at a time or simultaneously.

- Peripheral illumination
- Distortions
- Chromatic aberration (color fringing which occurs in the periphery of an image)
- Color blur (blue or red color blur which sometimes occurs at the edge of the highlighted area of an image)

# In the tool palette, select the [NR/Lens/ALO] tab sheet.

### Click the [Tune] button.

RAW	RGB	NR/Len	s/ALO	
Auto Lighting Optim	izer			
	Low	<b></b> Standard	Strong	
NR			Apply	
RAW				
Luminance noise (7)	0			20
Chrominance nois (8)	se O			20
TIFF/JPEG				
Luminance noise (0)	0	0	anaanaa fa	20
Chrominance nois (0)	se 0	0		20
ens aberration corr	ection		Tune	
Peripheral illumin	ation		OFF	
Distortion			OFF	
Chromatic aberra	tion		OFF	
Color blur			OFF	

→ The [Lens aberration correction] window appears.

### Checkmark the items to be corrected.



- → The image is corrected and redisplayed.
- Check the results of corrections to peripheral illumination or distortions in the full view.
- Check the results of corrections to chromatic aberration and colo blur by clicking the area on the image you want to check. In the top right of the window, the area is displayed at 200% in the enlargement display section (p.114).
- You can lessen the degree of correction by moving the slider to the left for the item you want to correct.
- You can respectively correct red chromatic aberration with the [R] slider of the [Chromatic aberration] or blue chromatic aberration with the [B] slider.

### Click the [OK] button.

- The [Lens aberration correction] window closes and the result of the corrections is applied to the image in the edit window and the image is redisplayed.
- The result of the settings of the [Lens aberration correction] window is also displayed in the tool palette.
- → In the main window, the [ ) mark is displayed on the image to indicate the lens aberration corrections (p.106).

	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
olor he	Editing JPEG/TIFF Images
to [R]	Reference
on	Index
t of the	

#### Introduction

## **About Shooting Distance Information Slider**

- When correcting RAW images shot with EOS-1Ds Mark III, EOS-1D Mark III, EOS 5D Mark II, EOS 50D, EOS 40D, EOS DIGITAL REBEL XSi/450D or EOS DIGITAL REBEL XS/1000D, if shooting distance information has been saved to the image, the slider is set automatically according to this shooting distance information. However, if no shooting distance information is saved to the image, the slider is set automatically to the right end at infinity position. If the image's shooting distance is not infinite, you can minutely adjust the distance by operating the slider while looking at the screen.
- When correcting RAW images shot with EOS-1D Mark II N, EOS-1Ds Mark II, EOS-1D Mark II, EOS-1Ds, EOS-1D, EOS 5D, EOS 30D or EOS DIGITAL REBEL XTi/400D DIGITAL, it is set automatically to the right end at infinity position. You can then minutely adjust the distance by operating the slider while looking at the screen if the shooting distance is not infinite.
- [Shooting distance information] slider is applied to all the correction items with check marks.

## **Correcting Multiple Images at a Time**

Select multiple images to correct in the main window. Display tool palette by selecting [View] menu ► [Tool palette]. If you perform correction procedures (p.60) when tool palette is displayed, you can apply the same corrections to all the images selected in the main window.

Also, you can apply same corrections by copying the recipe of the corrected image and pasting it onto the multiple images (p.37).

#### **?** Additional information

#### Some noise appeared in the periphery of an image after correcting [Peripheral illumination]

You can reduce the noise by using luminance and/or chromatic noise reduction of the noise reduction function (p.57). However, if you had applied high amount of [Peripheral illumination] correction to the images that have been shot at night or with a high ISO speed, the noise might not be reduced.

 The image appears with less resolution after correcting [Distortion]

You can make the image similar to the one before correction by applying more sharpness with the sharpness adjusting function (p.29).

 The colors of the image became weaker after correcting [Color blur]

You can make the image similar to the one before correction by adjusting the color tone (p.27) and/or the color saturation (p.89) to make the color deeper.

The result of [Color blur] correction cannot be detected

[Color blur] correction is effective for correcting blue or red color blur which occurs at the edge of the highlighted area of an image. If conditions do not match, correction cannot be made.

- The periphery of the image may be truncated when [Distortion] correction is made.
- For a list of the [Lens aberration correction] window functions, refer to p.114.

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



# **Performing Automatic Dust Erasure Processing**

The Dust Delete Data that is appended to images shot with the camera that can attach this data, can be used to automatically erase dust spots.

# **Compatible Cameras**

EOS-1Ds Mark III	EOS-1D Mark III	EOS 5D Mark II
EOS 50D	EOS 40D	EOS DIGITAL REBEL XSi/450D
EOS DIGITAL REBEL XTi/400D DIGITAL	EOS DIGITAL REBEL XS/1000D	

In the main window, select an image appended with Dust Delete Data.

### Select the [Tools] menu ▶ [Start Stamp tool]. → The copy stamp window appears.

When the image has redrawn itself, click the [Apply Dust Delete Data] button.



→ Dust spots are erased in a single operation.

# Click the [OK] button to return to the main window.

The [ ▲] mark (p.106) is displayed on an image from which dust spots have been erased.

### Additional information

 The dust-erased image can be reverted to its original condition at any time

A dust-erased image is displayed or printed as a dust-erased image. However, since the dust on the image is not actually erased, you can always revert to the original image by clicking the [Undo] button in the copy stamp window or performing the "Re-Editing an Image" procedure (p.39).

### Check dust erasure in the copy stamp window

Check dust erasure in the copy stamp window. Images before dust erasure are displayed in other windows and you will be unable to check them.

Printing dust-erased images

You can print as a dust-erased image by printing it in DPP.

#### • The [Apply Dust Delete Data] button cannot be clicked Even with an image that has Dust Delete Data attached to it in the camera, if there is no dust to remove by DPP from the image, the [Apply Dust Delete Data] button will be disabled.

 To erase dust spots that cannot be erased with the automatic dust erasure processing

In automatic dust erasure processing, dust spots are erased based on information relating to dust saved in the Dust Delete Data. However, there may be cases where you will not be able to erase dust spots depending on the type of dust. If this occurs, erase those dust spots using the repair function (p.64) or the copy stamp function (p.66).

### The image becomes a dust-erased image when converted and saved

The dust-erased RAW image actually becomes a dust-erased image when converted to a JPEG or TIFF image and saved (p.38).

Advanced Operation

Introduction

Contents at a Glance

Basic Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



### Useful functions of the copy stamp window

#### Checking the dust erased spots

After step 3, you can display and check in detail the erased dust spots one by one by pressing the  $\langle F \rangle$  key. (Press the  $\langle B \rangle$  key to return to the previous dust spot.)

### Canceling a specified erased dust spot only

After step 3, you can press the  $\langle F \rangle$  key or the  $\langle B \rangle$  key to display the erased dust spot, and then press the  $\langle delete \rangle$  key to cancel only the erased dust spot displayed.

 Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the  $< \Re > + <$ F11> keys.

### Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

For a list of the copy stamp window functions, refer to p.115.

# Automatic Dust Erasure Processing in the Main Window

In the main window, you can also automatically erase dust spots in multiple images appended with Dust Delete Data.

# Select multiple images appended with Dust Delete Data, and then select the [Adjustment] menu ▶ [Apply Dust Delete Data].

Dust spots in all the selected images are erased in a single operation.



# Manually Erasing Dust (Repair Function)

You can erase dust spots in an image by selecting them one by one.

- In the main window, select the image you want to erase dust spots.
- Select the [Tools] menu ▶ [Start Stamp tool]. → The copy stamp window appears.
- When the image has redrawn itself, double-click the point from where dust is to be erased.



- → The display changes to 100% view.
- The display position can be changed by dragging.

# Click the button that matches the dust spot to be erased.

- When you move the cursor over the image, the dust erasure range appears as [O].

Place the dust spot to be erased within the [O] and click.



- $\rightarrow$  The dust spot within the [O] is erased.
- Click on another part of the image to continue erasing dust spots in the image.
- To erase dust in another part of the image, click the button clicked in step 4 again to cancel dust erasure processing and perform the operation again from step 3.
- When the dust spot cannot be erased, [S] is displayed.

### Click the [OK] button to return to the main window.

The [ ] mark (p.106) is displayed on an image from which dust spots have been erased.

and	Introduction
	Contents at a Glance
ick	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
t spots	Processing Large Numbers of Images
n and	Editing JPEG/TIFF Images
<b>low.</b> ch dust	Reference
	Index

#### Introduction

Contents at

a Glance

### Additional information

- Click several times when dust spots are not erased completely Where unwanted dust spots are not erased even after performing step 5 once, they may be erased completely when you click several times.
- Mainly spots of dust can be erased with the repair function Spots of dust can be erased with the repair function. You may be unable to erase lines of dust. In this case, use the copy stamp function (p.66).
- The dust-erased image can be reverted to its original condition at any time

A dust-erased image is displayed or printed as a dust-erased image. However, since the dust on the image is not actually erased, you can always revert to the original image by clicking the [Undo] button in the copy stamp window or performing the "Re-Editing an Image" procedure (p.39).

#### Check dust erasure in the copy stamp window

Check dust erasure in the copy stamp window. Images before dust erasure are displayed in other windows and you will be unable to check them.

#### Printing dust-erased images

You can print as a dust-erased image by printing it in DPP.

 The image becomes a dust-erased image when converted and saved

The dust-erased RAW image actually becomes a dust-erased image when converted to a JPEG or TIFF image and saved (p.38).

E Useful functions of the copy stamp window

#### Checking the dust erased spots

After step 3, you can display and check in detail the erased dust spots one by one by pressing the <F> key. (Press the <B> key to return to the previous dust spot.)

#### Canceling a specified erased dust spot only

After step 3, you can press the  $\langle F \rangle$  key or the  $\langle B \rangle$  key to display the erased dust spot, and then press the  $\langle delete \rangle$  key to cancel only the erased dust spot displayed.

 Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the  $< \Re > + < F11 > keys$ .

#### Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

For a list of the copy stamp window functions, refer to p.115.



# Erasing Unwanted Parts of an Image (Copy Stamp Function)

You can correct an image by pasting a section copied from another part of the image to an unwanted part of the image.

# Follow steps 1 to 3 in "Manually Erasing Dust (Repair Function)" (p.64).

### Specify the section to be copied.

- Click on the section that is to be the copy source while holding down the <option> key.
- To change the section that is to be the copy source, perform the operation above again.
- To fix the position of the copy source, checkmark [Fix Copy Source position].

### Correct the image.

- Click or drag on the section you want to correct on the image. [+] in the window indicates the copy source and [O] indicates the copy destination.
- The copied image is pasted in the position to which it was dragged.
- For [Pen type], you can select from [Brush] (the pasted image's borders simulate a brush) and [Pencil] (the pasted image's borders are sharp).

## Click the [OK] button to return to the main window.

 $\rightarrow$  The [ ] mark (p.106) is displayed on a corrected image.

# Transferring a RAW Image to Photoshop

A RAW image can be converted to a TIFF image (16bit) and transferred to Photoshop.

# Select the [Tools] menu ▶ [Transfer to Photoshop].

→ Photoshop starts up and the transferred image is displayed.

### A single image can be transferred at a time

Only one image can be transferred at a time. To send multiple images at a time, refer to p.82.

- Compatible versions of Photoshop are CS or later.
  - Transferred images are automatically converted to TIFF images (16bit) to which an ICC profile (p.118) is added. The ICC profile contains information about [Preferences] (p.75) or work color space set for each image as described below and the appropriate color information is relayed to Photoshop.
  - When you quit Photoshop, only the original RAW image remains, and the transferred image will disappear. Saving the transferred image as a separate image in Photoshop is highly recommended.

# **Setting Work Color Space**

A different work color space (p.119) from the default settings (p.75) can be set for each image.

# Select the [Adjustment] menu > [Work color space] > color space to be set.

A color space set individually does not change even when the default setting is changed

If you set an image with a color space different to the default setting and then subsequently change the default color space setting (p.75), this default setting will not be applied and the individually set color space will remain.

÷

### The color space of a RAW image can be changed freely as many times as required

Since only the image processing conditions information changes, the color space of a RAW image can be changed at any time.

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



# **Printing with Shooting Information**

You can freely lay out one image on one sheet of paper and print together with titles and shooting information, etc.

- Select one image to be printed.
- Select the [File] menu ▶ [Print with detailed setting].
- Specify the required settings for printing, and then click the [Print] button.



Switches the settings tab sheet



- Print preview
- The image can be moved by dragging.
- Drag the four corners of the image to change the size.
- For the shooting information, click [1] on the [Text] tab sheet and select the necessary items in the window that is displayed.

# **Printing a Thumbnail List (Contact Sheet Printing)**

You can print rows of multiple images on one sheet of paper.

- Select images to be printed in a thumbnail list.
- Select the [File] menu ▶ [Contact Sheet Prints].
- Specify the required settings for printing, and then click the [Print] button.



Print preview

Introduction To maintain the settings The settings of each tab sheet in step 3 are memorized when the [Apply] Contents at button is clicked (excluding the contents of the [Text] tab sheet). The a Glance settings can be applied to another image when printing. Basic • You can set printer profiles (p.75). Operation If CMYK simulation has been set, the image is printed in the set colors (p.75). Advanced Operation Advanced Image Editing and **Printing** Processing Large Numbers of Images Editing JPEG/TIFF Images Reference Index



# **Printing RAW Images on a High-End Canon Printer**

# Printing with a High-End Canon Inkjet Printer

For high-end Canon inkjet printers that are compatible with the printing software Easy-PhotoPrint Pro, you can print with DPP by a simple operation that has the following features:

- Simple printing of RAW images
- Printing in faithful colors
- High quality printing using a wide color space of Adobe RGB, etc. and the wide color reproduction range of a high-end Canon inkjet printer

To print with DPP, first install Easy-PhotoPrint Pro version 1.3 or later on your computer.

# Select the [File] menu ▶ [Plug-in printing] ▶ [Print with Easy-PhotoPrint Pro].

→ Easy-PhotoPrint Pro starts up.

Specify the required settings for printing, and then print.

## Additional information

Print up to 1000 images at a time

You can print up to 1000 images selected in DPP at a time. When printing more than 1000 images, divide the printing into several jobs.

- Function set in DPP that is not applied to printing Specified CMYK simulation (p.75) is not applied.
- The printed image's color is not what you expected In the Easy-PhotoPrint Pro window, click the [Color Adjustment] button to display the [Color Management] tab sheet. In the tab sheet, make each of the settings [Enable ICC Profile] for [Color Mode], [Auto] for [Printer Profile], and [Perceptual] (p.119) for [Rendering Intent] and print.
  - Advantages of printing with Easy-PhotoPrint Pro

### Printing with faithful colors

When a color space is set (p.66, p.75), it is automatically transmitted from DPP to Easy-PhotoPrint Pro, allowing you to print with faithful colors.

### Printing with a wide color reproduction

When the color space setting (p.66, p.75) is set to a color space wider than sRGB (such as Adobe RGB), the image is printed with a wider color gamut than an image that has an sRGB color space, with green and blue in particular being reproduced vividly.

	Introduction
n obs.	Contents at a Glance
	Basic Operation
eet,	Advanced Operation
	Advanced Image Editing and Printing
tted ul	Processing Large Numbers of Images
ider Ier	Editing JPEG/TIFF Images
een	Reference
	Index

# **Printing with a Large-Format Canon Printer**

You can use DPP to print with the DPP-compatible Canon large-format imagePROGRAF printer. To print with DPP, first install imagePROGRAF Print Plug-In for Digital Photo Professional on your computer.

# Select the [File] menu ▶ [Plug-in printing] ▶ Plug-In for the printer you use.

→ The Plug-In starts up.

Specify the required settings for photograph printing, and then print.

### Additional information

A single image can be printed at a time

You can print a single image selected in DPP at a time. When printing multiple images, perform printing for each image individually.

• Functions set in DPP that are not applied to printing Specified output resolution (p.71) and CMYK simulation (p.75) are not applied. Advantages of printing with imagePROGRAF Print Plug-In

#### Printing with faithful colors

When a color space is set (p.66, p.75), it is automatically transmitted from DPP to the Plug-In, allowing you to print with faithful colors.

#### Printing with a wide color reproduction

When the color space setting (p.66, p.75) is set to a color space wider than sRGB (such as Adobe RGB), the color reproduction range of the imagePROGRAF printer is fully utilized and the image is printed with a wider color gamut than an image that has an sRGB color space, with green and blue in particular being reproduced vividly.



Introduction

# **Specifying Preferences**

You can change the various functions of DPP in the Preferences window. Check the contents of each window and set.

Also, depending on the item, a detailed explanation may be available, so refer to each window.

### Select the [Digital Photo Professional] menu ▶ [Preferences].

→ The [Preferences] window appears.

# Select the tab sheet, specify the settings, and then click the [OK] button.

Preferences			
General settings	View settings	Tool palette	Color management
Startup folder			
Last displayed folder     Specified folder     Browse     MacOSX/U	sers/canon/Deskto	р	
Save recipe			
• Display message when adding Add to file automatically	g file		
Viewing and saving RAW im	ages		
High quality (recommended)     Uiew images at high speed     High speed	View/save RAW in	mages at high qua	ality salette can be used
JPEG image quality			
<ul> <li>Remove block noise and mos</li> <li>Display thumbnails at high q</li> </ul>			
Default value of output reso	olution		
350 dpi(1-60000)			
At EOS Utility startup			
Edit image window enabled a	t EOS Utility start	ир	
		$\subset$	Cancel

# **General Settings**

You can specify the folder that opens when DPP is started up, image quality of displayed and saved RAW images, etc.

Preferences	
General settings View settings Tool palette Color management	Basic Operation
Startup folder	
Last displayed folder	
○ Specified folder	Advanced
Browse MacOSX/Users/canon/Desktop	Operation
Save recipe	
• Display message when adding file	Advanced
O Add to file automatically	Image Editing and Printing
Viewing and saving RAW images	and Printing
• High quality (recommended)	
View images at high speed (moiré reduction off)	Processing
C High speed View/save RAW images at high quality Moiré is reduced and the NR tool palette can be used	Large Numbers of Images
JPEG image quality	
Remove block noise and mosquito noise	
Display thumbnails at high quality	Editing JPEG/TIFF
Default value of output resolution	Images
350 dpi(1-60000)	
At EOS Utility startup	
Edit image window enabled at EOS Utility startup	Reference
Cancel OK	

Index

Introduction

Contents at

a Glance
#### • Viewing and saving RAW images

You can select from two types of image quality for displaying/saving RAW images: high image quality with false color reduction processing and noise reduction function (p.57) used, or high speed without false color processing and noise reduction function used.

#### [High quality]

- False color reduction processing is automatically applied, and the image can be displayed/saved as a false color reduced-high quality image. Furthermore, you can use the noise reduction function (p.57) to reduce the luminance noise and chrominance noise.
- Because the effects of the false color reduction processing and noise reduction function are difficult to see in the [50% view] or [Fit to window] display of the edit window and edit image window, use [100% view] or [200% view] to check.
- We recommend that you normally set [High quality] for a balance between image quality and display speed.

#### [View images at high speed (moiré reduction off)] of [High quality]

- If you checkmark [View images at high speed (moiré reduction off)], when the image is displayed in the edit window or the edit image window, false color reduction processing is not applied.
- As the [View images at high speed (moiré reduction off)] setting is the same as [High quality] other than for display of the image, the image undergoes false color reduction processing when it is saved and the noise reduction function is also available.

#### [High speed]

- Since false color reduction processing is not applied, the display speed of a RAW image in the edit window or the edit image window in the [100% view] or [200% view] enlargement display, and the time it takes to save a RAW image is less than in [High quality].
- You cannot use the noise reduction function (p.57).
- Depending on the image, it may be displayed/saved with false color or noise being noticeable.

## What is the difference between the [High quality] and [High speed] displays?

The display image quality of [High quality] and [High speed] is the same except when the image is displayed in the [100% view] or [200% view] enlargement display in the edit window or the edit image window.

## JPEG image quality

#### [Remove block noise and mosquito noise]

 You can improve the quality of a JPEG image by reducing the noise that is likely to occur when RAW images are converted to JPEG images and saved (p.38, p.81).

This setting is also effective for JPEG images that have been saved with a different name.

#### [Display thumbnails at high quality]

 You can have the thumbnails for JPEG images automatically displayed at high quality. If you checkmark [Display thumbnails at high quality], all subsequent JPEG image thumbnails imported into DPP will be displayed at high quality.

#### The extent of the improvement in noise reduction

The higher the JPEG image's compression rate, the more noise is reduced. When the compression rate is low, the effect of noise reduction is negligible.

### Default value of output resolution

You can set the resolution for RAW images converted and saved as JPEG or TIFF images (p.38, p.81).

Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index

## **View Settings**

You can specify settings relating to the display.

Gener	al settings	View settings	Tool palette	Color management
Grid pitch				
64 Pixels(8-2)	56)			
Locking selected	image			
🗹 Images opened i	n Edit windov	v remain selected	in main window	/
Magnification in	Edit windo	N		
• Fit to window	○ 50%	0	) 100%	○ 200%
Magnification wh	ien the Edit	/Edit image wi	ndow is doub	le-clicked
○ 50%	• 1009	6 C	200%	
RAW and JPEG				
Display only CR2	images for C	R2 and JPEG files	of the same na	me
Sort order in mai	in window			
Retain sort order				
Highlight/shadov	w warning			
Highlight	192	(192-255)		
Shadow	0	(0-64)		
Jacow	0	(0 04)		
Quick check tool	display			
		~	eduction off)	

#### Sort order in main window

You can set the order of images which have been rearranged in the main window to be maintained or not maintained (p.19).

If you checkmark the checkbox, the order of the rearranged images is maintained even if you quit DPP or select another folder in the folder area.

If you remove the check mark, the order of the rearranged images is not maintained and reverts to the previous order when you quit DPP or select another folder in the folder area.

#### Highlight/shadow warning

Highlighted/shaded areas that exceed the set range can be displayed on the image as warning indicators (p.51).



## **Tool Palette**

You can specify settings for the tool palette.

	Prefer	ences	
General settings	View settings	Tool palette	Color management
Default settings of RGB Tone	e curve mode	(	
Tone curve mode	Interpolation	method	Histogram
🖲 RGB R G B	• Curve		Before adjustment
C Luminance R G B	O Straight		<ul> <li>After adjustment</li> </ul>
Fool palette display in Edit II	mage Window		
Docking display			
Floating display			
Addified Picture Style setting	gs		
Retain settings of each Picture			
ool palette display mode			
Same for Main window and Edi	t window		
- Default noise reduction setti	ings		
	ings	······	
Apply camera settings			
) Set as defaults			
RAW luminance noise reduction:	((	» 🗢 🚽	
RAW chrominance noise reduction		) <del>(</del>	
		S - Mehndunii	n de la calcale de la calcale
TIFF/JPEG luminance noise reduction	n: ((	o)	
TIFF/JPEG chrominance noise reduct	tion: ((	0) 🖯	
			Cancel OK
		6	

#### Default settings of RGB Tone curve mode

You cannot apply changes to the settings until you re-open the folder.

#### Changes are not applied to the edited image

Even if the default setting is changed, the new default setting is not applied to edited (i.e., adjusted using the tool palette, trimmed, dusterased) images. Change each one individually.

### Modified Picture Style settings

You can select whether the [Color tone], [Color saturation], [Contrast] and [Sharpness] settings will be changed or retained, when you change the Picture Style.

- If you checkmark the checkbox, the [Color tone], [Color saturation], [Contrast] and [Sharpness] settings will be changed to match the camera's preset settings, when you change the Picture Style.
- If you remove the check mark, the [Color tone], [Color saturation], [Contrast] and [Sharpness] settings will be retained, even if you change the Picture Style.

#### Default noise reduction settings

You can set a default beforehand for the noise reduction level. RAW Images

- When [Apply camera settings] is selected, you can pre-set a noise reduction level that suits the camera settings beforehand as the default.
- When [Set as defaults] is selected, you can pre-set a preferred default setting for the noise reduction level beforehand.
   JPEG/TIFF Images

• You can set a desired default noise reduction level beforehand. For images not having a recipe attached, the default set here for noise reduction level is applied. However, if you want to apply settings to images in the opened folder, you need to re-open the folder after making settings here. For images with a recipe attached, the noise level recorded in the recipe remains as it is and the default for noise reduction level set here is not applied.

#### C Advantages of setting a noise reduction default

In instances where the same level of noise occurs in several images, such as images shot with high ISO speed, setting an appropriate default noise reduction setting enables you to apply a batch noise reduction default to all the images displayed in DPP (excluding images with a recipe attached). This eliminates the need to apply noise reduction to each individual image. And, since you always shoot with the same conditions, it is also useful when you want to set the same noise reduction level for all shot images. Basic Operation Advanced Operation

Introduction

Contents at

a Glance

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



## **Color Management**

You can specify settings relating to color management, such as settings for work color space, conditions for color matching, etc.

	Prefe	rences	
General settings	View settings	Tool palette	Color management
Default settings of Work co	lor space		
• sRGB Adobe RGB			
Wide Gamut RGB			
Apple RGB			
ColorMatch RGB			
-			
CMM settings for print			
or display :			
🖲 sRGB			
O Monitor profile			
	y/ColorSync/Profil	es/Displays/Acer	AL1922-1CAB49B4.icc
	y/ColorSync/Profil		AL1922-1CAB49B4.icc ering intents:
Browse ENG/Librar	y/ColorSync/Profil		
Browse ENG/Librar	y/ColorSync/Profil	Rend	ering intents:
Browse ENG/Librar	y/ColorSync/Profil	Rend	ering intents: ) Perceptual
Browse ENG/Librar Printing profile: None	y/ColorSync/Profil	Rend	ering intents: ) Perceptual ) Relative Colorimetric
Browse ENG/Librar Printing profile: None CMYK simulation profile:	y/ColorSync/Profil	Rend	ering intents: ) Perceptual ) Relative Colorimetric ering intents:
Browse ENG/Librar Printing profile: None CMYK simulation profile: None		Rend	ering intents: ) Perceptual • Relative Colorimetric ering intents: ) Perceptual
Browse ENG/Librar Printing profile: None CMYK simulation profile: None		Rend	ering intents: ) Perceptual • Relative Colorimetric ering intents: ) Perceptual
Browse ENG/Librar Printing profile: None CMYK simulation profile: None Rendering intents when usi		Rend	ering intents: ) Perceptual • Relative Colorimetric ering intents: ) Perceptual
Browse ENG/Librar Printing profile: None CMYK simulation profile: None Rendering intents when usi Perceptual		Rend	ering intents: ) Perceptual • Relative Colorimetric ering intents: ) Perceptual

#### Default settings of Work color space

You can select from five types of color space (p.119) that is applied as a default setting in RAW images. Color space that has been set is applied as the color space when a RAW image is converted and saved (p.38, p.81) or printed (p.39, p.42, p.44, p.67 to p.70).

- If you have changed the setting, and you restart DPP, the new setting is applied as the default setting color space.
- You can check color space that has been set in an image in the edit window (p.107) and the edit image window (p.111).

#### Changes are not applied to the edited image

Even if the default setting is changed, the new default setting is not applied to edited (i.e., adjusted using the tool palette, trimmed, dusterased) images. Change each one individually.

You can set a color space that is different from the default settings for each image (p.66).

#### Display setting (color setting of the monitor)

Where a profile (p.118) is attached to the monitor you are using, you can display an image in more faithful colors by setting the profile.

 Select the [Monitor profile], click the [Browse] button and in the dialog box that appears, select a profile for your monitor.



#### Precise coloring with a third-party monitor color reader

If you use a profile created using a third-party monitor color reader, images can be displayed in even more precise colors.

	Operation
_	
	Advanced Operation

Introduction

Contents at

a Glance

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



### Setting of printing profile (color setting of the printer)

Where a profile (p.118) is attached to the printer you are using to print images, you can print an image and simulate the colors displayed on screen by setting the profile. The profile that has been set is applied to all printing (p.44, p.67, p.68) except for printing using a Canon inkjet printer (p.39, p.42) or linked printing (p.69, p.70).

## **?** The adjustment function of the printer driver should not be used

Even if you set a printer profile, if you use the color adjustment function of the printer driver, the image may print in colors different from those displayed on screen.

#### Automatic settings for printing using EPP EX, EPP, and linked printing

If you are printing using a Canon inkjet printer (p.39, p.42) or using linked printing (p.69, p.70), a profile is set automatically even when the [Printing profile] setting is not performed. This allows you to print faithful colors easily.

### Setting of CMYK simulation profile

You can select the color when printing in the CMYK environment of a printing machine, etc. from four types of profiles (p.119) and perform simulation on screen.

- When CMYK simulation has been set, [CMYK] appears (p.104, p.105, p.107, p.111) in the bottom of the main window, edit window and edit image window, and colors can be checked.
- To temporarily cancel CMYK simulation, press the <space> key.

### Rendering intents when using Easy-PhotoPrint

You can set a rendering intent (matching method) (p.119) for printing using Easy-PhotoPrint (p.42).

- The rendering intent is ordinarily set to [Relative Colorimetric].
- When colors with [Relative Colorimetric] are not satisfactory, set to [Perceptual].



## **4** Useful Functions for Processing Large Numbers of RAW Images



For users shooting a large amount of RAW images, the convenient function of batch processing large amounts of RAW images is explained here.

Utilizing Adjustment Contents (Recipe)
Loading and Pasting Recipes
Copying a Recipe and Applying to Another Image 79
Batch Apply White Balance to Images (Personal White
Balance)
Registering Personal White Balance
Applying Personal White Balance
Batch Save as JPEG or TIFF Images (Batch
Processing)81
Batch Transfer Images to Image Editing Software 82
Batch Change the File Name of Images
Changing the File Name of Images in the Order in the
Main Window83

	Introduction
b	Contents at a Glance
8 9 9	Basic Operation
9 9	Advanced Operation
0 0 0	Advanced Image Editing and Printing
1	Processing Large Numbers of Images
2 3	Editing JPEG/TIFF Images
3	Reference
	Index

## **Utilizing Adjustment Contents (Recipe)**

All the adjustment contents (recipe) made using the tool palette can be saved as an individual recipe file (extension ".vrd") and loaded and applied to another image.

You can edit images efficiently by selecting and adjusting one image from images shot with the same shooting environment and batch applying the adjustment results to a large number of images.





Contents adjusted using the tool palette can be handled individually as a recicpe file (extension ".vrd"). Additional information

#### Recipe data includes tool palette contents

Recipe data includes adjustments made with the tool palette ([RAW], [RGB] and [NR/Lens/ALO]). For this reason, other editing content such as trimming or dust-erasure (copy stamp) is not included in the recipe data.

 Recipes adjusted with the [RAW] tool palette can only be applied to RAW images

Adjustments in the [RAW] tool palette, which can only be made for RAW images, are not applied to a JPEG or TIFF image even if they are pasted.



Introduction

Reference

Index



The adjustment contents of JPEG or TIFF images (p.85) can be saved as a recipe file (extension ".vrd") and loaded and applied to another image in the same way as with RAW images.

## Saving Recipes as a File

- Select an edited image, and then select the [Edit] menu ▶ [Save recipe in file].
- → The [Save] dialog box appears.
- Select the destination folder, enter a file name, and then click the [Save] button.

#### **?** Check the contents of a recipe file by pasting to an image

When you do not know the contents of a recipe file, paste it to an image and check the settings in the tool palette. When only a few settings are adjusted, we recommend you use a file name that describes the contents or that you separately record the adjustments as text information.

## **Loading and Pasting Recipes**

- Select the image to which a recipe is to be applied, and then select the [Edit] menu ▶ [Read and paste recipe from file].
  - → The [Open] dialog box appears.
- Select a recipe and click the [Open] button.
- $\rightarrow$  The recipe is applied to the image.

## Copying a Recipe and Applying to Another Image

You can copy a recipe of an edited image and then apply it to another image.

- Select the image from which a recipe is to be copied and then select the [Edit] menu ▶ [Copy recipe to clipboard].
  - → The recipe is copied.
- Select the image to which the recipe is to be applied and then select the [Edit] menu ▶ [Paste recipe to selected image].
  - → The recipe is applied to the image.



## **Batch Apply White Balance to Images (Personal White Balance)**

The white balance adjustments made to a RAW image shot in a specific shooting environment can be registered as personal white balance. You can then perform efficient white balance adjustment by applying this personal white balance to a large number of RAW images shot in the same shooting environment.

## **Registering Personal White Balance**

- Adjust the white balance (p.25, p.26, p.52).
- To adjust white balance, select a setting other than [Shot settings] from the [White balance adjustment] list box (p.25). You will be unable to register the adjustments if you select [Shot settings].

## In the [RAW] tool palette, click the [Register] button.

- → The [Register personal white balance] dialog box appears.
- Select the button number to be registered from the list and click the [OK] button.



## **Applying Personal White Balance**

- In the main window, select the image to which white balance is to be applied.
- Click the [Tools] button on the toolbar. → The tool palette appears.
- Click the personal white balance number button tha is to be applied.



te	Contents at a Glance
at	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

Introduction

→ Personal white balance is applied to all the selected images.

## **Batch Save as JPEG or TIFF Images (Batch Processing)**

You can batch convert and save edited RAW images to highly versatile JPEG or TIFF images.

The images are saved as separate images, so the RAW images remain unaffected.

In the main window, select multiple images to be converted.

# Click the [Batch process] button on the toolbar (p.104).

→ The [Batch settings] window appears.

Specify the required settings, and then click	the
[Execute] button.	

	Batch settings
IMG_0001.CR2	Save folder
IMG_0002.CR2	MacOSX/Users/canon/Documents Browse
IMG_0003.CR2	File format
IMG_0004.CR2	
IMG_0005.CR2	Kind of file Exif-JPEG
IMG_0006.CR2 IMG_0007.CR2	Image quality
IMG_0007.CR2 IMG_0008.CR2	Output setting
IMG_0009.CR2 IMG_0010.CR2	Output resolution 350 dpi 🗹 Embed ICC profile
IMG_0011.CR2	Resize setting
IMG_0012.CR2 IMG_0013.CR2	Resize Width Height Unit
IMG_0014.CR2	3456 x 2304 pixel +
IMG_0015.CR2	(3456 pixel) (2304 pixel)
	☐ Lock aspect ratio
	File name
	Current file name String
	• New file name
	String Sequence number
	DPP_ 0001 Save sequence number
	Ex.: DPP_0001.JPG, DPP_0002.JPG
	Image transfer settings
	Open image using software
	Browse
	Convert RAW images only Cancel

- → The processing dialog box appears and saving begins.
- When all the images are saved, the [Terminate] button appears in the processing dialog box.



[Save] cannot be performed



#### $\dot{F}$ To save the developing/editing results for the version you are currently using

DPP's RAW image development processing technology is continually being improved upon so that you can perform the latest image processing more appropriately.

Meaning that, between two differing versions of DPP, processing results may differ very slightly even if with the same RAW image data, or the results of significant editing of RAW image data with an attached recipe may be different.

When you want to save the developing or editing results of the version you are currently using as it is, it is recommended that you convert and save images as JPEG image or TIFF images.

## Skillful batch saving

 While saving is being performed, you can continue working in another window

Since the saving function operates independently in the background, you can continue with an operation in another window such as the main window or the edit window during the saving process.

 To convert all images and save, do not select an image in the main window

If you do not perform step 1 and perform step 2 with no image selected in the main window, all the images displayed in the main window will be converted and saved.

- If you have selected [New file name] in [File name], [Sequence number] has to be set.
  - By saving as explained on this page, a trimmed image (p.35, p.93) or dust-erased image (p.62 to p.66, p.95 to p.99) actually becomes a trimmed image or dust-erased image.
  - For a list of [Batch settings] window functions, refer to p.116.

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



## **Batch Transfer Images to Image Editing Software**

You can transfer multiple images to image editing software. Unlike [Transferring a RAW Image to Photoshop] (p.66), you transfer images that have first been converted and saved as a seperate image, so the transferred image will not disappear after quitting the destination software. The software used here as an example is Adobe Photoshop CS.

- In the main window, select multiple images to be transferred.
- Click the [Batch process] button on the toolbar (p.104).
  - → The [Batch settings] window appears.

Click the [Browse] button.

Perform settings required for transferring (e.g. file format).

	Batch settings Save folder		
IMG_0001.CR2			
IMG_0002.CR2	MacOSX/Users/canon/Documents Browse		
IMG_0003.CR2	File format		
IMG_0004.CR2			
IMG_0005.CR2	Kind of file Exif-JPEG		
IMG_0006.CR2	Image quality		
IMG_0007.CR2			
IMG_0008.CR2	Output setting		
IMG_0009.CR2 IMG_0010.CR2	Output resolution 350 dpi 🗹 Embed ICC profile		
IMG_0011.CR2	Resize setting		
IMG_0012.CR2	Resize		
IMG_0013.CR2	Width Height Unit		
IMG_0014.CR2	3456 x 2304 (pixel \$		
IMG_0015.CR2	(3456 pixel) (2304 pixel) √ Lock aspect ratio		
	File Name		
	Current file name String		
	New file name     String Sequence number		
	DPP_ 0001 Save sequence number		
	Ex.: DPP_0001.JPG, DPP_0002.JPG		
	Image transfer settings		
	✓ Open image using software          Browse		
	Cancel		

→ The [Open] dialog box appears.

## Select Photoshop CS.

- In the [Open] dialog box, select a Photoshop CS file or an alias and click the [Open] button.
- The [Open] dialog box closes and [Image transfer settings] in the [Batch settings] window is set to Photoshop CS.

## Checkmark [Open image using software].

Open image using software	
Adobe Photoshop CS	Browse

### Click the [Execute] button.

- → The processing dialog box appears and batch transfer begins.
- → When the first image has been transferred, Photoshop CS starts up and transferred images are displayed in transferred order.



## **Batch Change the File Name of Images**

In the main window, select multiple images of which the file names are to be changed.

Select the [Tools] menu ▶ [Start Rename tool]. → The rename window appears.

Specify the required settings (p.117) and click the [Execute] button.

	MacOSX/Users/ca	non/Pictures/Photo/xxxx_xx_xx		
File Name		Extension		
DPP	Shooting Date/Tir	ne 💽 Sequence number 💽 Do not change 💽		
Basic Settings		Format settings		
Sort		Sequence number		
💽 Fit to mai	n window	0001 Save sequence number		
O File Name				
O Shooting	Date/Time	Shooting Date/Time		
Same file name for RAW+JPEG images		Month Day Year		
Copy & Ren	ame Browse	MM-DD-YY		
MacOSX/Users/	anon/Desktop	🗹 Insert underbar		
Original File		Modified File Name		
MG_0001.CR2		DPP_09-13-06_0001.CR2		
MG_0001.JPG		DPP_09-13-06_0002.JPG		
MG_0002.CR2		DPP_09-13-06_0003.CR2		
MG_0002.JPG		DPP_09-13-06_0004.JPG		
-		555 00 13 0C 0005 CB3		
MG_0003.CR2		DPP_09-13-06_0005.CR2		
MG_0003.CR2 MG_0003.JPG		→ DPP_09-13-06_0006.JPG		
MG_0003.CR2 MG_0003.JPG MG_0004.CR2		→ DPP_09-13-06_0006.JPG DPP_09-12-06_0007.CR2		
MG_0003.CR2 MG_0003.JPG MG_0004.CR2 MG_0004.JPG		→ DPP_09-13-06_0006.JPG		
MG_0003.CR2 MG_0003.JPG MG_0004.CR2 MG_0004.JPG MG_0005.CR2 MG_0005.JPG		→ DPP_09-13-06_0006.JPG DPP_09-12-06_0007.CR2 DPP_09-12-06_0008.JPG		
MG_0003.CR2 MG_0003.JPG MG_0004.CR2 MG_0004.JPG MG_0005.CR2	, ).	→ DPP_09-13-06_0006.JPC DPP_09-12-06_0007.CR2 DPP_09-12-06_0008.JPC DPP_09-13-06_0008.CR2		
MG_0003.CR2 MG_0003.JPG MG_0004.CR2 MG_0004.JPG MG_0005.CR2		→ DPP_09-13-06_0006_JPG DPP_09-12-06_0007_CR2 DPP_09-12-06_0008_JPG DPP_09-13-06_009_CR2 DPP_09-13-06_0010_JPG		

→ Processing begins and the file names are changed.

### **?** Changes cannot be made when the file name is duplicated

If a file name in red text has appeared in [Modified File Name], the file name has been duplicated. Changes cannot be made if even one file name has been duplicated. Change the settings so that duplication does not occur.

- You cannot start up the rename tool from the [Collection] window (p.33, p.105).
  - For a list of the rename window functions, refer to p.117.

## Changing the File Name of Images in the Order in the Main Window

When you change the order of the images in the main window (p.19), you can change in one operation the names of the files for the images, in the order they were rearranged.

- Change the order of the images in the main window (p.19).
- In the main window, select multiple images of which the file names are to be changed.
- Select the [Tools] menu ▶ [Start Rename tool].

## Select [Fit to main window].

	MacOSX
File Name	
DPP	Shooting
Basic Settings	
Sort	
💽 Fit to main window	
O File Name	
Shooting Date/Time	

### Specify the required settings (p.117).

To copy an image, checkmark [Copy & Rename].

## Click the [Execute] button.

The file names are changed and the order in the main window is maintained.

Introduction

Contents at

a Glance

## **5** Editing JPEG and TIFF Images



DPP is software mainly aimed for advanced RAW image editing, but it also has JPEG and TIFF image editing functions. Here, the editing and saving of JPEG and TIFF images are explained.

Editing JPEG and TIFF Images	
About the RGB Tool Palette	
Automatically Adjusting Brightness and Color (Tone	
Curve Assist)	
Adjusting Brightness and Contrast	
Adjusting Color Tone Using Click White Balance 88	
Adjusting Hue, Saturation and Sharpness	
Tone Curve Adjustment90	
Adjusting Dynamic Range91	
Reducing Noise	
Trimming an Image	
Performing Automatic Dust Erasure Processing 95	
Compatible Cameras	
Automatic Dust Erasure Processing in the Main	
Window 96	
Manually Erasing Dust (Repair Function)	
Erasing Unwanted Parts of an Image (Copy Stamp	
Function)	
Saving Editing Results	
Saving Editing Content to an Image	
Saving as a Separate Image 100	
Applying Editing Contents to Another Image 100	
Printing 100	
Re-Editing an Image 100	



## **Editing JPEG and TIFF Images**

With DPP, you can adjust JPEG and TIFF images in the same way as RAW images using the [RGB] and [NR/Lens/ALO] tool palettes. Because adjustment made with the tool palette (recipe) only changes the image processing conditions, the "original image data itself" remains unaffected. Therefore, there are no problems with image deterioration that arise with editing and you can readjust your images any number of times.





In DPP all the adjustments (image processing conditions information) made with the tool palette can be saved in the image as data called a "recipe" (p.99), or can be saved, downloaded and applied to other images as a separate recipe file (extension ".vrd") (p.78, p.100).

## About the RGB Tool Palette

With the functions in the [RGB] tool palette, you can adjust JPEG and TIFF images with the same functions as ordinary image editing software.

However, because the adjustment width of the adjustment functions in the [RGB] tool palette is wider than the [RAW] tool palette, the image color may be saturated, or the image quality may deteriorate if you adjust too much. Therefore, take care not to adjust your images to an excessive degree.

You can adjust RAW images with the functions in the [RGB] tool palette However, for functions other than tone curve adjustment (p.90) and automatic adjustment (p.86), we recommend adjusting RAW images using the same functions available in the [RAW] tool palette.

i	Contents at a Glance
n	
	Basic Operation
te.	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

## Automatically Adjusting Brightness and Color (Tone Curve Assist)

In order to make the image a desirable standard image, automatically adjust the image tone curve (p.118). You can select the degree of automatic adjustment from "Standard" and "High".

### Click the desired automatic adjustment button.

- **Standard:** Standard automatic adjustment. Suitable for most images.
- **High:** Use when the effect achieved in standard automatic adjustment is not strong enough.



→ The tone curve changes as adjusted.

Images not suitable for automatic adjustment (tone curve assist)

The result of automatic adjustment (tone curve assist) may not be as expected with the following images:

- Images which have been shot with the proper exposure
- Images where the brightness is unbalanced
- Images which are too dark
- Images which have extreme backlighting
- If you click the [25] button, the tone curve as well as the [Hue] and [Saturation] revert to the default settings. Take care when adjusting the [Hue] and [Saturation] individually (p.89).

S	Contents at a Glance
	Basic Operation
]	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

## **Adjusting Brightness and Contrast**

The brightness and contrast of an image can be adjusted.



- Brightness: Move the slider to the right to make an image brighter and to the left to make an image darker.
- Contrast:

difference of the left to make an image darker.
 Used to adjust modulation and degree of contrast of color. Move the slider to the right to make contrast of an image stronger and to the left to make contrast weaker.



The adjustment range is –100 to +100 (in 1-stop increments when entering a value).

## Adjusting Color Tone Using Click White Balance

You can adjust white balance using a selected part of an image as the standard for white to make the image appear natural. Using click white balance is effective when using it in parts of an image where white color tone has changed under the influence of a light source.



Click on a point that is to be the standard for white.



The coordinates of the cursor position and the RGB values (8-bit conversion)

- The color of the image is adjusted with the point you selected as the standard for white.
- If you click on another point in the image, the white balance is adjusted again.
- To finish click white balance, click the [7] button again.

#### When there are no white areas in your image

When there are no white areas in your image, you can adjust the white balance by clicking on a grey point of the image in step 2. This has the same adjustment result as selecting a white point.

 The image is adjusted based on the average value of 5 x 5 pixel range from the clicked point.

 The histogram display changes according to adjustment. You can also fix the histogram display to the display before any adjustments (p.74).

Introduction Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editing JPEG/TIFE Images Reference Index

## **Adjusting Hue, Saturation and Sharpness**

You can adjust hue (tone) and saturation and make the overall atmosphere of an image harder or softer.



Drag the sliders left or right

- Hue: Move the slider to the right to make color tones more yellow, and to the left to make color tones redder.
- Saturation: Move the slider to the right to make the color deeper, and to the left to make the color weaker.
- Sharpness: Move the slider to the right to make an image harder, and to the left to make an image softer.

Sharpness is unnatural

sharpness will seem unnatural.

value).

or [200% view]. If the view is set to [Fit to window] (full view), the

and 0 to 500 for sharpness (in 1-stop increments when entering a



## **Tone Curve Adjustment**

You can adjust the brightness, contrast and color of a specific area by changing the tone curve (p.118).

# Select the tone curve mode and interpolation method.



Introduction Make adjustments. Batch adjusts RGB Adjusts each channel Contents at a Glance RAW RCB NR/Lens/ALO Tone curve assist 0 0+ 05 Tone curve adjustment • Basic Operation RGB G R В 255 Advanced Operation Advanced Click to add a  $[\Box]$  (point) **Image Editing** Adjust by dragging [ and Printing Processing Large Numbers of Images 0 255 0 Editing 0 JPEG/TIFF Brightness: Images 0 Contrast: 0 🛟 5 Hue: ...... 100 🛟 5 Saturation: Reference **Q**..... 0 Sharpness: 5 The horizontal axis shows the input level and the vertical axis shows the output level. Index The maximum number of []] is 8. To delete a [□], double-click on the [□]. The histogram display changes according to adjustment. You can also fix the histogram display to the display before any adjustments (p.74). • The tone curve mode and interpolation method for a tone curve can also be changed in [Preferences] (p.74).

## **Adjusting Dynamic Range**

Dynamic range (width of gradation expression) from dark points to bright points in an image can be adjusted.



• The horizontal axis shows the input level and the vertical axis shows the output level.

The setting range of shadow points is 0 to 247 (in 1-stop increments when entering a value).
The setting range of highlight points is 8 to 255 (in 1-stop increments when entering a value).
The histogram display changes according to adjustment. You can also fix the histogram display to the display before any adjustments (p.74).



## **Reducing Noise**

You can reduce noise that arises in JPEG and TIFF images that have been shot at night or with a high ISO speed.

Select the [NR/Lens/ALO] tab sheet from the tool palette in the edit window or edit image window.

## Adjust an image.

RAW RGB NR/Lens/ALO	
Auto Lighting Optimizer	
Low Standard Strong	
NR Apply	
RAW	
Luminance noise 0 20	
Chrominance noise (0) 0 20	
TIFF/JPEG	
Luminance noise 0 0 20	Drag the sliders right
Chrominance noise 0 20	
Lens aberration correction Tune	
Peripheral illumination	
Distortion	
Chromatic aberration	
Color blur	

You can set a noise reduction level from within a range of 0 to 20. The larger the setting, the larger the noise reduction effect.

## Click the [Apply] button.

→ Noise reduction is applied to the image and the image is redisplayed.



Display the image in the [100% view] or [200% view].

display it

Because noise reduction effect is difficult to see in the [50% view] and [Fit to window] displays, use [100% view] or [200% view] to check the noise reduction.

- If [Luminance noise] has been set, resolution may be reduced along with reduction of noise.
  - If [Chrominance noise] has been set, color bleeding may occur along with reduction of noise.
  - You can set the batch processing settings for noise reduction beforehand, using [Default noise reduction settings] in the [Tool palette] tab sheet in Preferences (p.74). This is particularly useful for applying noise reduction to all the images in a folder at once, such as batch noise reduction for images with high ISO speeds. However, where images have a recipe attached, the noise level recorded in the recipe is applied.
  - For a list of tool palette functions, refer to p.109.

JPEG/TIFF Images

Reference

Index

## **Trimming an Image**

You can trim only the part of an image you need, or change the composition of an image where an image shot horizontally becomes vertical.

Also, when aspect ratio information is attached to an image shot with EOS-1Ds Mark III or EOS-1D Mark III, the trimming range based on the aspect ratio information is displayed.

### Select the image to be trimmed.

## Select the [Tools] menu ▶ [Start Trimming tool].

 $\rightarrow$  The trimming window appears.

# When the image has redrawn itself, select a ratio and drag the trimming range.



The trimming range can be moved by dragging.

 You can enlarge or reduce the size of the trimming range by dragging the four corners of the trimming range.

List of aspect ratios (width : height)	
✓ Free	
1:1	Conte
3:2	a Gla
2:3	
4:3	- Day
3:4	Bas Opera
5:4	
4:5	
A Size Landscape	Adva
A Size Portrait	Opera
Letter Landscape	
Letter Portrait	Adva
Custom	Image I and Pr

[Free]: You can trim an image to any size, regardless of the selectable ratio.

[Custom]: You can trim an image at the specified ratio.

## Click the [OK] button to return to the main window.

- → The trimming range frame is displayed in the trimmed image (p.106).
- When the trimmed image is displayed in an edit window or the edit image window, it is displayed in its trimmed form.

Contents at a Glance
Basic Operation
Advanced Operation
Advanced Image Editing and Printing
Processing Large Numbers of Images
Editing JPEG/TIFF Images
Reference
Index
$\bigcirc$

#### About trimmed images

 The trimmed range can be reverted to its original condition at any time

A trimmed image is displayed or printed as a trimmed image. However, since the image is not actually trimmed, you can always revert to the original image by clicking the [Reset] button in the trimming window or performing the "Re-Editing an Image" procedure (p.100).

#### Display of the trimmed image in each window

- Main window: The frame showing the trimming range is displayed on the image (p.106).
- Edit window: The image is displayed in its trimmed condition.
- Edit image window: The thumbnail image is the same as the main window display, and the enlarged image is the same as the edit window display.

#### Printing a trimmed image

You can print as a trimmed image by printing it in DPP.

## The image becomes a trimmed image when saved as a separate image

The trimmed JPEG or TIFF image actually becomes a trimmed image when saved as a separate image (p.100).

## Images that have aspect ratio set will be displayed as trimmed images

When aspect ratio information is attached to an image shot with EOS-1Ds Mark III or EOS-1D Mark III, the set trimming range based on the aspect ratio information is displayed. However, since the image is not actually trimmed, you can change the trimming range or revert to the condition before trimming.

When reverting to the condition before trimming is performed based on the aspect ratio information at the time of shooting, click the [Reset] button. Also, if you want to cancel all the trimming range, click the [Clear] button (p.113). Convenient functions of the trimming window

#### Switch between screens using the keyboard

You can also switch between full screen display/normal screen display by pressing the  $< \Re > + < F11 >$  keys.

#### Operate using the menu

Each operation can also be performed with the menu which appears by clicking on the image while holding down the <control> key.

Apply the trimmed range to another image

You can apply the trimmed range to another image by clicking the [Copy] button to copy the trimmed range, displaying another image and then clicking the [Paste] button.

To batch apply a copied trimming range to multiple images, select the trimmed image and the multiple images to which you want to apply the trimmed range in the main window, and display the trimming window. With the trimmed image displayed, click the [Copy] button and then click the [Apply All] button. This will apply the trimming range to all the images selected when the trimming window is displayed.

## Operation

Advanced Operation

Introduction

Contents at

a Glance

Basic

Advanced Image Editing and Printing

Processing Large Numbers of Images

#### For a list of the trimming window functions, refer to p.113.

Editing JPEG/TIFF Images

Reference

Index



## **Performing Automatic Dust Erasure Processing**

The Dust Delete Data that is appended to images shot with the camera that can attach this data, can be used to automatically erase dust spots.

## **Compatible Cameras**

EOS-1Ds Mark III	EOS-1D Mark III	EOS 5D Mark II
EOS 50D	EOS 40D	EOS DIGITAL REBEL XSi/450D
EOS DIGITAL REBEL XTi/400D DIGITAL	EOS DIGITAL REBEL XS/1000D	

In the main window, select an image appended with Dust Delete Data.

#### Select the [Tools] menu ▶ [Start Stamp tool]. → The copy stamp window appears.

# When the image has redrawn itself, click the [Apply Dust Delete Data] button.



→ Dust spots are erased in a single operation.

### Click the [OK] button to return to the main window.

The dust-erased image can be reverted to its original condition

A dust-erased image is displayed or printed as a dust-erased image.

However, since the dust on the image is not actually erased, you can

always revert to the original image by clicking the [Undo] button in the

Check dust erasure in the copy stamp window. Images before dust

erasure are displayed in other windows and you will be unable to

Even with an image that has Dust Delete Data attached to it in the

camera, if there is no dust to remove by DPP from the image, the

To erase dust spots that cannot be erased with the automatic

In automatic dust erasure processing, dust spots are erased based on information relating to dust saved in the Dust Delete Data. However, there may be cases where you will not be able to erase dust spots depending on the type of dust. If this occurs, erase those dust spots using the repair function (p.97) or the copy stamp function (p.99).
 The image becomes a dust-erased image when saved as a

copy stamp window or performing the "Re-Editing an Image"

You can print as a dust-erased image by printing it in DPP.
The [Apply Dust Delete Data] button cannot be clicked

Check dust erasure in the copy stamp window

[Apply Dust Delete Data] button will be disabled.

**Additional Information** 

at any time

check them.

procedure (p.100).

Printing dust-erased images

dust erasure processing

separate image

The [ ▲] mark (p.106) is displayed on an image from which dust spots have been erased.

## Introduction

Contents at a Glance

Basic Operation

Advanced Operation

#### Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index

The dust-erased JPEG or TIFF image actually becomes a dusterased image when saved as a separate image (p.100).

### Useful functions of the copy stamp window

#### Checking the dust erased spots

After step 3, you can display and check in detail the erased dust spots one by one by pressing the  $\langle F \rangle$  key. (Press the  $\langle B \rangle$  key to return to the previous dust spot.)

#### Canceling a specified erased dust spot only

After step 3, you can press the  $\langle F \rangle$  key or the  $\langle B \rangle$  key to display the erased dust spot, and then press the  $\langle delete \rangle$  key to cancel only the erased dust spot displayed.

 Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the  $< \Re > + <$ F11> keys.

#### Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

For a list of the copy stamp window functions, refer to p.115.

## Automatic Dust Erasure Processing in the Main Window

In the main window, you can also automatically erase dust spots in multiple images appended with Dust Delete Data.

# Select multiple images appended with Dust Delete Data, and then select the [Adjustment] menu ▶ [Apply Dust Delete Data].

Dust spots in all the selected images are erased in a single operation.



## Manually Erasing Dust (Repair Function)

You can erase dust spots in an image by selecting them one by one.

- In the main window, select the image you want to erase dust spots.
- Select the [Tools] menu ▶ [Start Stamp tool]. → The copy stamp window appears.
- When the image has redrawn itself, double-click the point from where dust is to be erased.



- → The display changes to 100% view.
- The display position can be changed by dragging.

# Click the button that matches the dust spots to be erased.

- If the dust spot is dark in color, click the [ ...] button, and if the dust spot is light in color, click the [ ...] button.
- When you move the cursor over the image, the dust erasure range appears as [O].

Place the dust spot to be erased within the  $[\bigcirc]$  and click.



- → The dust spot within the [O] is erased.
- Click on another part of the image to continue erasing dust spots in the image.
- To erase dust in another part of the image, click the button clicked in step 4 again to cancel dust erasure processing and perform the operation again from step 3.
- When the dust spot cannot be erased, [S] is displayed.

### Click the [OK] button to return to the main window.

→ The [ ] mark (p.106) is displayed on an image from which dust spots have been erased.

nd	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
spots	Processing Large Numbers of Images
nd	Editing JPEG/TIFF Images
<b>)W.</b> n dust	Reference
	Index

#### Additional information

- Click several times when dust spots are not erased completely Where unwanted dust spots are not erased even after performing step 5 once, they may be erased completely when you click several times.
- Mainly spots of dust can be erased with the repair function Spots of dust can be erased with the repair function. You may be unable to erase lines of dust. In this case, use the copy stamp function (p.99).
- The dust-erased image can be reverted to its original condition at any time

A dust-erased image is displayed or printed as a dust-erased image. However, since the dust on the image is not actually erased, you can always revert to the original image by clicking the [Undo] button in the copy stamp window or performing the "Re-Editing an Image" procedure (p.100).

#### Check dust erasure in the copy stamp window

Check dust erasure in the copy stamp window. Images before dust erasure are displayed in other windows and you will be unable to check them.

#### Printing dust-erased images

You can print as a dust-erased image by printing it in DPP.

 The image becomes a dust-erased image when saved as a separate image

The dust-erased JPEG or TIFF image actually becomes a dusterased image when saved as a separate image (p.100). Useful functions of the copy stamp window

#### Checking the dust erased spots

After step 3, you can display and check in detail the erased dust spots one by one by pressing the <F> key. (Press the <B> key to return to the previous dust spot.)

#### Canceling a specified erased dust spot only

After step 3, you can press the  $\langle F \rangle$  key or the  $\langle B \rangle$  key to display the erased dust spot, and then press the  $\langle delete \rangle$  key to cancel only the erased dust spot displayed.

 Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the  $< \Re > + < F11 > keys$ .

#### Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

For a list of the copy stamp window functions, refer to p.115.

Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editing JPEG/TIFF Images Reference Index

Introduction

Contents at

a Glance

## Erasing Unwanted Parts of an Image (Copy Stamp Function)

You can correct an image by pasting a section copied from another part of the image to an unwanted part of the image.

### Follow steps 1 to 3 in "Manually Erasing Dust (Repair Function)" (p.97).

#### Specify the section to be copied.

- Click on the section that is to be the copy source while holding down the <option> key.
- To change the section that is to be the copy source, perform the operation above again.
- To fix the position of the copy source, checkmark [Fix Copy Source position].

#### Correct the image.

- Click or drag on the section you want to correct on the image. [+] in the window indicates the copy source and [O] indicates the copy destination.
- The copied image is pasted in the position to which it was dragged.
- For [Pen type], you can select from [Brush] (the pasted image's borders simulate a brush) and [Pencil] (the pasted image's borders are sharp).

### Click the [OK] button to return to the main window.

 $\rightarrow$  The [ ] mark (p.106) is displayed on a corrected image.

## Saving Editing Results

## Saving Editing Content to an Image

Select the [File] menu & desired item

All the contents (recipe) adjusted with the tool palette (p.85 to p.92) as well as the trimmed range (p.93) and dust-erasure (p.95 to p.99) information can be saved to a JPEG or TIFF image, or to a separate JPEG or TIFF image.

	uesire	
ile Open in Edit window Open in Edit window (enlarged) Close all	жо	
Open window	ЖN	
Close window	жw	
Save	жs	
Save As	û₩S	
Add thumbnail to image and save	ûЖТ	
Convert and save	жD	
Batch process	ЖB	
Create new folder	ŵ ЖN	
Page setup	ûжР	
Print	ЖP	
Print with detailed setting	企業D	
Contact Sheet Prints	^ ፝ # P	
Plug-in printing	•	
Add to collection	ЖG	
Remove from collection	ŵжG	
Delete	¥⊗	
Info	жı	

→ Your adjustments are saved to the image.

a Glance
Basic
Operation
Advanced
Operation
Advanced
Image Editing and Printing
unu i interio
Processing
Large Numbers
of Images
Editing JPEG/TIFF
Images

Index

ence



## Saving as a Separate Image

If a JPEG or TIFF image is adjusted with the tool palette (p.85 to p.92) and then saved in the same way as a RAW image as described below, the image can be saved as a separate image with the adjustments (recipe) applied to it.

Furthermore, if a trimmed image (p.93) or dust-erased image (p.95 to p.99) is also saved in the same way, it actually becomes a trimmed or dust-erased image.

- Saving as a JPEG or TIFF Image (p.38)
- Batch save as JPEG or TIFF images (batch processing) (p.81)

By saving as a separate JPEG or TIFF image as explained above, the adjustments made with the tool palette are applied, and some image deterioration that accompanies editing/saving occurs as when editing with ordinary image editing software.

## Applying Editing Contents to Another Image

You can copy the adjustment contents (recipe) of JPEG and TIFF images that have been adjusted with the tool palette and apply them to another image with the procedures below, in the same way as with RAW images.

- Applying adjustment contents to another image (p.37)
- Utilizing adjustment contents (recipe) (p.78)

## Printing

Edited JPEG and TIFF images can be printed with the procedures below as with RAW images.

- Printing (p.39)
- Printing with shooting information (p.67)
- Printing a thumbnail list (contact sheet printing) (p.68)
- Printing RAW images on a high-end Canon printer (p.69)

## **Re-Editing an Image**

Only the image processing conditions are changed in images adjusted with the tool palette (p.85 to p.92), so the "original image data itself" remains unaffected. Also, the trimming range or dust-erasure information of a trimmed image (p.93) or dust-erased image (p.95 to p.99) is simply saved to the image.

For this reason, you can undo any adjustments saved (p.99) to the image, trimming range and dust-erasure information, and revert to the condition when last saved, or when the image was shot.

#### Operation Select the image that is to be re-edited. Advanced Operation Select the [Adjustment] menu > desired item. Adjustment Advanced Rotate Left ℋL Image Editing and Printing ₩R **Rotate Right** Add check mark1 ₩F1 Processing Add check mark2 ₩F2 Large Numbers Add check mark3 ₩F3 of Images Clear check mark ₩F4 Editing Apply Dust Delete Data JPEG/TIFF Images Work color space ► Tone curve assist - Standard Tone curve assist - High Reference Revert to last saved settings ~₩Z Revert to shot settings ^%Z → The image reverts to the conditions of the selected item. Index



Introduction

Contents at

a Glance

Basic

## Reference



This reference section has been provided to enhance your experience using DPP.

It contains various troubleshooting solutions, how to delete DPP from your computer, explanations of the various windows and a glossary. An Index is provided at the end of the chapter for you to easily find information you are looking for.

Troubleshooting
Deleting the Software (Uninstalling) 103
List of Main Window (Folder Window) Functions 104
List of Main Window (Collection Window) Functions 105
Image Frame Information in the Main Window and Edit
Image Window 106
List of Edit Window Functions 107
List of Tool Palette Functions 108
List of Quick Check Window Functions 110
List of Edit Image Window Functions 111
List of Convert/Save One Image Window Functions 112
List of Trimming Window Functions 113
List of Lens Aberration Correction Window Functions 114
List of Copy Stamp Window Functions 115
List of Convert/Save Multiple Images Window (Batch
Processing) Functions 116
List of Rename Window Functions 117
Glossary 118
Index 120
About This Instruction Manual 124
Trademark Acknowledgments 124





## Troubleshooting

If DPP is not operating correctly, refer to the items below.

#### Installation could not be completed correctly

 You cannot install software unless you are logged into an account with Administrator privileges. Log in again into an account with Administrator privileges. For how to log in and how to specify Administrator settings, refer to the User's Manual for the Macintosh computer you are using or for OS.

### **DPP** does not work

- DPP does not operate correctly on a computer if its system requirements does not meet. Use DPP on a computer with compatible system requirements (p.3).
- Even if your computer has the RAM capacity (memory) described in the system requirements (p.3), if other applications are running at the same time as DPP, you may not have sufficient RAM (memory). Quit any applications other than DPP.

### Images do not display properly

- Images that are not supported by DPP do not display. There are various types of JPEG and TIFF images, so JPEG images other than Exif 2.2 and 2.21 compatible images and TIFF images other than Exif compatible images may not display properly (p.3).
- When a dust-erased image (p.62 to p.66, p.95 to p.99) is displayed in a window other than the copy stamp window, it is displayed as it was before dust erasure was performed. Check dust-erased images in the copy stamp window.

### An image could not be adjusted

 The JPEG and TIFF images cannot be adjusted using the image adjustment function of the [RAW] tool palette. Adjust these images with the [RGB] tool palette (p.108).

### A recipe could not be pasted (applied) to another image

- You cannot paste (apply) rotation (p.10, p.23, p.104, p.110, p.111), trimming (p.35, p.93), dust erasure (copy stamp) (p.62 to p.66, p.95 to p.99) of an image to another image as a recipe. Trim the image or erase dust of the image using the copy/paste function in each window and rotate each image individually.
- The adjustment contents (recipe) of RAW images that has been adjusted with the [RAW] tool palette cannot be applied to JPEG or TIFF images (p.108).
- The Auto Lighting Optimizer (p.56) is a function that is only available for RAW images shot with EOS 5D Mark II and EOS 50D. You cannot apply the Auto Lighting Optimizer's adjustment contents to RAW images shot with other cameras.

# Color appears weak in the image when viewed with other software

A RAW image which has a color space other than sRGB set (p.66, p.75) and is then converted and saved as a JPEG or TIFF image will appear weak in color when viewed in software that is only compatible with sRGB color space. In this case, set the RAW image color space to sRGB, convert again to a JPEG or TIFF image and save, and then view this image.

Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editing JPEG/TIFF Images Reference

Introduction

Index



# The colors of the image displayed on screen and the colors of the printed image do not match

- If the color of the monitor that displays an image is not adjusted correctly, or if a profile for a printer that is to print images, has not been set up, the color of the image displayed on screen and the color of the printed photograph may differ greatly. If the color of the monitor that displays images is corrected (p.75) and a profile for a printer is set up correctly (p.75), the color of a printed photograph and the color of an image on screen can be more closely matched. Using a Canon printer (p.39, p.42) or linked printing (p.69, p.70) automatically sets up printer profiles, so you only need to set the color of the monitor to bring the colors closer together.
- When printing using Easy-PhotoPrint and the Easy-PhotoPrint automatic compensation function and the various types of image adjustment functions are operating, colors are not printed correctly. Cancel all Easy-PhotoPrint image adjustment functions (p.43).
- Even if you set a printer profile, if you use the color adjustment function of the printer driver, the image may print in colors different from those displayed on screen. Do not use the color adjustment function of the printer driver.

#### Printing a large number of images in batches cannot be performed

 If a large number of images are printed in batches, printing may stop in the middle or the images may not be printed. Reduce the number of images to print or increase the memory on your computer.

## A file remains in the folder after images are deleted

- Delete [CRW\_YYYY.THM] (camera index display image) if it remains in the folder from which images have been deleted (p.45).
  - \* Numbers are entered for [YYYY] in the file name.

## The image information does not display

 A JPEG image set to Adobe RGB and shot with EOS 10D and EOS DIGITAL REBEL/300D DIGITAL may not display image information (p.10, p.21).

## Deleting the Software (Uninstalling)

Quit any applications before uninstalling the software.

Log into the account used when installation was performed.

- When you have moved the folders and the software to be deleted to the Trash, select the [Finder] menu ▶ [Empty Trash] and empty the Trash. You cannot reinstall the software until you have emptied the Trash.
- Display the folder in which the software is saved.
  Open the [Canon Utilities] folder.



Drag the folder for the software to be uninstalled to the Trash.

### Select [Finder] menu on the desktop ▶ [Empty Trash].

- The software is deleted.
- When uninstallation ends, restart your computer.



You cannot retrieve data that you have emptied into the Trash and deleted, so be particularly careful when deleting data.



\*3 Displays the coordinates of the cursor position and the RGB values (8-bit conversion) when click white balance was performed with the tool palette.

## List of Main Window (Collection Window) Functions (p.33)



displayed in the () in the [Collection] tab sheet. Accordingly, when an image is added that is displayed as a single image (p.20), twice the total number of displayed images is displayed.

## Image Frame Information in the Main Window and Edit Image Window (p.10, p.31)

Information displayed when [Large thumbnail] (p.10) is selected



- <sup>\*1</sup> Does not display with [Small thumbnail].
- \*2 Displays in RAW+JPEG images displayed as a single image (p.20). [RAW] is displayed in RAW images.
- (In [Small thumbnail] (p.10), [R] is displayed.)
- \*3 Does not display with [Medium thumbnail] or [Small thumbnail].
- \*4 Displays in an image edited with the [RAW] tool palette in the edit window and the edit image window.
- \*5 Displays in an image edited with the [RGB] tool palette in the edit window and the edit image window.
- \*6 When aspect ratio information is attached to an image shot with EOS-1Ds Mark III or EOS-1D Mark III, the image is displayed as a trimmed image.

## List of Edit Window Functions (p.11, p.23)

Path and file name of image





- \*1 To switch between show/hide, select the [View] menu ▶ [Tool palette].
   \*2 Displays the coordinates of the cursor position and the RGB values (8bit conversion).
- \*3 RAW images are displayed with [RAW].

\*4 The item selected in [Viewing and saving RAW images] (p.71) of the [Preferences] window is displayed.
# **List of Tool Palette Functions**

### RAW Tool Palette (p.23)





 \* If an image is displayed enlarged, the enlargement display position can be moved by dragging. The enlargement display position appears when [Docking display] (p.74) has been set and the edit image window (p.111) has been enlarged.

### NR/Lens/ALO Tool Palette (When a RAW image is selected)



NR/Lens/ALO Tool Palette

\* If an image is displayed enlarged, the enlargement display position can be moved by dragging. The enlargement display position appears when [Docking display] (p.74) has been set and the edit image window (p.111) has been enlarged.

# List of Quick Check Window Functions (p.16, p.17)



- \*1 You can select 50% view/100% view (moiré reduction off) by selecting [Preferences] in the [Digital Photo Professional] menu and using [Quick check tool display] in the [View settings] tab sheet. You can also move the display position in the enlarged display by dragging the image.
- $^{*2}$  To return to the normal screen, press the <esc> key.

# List of Edit Image Window Functions (p.31, p.33)



\*<sup>5</sup> The item selected in [Viewing and saving RAW images] (p.71) of the

[Preferences] window is displayed.

- \*2 Displays the coordinates of the cursor position and the RGB values (8-bit conversion).
- \*<sup>3</sup> Displays images selected in the main window. The image selected here is enlarged and displayed on the right.

# List of Convert/Save One Image Window Functions (p.38)

		Convert and save		Contents at
		Save As: DPP_001	File name	a Glance
Types of image			——— Save destination	
Type of image	Extension	Where: 📁 Photo		Basic Operation
Exif-JPEG	.JPG	File format		
Exif-TIFF 8bit	.TIF			
TIFF 16bit	.TIF	Kind of file Exif-JPEG		Advanced Operation
Exif-Tiff 8bit+Exif-JPEG	.TIF/.JPG	Image quality 🔨 👘 👘 🖓 10	JPEG compression rate* <sup>3</sup>	oporation
TIFF 16bit+Exif-JPEG	.TIF/.JPG	Output setting	Embeds of ICC profiles*2 (p.118)	
		Output resolution 350 dpi Embed ICC profile		Advanced Image Editing and Printing
Resolution*1				
Size changing*4		Resize setting       Resize       Width     Height       3504     x       2336     pixel		Processing Large Numbers of Images
		(3504 pixel) (2336 pixel) ✓ Lock aspect ratio		Editing JPEG/TIFF Images
		(Cancel) (Save	Save	
			•	Reference

- \*<sup>1</sup> The setting range is 1 to 60,000 dpi.
- \*2 Color space (p.66, p.75) information that is set in an image is attached to an ICC profile.

Even if you remove the check mark from images that have been set to Apple RGB, ColorMatch RGB or Wide Gamut RGB color space (p.66, p.75), the ICC profiles are embedded automatically.

- \*<sup>3</sup> The setting range is 1 to 10. The higher the numerical value, the higher the image quality becomes.
- \*4 The larger of the two values set in [Width] and [Height] is applied to the longer edge of an image and change its size.

Index

# List of Trimming Window Functions (p.35, p.93)



- \*1 If [Free] has been selected in the [Aspect ratio] list box, you can also drag the borders of the trimmed range to change its range.
- \*2 Operates when you have selected multiple images and the trimming window is displayed.



\* The area you clicked on the image (Enlargement display position) is displayed at 200%.

# List of Copy Stamp Window Functions (p.62 to p.66, p.95 to p.99)



Operates when you have selected multiple images and the copy stamp window is displayed.

# List of Convert/Save Multiple Images Window (Batch Processing) Functions (p.81)



- \*<sup>1</sup> The setting range is 1 to 60,000 dpi.
- \*2 Color space (p.66, p.75) information that is set in an image is attached to an ICC profile.
  - Even if you remove the check mark from images that have been set to Apple RGB, ColorMatch RGB or Wide Gamut RGB color space (p.66, p.75), the ICC profiles are embedded automatically.
- \*<sup>3</sup> The setting range is 1 to 10. The higher the numerical value, the higher the image quality becomes.
- \*4 The larger of the two values set in [Width] and [Height] is applied to the longer edge of an image and change its size.
- \*5 Appears when you click the [Batch process] button (p.104, p.111) without an image selected in the main window or the edit image window. To convert RAW images only, instead of clicking the [Execute] button, click this button.

# List of Rename Window Functions (p.83)



# Glossary RAW image

EOS DIGITAL camera RAW images are recorded in an uncompressed 14bit or 12bit format.

Because RAW images are special images in an undeveloped status, you need software with development processing functions such as DPP in order to view them. The advantage of the undeveloped RAW images is that you can make a variety of adjustments to RAW images with almost no deterioration of the image.

\* "RAW" meaning "in a natural condition" or "not processed or refined".

# JPEG image

The most ordinary image in non-reversible compressed 8bit format. The advantage of this is that by saving at a high compression rate, the file size can be small, even for image data that has a high pixel count. Because during saving and compression part of the data is thinned out to make the file size small, every time you edit or save, the image deteriorates.

With DPP, even if you repeat editing/saving, only the recipe data is modified, and no overwriting or compression occurs so the original image data does not deteriorate.

\* JPEG is an abbreviation of "Joint Photographic Experts Group".

### **TIFF** image

Bitmap-format image recorded in a 8bit/16bit uncompressed format. Because TIFF images are in uncompressed format, they are suitable for saving an image while maintaining the original high image quality. \* TIFF is an abbreviation of "Tagged Image File Format".

# Recipe

The "Image processing conditions information" for RAW images that can be edited in DPP is called a "recipe".

Further, in DPP, you can perform image editing on JPEG and TIFF images that use "recipes" as with RAW images.

### bit number

Binary unit of information volume in the color of an image. The number shows the number of bits per pixel.

The larger the number of bits, the more the color numbers and the gradation becomes smoother. A one-bit image is a black-and-white image.

### **Color Management System (Color Matching)**

Digital cameras that shoot images, monitors that display images, and printers that print images each have a different way of creating color. For this reason, there may be a difference between the color of an image when viewed on a monitor and when printed.

A color management system is a system for managing color in order to bring these colors closer together. With DPP, you can more closely match color between different devices using ICC profiles between different devices.

# **ICC** profiles

ICC profiles are files containing color information such as color characteristics and color space for various devices, set by the ICC (International Color Consortium). Most devices such as the monitor we use to view images or the printer we use to print images can be managed (color management) using these ICC profiles and the color between different devices can be more closely matched. DPP has color management that uses these ICC profiles.

### **Tone Curve**

A tone curve shows values before adjustment (input) as the horizontal axis on a graph, and the values after adjustment (output) as the vertical axis. Since the values of before adjustment and after adjustment are the same before any adjustment is made, the tone curve displays as a straight line from bottom left to top right, and by changing this tone curve, you can adjust in detail the image's brightness, contrast and color. The more you go right on the horizontal axis, the more the plus value it becomes, and the higher you go on the vertical axis, the more the plus value it becomes. Basic Operation Advanced Operation

Introduction

Contents at

a Glance

Advanced Image Editing and Printing

Processing Large Numbers of Images

> Editing JPEG/TIFF Images

Reference



### **Color space**

A color space is the reproducible color range (color gamut

characteristics). DPP supports the following five kinds of color space.

- sRGB :Standard color space for Windows. Widely used for<br/>the standard color space of monitors, digital<br/>cameras, and scanners.Adobe RGB :A wider color space than sRGB. Mainly used for<br/>printing for business purposes.
- Apple RGB :
   Standard color space for Macintosh. A slightly wider color space than sRGB.
- **ColorMatch RGB** : A slightly wider color space than sRGB. Mainly used for printing for business purposes.

Wide Gamut RGB : A wider color space than Adobe RGB.

Refer to the color chart below for the color area of each color space.

### Color chart of color spaces compatible with DPP



	Gamma value	White point (color temp.)
 sRGB	2.2	6500K(D65)
 Adobe RGB	2.2	6500K(D65)
 Apple RGB	1.8	6500K(D65)
 ColorMatch RGB	1.8	5000K(D50)
 Wide Gamut RGB	2.2	5000K(D50)

# **CMYK simulation profiles**

A profile that simulates colors when printing in a CMYK environment (printing machine, etc.). With DPP, you can simulate color with four types of profile.

Euro Standard :	Profile normally used for book printing in
	Europe, suitable for simulation of standard
	European printing.
JMPA :	Profile normally used for book printing, etc. in
	Japan, suitable for simulation of magazine
	advertising standard color printing.
U.S.Web Coated :	Profile normally used for book printing in
	North America, suitable for simulation of
	North American standard printing.
JapanColor2001 type3	: Profile becoming a standard in the Japanese
-	printing industry, suitable for simulation of
	JapanColor standard printing.

### **Rendering intent**

Rendering intents are color conversion methods when printing an image. The conversion method of each rendering intent is shown below.

Perceptual : Before and after conversion, all colors are converted to maintain the relationship between colors. Even where colors slightly change, you can print a natural-looking image which has maintained color harmony. However, depending on the image, the saturation may change overall.

Relative Colorimetric : There will not be much conversion to colors which are similar before and after conversion, but colors which are not similar are converted appropriately. Because there are little changes to similar colors which comprise most of an image, you can print a natural-looking image in which the saturation has not changed greatly. However, depending on the image, there are cases where the overall tone of an image changes somewhat as colors which are not similar and highlights change. Advanced Image Editing and Printing Processing Large Numbers of Images

Introduction

Contents at

a Glance

Basic

Operation

Advanced

Operation

Editing JPEG/TIFF Images

Reference



# Index

A
Adjust JPEG Images
Adjust RAW Images 23
Adjust TIFF Images
Adjusting (JPEG or TIFF Image)
Automatic Adjustment (Tone Curve Assist)
Brightness
Click White Balance
Contrast
Dynamic Range
Hue
RGB Tool Palette 108
Saturation
Sharpness
Tone Curve Adjustment
Adjusting (RAW image)
Apply Adjustments 79
Automatic Adjustment (Tone Curve Assist) 30
Brightness 24
Click White Balance 26
Color Saturation 27
Color Temperature 52
Color Tone
Color Wheel
Contrast
Copy Adjustments
Dynamic Range
Filter Effect
Monochrome
Personal White Balance
Picture Style
Picture Style File
RAW Tool Palette
Save Adjustments
Sharpness
Tone Curve Adjustment
Toning Effect
White Balance

Adjustment Contents (Recipe)	
Adobe RGB	119
Apple RGB	119
Arrange Images	
Auto Lighting Optimizer	<mark>56</mark>
Automatic Adjustment (Tone Curve Assist)	
Automatic Dust Erasure Processing	62, 63, 95, 96
В	
Batch Apply White Balance to Images (Personal White B	Balance) 80

—
Batch Apply White Balance to Images (Personal White Balance) 80
Batch Change the File Name of Images
Batch Convert/Save Images (Batch Process)
Batch Process (Batch Save JPEG and TIFF Images)
Batch Process of Multiple Images
Change File Name83
Convert/Save (Batch Process)
Personal White Balance80
Recipe Data78
Transfer
Batch Settings Window
Batch Transfer Images
Batch Transfer Images to Image Editing Software
Before/After Comparison Display 49
bit Number 118
Bookmark
Brightness
•

### С

•
Change File Name
Changing the File Name of Images in the Order in the Main Window. 83
Check Mark 17, 18, 106, 110
Chromatic Aberration Correction
Chrominance Noise Reduction (JPEG, TIFF Images)
Chrominance Noise Reduction (RAW Images) 57
Click White Balance
CMYK Simulation
Collection Window 6, 33, 105

Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images

Introduction

Contents at a Glance

Basic Operation

Editing JPEG/TIFF Images

Reference



Color Blur Correction	60
Color Chart	119
Color Management (Color Matching)	118
Color Setting of the Monitor (Profiles)	75
Color Setting of the Printer (Profiles)	
Color Space	
ICC Profiles	
Color Management (Preferences)	
Color Saturation	
Color Setting of the Monitor (Profiles)	
Color Setting of the Printer (Profiles)	
Color Space	
Adobe RGB	
Apple RGB Color Space Setting for Each Image	
ColorMatch RGB	
Default Setting of Color Space	
sRGB	
Wide Gamut RGB	119
Color Space Setting for Each Image	66
Color Temperature	52
Color Tone	27
Color Wheel	52
ColorMatch RGB	119
Compatible Cameras with the Lens Aberration Correction Function	58
Compatible Lenses with the Lens Aberration Correction Function	58
Contact Sheet Printing (Printing a Thumbnail List)	68
Contrast 27	, 87
Convert to JPEG or TIFF Image and Save 38, 81, 112,	116
Convert/save One Image Window 38, 7	112
Copy Stamp (Image Correction) 66	, 99
Copy Stamp Window 62, 64, 95, 97, 7	115
Copying and Pasting (Applying) Recipes	79
Correct Images (Copy Stamp Function) 66	
Creating a Folder	
-	

D	Introduction
Default Noise Reduction Settings74	
Default Setting of Color Space	Contents at
Delete Images 45	a Glance
Deleting	
Delete Images	
Delete the Software 103	Basic
Deleting DPP (Uninstalling) 103	Operation
Detailed Setting Printing (Printing with Shooting Information)	
Display	Advanced
Before/After Comparison Display	Operation
Enlarged Display (Edit Window) 11, 107	
Enlarged Display (Quick Check Window) 16, 110	Advanced
Shooting Information Display 10, 21	Image Editing
Single Image Display 20	and Printing
Synchronize Edit Window 50	
Thumbnail Display (Main Window) 10, 104	Processing
Thumbnail Display and Enlarged Display	Large Numbers
(Edit Image Window)	of Images
Distortion Correction	
Downloading an Image to Your Computer	Editing JPEG/TIFF
Downloading Images from a Camera	Images
Downloading Images from a Card Reader	
Downloading Images	
Downloading Images from a Camera	Reference
Downloading Images from a Card Reader	
Dust Delete Data	
Dust Erasure Processing	Index
Automatic Dust Erasure Processing 62, 95	muex
Image Correction (Copy Stamp Function) 66, 99	
Manual Dust Erasure (Repair Function)	
Dynamic Range	
E	
Edit Image Window 31, 111	
Edit Window 11, 107	
Editing→Adjusting	
Enlarged Display (Edit Window) 11, 107	

Enlarged Display (Quick Check Window) 110 EOS Utility
FFalse Color ReductionFilter Effect28Folder Window6, 104
G General Settings (Preferences)
H HelpCover Highlight Area Warning Indicator
ICC Profiles       118         Image Frame Information (Image Marks)       106         Image Marks (Image Frame Information)       106         Image Quality       106         Default Noise Reduction Settings       74         False Color Reduction       71, 72         Improve the Quality of an Image (Main Window)       21         Noise Reduction of a JPEG Image (Luminance, Chrominance)       92         Noise Reduction of a RAW Image (Luminance, Chrominance)       57
View and Save a RAW Image71, 72Image Shooting Information Display10, 21Improve the Quality of an Image (Main Window)21
J JPEG Image 118
L Lens Aberration Correction

### Μ

Main Window	10, 104
Manual Dust Erasure (Repair Function)	64, 97
Monochrome	
Filter Effect	28
Toning Effect	28
Move or Copy Folders	46
Move or Copy Images	46

### Ν

Noise Reduction (JPEG or TIFF Image)	
Noise Reduction (RAW Image)57	
Noise Reduction of a JPEG Image (Luminance, Chrominance) 92	
Noise Reduction of a RAW Image (Luminance, Chrominance) 57	
NR/Lens/ALO Tool Palette 109	

### 

Organize Images 45	
Organizing Images 45	
Create a Folder 45	
Delete Images 45	
Move or Copy Folders 46	
Move or Copy Images 46	
Register Folders as Bookmarks 47	

### Ρ

1	
Peripheral Illumination Correction	
Personal White Balance	
Picture Style	
Picture Style File	
Preferences	
Color Management75	
General Settings	
Tool Palette	
View Settings73	
Printing	
Printing a Thumbnail List (Contact Sheet Printing)	
Printing One Sheet of Paper 14, 44	
Printing Using Easy-PhotoPrint42	



Reference

Index



### Introduction

Contents at a Glance

Printing Using Easy-PhotoPrint EX	39
Printing with a High-End Canon Printer	
Printing with a Large-Format Canon Printer	
Printing with a Printer other than the Canon Printers	
Printing with Canon Inkjet Printers	
Printing with Easy-PhotoPrint Pro	69
Printing with Shooting Information (Detailed Setting Printing)	67
Rendering Intents when Using Easy-PhotoPrint	76
Printing a Thumbnail List (Contact Sheet Printing)	68
Printing One Sheet of Paper 14,	<b>4</b> 4
Printing Using Easy-PhotoPrint	42
Printing Using Easy-PhotoPrint EX	
Printing with a High-End Canon Printer	
Printing with a Large-Format Canon Printer	
Printing with a Printer other than the Canon Printers	44
Printing with Canon Inkjet Printers	42
Printing with Easy-PhotoPrint Pro	69
Printing with Shooting Information (Detailed Setting Printing)	
Q	

Quick Check Window	16,	110	
Quitting DPP		14	

# Quitting DPP14RRAW Image118RAW Tool Palette108Re-Adjusting an Image39, 100Recipe78, 118Recipe File78Re-Editing an Image39, 100Registering Folders as Bookmarks47Rename Window83, 117Rendering Intent (Matching Method)119Rendering Intents when Using Easy-PhotoPrint75, 76Repair (Manual Dust Erasure)64, 97RGB Tool Palette108

Rotate Images 10, 23, 104, 105, 110, 111	Introduction
S	
Saturation	Contents at
Save	a Glance
Batch Convert/Save Images (Batch Process)	
Convert to JPEG or TIFF Images and Save	Desia
Save	Basic Operation
Save As	
Save JPEG or TIFF Image as a Separate Image	
View and Save RAW Images	Advanced
Save As	Operation
Salving Recipes	
Select Images 10, 16, 31 Shadow Area Warning Indicator 51	Advanced
C C	Image Editing and Printing
Sharpness	
Shooting Information Display 10, 21	Processing
Shortcut Keys	Large Numbers
Single Image Display of DAW and IDEC Image 20	of Images
Single Image Display of RAW and JPEG Image	
Sorting Images (Check Marks) 17, 18	Editing JPEG/TIFF
sRGB	Images
Starting up DPP	
Supported Images	Defense
Synchronization (Edit Window)	Reference
Synchronize Edit Windows	
Synchronize Images	
System Requirements 3	Index
Т	
Thumbnail Display (Main Window) 10, 104	
Change the Display 10	
Thumbnail Display and Enlarged Display (Edit Image Window) 31	
Thumbnail Display of Images (Main Window) 10	
Change the Display	
TIFF Image 118	
Tone Curve 118	
	123

Tone Curve Adjustment	54, 90
Tone Curve Assist (Automatic Adjustment)	30, 86
Toning Effect	
Tool Palette	
NR/Lens/ALO Tool Palette	109
RAW Tool Palette	
RGB Tool Palette	
Tool Palette (Preferences)	
Transfer	
Batch Transfer Images to Image Editing Software	80
Transfer an Image to Photoshop	
Transfer an Image to Photoshop	
-	
Trimming an Image	
Trimming Window	35, 93, 113
V	
View Settings (Preferences)	
W	
	05
White Balance	
Click White Balance	
Color Temperature	
Color Wheel	52
Personal White Balance	80
Wide Gamut RGB	119

### **About This Instruction Manual**

- It is prohibited to reproduce, in whole or part, the contents of this Instruction Manual without permission.
- Canon may change without notice the software specifications and contents of this Instruction Manual.
- The software screens and displays printed in this Instruction Manual may differ slightly from the actual software.
- The content of this Instruction Manual has been reviewed thoroughly. However, if you should notice any errors or omissions, please contact a Canon Service Center.
- Please note that irrespective of the above-mentioned, Canon does not take responsibility for the outcome of the operation of the software.

### **Trademark Acknowledgments**

- Macintosh is a trademark of Apple Inc., registered in the United States and other countries.
- Adobe and Photoshop are registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.
- Other names and products not mentioned above may be registered trademarks or trademarks of their respective companies.

Contents at a Glance
Basic Operation
Advanced Operation
Advanced Image Editing and Printing
Processing Large Numbers of Images
Editing JPEG/TIFF Images
Reference
Index