

Release Notes: Oracle AutoVue 20.2.1, Client/Server Deployment

For the most up-to-date version of this document, go to the AutoVue Documentation Web site on the Oracle Technology Network at http://www.oracle.com/technetwork/documentation/autovue-091442.html.

Application User License

- AutoVue includes a Desktop Deployment and a Client/Server deployment. For Application User licensing metric (in the Component licensing model) or Custom Suite User licensing metric (in the Custom Applications Suite licensing model), a single license cannot be split or shared between two users (e.g., one user using the AutoVue Desktop Deployment and a different user using the Client/Server deployment would require two licenses).
- For the purposes of the following programs: Oracle AutoVue Office, Oracle AutoVue 2D Professional, Oracle AutoVue 3D Professional Advanced, Oracle AutoVue EDA Professional, Oracle AutoVue Electro-Mechanical Professional, Oracle AutoVue 2D Professional for Agile and Oracle AutoVue Electro-Mechanical Professional for Agile a user external to your company who participates in and attends an AutoVue Real-Time Collaboration session or AutoVue web conference, but neither initiates nor hosts it, is not required to be separately licensed. All users within your company must be licensed.

Installation

- If you are upgrading from AutoVue 20.x, you do not need to run the uninstaller before you install AutoVue 20.2.1. You can just run the installer for AutoVue 20.2.1. The installer detects if AutoVue 20.0/20.1.x/20.2 is installed on your machine. If it is installed, the installer backs up required data, uninstalls version 20.0/20.1.x/20.2 and then installs 20.2.1 to the same location.
- If installing on a Linux OS, make sure you have the correct version of WINE installed. The version of WINE compatible with AutoVue 20.2.1 is wine-av-20040914-21.i386.rpm. You can download this version of WINE from http://oss.oracle.com/AutoVue.
- When upgrading AutoVue, if the client and server versions do not match, AutoVue now displays an error message indicating the incompatibility. Ensure that the client jars are upgraded when you upgrade the server.
- AutoVue installer can now scan for default RMI ports during interactive installation and prompt user to use another port if the default ports are already in use.
- AutoVue documentation, with the exception of the *User's Manual*, are no longer included in the AutoVue installation. Refer to Documentation Updates for more information.
- For pre-requisites and complete secure installation instructions, refer to the *Oracle AutoVue Installation and Configuration Guide*.

System Requirements

Component

Oracle-Certified Operating Systems and Software

Server

(The installation requires about 400MB of free space. Additional space will be required by AutoVue for storing other data such as streaming files and markups. Refer to the *AutoVue Planning Guide* for additional information.)

Windows

- Windows Server 2003
 - 32-bit
 - 64-bit (AutoVue running in 32-bit mode)
- Windows Server 2008
 - 32-bit
- 64-bit (AutoVue running in 32-bit mode)
- Windows Server 2008 R2
 - 64-bit (AutoVue running in 32-bit mode)

Important: Windows 2008R2 has improved memory management compared to Windows 2008 and Windows 2003. It is recommended that you run AutoVue on Windows 2008R2 for better memory handling and long-term stability.

Linux

- Oracle Linux 5.8 (x86)
 - 32-bit
 - 64-bit (AutoVue running in 32-bit mode)
- Red Hat Enterprise Linux 5.8 (x86)
 - 32-bi
 - 64-bit (AutoVue running in 32-bit mode)

Virtualization

- VMWare Server version ESX 4.1
- Oracle Virtual Machine 2.2.2

Client

- Clients running the following Java Virtual Machines:
 Java SE 6 Update 31—32-bit and 64-bit
- Java SE 7u5—32-bit

Windows OSes (XP, Vista, and 7)—32-bit and 64-bit

- Internet Explorer 7
- Internet Explorer 8
- Internet Explorer 9
- Firefox ESR 10
- Chrome 19

MAC OS X 10.7

- Safari 5.0
- Firefox ESR 10

RedHat Enterprise Linux 5

Firefox ESR 10

Ubuntu 10.04 LTS

Firefox ESR 10

Solaris 10 (Sparc)

Firefox 9

Note: Ensure that the JRE used for the AutoVue client supports SWING UI.

Application Server

The VueServlet has been certified on the following application servers:

- WebLogic 9.x and up
- Oracle Application Server 10g
- Tomcat 6.x and up
- WebSphere 6.1 and up
- Jetty 6.0 and up

Integrations with AutoVue 20.2.1

The following integrations have been certified with AutoVue 20.2.1:

- VueLink for UCM 20.1
- VueLink for Documentum 19.3.2

General Enhancements

The functionality changes include:

- Added support for Decimeter Unit for measurement
- Enhancements to markups
 - Added support for aligning the text in markups in conversion The markup text will be aligned in the converted output as it is aligned in the display.
 - Added DPI support for markup printing
 - The printout matches the workspace display. For example, Hyperlink and Note icons appear as displayed in the workspace.
 - Added support for Stamp conversion to PDF
 - The background image of a Stamp now displays after conversion to PDF
 - Added markup stamp support to AutoVue Office
- AutoVue can work with Oracle Business Process Management (BPM) through AutoVue Web Services (for
 example, users can call AutoVue printing Web Services in order to automate the printing of documents as part of
 a workflow built in Oracle BPM). For more information on BPM, search for Business Process Management
 documentation on the Oracle Technology Network (OTN).
- Enhancement to print functionality
 - Added support to share print settings amongst multiple AutoVue child windows
- Enhancements to AutoVue hotspot capabilities:
 - Added support for polygon regional hotspots Allows hotspots in 2D drawings, images and PDFs to be defined as polygons, rather than only by rectangles.
 - Added support for page specific hotspots to support the case whereby the same regional hotspot (box or polygon) appears on multiple pages.
 - Enhanced text hotspot support for PDF format with more accurate string/character recognition.

Format Enhancements

MCAD Formats

- Added support for Autodesk Inventor 2013
- Added support for Unigraphics NX8
- Added support for CATIA V5-6R2012
- Added support for Creo Parametric 2.0
- Added support for JT (Direct Model) versions 9.2 to 9.5 (i.e. 9.2, 9.3, 9.4 and 9.5)
- Added bookmarks for family tables in Creo Parametric (Pro/ENGINEER) files. The xpr and xas accelerator instance files for each entry in the family table are required for correct display.
- General bug fixes for:
 - Unigraphics
 - Creo Parametric (Pro/ENGINEER)
 - · Autodesk Inventor
 - CATIA 5
 - DirectModel (JT)

· Solid Edge

AEC Formats

- Added support for AutoCAD 2013 and AutoCAD Mechanical 2013
- Added support for embedded rasters generated by the AutoCAD Raster Design for DWG files
- General bug fixes for:
 - · AutoCAD/DXF
 - Autodesk DWF 3D
 - MicroStation 7
 - Visio

EDA Formats

- Added support for Mentor CCZ Schematics format
- General bug fixes for:
 - · Cadence Allegro
 - · Mentor Expedition

Desktop/Office Formats

- Improved support for image rendering, arrow display in PowerPoint XML files
- Improved support for shading and gradient fill, Eschers shapes PowerPoint Binary files
- Added support for OLE objects in PowerPoint file
- Added support for viewing PDF/A files
- · Added support for check boxes in Excel
- General bug fixes:
 - · Text
 - · Acrobat PDF
 - Word
 - Excel
 - · PowerPoint
 - Outlook

Re-introduced File Formats

- · Altium Designer
- RTF
- JPEG 2000

Documentation Updates

The following documents, with the exception of the *User's Manual* and JavaDocs, are no longer included in the AutoVue installation. All of these documents can be found on the Oracle AutoVue Documentation OTN site under "AutoVue 20.2.1" at http://www.oracle.com/technetwork/documentation/autovue-091442.html.

- The following document is new in 20.2.1:
 - Augmented Business Visualization Developer's Guide
- The following documents have been updated in 20.2.1:
 - Installation and Configuration Guide
 - · Viewing and Configuration Guide

- AutoVue API Programmer's Guide
- · User's Manual
- Acknowledgments
- · Supported File Formats
- · Release Notes
- Product Variations Feature Matrix
- · Testing Guide
- · Security Guide
- · Planning Guide

New INI File Settings

INI options described in following sections should be set in user INI files.

DWF3D Options

Configure options for Autodesk DWF3D files.

[Options]

Parameter	Description	Default
DWFLOADPMI = [0 1]	Controls the loading of PMI entities in DWF 3D files. Set to 1 to enable loading of PMIs. Set to 0 to disable loading of PMIs.	1

Hotspot INI Options

All of the following options have to be placed in the [HOTSPOTS] header of the INI file:

Parameter	Description	Default
ADVANCEGAP =[integer]	Specify the maximum number of spaces between consecutive text strings. When there is large spacing between characters, you can increase the value assigned to the INI option.	3

De-supported INI Options

- The following INI options were removed in AutoVue:
 - Removed SHOW_POINTTOPOINT_PAGE INI option
 - Removed the use of TRYWITHMSXMLPARSER INI option
 - Removed UIENABLEPRINTTYPESELECTION and HIGHRESOLUTION
 - Removed TILED parameter for FORMAT
- Removed AdminDoc option from CHOSEN INSTALL FEATURES Parameter for Silent Installation

Updated INI Options

The following INI options were updated in AutoVue:

- The default value of MAXPLAINTEXTPAGES has changed to 100. Earlier, the default was 1000.
- The default value of DISABLE3DMODEL for MicroStation 7 has changed to 1.

Refer to the *Oracle AutoVue Client/Server Deployment Viewing Configuration Guide* for more information regarding these options.

De-supported File Formats/Versions

Oracle AutoVue has dropped support for some file formats/versions, which had very limited usage and low demand from our customers. This will allow Oracle AutoVue to focus development efforts on formats which are most strategic to our customers. The following file formats/versions were officially de-supported in release 20.1.1 and are not supported in this release of AutoVue (that is, when these files are opened in AutoVue, the Unsupported File Format/Version message appears).

De-supported File Formats

The following formats have been de-supported in 20.2.1.

MCAD Formats

- I-deas
- Pointcloud

AEC Formats

- MicroStation 8 3D
- AutoCAD Slide/AutoCAD Slide Library/AutoCAD Sheetset
- CADkey
- · ESRI Shapefile

EDA Formats

- PCAD
- PDIF
- Allegro IPF
- OrCAD Layout
- Cadence Specctra
- Zuken Cadif
- · Zuken Cadstar
- IFF
- Barco PDF
- CIF
- Protel

Raster Formats

- X-Windows Dump
- IBM-IOCA

Archive Formats

- Tar
- Gzip

De-supported File Versions

The following format versions have been de-supported in 20.2.1.

MCAD Formats

- CATIA 5 2D/3D prior to version V5R17
- AutoDesk Inventor 2D/3D prior to version 10
- Creo Parametric (Pro/ENGINEER) 2D/3D prior to version Wildfire
- CoCreate Modeling/SolidDesigner prior to version 15
- Solid Edge prior to version 18
- SolidWorks prior to version 2006
- Unigraphic prior to NX3

EDA Formats

- Cadence Design Suite prior to version 15
- PADS prior to version 2005

AEC Formats

- AutoCAD prior to version 2000
- AutoDesk DWF prior to version 5
- AutoDesk DXF prior to version 2000
- CoCreate Drafting/ME10 prior to version 2006/V14

MS Office Formats

- Excel prior to version 2003
- PPT prior to version 2003
- Word prior to version 2003

De-supported Functionality

Oracle AutoVue will no longer support some of its functionality, which had very limited usage and low demand from our customers. This will allow Oracle AutoVue to focus development efforts on functionalities which are more important to our customers. Following is the list of functionalities that are de-supported in Release 20.2.1:

- Interference Checking The Check for interference menu item in 3D modes has been removed
- Set User Coordinate System The Set User Coordinate System menu item in 3D modes has been removed
- Align Parts The Align Parts menu item in 3D modes has been removed
- Contrast Visual Effects The contrast visual effects cannot be applied in any of the modes.
- Verify Design The Verify Design menu item has been removed in the EDA modes.
- Magnify Glass This menu item is removed for all the applicable modes.
- Magnify Window The Magnify Window menu item has been removed for all the applicable modes.

Note: The Pan and Zoom Window feature can be used to achieve the "Magnify Window", and "Magnify Glass" functionalities.

- Flip The Flip menu item, both horizontal and vertical, from all the applicable modes
- Hyperlink The **Follow Hyperlink**, **Hyperlink History**, and **Hyperlink Go Back** menu items have been removed. You can still launch a hyperlink when selecting a link from the AutoVue workspace.
- All Markup Object Rotate The functionality to select and rotate all markup entities has been removed. Markups can only be rotated along with the base file. The capability to arbitrarily rotate individual entities still exists.
- AutoVue in Offline Mode Support for Offline mode is deprecated.

• Conversion to the following formats has been removed: VRML, CALS GP4, Encapsulated Postscript, PCL, PCX Bitmap, Run Length RLC.

Note: Please contact your Customer Support Representative in case you want any of the above de-supported formats/file versions/functionalites to be included in the Oracle AutoVue product.

Known Issues

For information on known issues, refer to the Knowledge Base: https://support.us.oracle.com/oip/faces/secure/km/DocumentDisplay.jspx?id=1488647.1

Release Notes: Oracle AutoVue 20.2, Client/Server Deployment

For the most up-to-date version of this document, go to the AutoVue Documentation Web site on the Oracle Technology Network at http://www.oracle.com/technetwork/documentation/autovue-091442.html.

Application User License

- AutoVue includes an AutoVue Desktop Version, a Desktop Deployment, and a Client/Server deployment. For
 Application User licensing metric (in the Component licensing model) or Custom Suite User licensing metric (in
 the Custom Applications Suite licensing model), a single license cannot be split or shared between two users
 (e.g., one user using the AutoVue Desktop Version and a different user using the Desktop Deployment would
 require two licenses).
- For the purposes of the following programs: Oracle AutoVue Office, Oracle AutoVue 2D Professional, Oracle AutoVue 3D Professional Advanced, Oracle AutoVue EDA Professional, Oracle AutoVue Electro-Mechanical Professional, Oracle AutoVue 2D Professional for Agile and Oracle AutoVue Electro-Mechanical Professional for Agile a user external to your company who participates in and attends an AutoVue Real-Time Collaboration session or AutoVue web conference, but neither initiates nor hosts it, is not required to be separately licensed. All users within your company must be licensed.

Installation

- AutoVue 20.2 provides a secure installation by default. During the installation process, the installer lets you configure AutoVue for Secure Socket Layer (SSL) and identity authentication.
- The Oracle AutoVue installer no longer deploys AutoVue client components on a Web server in order to avoid dependencies on external web servers. That is, the installer no longer prompts you to install with IIS/Oracle HTTP/Apache Web servers. The installer installs the sample HTML files with the Jetty application server that ships with AutoVue.
- The following silent installation configuration parameters are obsolete since the installer does not deploy client components with a Web server
 - WEBSERVER HOST
 - WEBSERVER DOCROOT
 - WEBSERVER PATH
- If you are upgrading from AutoVue 20.x, you do not need to run the uninstaller before you install AutoVue 20.2. You can just run the installer for AutoVue 20.2. The installer detects if AutoVue 20.0/20.1.x is installed on your machine. If it is installed, the installer backs up required data, uninstalls version 20.0/20.1.x and then installs 20.2 to the same location.
- The components available for default installation have changed. The Example Client Application is no longer installed by default. If you wish to install the demo htmls, you should do a custom installation and select **Example Client Application**.

Note: If you are upgrading from a previous release and you select default installation, the Example Client Application will not be installed.

- If installing on a Linux OS, make sure you have the correct version of WINE installed. The version of WINE compatible with AutoVue 20.2 is wine-av-20040914-21.i386.rpm. You can download this version of WINE from http://oss.oracle.com/AutoVue.
- For pre-requisites and complete secure installation instructions, refer to the *Oracle AutoVue Installation and Configuration Guide*.
- Customers upgrading from a previous release of AutoVue to the new release must ensure that all locations referenced by the CODEBASE parameter of the AutoVue client are updated with the 20.2 client jars (jvue.jar, jogl.jar, gluegen-rt.jar)

Refer to KM Note: https://support.us.oracle.com/oip/faces/secure/km/DocumentDisplay.jspx?id=1439152.1 for instructions on how to verify if the client components are updated.

System Requirements

Component

Oracle-Certified Operating Systems and Software

Server

(The installation requires about 400MB of free space. Additional space will be required by AutoVue for storing other data such as streaming files and markups. Refer to the *AutoVue Planning Guide* for additional information.)

Windows

- Windows Server 2003
 - 32-bit
 - 64-bit (AutoVue running in 32-bit mode)
- Windows Server 2008
 - 32-bit
 - 64-bit (AutoVue running in 32-bit mode)
- Windows Server 2008 R2
 - 64-bit (AutoVue running in 32-bit mode)

Important: Windows 2008R2 has improved memory management compared to Windows 2008 and Windows 2003. It is recommended that you run AutoVue on Windows 2008R2 for better memory handling and long-term stability.

Linux

- Oracle Linux 5.6 (x86)
 - 32-bit
 - 64-bit (AutoVue running in 32-bit mode)
- Red Hat Enterprise Linux 5.6 (x86)
 - 32-bit
 - 64-bit (AutoVue running in 32-bit mode)

Virtualization

VMWare Server version ESX 4.1

Client

Clients running the following Java Virtual Machines:

• J2SE 6.0 update 26—32-bit and 64-bit

Windows OSes (XP, Vista, and 7)—32-bit and 64-bit

- Internet Explorer 7
- Internet Explorer 8
- Internet Explorer 9
- Firefox 8

MAC OS X 10.6

- Safari 5.0
- Firefox 8

RedHat Enterprise Linux 5

Firefox 8

Ubuntu 10.04 LTS

Firefox 8

Solaris 10 (Sparc)

Firefox 8

Note: Ensure that the JRE used for the AutoVue client supports SWING UI.

Application Server

The VueServlet has been certified on the following application servers:

- WebLogic 9.x and up
- Oracle Application Server 10g
- Tomcat 6.x and up
- WebSphere 6.1 and up
- Jetty 6.0 and up

Integrations with AutoVue 20.2

The following integrations have been certified with AutoVue 20.2:

- VueLink for UCM 20.1
- VueLink for Documentum 19.3.1 with patch 13355092

General Enhancements

- Enhancements to markups
 - The Stamp markup entity has been renamed to Symbol.
 - The Intellistamp markup entity has been renamed to Stamp.
 - Enhancements to Stamp (formerly Intellistamp):
 - Stamps can now be defined to have fields that store their values locally or in the back-end system. The original value and constraints (lists of possible values) can come from the back-end system even if the field value is stored locally.
 - Stamps can be defined to have a fixed physical size (e.g. 10cm by 10cm) to comply with industry or corporate standards.
 - Stamps with an Enhanced Metafile (EMF) background image will have a better appearance when resizing text and the background image will keep the same relatively size and location.
 - Enhanced attribute permissions (readonce, read, write and edit).
 - Ability to resize both the Stamp and the Stamp text (supported only when EMF is used as the Stamp background).
 - Ability to specify the Stamp size (fixed, default, resizable).
 - Improvements to the Stamp Designer includes:
 - View preview text in the designer to speed up stamp design process.
 - Set a specific bounding box for each field.
 - Set the alignment of text in each field.
 - New designer available. To invoke the designer, run designer.bat located at <AutoVue Install Dir>\bin.
- AutoVue provides the ability to do batch stamping. An API sample to demonstrate batch stamping is available at <AutoVue Installation Directory>\Examples\BatchStamping.
 - AutoVue now exits markup creation mode after you create a markup entity. In previous releases of AutoVue, you were able to continue adding markups until you right-click the workspace.
- Enhancements to AutoVue's hotspot capabilities:
 - New regional hotspots: Allow hotspots in 2D drawings and images to be defined as boxes, rather than only by text strings to:
 - Support cases where the underlying document has no textual information (Tiff or scanned document).
 - Create hotspots that more closely match the area of interest e.g. a block or other object in a drawing.
 - New 3D hotspots: Allow 3D parts to become hotspots, based on metadata attributes such as 'part number' or 'asset id' to:
 - Enable augmented business visualization in 3D models.
 - Allow the parts and components of a 3D model to be used to trigger actions, or to be highlighted as part of a visual dashboard.
- Added Unicode support for Layers, Views, Blocks and 3D attributes.
- Added support for layer printability for AutoCAD and PDF files. AutoVue does not print layers that are marked "non-printable". Note the following:
 - Layer printability does not take effect when in Compare mode.
 - Layer printability does not apply to conversion.
- Added support for multi-selection of local files in the file open dialog.
- Added support for specifying a page range when converting to PDF.
- Improvements to logging to be able to detect files that hang the server. A new property (docserver.timeout) has been added to let system administrators configure the time at which AutoVue should generate the hang report. If

an operation takes more time than this period, AutoVue generates a message in the Document Server log indicating that there could be a problem with this file.

• Added support for the Dutch language (locale NL) for the AutoVue user interface.

MCAD Formats

- Added support for CATIA 5R21
- Added support for SolidWorks 2012
- Added support for Solid Edge ST3, ST4
- Added support for Creo Parametric 1.0
- Added support for Creo Element\Direct Modeling 17.10, 17.20, 17.25, 17.30 and 18.00
- Added support for PLM XML
- Improved handling of background of AutoDesk Inventor drawings. If drawings contain a background image, AutoVue displays it, but does not print this background image.
- Added support for shaded views in Pro/ENGINEER 2D files.
- Enhanced support for IGES:
 - Added support for 3D layers
 - Improved loading performance
- General bug fixes:
 - CATIA 4
 - CATIA 5
 - IGES
 - · Autodesk Inventor
 - Creo Parametric (Pro/ENGINEER)
 - · Unigraphics
 - · SolidWorks
 - · Solid Edge
 - STEP

AEC Formats

- Added support for Creo Element/Direct Drafting 17.10 to 18.00
- Enhanced support for AutoCAD DXF:
 - Added support for layout pages
 - · Added support for OLE embedded objects
 - · Added support for raster embedded entities
 - Added support for Viewports in layout pages
- General bug fixes:
 - AutoCAD (DWG & DXF)
 - MicroStation
 - Creo Element/Direct Drafting (ME10)
 - Visio
 - TIFF

EDA Formats

- Added support for Cadence Concept HDL 16.5
- Added support for Allegro Layout 16.5
- Added support for Orcad Capture 16.5
- Added support for Board Station ASCII Symbol Geometry
- Added support for Cadence Cell Library
- General bug fixes:
 - · Cadence Allegro
 - EDIF
 - OrCAD Capture
 - · Mentor BoardStation
 - PADS Logic

Desktop/Office Formats

- Added support for Word 2010
- Added support for Excel 2010
- Added support for PowerPoint 2010
- Added support for Outlook 2010
- Enhancements to Desktop/Office formats:
 - · Improved handling of PDFs with large JPEG images
 - Added support for PDF files embedded in Excel files
 - Improvements to hyperlinks in Excel
 - · Added Workbook protection for binary Excel binary files
 - Improvements to field display support in PowerPoint (date, time, page, number)
 - Improvements to arrow head rendering in PowerPoint
 - Added gradient fill support in Word XML
- General bug fixes:
 - Excel
 - Outlook
 - PowerPoint
 - Word
 - PDF
 - TXT

Documentation

- The *Oracle AutoVue Security Guide* (SecurityGuide.pdf) is included with the installation. It provides guidelines on how to securely install and configure the AutoVue server and its associated components.
- The following documents have been updated in 20.2:
 - · Installation and Configuration Guide
 - · Viewing and Configuration Guide
 - · Planning Guide
 - · User's Manual
 - · Acknowledgments
 - Supported File Formats
 - · Release Notes
 - Product Variations Feature Matrix

New jvueserver.properties Options

The following are new options that can be set in jvueserver.properties file located in the <AutoVue Installation folder>\bin directory. For more information on these options, refer to the *Oracle AutoVue Installation Guide*:

Option in jvueserver.properties	Description
docserver.timeout=N, classname	Specify the timeout in minutes after which the AutoVue server hang logs will be generated. It is possible to implement a custom action to invoke on a hang situation. When implemented, replace ClassName with the name of the class implementing the custom action. Default: 10 (minutes)

New INI File Settings

INI options described in following sections should be set in user INI files.

Acrobat Options

Configure options for Acrobat files.

Parameter	Description	Default
PDFOVERPRINTPREVIE W = [0 1]	Displays content that otherwise may be obscured by overprinted fills. Set to 1 so that overprinted fills are not displayed if they use a spot color. Set to 0 so that overprinted content is shown as in Adobe Acrobat.	0

Autodesk Inventor Options

Configure options for Autodesk Inventor files.

[Options]

Parameter	Description	Default
DRAWINGPAGE = [0 1]	Set to 1 to limit the display of the drawing to the sheet borders. Set to 0 to display the whole drawing.	0
INVENTOR_HIDE_CONS TRUCTION_GEOMETRY = [0 1]	Option to control the visibility of construction/non-manifold geometries for Inventor 3D files. Set to 0 to display non-manifold/construction geometries. Set to 1 to hide non-manifold/construction geometries.	1

CATIA 5 Options

Configure options for CATIA 5files.

Parameter	Description	Default
LOAD_ATTRIBUTES = [0 1]	Control the loading of attributes when viewing CATIA 5 part or assembly files. Set to 1 to read attributes and attach them to their appropriate entities. Set to 0 to disable the loading of attributes. Note: This option may be used for performance tweaking for large assembly files with many attributes.	1
MINIMIZETREENODES = [0 1]	Set to 1 to minimize the number of nodes in the model tree and to increase performance. Set to 0 to build a model tree similar to the CATIA 5 feature tree. Note: This option is only valid in BREP mode (LOADFACETEDDATA=0).	0
CATIA5BUILDINTERMED IATECGMBODIES = [0 1]	This option controls the building and display of intermediate CGM bodies Set to 1 if you wish to process and display all intermediate CGM bodies. (You also need to set the INI option CATIA5BuildInvisibleCGMBodies to 1 if the intermediate bodies are saved as invisible. File will take longer to load if it contains lots of intermediate bodies). Set to 0 to disable the loading and display of intermediate CGM bodies. Note: The option takes effect only in BREP mode (LOADFACETEDDATA=0).	0

Creo Element/Direct Drafting (ME10) Options

Configure options for Creo Element/Direct Drafting (ME10) files.

[Options]

Parameter	Description	Default
ME10_USEHTMLASCIIC ODES=[0 1]	Specify whether or not to use the HTML ASCII CODES table for character mapping when accessing ME10 native fonts. Set to 0 to use ME10's native character mapping instead of the HTML ASCII CODES table. Set to 1 to use HTML ASCII CODES table for character mapping for special characters.	0

IGES Options

Configure options for IGES files.

Parameter	Description	Default
IGESDETAILEDTREE = [0 1]	Set to 1 to display every face (surface) as a separate node in the model tree. Set to 0 to merge all single faces together into one body.	0
IGESHIERARCHYCOLOR = [0 1]	Controls the color overwrite setting of IGES files. Set to 1 so that the child entity color always overwrites the parent entity color. For example, the color of the face, if set, always overwrites color of the body.	1
IGESINVISIBLEPARTS = [0 1 2]	Set to 0 so that hidden entities are not loaded. Set to 1 to load but not display hidden entities. Set to 2 to load and display hidden entities.	1
IGES3DLAYERS = [0 1]	Set to 0 to disable loading of layers in IGES files containing layer information. Set to 1 to enable loading of layers in IGES files containing layer information.	1
IGESFACEORIENTATION = [0 1]	Set to 0 to disable validation of face orientations in IGES 3D files Set to 1 to enable validation of face orientations in IGES 3D files	0
IGESSHOWALL = [0 1]	Set to 0 to disable loading of subordinate entities in IGES 3D files Set to 1 to load subordinate entities (children) in IGES 3D files	0

Mentor Options

Configure options for Mentor files.

[ECAD]

Parameter	Description	Default
MENTOR_PCB_DESIGNT OOL = [0 1 2]	Controls which Mentor PCB Design Tool's display to match. Set to 0 so that AutoVue matches the display of Mentor Librarian. Set to 1 so that AutoVue matches the display of Mentor Layout. Set to 2 so that AutoVue matches the display of Mentor Fablink.	0 for Mentor ASCII Geometry Symbol file 2 for Mentor PCB designs

Microsoft Office Options

Configure options for Microsoft Office files.

[Options]

Parameter	Description	Default
TRYWITHMSXMLPARSE R = [0 1]	Specify which parser to use when loading Office XML files. Set to 1 to use the MSXML parser that is included with Windows OS. Set to 0 to use the Xerces XML parser. Note: This option affects the following formats: WordXML PPTXML, ExcelXML	1

Creo Parametric (Pro/ENGINEER) Options

Configure options for Creo Parametric (Pro/ENGINEER) files.

Parameter	Description	Default
PROEBACKGROUNDCOL OR= <integer></integer>	Specify the background color of shaded views in Creo Parametric (Pro/ENGINEER) 2D drawing (when in saved display list and/or picture mode) to the background color used in Creo Parametric at the time the drawing (shaded view) was created. To obtain the background color from Pro/ENGINEER, select View > Display Settings > System Colors > Background Color. Note: If no color is specified (PROEBACKGROUNDCOLOR=-1), the hard-coded default Creo Parametric (Pro/ENGINEER) 2D background color is used: • For versions Wildfire, Wildfire2: RGB(183, 183, 183) • For versions Wildfire3, Wildfire4: RGB(51, 50, 46) • For version Wildfire5: RGB(160, 186, 212) • For Creo 1.0: RGB(251, 251, 252)	-1

Parameter	Description	Default
PROE2DVIEWDEFAULTS TYLE = [HIDDEN WIREFRAME SHADING NO HIDDEN]	Specify a default style to display 3D projected views. This option controls the amount of detail in projected views. Showing less detail in views might improve the performance: • HIDDEN • WIREFRAME • SHADING • NO HIDDEN This option will work in the following conditions:	NO HIDDEN
	 When the view's display style follows the global style (that is, Pro/Engineer environment variable Display Style is set to Follow Environment) Loading drawing files in picture mode is turned off (PROE2DLOADPICTURE=0) Loading drawing files from display list is turned off (PROE2DLOADSAVEDDISPLAYLIST=0) 	

Raster Options

Configure options for Raster files.

[Options]

Parameter	Description	Default
APPLYRASTERTRANSPA RENCY=[0 1]	Set to 0 to ignore alpha-channel and display the whole bitmap opaque. Set to 1 to use the alpha-channel stored in the file to apply transparency.	1

Text Options

Configure options for Text files.

Parameter	Description	Default
DEFAULTDOCMARGINS= [leftMargin, rightMargin, topMargin, bottomMargin]	Specify page margins in inches for plain Text files. If this option is not set, a default of 1 inch for each margin is set. Sample Syntax: DEFAULTDOCMARGINS=1.2, 1, 0.8, 0.8	1, 1, 1, 1

TIFF Options

Configure options for TIFF files.

[Options]

Parameter	Description	Default
TIFF_LOADPREVIEWS = [0 1]	Specifies if the TIFF images with reduced resolution (that is, preview pages) are displayed. Set to 1 to display all pages including the preview pages. Set to 0 so that the preview pages are not displayed.	0

De-supported in Release 20.2

- The INI option SENDPAGEASIMAGE has been de-supported since it is no longer needed.
- The integrations backward compatibility option dms.vuelink.version=19.3 has been de-supported.
- INI option FolderPermissions has been de-supported for security reasons.

Known Issues

For more information on known issues, refer to the Knowledge Base: https://support.us.oracle.com/oip/faces/secure/km/DocumentDisplay.jspx?id=1401724.1

- Copy/Paste feature is not supported for Stamp markup entity.
- Stamping does not work in 3D files.
- There is a known issue with 64-bit JREs when loading 3D files. In some situations (for instance, using Remote Desktop to access AutoVue), 3D files will not display. This is a known issue with JOGL 1.1.1. See JOGL bug: https://jogamp.org/bugzilla/show_bug.cgi?id=427: https://jogamp.org/bugzilla/show_bug.cgi?id=427
- There are some known issues with the Universal File Open dialog:
 - If loading the client on Windows 7, there maybe situations where the icons do not display. Refer to SUN bug: http://bugs.sun.com/view bug.do?bug id=6840086.
 - If loading the client on a MAC OS, the universal file open dialog will not display correctly. Refer to SUN bug: http://bugs.sun.com/bugdatabase/view bug.do?bug id=7077418.
 - A workaround is to use the native file open dialog by setting INI option ENABLEUNIVERSALFILECHOOSER to 0.
 - If loading the client on a Linux client that uses GNOME, the Universal File Open dialog may not show the DMS Browse and Search Buttons. A workaround is to use the KDE desktop environment. Refer to SUN bug: http://bugs.sun.com/view bug.do?bug id=6840086.

Copyright © 1999, 2012, Oracle and/or its affiliates. All rights reserved.

Portions of this software Copyright 1996-2007 Glyph & Cog, LLC.

Portions of this software Copyright Unisearch Ltd, Australia.

Portions of this software are owned by Siemens PLM © 1986-2012. All rights reserved.

This software uses ACIS® software by Spatial Technology Inc. ACIS® Copyright © 1994-2008 Spatial Technology Inc. All rights reserved.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.