WIPE

USER MANUAL



Table of Contents

PREFACE	I
WHO SHOULD READ THIS MANUAL	I
WIPE OVERVIEW	1
Introduction	
What is WIPE?	
WIPE as a Tool for Different Types of Users	
OVERVIEW OF WIPE FEATURES	
Ingestion Engine	
Data Server Engine	
Built-in Interpreter Language	
Supported Data Types	
Supported Data Formats	
Middleware Used	
Satellite Data Sources Presently Supported	
Customization Support	4
SUPPORTED DATA PROVIDERS AND RESPECTIVE DATA SETS	6
SERVER SIDE REQUIREMENTS	
Server Side Minimum Hardware Requirements	
Client Side Minimum Hardware Requirement	
CLIENT SIDE REQUIREMENTS	
Browser Requirements	
Hardware Requirements	
Data Access Rights	8
HIGH LEVEL SEARCH BROWSER	9
DESCRIPTION OF THE HLSB SCREEN	
HLSB MENU OPTION DESCRIPTIONS	11
Tool Bar Menu	12
Pop-Up Menu	12
Interaction With Session Profile Administrator	
IMAGE ANIMATION	
Applet Based Animation	
Javascript Animation	14
INTERACTIVE DATA BROWSER	10
DESCRIPTION OF THE IDB SCREEN	16
IDB MENU OPTIONS DESCRIPTIONS	
ToolBar Menu	
Volumetric Visualization	
OVERLAYING OPTIONS ON IMAGE SCREEN	
IMAGE ANIMATIONS	25
IDR Animation	24

Volumetric Visualization through Java Movie Sequence	25
ACCESS TO BUILT-IN INTERPRETER LANGUAGE	26
Custom Script Tab in Image Display Screen	
Custom Scripting via DataSet Control	26
GLOSSARY OF TERMS	26
WIPE TUTORIALS	31
Introduction	31
HLSB TUTORIALS	31
High Level Search Browser Basic Operations	
INTERACTIVE DATA BROWSER TUTORIALS	34
Interactive Data Browser Basic Operations	34
Basic Plotting Functions - IDB	35
Volumetric Visualization Guide	36
IMAGE ANIMATION	
Applet Based Animation	
JavaScript Animation	38
CUSTOM SCRIPT EXAMPLES.	

PREFACE

Who Should Read This Manual

The WIPE USER's MANUAL provides an in depth description of the WIPE system and how to use it. This manual contains the information needed for an end-user of WIPE to view datasets, perform analysis, and create custom scripts. A separate manual for the WIPE administrator provides the information on making changes to the server, such as adding or removing users, creating custom menus, and ingesting new datasets.

WIPE OVERVIEW



Introduction

What is WIPE?

The WWW Image Processing Environment (WIPE) - is a WEB based Image Processing and Geographical Information System (IP/GIS) that provides network centric manipulation of geo-spatial/temporal data associated to Earth observing sensors. Web based users can interactively produce high-level products resulting from the data fusion of recent and historical satellite imagery with other static/dynamic data sets.

WIPE was originally implemented to support the US and NATO's Rapid Environmental Assessment (REA) exercises during FY96-98. That particular version of WIPE was called the Warfighter Image Processing Environment. The present version of WIPE has evolved to support both military and non-military communities.

WIPE as a Tool for Different Types of Users

From a high level, the WIPE system provides support for major classes of users associated with the flow of geo-spatial/temporal data. These are: the data manager, the data provider, and the end-user accessing one or multiple sources of data.

Data Manager Perspective

WIPE solves the problems of efficiently ingesting/archiving/serving large data volumes and quickly geo-referencing recent and legacy geo-spatial/temporal data. For a data manager, WIPE provides a key building block in the implementation of a LAN based geo-spatial data-warehouse. Depending on the specific project constraints, it may be optimum to locate the WIPE server(s) at the:

 Data provider facility, i.e. a satellite ground station where the data is collected

- Main data fusion center
- Regional fusion center

or all of the above.

Data Provider Perspective

Once a data provider moves data into a pre-established directory, the data assimilation engine will automatically pre-process, geo-reference, and get the data ready for remote access via the WIPE server engine.

End-User Perspective

For the end-user WIPE facilitates going all the way from high level searches on the metadata to interactive access and download to the actual data or virtual data products. Remote end-users can access the server engine via:

- 1. User application that is HTTP or CORBA enabled, e.g. ProVIEW.
- 2. WIPE's High Level Search Browser (HLSB) Applet
- 3. WIPE's Interactive Data Browser (IDB) Applet

Overview of WIPE Features

WIPE provides a fully integrated hardware/software system for the assimilation, processing, and fusion of different satellite image data sets via a simple to use WEB based interface. A single WIPE system consists of an automatic data ingestion engine, and a network enabled server engine. Both the ingestion and server engines provide:

Low Cost Hardware – servers are implemented in Windows NT systems

Multiprocessor capability – the computational load can be distributed over multiple Windows/NT servers. The ingestion and server engines can reside on different machines.

Effective use of the Available Bandwidth – imagery data is automatically geo-referenced and re-sampled for display at the selected user resolution!

Ingestion Engine

The ingestion engine is constantly checking for the arrival of new data to be processed. It also captures all the methods for the processing of the recently received data.

As part of the ingestion process the source image data is stored in an intermediate format (virtual file format [VFF]) which provides rapid data access over the WWW at any resolution. *Conversion to the VFF is optional*.

The system is modular enough such that new data formats can be rapidly added into the ingestion engine.

Data Server Engine

The WIPE server engine is constantly checking for the arrival of data requests from a user. The server engine also captures all the different methods to make data available to the remote or local user. Highlights of the server engines include:

Modular Design – servers can be configured to access data in other WIPE servers

Data Access Restrictions – multiple access layer restrictions are built on top of the Windows NT operating system.

Client/Server – the data can be accessed from anywhere over the WWW. The user has the flexibility to process the data on the server in the client side. WIPE's architecture allows transferring portions of the data to the client side and performing sophisticated data analysis in his computer.

Long term archival - Once the hard disk quota is reached, the WIPE system administrator can specify what to do with data sets that can be off-loaded from the system.

For users connecting to the server engine via a WEB browser there are two basic JAVA applets that facilitate the interaction: the High Level Search Browser (HLSB), and the Interactive Data Browser (IDB).

High Level Search Browser (HLSB) Features

The HLSB is used to find where data is available as a function of sensor, time, and spatial location. The HLSB provides:

Spatial/Temporal/Sensor Queries – metadata queries are done using time, spatial, and sensor constraints via the HLSB simple to use graphical user interface.

Classification Status of Data –products can be labeled according to their classification status, unclassified, confidential, secret, top secret.

Manual Geo-referencing Adjustments - the user can manually fine tune the registration of an image with respect to known ground control point features, e.g. coastal database, or river database.

Flexible image sizing – the user has the ability of interactive zoom (in and out) and scrolling over an image.

Data Coverage Maps – easy to interpret data availability is overlaid on different Earth Maps.

Interactive Data Browser (IDB) Features

The IDB provides direct access to the numeric values of the data, and products. Highlights of the IDB include:

Generation of Image Mosaics on the Fly – the user can specify which images to use for a mosaic generation and establish the overlay order.

Relational Region of Interests – simple interface to locate and/or identify pixel locations on one image based on the pixel values of other images

Extensive Visualization Options – the user can visualize the data as an image, 2d-plots, 3d-plots, or video clip.

Extensive Download Options – access is provided to the actual data for user-defined regions of interest. The data can be downloaded in a number of industry wide formats, e.g. NetCDF, float files, ASCII files, JPEG, etc.

Dynamically generated products - most of the products are generated on the fly depending on the user requests

Disk Caching system - intermediate products are cached for a predetermined amount of time for rapid serving of future requests.

Extraction of Image features on the fly - the analyst/end-user can dynamically decide which region he wants to process and what type of features/algorithms he wants to apply to the data.

Image Mensuration - Latitude and longitude information is dynamically provided to the user as the pointer is moved over the image. The user can make distance measurements over arbitrary paths.

Session Profiles – the user can save, edit, and recall the state of a WIPE server (a session profile). This is particularly useful to share information with other users.

Built-in Interpreter Language

Because WIPE's engine is built on top of ProVIEW, it inherits many of ProVIEW's built in capabilities. A detailed description of ProVIEW can be obtained from the on-line manual at http://wipe.actgate.com. In addition, a user in ProVIEW can access the services in WIPE via CORBA and HTTP interfaces.

Supported Data Types

WIPE supports points, vectors, gridded, non-gridded, volumetric, image blobs, and N-dimensional data.

Supported Data Formats

SQL relational databases, Vector Product Format, Arc View GIS Shapefiles, NetCDF, CEOS, ASCII Tables, and Planetary Data System (PDS/NASA) formats (See table following this section for additional information)

Middleware Used

WIPE can be accessed from a WWW browser running the WIPE applet or from a stand-alone application. The middleware interfaces are, respectively, HTTP/CGI and CORBA. Building on top of WIPE's CORBA capabilities, ACT has been demonstrating the NAVY's Data Exchange Interface (DEI/CORBA) middle-ware. This has demonstrated access to the NAVY/TEDS servers via WIPE.

Satellite Data Sources Presently Supported

Satellite imaging sensors supported under WIPE are: ERS-2/SAR, ERS-GSST, LANDSAT, SPOT, SeaWIFS, RADARSAT, TOPEX/Poseidon, SeaWIFS, SSM/I, and NEMO. Examples of static data sets are bathymetry (water depth) and digital terrain elevation (DTED) from the National Imagery Mapping Agency, and the Naval Oceanographic Office. A complete list of supported data sources and data formats is provided on the following page.

Customization Support

An organization can contract ACT to create a custom version of WIPE to add functionality not present in the base system.

Supported Data Providers and Respective Data Sets

ACT has developed automatic data ingestion modules for many key remote sensing sensor systems and data formats, e.g. ERS-2/SAR, NOAA GOES data, ERS-GSST, LANDSAT, SPOT, SeaWIFS, RADARSAT, TOPEX/Poseidon, AVIRIS, ArcInfo Shape files, text data, SQL Tables. The following table provides a comprehensive list of all data sources/formats presently supported by WIPE.

Data Provider to WIPE	Sensor	Dataset Name in WIPE	Source Data Format	Internal Format
CIA (static file)	N/A - Static data	WDB Coastal Outline	Custom vector format	Same as Source
NATO/SACLANTC/DERA	ERS	GSST	Float flat file	WIPE's Internal VFF
FNMOC via TEDS	N/A Simulation	TEDS_3Dtemp	NetCDF	NetCDF
NASA via NRL	AVIRIS	AVIRIS Hyper-spectral	BIL, BIP	BIL, BIP
National Global Data Center	NGDC VAP	NGDC_Global Relief	GIF Color Image	WIPE's Internal VFF
NATO/SACLANTC	N/A – Static data	Water/Land Mask	Shapefiles	Shapefile format
NATO/SACLANTC	LANDSAT	LANDSAT	CEOS format	WIPE's Internal VFF
NATO/SACLANTC	AVHRR	Med_AVHRR	NetCDF	WIPE's Internal VFF
NATO/SACLANTC	SeaWIFS	Med_SeaWIFS	NetCDF	WIPE's Internal VFF
NATO/SACLANTC	TOPEX/Poseidon	Med_TOPEX	NetCDF	NetCDF
NATO/SACLANTC	RADARSAT-1	RADARSAT	CEOS	WIPE's Internal VFF
NATO/SACLANTC	ERS-2 SAR	SAR	CEOS	WIPE's Internal VFF
NATO/SACLANTC	SeaWIFS	SeaWIFS	Float flat files	WIPE's Internal VFF
NATO/SACLANTC	TOPEX	Topex_Gridded	Float flat file	WIPE's Internal VFF
Naval Oceanographic Office	UNK	NAVO Wrecks	DBF	DBF
Naval Oceanographic Office	UNK	NAVO_ACOUSTIC	CHAR	WIPE's Internal VFF
Naval Oceanographic Office	P3-OWL	NAVO_Bathy	Float flat file	WIPE's Internal VFF
Naval Oceanographic Office	UNK	NAVO_Mines	DBF	DBF
Naval Oceanographic Office	UNK	NAVO_Roughness	Shapefiles	Shapefiles
Naval Oceanographic Office	N/A	NAVO_Sediments	Shapefiles	Shapefiles
Naval Oceanographic Office	SPOT	NAVO_SPOT	GeoTiff	WIPE's Internal VFF
Naval Oceanographic Office	MODEL	NAVO_Temperature	NetCDF	NetCDF
Naval Research Laboratory	MODEL	NEMO	ORASIS Compressed	ORASIS Compressed
Naval Research Laboratory	N/A – Simulation	TEDS	NetCDF via DEI	REMOTE ACCESSS
NIMA data via NRL	N/A – Static Data	DBDB V1.0	NIMA's format	WIPE's Internal VFF
NIMA data via NRL	N/A	DTED	NIMA's format	WIPE's Internal VFF
NOAA	MODEL	FNMOC	GRIB format	NetCDF
NOAA	RADARSAT-1 & ERS-2 SAR	CW_SAR	CEOS	WIPE's Internal VFF
NOAA	NOAA Buoy's	BUOY Measurements	ASCII files	SQL Table
NOAA	GOES	GOES_IR	Flat file	WIPE's Internal VFF
NOAA	GOES	GOES-8	Float flat time	WIPE's Internal VFF
NOAA	SSM/I	SSMI_Wind	ASCII Table	SQL & Float file with 0.3deg resolution
NOAA	NOAA-14/15	SST_14Km	Float Flat file	NetCDF
NOAA / JHU/APL	SAR VAP	APL_SAR_Wind	NetCDF	WIPE's Internal VFF
NOAA / ERIM International	N/A -VAP	Derived Ship locations	ASCII Table	DB Table
NRL and NASA	Clementine	Clementine	PDS	PDS

Server Side Requirements

Server Side Minimum Hardware Requirements

The minimum hardware requirement for WIPE is a fully dedicated Windows NT machine (4.0 or higher). Hard disk requirement depends on the data ingestion and serving needs. Note: A high-end WIPE system can consist of a network of WIPE servers with terabyte archive storage capabilities.

Client Side Minimum Hardware Requirement

The minimum hardware requirement on the client side is any computer with a recent version of Netscape or Internet Explorer (IE) browser. At this time WIPE has been tested with:

- Netscape (version 4.0 or above)
- Internet Explorer (5.0 or above)

In either case we use the SUN's swingjar JAVA classes to provide a consistent graphical user interface between platforms. The swingjar classes can be downloaded from http://wipe.actgate.com.

In WIPE most of the work is done at the server. Hence, the basic load on the on the client computer is to run the WIPE applets. As the user downloads more images, the applet will use more memory resources to facilitate easy access to previously downloaded images quickly.

Client Side Requirements

Browser Requirements

The basic interface to a WIPE server is via a WEB browser. At this time the two browsers under which WIPE has been tested are:

Netscape (version 4.0 or above)

Internet Explorer (5.0 or above)

In either case we use the SUN's swingjar JAVA classes to provide a consistent graphical user interface between platforms. The swingjar classes can be downloaded from SUN or from ACT http://wipe.actgate.com.

Hardware Requirements

Almost any computer with a browser can connect to a WIPE server over the INTERNET. In WIPE most of the work is done at the server. Hence, the basic load on the on the client computer is to run the WIPE applets. As the user downloads more images, the applet will use more memory resources to facilitate easy access to those previously downloaded quickly.

Data Access Rights

Security in WIPE is build on TOP of the Windows/NT security. Each user must have a dedicated login and password. In addition to the Windows/NT security the WIPE administrator can control:

- IP addresses that can have access to the WIPE server
- Data-set level user group access. For example, if a given user belongs to the NATO group, then all NATO data will be accessible.
- WIPE commands that the user can execute in the interpreter engine

HIGH LEVEL SEARCH BROWSER

Description of the HLSB Screen

The WIPE High Level Search Browser is used to simplify the process of finding data. Data is found by specifying constraints in region of interest (ROI), time of interest (TOI), and dataset types. These constraints are checked against the Meta-data records in WIPE. The HLSB is the equivalent of a catalog for data available at the particular WIPE server to which the user is connected.

The following figure shows an example of the High Level Search Browser applet. The applet display, buttons, and menu tabs are explained in the tables below the figure.




Figure 1 Sample Screen of 'High Level Search Browser'

HLSB Controls

Screen Item	Description
	TOI or Time-of-Interest – this block of data is used to specify the window of
TOI	time to use in the meta-data query. It allow the user to request an absolute time
101	range, or a relative time range, e.g. the last 5 months, or 5 hours, etc. TOI is
	defined in UTC time (more commonly known as GMT).
	Region of Interest to be used in the construction of the spatial query. Must be in
ROI	Rectangular Mode in HLSB. The user can either draw a box over the image to
	specify the ROI, or enter the bounding latitude and longitude values.
Background	Click on pull down menu to display the list of available background data sets to
Dackground	use in the image display. Available backgrounds depend on the particular WIPE
	server configuration.
	Select any dataset from this list of datasets by clicking on checkbox. Click on
Data Sets	the UPDATE button to view the dataset coverage on the Image Display Screen.
(List)	Change the position of the dataset in the list by clicking on the dataset name to
(List)	highlight it and click on the up and down arrow buttons. The double-arrow
	buttons move the highlighted dataset to the top or bottom of the list.
Overlays	Select the optional overlays to be used in the display. Some of the normally used
Overlays	overlays are: vector shore lines, lat-lon grid, rivers, etc.
Data Sets	Displayed above the image window. Provides a summary of the data sets
On Display	displayed on the image screen.
Xfactor	N/A - this field does not have useful information in the HLSB
V.PixelRes	Vertical Pixel Resolution. Provides the actual vertical screen resolution of a

	pixel.
Reset	Click to reset the applet. The Image Display Screen will reset to default zoom, overlay, and background. All datasets will be unselected and cleared from image display.
Update	Click to update the display with newly selected datasets, overlays, ROI, and TOI. NOTE: the update button MUST be clicked to enable any changes in the above items. The applet can also be updated using the pop-up menu accessed in the image display (see Pop-Up Menu table below).

HLSB Image Display Tabs

Image	Description	
Display Tabs		
Image	Image Display Screen. Shows datasets, overlays, and background image. At zoomed-in mode the navigation arrows surrounding the display can be clicked on to move the viewing window. Also, right clicking while in the image display brings up a pop-up menu (see Pop-Up Menu table below).	
URL_Info	Displays the separate variables that are passed to the WIPE server via the URL at the top of the screen. The variables themselves are described in the WIPE Server Manual. This will help in the creation of custom scripts by showing the current values of the more commonly used variables.	
Server messages	Displays a time-ordered list of command calls made by applet. Used primarily to trace errors that may have occurred while running WIPE.	
Options	Customized for individual institutions. Some examples of options are: selecting lat/lon format display (decimal notation vs. hours, minutes, seconds notation) and view centering on specific longitudes.	

HLSB Menu Options

Main Menu

Menu Item	Menu Item List	Description
Preferences	Session Profile	Click to access the Session Profile Administrator (SPA) and the
	Admin	SPA will open in a separate window. From the SPA the user can
		save, edit, and recall the state of a WIPE server (a session
		profile). This allows for easy distribution of information
		between different users.
	Resize Applet/Image	Allows the user to Resize Applet/Image. Click on menu choice
		to edit the display properties (Width, Height) of the Applet and
		Image Display. Click SUBMIT to enable changes.
TimeSeries	By Months	Displays in tabular format, by month, the datasets found within a
		user-defined ROI and TOI.
	By Days	Same as above, with datasets sorted by days
	By Hours	Same as above, with datasets sorted by hours
Access	Get Data in Box	Opens the Interactive Data Browser (IDB) window for more
		detailed user manipulation of the selected datasets. See the IDB
		section for more detailed explanation of the browser functions.

	Get Metadata in Box	Shows the datasets and content type of the datasets found within the user-defined ROI. Content information includes: Date, Time, Size of image (row by column, in pixels), File Format, approx. area covered, and bounding box lat-long coordinates.
Info	Overlay Info Storage Statistics	Describes the overlays currently selected in the HLSB screen. Shows how much data has been processed over certain periods of time (last hour, last 24 hours, total) as well as how much data is currently being processed by the WIPE server.
	Usage Statistics	Displays access statistics such as number of times accessed, number of files downloaded, and number of pages viewed.
Animation	Play Animated Data	Opens a WIPE Animated Data Viewer browser, which starts playing stored frames of the Image Display screen. See the Image Animation section for further detail on how to use the Viewer.
Geo-	Country	Select a country to view in the Image Display Screen.
Locator	State/Province City	Select a State or Province to view in the Image Display Screen. Select a city to view in the Image Display Screen.
Image	Get Pixel Values	Not applicable to the HLSB; menu choice is grayed out.
Help	About	Displays an overview of WIPE in PDF file format.(A PDF reader, such as Acrobat Reader 4.0 is needed).
	DataSets Info	Opens a separate browser which lists the available datasets, gives a brief description of them, and links to web sites which can provide more information.
	Wipe User Manual	Displays the Wipe User's Manual. This requires Adobe Acrobat Reader or Adobe Acrobat 4.0 or higher to read the PDF file.
	ProviewUser Manual	Displays Proview User's Manual. This requires Adobe Acrobat Reader or Adobe Acrobat 4.0 or higher to read the PDF file.

Pop-Up Menu

Right-click while the pointer is on the image display screen in order to bring up a pop-up menu. This allows for greater flexibility in interacting with the image. Close by left clicking outside of the menu.

Menu Item	Description
Center on Point	Centers the Image Display window on the mouse pointer.
(Dbl-Click)	Double clicking in the Image Display Screen performs the same
	function.
Zoom In	Zooms into the user-defined ROI. If no ROI is defined, a
	rectangular ROI will be created, with corner points at the upper
	left corner of the image display, and the mouse pointer. The
	applet will then zoom into the rectangular ROI.
Zoom Out	Zoom out to the next highest scale factor
Previous – Next	WIPE will cache the applet state such that the user can switch
	back and forth between already created states using the Previous
	and Next buttons. A state is cached when the user presses the
	zoom, update, or reset buttons.
Update – Reset	Functions the same as the Update and Reset buttons on the
	HLSB main display.
Clear ROI Selection	Removes a user-defined ROI from the Image Display Screen.

Iterate All	Starts the applet based animation. (see Image Animation below)
Go to Full Resolution	Displays the selected dataset in full-scale resolution. (xfactor=1)

Interaction With Session Profile Administrator

The Session Profile Administrator screen allows the user to manage different session profiles. These profiles allow the user to save an applet state for later analysis and sharing of information with other users. The next figure shows an example Session Profile Administration Window.




Figure 2 Sample Screen of 'Session Profile Administratorr'

Save Session Profile

Perform the following steps to save a session profile:

- 1. Click on the "Save Current Applet Settings" button and type in the name of the profile you wish to save in.
- 2. Click on the "Share with:" pull down menu and select NONE, ALL or WIPE ADMIN. Note: this can be further customized to allow access to certain groups.
- 3. Enter any comments in the "Comments" message box.
- 4. Click on the SUBMIT button.

Load and Delete Session Profile

Perform the following steps to load a session profile:

- 1. Click on the "Invoke a Profile from List:" button and select a session profile from the pull-down list.
- 2. Select the "Image Size Factor" desired.
- 3. Click on the SUBMIT button.

To delete a session profile from the list:

- 1. Click on the "Delete a Session Profile" button and select the desired profile to delete from the pull down list.
- 2. Click on the SUBMIT button

Image Animation

Image Animation refers to the cycling of cached image displays in succession, either through the applet itself, or through the WIPE Animated Data Viewer (WADV). The WADV is a custom JavaScript executed by the applet when the user selects certain animation commands. When describing the image animation methods, the individual images may sometimes be referred to as frames.

Applet Based Animation

Applet based animation in the High Level Search Browser (HLSB) is done by cycling through a series of cached images or frames and displaying them in the Image Display Screen (IDS). Please refer to the tutorial at the end of this document for detailed steps on how to create an animation sequence.

Javascript Animation

This method uses the Animated Data Viewer (JavaScript viewer) for finer control of the animation. The method used to create the images is the same as the one for applet-based animation.

Once a sufficient series of images has been created, click on the DATA button in the ToolBar Menu, and select PLAY ANIMATED DATA. This should bring up the WIPE Animated Data Viewer. The following page shows an example of the Viewer, along with a table describing the different Viewer controls.




Figure 3 Screenshot of WIPE Animated Data Viewer

Animated Data Viewer Menu Options

Menu Item	Description
Loop Mode	Set the continuous looping method used by the Viewer. The left button sets looping
	to start with frame 0, cycle to last frame, then start back at frame 0. The right button
	sets looping to go from frame 0 to last frame, then reverse direction back to frame 0.
Animate Frames	Start and stop frame animation and determine the looping direction for the frames
	displayed. Left and right buttons determine direction, center button stops animation
Dwell First	Left and right buttons decrement and increment the amount of dwell time spent on
	the first frame in the frame list.
Dwell Last	Left and right buttons decrement and increment the amount of dwell time spent on
	the last frame in the frame list.
Adjust Speed	Increase and decrease the frame cycle time with the left and right buttons
Advance One	Advance or Step back in one frame increments with these buttons.
Frame No:	Current frame displayed in viewer window
Omit Frame	Select frames to omit from animation cycle by clicking on checkbox
Link to Zip File	The hypertext link at the bottom of the Animated Data Viewer starts an on-the-fly
	zip file creation process, which the user can download to the client machine. The zip
	file contains all the images and an html page needed to view the animation on the
	client machine.

INTERACTIVE DATA BROWSER

Description of the IDB Screen

The Interactive Data Browser (IDB) contains the menu choices and list boxes that allow the user to select, in detail, the data content that will be displayed on the image display screen. It also allows the user to analyze the data using various visualization tools. The layout of the IDB screen is very similar to that of the HLSB screen. The TOI section is no longer displayed because the user is now concentrating on the data sets that fit within the Time-of-Interest specified in the HLSB. The menu toolbar, data set list and other items contain choices that deal more directly with the data sets of interest and tools necessary to process the data.




Figure 4 Sample Screen of 'Interactive Data Browser', depicting derived Wind directions with shoreline and latlon grid overlays. Note the additional layers displayed in the 'Layers' window, which indicate the availability of data at different altitudes.

IDB Applet Controls

Screen Item	Description
ROI	The drop-down menu allows the user to choose the method of defining the Region of
	Interest (ROI). It can be defined as a rectangular ROI, a line, or a series of points. The
	ROI method is used in conjunction with various plotting tools, e.g. Line method must be
	used in order to use the 'ROI Line Plot' Menu Item.
	The "N,S,W,E" boxes show the current latitude, longitude bounds of the Image Display
	and can be user-edited to quickly change the viewing window location.
xFactor	Displays the scaling factor used by the Image Display Screen.
V.PixelRes	Displays the actual vertical resolution of a pixel on the Image Display Screen.
Zoom	Perform same function as in HLSB. Click to zoom into or out of the ROI.
Prev – Next	Located below the zoom buttons are 2 arrows facing left and right. They allow the user
Arrows	to go back and forth between the previously cached applet states. An applet state is
	cached when the user presses the zoom and update buttons.
Navigation	Surrounding the Image Display are navigation arrows. They allow the user to move the
arrows	viewing window in the direction indicated by the arrows.
Data Sets	Select any dataset from this list of datasets by clicking on checkbox. Then click on the
(List)	Update button to view the dataset coverage on the background. This list provides a more
	detailed breakdown of the datasets chosen in the HLSB; ex. the user selects the "IR"
	dataset in the HLSB, then the IDB will show a list of IR bands within the "IR" dataset.
Layers	The data set may be further subdivided into layers, e.g. altitude bands for atmospheric
	data. If so, then the layers will be displayed here for selection by the user.

Overlays	As in the HLSB, the Overlays list allows the user to display other information of interest	
	over the datasets in the Image Display. Some examples of useful overlays are: LatLon	
	grid, Magnification Factor, shorelines, etc.	

IDB Image Display Tabs

Display Tab	Description	
Image	Image Display Screen. Clicking on this tab displays the image mosaic of the currently selected datasets.	
URL Info	Displays the variables passed to the ProviewWeb script as well as the script that is called. Useful for determining the kind of variables needed to generate a custom script that will generate the same image as that currently displayed in the <i>Image</i> tab. See the <i>Wipe Server Manual</i> for more information about the commonly used WIPE variables.	
Server Messages	Shows the status messages returned by the WIPE server after it has finished processin commands generated by the WIPE applet. These commands could be the generation of an image mosaic, javaviewer animation or plot function. The status messages are useful for tracking down any errors encountered in processing and to verify the list of selected datasets. NOTE: The status messages are specific to the current applet. For example updating the display in the HLSB would not update the trace list in the IDB. Also, two IDB applets would have their own separate list of server messages.	
Dataset	Shows a listing of the currently selected datasets and various parameters. (See figure for	
Control	Dataset Control). Also allows the user to customize the region of interest of each individual dataset via the MSHELL scripting language. From the list of currently selected datasets, the user can click on the EDIT button under XROI to bring up a mini console screen display. Within the display, the user can click on EXAMPLE CODE to examine a sample script, type in a script of their own, and click OK to enable the script or cancel to exit out of the mini-console. The user must then click UPDATE in the IDB to execute the script.	
Custom Script	Allows the user to build and execute a custom script for execution (via MSEHLL, the image processing interpreter language). See "Built-In Interpreter Language (MSHELL & PROVIEW)" for more detail.	
Options	Customized for individual institutions. An example option is: selecting lan/lon format display (decimal degrees notation vs. hours, minutes, seconds notation).	

DataSet Control

The DataSet Control tab shows a table of parameters being used to control how the data values are displayed in the Image Display Screen (IDS). These values are set to the defaults when the applet is initialized. The default values are specified in the SQL table 'Data Control'. The user may then change the values that control the way the data is displayed. Any changes are then stored by the applet for the current session. These changes are applet specific. Thus, multiple users may work on the same dataset, each using a separate applet and assigning different parameters to the dataset.

This table will display the parameters for a dataset as soon as the user selects it by clicking on the checkbox in the dataset window. However, the dataset itself will not be shown until the user hits the Update button. This allows configuration of parameters before dataset display.




Figure 5 Close up view of the DataSet Control tab in the Image Display Browser.Note that the selected DataSet and ID are the same but that the layer values are increasing. This is an example of a multi-layered dataset.

DataSet Control Fields

Field Name	Description	
DataSet	Shows the currently selected datasets.	
ID	Displays the DataSet ID. It is usually a string based on the data collection time or so other identifier that separates it from other data files within the same DataSet.	
Layer	The selected layer within a particular DataSet-ID. The figure above illustrates the ability to set the parameters for different layers within a particular DataSet-ID group. In the figure, the DataSet consists of Wind Direction data values, the ID defines the particular data values are for Jun 24, 2000 and the multiple layers indicate the data is stored in arrays corresponding to specific altitudes.	
Rmin	The minimum value to use.	
Rmax	The maximum value to use.	
XROI	Clicking the 'EDIT' button brings up a text window which allows the user to specify a GROI for the dataset by using the ProVIEW scripting language.	
Interpolation	Displays the type of interpolation used on the data values. 0 to use zero order interpolation, 1 to use first order interpolation.	
IMF Displays the Image Mapping Function and min, max values to use for the furbelow for a more detailed description of the three available functions and the the displayed image.		
Palette	Palette Specifies the palette file to use when mapping data values to color values.	

IDB Menu Options

ToolBar Menu

Menu Item	Menu Item List	Description
Preferences	Session Profile Admin	Functions the same as the 'Session Profile Admin' item in the
		HLSB. See the "HLSB ToolBar Menu" table for more details.
	Resize Applet/Image	Functions the same as the "Resize Applet/Image" item in the
		HLSB. See the "HLSB ToolBar Menu" table for more details.
Image	Geo-register	Allows the user to affix the dataset image to a geographical feature (such as a shoreline). Must first select ROI Line and draw a line from the image to the geographical feature before calling this function.
	Get Pixel Values	Enables the Image Display Screen to show actual data values for each pixel as the user moves the mouse pointer over the image. A small display at the base of the pointer will show the lat, lon, and pixel values.
Legend	Legend Info	Displays information about the ROI selected in the Image Display Screen on a separate window. This includes the dataset name, overlays used, image size, and area of interest.
	Overlay Info	Shows information about the overlays selected by the user.
Plot	ROI Line Plot	Creates a line plot which corresponds to an ROI line drawn on the image display. The x-axis is the distance along the ROI Line (in units corresponding to the dataset) and the y-axis is the value of the data along the line. WIPE will also generate a hypertext link to an ASCII file containing the data used in the plot creation. NOTE: The user must first select the ROI Line method and click-and-drag an ROI Line across the image display.
	ROI 3D Plot	Creates a 3-dimensional data plot corresponding to a rectangular ROI. NOTE: The user must first select the ROI Rectangular method and click-and-drag a rectangular box across the image display.
	Layer Plot	Used for multi-layered dataset plots. At least 2 layers must be selected before clicking this menu item. The plots depend on the ROI type selected by the user: Rectangular ROI results in one 3-D plot per layer. Line ROI results in a line plot for each layer. Points ROI returns a single, multi-line plot.
	Topo Drape	The dataset image is mapped to internal digital terrain elevation and bathymetry databases in order to create an image of the data draped over topological features. This allows for instant visual referencing of the data to known geographical features. Topo Drape can also be customized via several menu options. Explained in Topo Drape Options (see below).
Download	Flat File	Displays a hypertext link to a downloadable file containing the pixel values as shown in the Image Display Screen along with a short description of the file type and a jpeg of the image to be downloaded.

	Volumetric Visualization	Allows the user to choose between different display methods for viewing multiple image planes in the same volumetric space. See Volumetric Visualization Methods for more detail.
Info	Storage Statistics	Shows how much data has been processed over certain periods of time (last hour, last 24 hours, total) as well as how much data is currently being processed by the WIPE server.
	Usage Statistics	Displays access statistics such as number of times accessed, number of files downloaded, and number of pages viewed.
Animation	Play Animated Data	Opens the Animated Data Viewer, which starts playing stored frames of the Image Display Screen. The stored frames are specific to the IDB, and will not impact the frames stored for the HLSB. Otherwise, the instructions for creating an animation are the same as in the HLSB Image Animation section.
Execute	Edge Detection	Displays results of a script that tries to detect "edges" of an image, as defined by sharp contrast differences.
METOC	Data Probe for Points Selected	Generates a plot of meterological conditions at user selected points on the image. Requires that the WIPE server have access to meteorological data.
	Flight Path Profile	Generates plots of meterological conditions along a flight path traced by the user across the image. Requires the WIPE server to have access to meteorological data.
Help	DataSets Info	Opens an HTML table which lists the available datasets, a brief description of each dataset, and a URL link to a site containing more information about the dataset.
	Wipe Users Manual	Opens the Wipe Users Manual (in PDF file format).
	ProVIEW Users Manual	Opens the ProVIEW users Manual (in PDF file format).
	About	Displays an overview of WIPE, its features and a sample animated gif created by a WIPE module.

ROI Line Plot




Figure 5 Sample Output of "Plot/ROI LINE PLOT" The x-axis shows the distance from the starting point along the ROI LINE. The y-axis shows the pixel values along the line. The hypertext link allows downloading of plot data to the client computer.

ROI 3D Plot




Figure 6 Sample Output of "Plot/ROI 3D PLOT"

Topo Drape




Figure 7 Sample Output of "Plot/Topo_Drape" option. Note the menus at the top that allow for user rotation, tilt, size, scale, and topo choice. This plot allows for easy identification of the mountain region in the upper left corner, as well as the island at the entrance to the harbor.

Topo Drape Options

The topo drape view window also contains several drop-down menus which both show the current settings for the topo drape options and allow the user to change those settings. The menu headers will also display the following information via tool tips (shown when the pointer rests on the header):

Topo Drape Option	Description
Current Rotation	The rotation angle (in degrees) of the topo image relative to the original orientation. Rotation is measured positive counterclockwise along the vector normal to the image.
Current Tilt	The tilt angle of the topo image (in degrees) relative to the original orientation. Tilt is measured positive clockwise along a vector in the plane of the image and normal to the right side of the image.
Current Image Size	The size of the image measured as an N by N box, where N is selected by the user.
Current Scale Num	The amount by which height differences are exaggerated. A higher scale number increases the exaggeration.
Current Topo Choice	Choose whether to use only DTED (digital terrain elevation data), only Bathymetry (ocean depth data), or both

Volumetric Visualization

There are many instances where datasets will overlap a given region of interest. Several examples are, infrared sensor collections, bathymetry measurements, and repeated satellite images of the same location at different times. In addition, each dataset type may have different layers depending upon the data format. It is often valuable to the user to be able to view different datasets for one particular region. WIPE contains different methods of viewing data in this manner, using the Volumetric Visualization menu item (located under the DATA tab in the IDB toolbar).

Visualization Method	Description
Create a NetCDF file	Creates a NetCDF file and a hyperlink to
	the file to be downloaded. See Tutorial for
	more details on the NetCDF file option.
Generate a 3D Layer	Creates a 3D image cube which contains
Cube	the datasets as images arranged in layers
	parallel to the top face of the cube. See
	figure below for example output.
Generate a Java Movie	Creates a separate frame for each image
Sequence	layer and opens the Animated Display
	Viewer to cycle through each frame.

Data Visualization and Formatting For Download




Figure 8 Sample output of "Data |Volumetric Visualization|Generate 3d layer cube". This visualization option allows for simultaneous viewing of the same region from different sensor datasets.

Overlaying Options on Image Screen

Image Animations

Image animations in the IDB are created in the same manner as in the High Level Search Browser. The two animation options are applet-based and JavaScript based. There are two different display modes that utilize the javascript viewer – IDB animation and Volumetric Visualization.

IDB Animation

IDB Animation is the cycling of frames created in the IDB Image Display Viewer. The frames are stored separately from the frames in the HLSB, and thus can be manipulated, and even RESET without affecting the HLSB animation frames.

Volumetric Visualization through Java Movie Sequence

The Volumetric Visualization menu item (under the DATA tab in the Toolbar) is used to visualize multiple datasets, and multiple layers within those datasets, covering the same region of interest. One method of visualization is via a Java movie sequence. The Java movie sequence essentially cycles between the selected datasets and layers that fall within the bounds of the Image Display Screen.

Access to Built-in Interpreter Language

WIPE allows the user access to its internal engine via various "custom script" menu choices. This allows for a highly customizable processing environment. The user is able to directly enter custom commands via the Custom Script Tab in the Image Display Screen (for both the HLSB and the IDB). Within the IDB the user is also able to enter custom scripts for individual datasets using the Database Control tab and selecting the XROI button. The scripts are written in MSHELL, the WIPE image processing interpreter language.

Custom Script Tab in Image Display Screen

The Custom Script Tab transforms the IDS into a rudimentary text editor used to enter MSHELL code. The user should first select the Output Type. This not only determines the output format, but also allows for different scripting methodologies. For example, the output could be unformatted MSHELL output intended for quick problem resolution or output in nicely formatted HTML for use in sharing information. WIPE currently supports the following output types:

- ProVIEW Calculator (HTML preformatted) used for quick calculations or scripting with minimal output formatting. The output is sent to a separate browser window and is contained within default HTML code.
- HTML Text (Using HTML formatting) allows for greater customization of output by using HTML code. Formatting is done through the use of PRINT statements containing HTML code, i.e. print "<HTML><BODY> Hello World </BODY></HTML>"
- User-defined (Must specify content-type) Allows for even greater customization through the use of different contenttypes to display on the web page. Some examples are, image content-type (for displaying jpeg output) and message contenttype (for email and/or download).

Custom Scripting via DataSet Control

Occasionally the user may need to define a region of interest that is not spatially dependent, but rather dependent on dataset values. Or the user may want to automate the definition of a region of interest such that it can be quickly and easily applied to a dataset. Through the Dataset Control tab in the IDB display, the user can edit the XROI of a particular dataset and enter custom MSHELL scripts.

Common WIPE applet variables

The following table shows the more common WIPE variables a user can manipulate via custom scripts:

Variable	Description	
----------	-------------	--

CenterLong	Center longitude as calculated by the following formula: $CenterLong = str2float(\$AxI) + (str2float(\$Ax2)-str2float(\$AxI))/2$
M_longlat0	Global variable which contains the corners of the world (in lat-lon coordinates) in a rectangular ROI going from upper-left, upper-right, lower-right, lower-left (UL,UR,LR,LL).
M_longlat	Global variable which defines the corner boundaries of the image display in lat-lon coordinates, going from UL,UR,LR,LL.
M_longlat_2d	Global variable which defines the corner boundaries of the rectangular ROI defined by the user in the image display (in lat-lon coordinates).
LongDif	Absolute difference (degrees) between the two longitude lines that define the sides of the image display.
M_H	Global variable which defines the image display size height in pixels, can be changed by selecting <i>Resize Applet/Image</i> in the applet menu bar.
M_W	Global variable which defines the image display size width in pixels, can be changed by selecting
d: 11	Resize Applet/Image in the applet menu bar.
\$ipaddr	The IP address of the client computer displaying the WIPE applet.
\$count	Each image on the image display window is actually a jpeg file with a specific filename. The filename is based on <i>\$ipaddr</i> , the current time, and <i>\$count</i> , which increments by 1 in order to prevent files being overwritten when 2 requests for images are sent to the applet within a very small period of time (such as when a user enters a rapid succession of clicks to the applet).
\$x1	Longitude of upper left-hand corner of rectangular ROI. Same as \$vx1 for no user defined ROI.
\$y1	Latitude of upper left-hand corner of rectangular ROI. Same as \$vy1 for no user defined ROI.
\$x2	Longitude of lower left-hand corner of rectangular ROI. Same as \$vx2 for no user defined ROI.
\$y2	Latitude of lower left-hand corner of rectangular ROI. Same as \$vy2 for no user defined ROI.
\$c1	Column number of the upper left-hand corner of a rectangular ROI box on the image display screen (IDS). This number starts at zero (at the upper left-hand corner of the IDS) and increases toward the right hand side of the IDS. The upper limit of \$c1\$ is \$M_W\$. If the user does not define an ROI then the entire image display screen is treated as the ROI.
\$r1	Row number of the upper left-hand corner of a rectangular ROI box on the image display screen (IDS). This number starts at zero and increases toward the bottom of the IDS. The upper limit of \$r1 is M_H. If the user does not define an ROI then the entire image display screen is treated as the ROI.
\$c2	Number of columns in the rectangular ROI on the image display screen.
\$r2	Number of rows in the rectangular ROI on the image display screen.
\$vx1	Longitude of upper left-hand corner of image display.
\$vy1	Latitude of upper left-hand corner of image display.
\$vx2	Longitude of lower left-hand corner of image display.
\$Ax1	Longitude of upper left-hand corner of world as projected on a rectangular flat surface.
\$Ay1	Latitude of upper left-hand corner of world as projected on a rectangular flat surface.
\$Ax2	Longitude of lower right-hand corner of world as projected on a rectangular flat surface.
\$Ay2	Latitude of lower right-hand corner of world as projected on a rectangular flat surface.
	Defines the amount by which M_longlat has to be adjusted in order to center the world view on a
\$adjust	different longitude. Set by the user in the Options/Center View at Longitude field in the applet.
\$DataSet	List of datasets in the following format: "dataset1 dataset1id@layer1,dataset2 dataset2id@layer2". Note that each dataset-id-layer string is comma delimited. The dataset and dataset ID should correspond exactly to that shown in the datasets list window in the applet. Also, the layer number corresponds to the layer selected for that particular dataset. Note that this variable is updated only after the user has clicked on the <i>UPDATE</i> button on the applet
\$GROI	The Generalized Region Of Interest for each dataset in \$DataSet, in the creation of the image shown in the image display. If it is not specified it defaults to "[s1][s1][s2][s1]" where [s2] is the separator between the GROI for each dataset.
\$Scaling	The scaling factors used for each dataset in \$DataSet, in the creation of the image shown in the image display. If it is not specified it defaults to "Default[s1][s1]" with "[s2]" being the separator

between the scaling factors. Scaling factors are two numbers corresponding to min scale and max scale.
The palette used for each dataset in \$DataSet with "[s2]" being the separator between the palettes. The palette choices are the numbers used in the woolut table (defined in the ProVIEW manual).
Currently set to "Default[s1][s1]" for each dataset in \$DataSet with [s2] being the separator. Not
currently implemented, but will be used in a future version to create contour lines as an overlay on
the image.
Column vector where each row shows the layers used in \$DataSet. If the layers are all the same,
then it returns a single value.
Comma delimited string containing all the overlays used in the creation of the image.
Defines which background is used in the creation of the image in the IDS.
Defines the ROI type currently selected in the applet. "0" is line, "1" is rectangular, and "2" is
point ROI.
Contains the column coordinates for a line segment, used in the creation of line and layer plots.
Contains the row points for a line segment, used in the creation of line and layer plots.
Longitude coordinates for the points in \$lsc,\$lsr.
Latitude coordinates for the points in \$lsc,\$lsr.
Name of the institution for which the WIPE server is running and processing data. Used to identify
the SQL database (or databases) used by the WIPE server.
Width of the entire applet in pixels
Height of the entire applet in pixels
Width of the image display screen in pixels
Height of the image display screen in pixels
Selects which applet type to use – HLSB or IDB
Starting date and time of interest.
Ending date and time of interest.
Global variable which defines the time to use as the start of a day, usually "00:00:00".
Global variable which defines the time to use as the end of a day, usually "23:59:59".
Defines the number of \$Time_Delta_Units to search for.
Defines the time unit used when performing a relative time search. Ex. "hour", "month", "day".
Sets method used to determine time of interest in the applet. For a "0" value it uses the Start Time
and End Time fields in the applet to define the time of interest. For a "1" value it searches for data
in the last \$Time_Delta amount of \$Time_Delta_Units. Ex, "Last 24 hours" would be
\$Time_Delta=24, \$Time_Delta_Units="hour"
Contains the code entered by the user in the "Custom Script" tab on the IDS as well as supporting
code needed to run it and output to a browser window.
Global variable which sets which applet type to use – HLSB or IDB
Used in various external functions to describe the data currently being processed. In the context of
the IDB for example it describes the image shown in the IDB as "Compiled_Data".
Column vector where each row is a string corresponding to the dataset-id-layer item contained in
\$DataSets
Global variable defining the start date and time of interest.
Global variable defining the end date and time of interest
Global variable defining the layers being used
Global variable defining the overlays used in the image displayed.
Same as <i>M_H</i> except in string variable format
Same as M_W except in string variable format

Glossary of Terms

Applet State

Refers to the state of the WIPE applet with regard to the selected ROI, TOI, datasets, overlays and layers. The applet does not change its state until it is called by WIPE, and is executed whenever the user clicks the UPDATE, or ZOOM buttons. Also, each WIPE applet has its own associated state. Thus, the state of an IDB and a HLSB will be separate and not interfere with each other, or with other IDB and HLSB applets currently being run.

GROI

The Generalized Region Of Interest. Defines the regions of an image that satisfy a user-defined set of criteria. The regions may be spatially separate or even exist as a series of points. For example, a GROI of an image could be any pixel that is 10 units above the mean pixel intensity value. Also referred to as an "image blob". GROI may be specified by utilizing custom MSHELL scripts.

Image Plane

An arbitrarily defined plane which contains the image information for a specific dataset. In the case of datasets with multiple layers, each layer selected occupies its own image plane. Used in the creation of a volumetric visualization cube or NetCDF file.

Metadata

Data about data. It describes how, when, and by whom a particular set of data was collected and how the data is formatted. Used to understand the dataset information stored in WIPE.

MSHELL

A 32-bit interpreted image/signal processing language, used to generate custom WIPE interfaces. MSHELL scripts allow the user to customize the power of existing WIPE processing functions to fulfill his specific needs.

NetCDF

The Network Common Data Form, a file format that contains array oriented data in a form that is self-describing and network transparent.

"Self-describing" refers to the file containing information about the data it contains. "Network transparent" means that the file is such that it can be accessed by computers with different ways of storing integers, characters, and floating point numbers. Within the WIPE process a NetCDF file can be visualized as a cube of data, where the length and width of the cube are the N X M dimensions of the data arrays, and the height of the cube is the number of data arrays contained. NetCDF variables then can store data such that they contain the same sized arrays (N X M) and varying numbers of such arrays within the cube. This works well when dealing with layered datasets such as atmospheric temperature data which is collected at different altitudes. A complete format can explanation of the NetCDF be found http://www.unidata.ucar.edu/packages/netcdf/guide.txn toc.html.

ROI

Region of Interest. A spatial area of interest defined by using WIPE methodology for selection: Rectangular, Line and Points. Rectangular method specifies an area of interest by clicking and dragging a box on the Image Display Screen. Line defines the area by clicking and dragging a line. Points allows for ROI definition by clicking at various points on the IDS.

Universal Time Coordinated (UTC)

Also known as Coordinated Universal Time, formerly and widely known as Greenwich Mean Time (GMT). UTC is based on an atomic clock to which adjustments of a second (leap second) are sometimes made to allow for variations in the solar cycle. It nominally reflects the mean solar time along the Earth's prime meridian, which runs through the Greenwich Observatory outside of London.

Viewing Window

The field of view of the Image Display Screen with respect to the image plane. The ZOOM buttons change the field of view. The IDS size itself is changed by using the RESIZE APPLET/IMAGE menu item.

WIPE TUTORIALS

Introduction

The following tutorials cover the basic operations of WIPE and are intended to enable the user to start processing and analyzing data as quickly as possible. The datasets shown in these examples will not necessarily be the same as that in the user's own WIPE server due to the fact that each server is configured to the specific needs of each institution. However, WIPE offers the same functionality regardless of dataset, and the user is encouraged to follow along, substituting his own datasets for those in the example.

HLSB Tutorials

High Level Search Browser Basic Operations

This tutorial will explain how to select datasets for display in the HLSB, zoom in on the datasets, manipulate them, and change the viewing window. Before following the tutorial, please make sure of the following:

- WIPE HLSB is running and user is logged into a WIPE Server with access to at least 1 dataset.
- HLSB is in default view. The view should show a world background and have no datasets selected. Press the RESET button near the upper right corner of the HLSB if this is not the case.

Selection of Datasets in HLSB

- Select a dataset to display by clicking on a checkbox next to one of the available datasets in the DATA SETS list.
- 2. Check the OVERLAY list and make sure the LatLon Grid overlay is selected. Click in the checkbox if it is not.

- 3. Click the UPDATE button. The status bar along the lower left edge of the HSLB should show "status: Updating applet". When the applet is done updating the display the status bar should return to "Status:".
- 4. The Image Display Screen (IDS) should now show at least one small colored polygon. The colored polygon serves to illustrate the dataset coverage. The "Data Sets on Display" bar above the IDS should also show the name of the selected dataset. There may be more than one colored polygon depending on the institution. If there is no polygon visible, then the area covered by the dataset may be smaller, and harder to visualize against the background.
- Ensure that the ROI menu tab is showing ROI:Rectangular.
 The user will now use the zoom features to zoom in closer to a selected dataset.
- 6. Move the mouse pointer over the left hand corner of a colored polygon then click the left mouse button down and drag it such that a dotted rectangle encloses the polygon.
- Click on the UPDATE button. The HLSB will now update the display such that the dotted rectangle fills the IDS. You can also update the display by right-clicking and selecting ZOOM IN from the pop-up menu.
- 8. Notice how the colored polygon now fills a larger portion of the IDS. Use the arrows bordering the IDS to move the viewing window left, right, down, and up. Then double-click on the center of the colored polygon. The display will update and center itself on that point.

Feel free to experiment with the ZOOM buttons on the HSLB and on the pop-up menu (right-click on the IDS to bring up the menu). When no ROI is selected the ZOOM buttons utilize the center of the IDS as a reference point.

Displaying Available DataSets for a Given Time

In some cases the user may have need to determine the amount of dataset coverage for a given time window, as well as having a means of tabulating this information. The TimeSeries menu item in the HLSB serves this purpose. It allows the user to quickly see which sensors have coverage for a given area and time span as well as seeing which sensors have concurrent data for a given time increment. The following demonstrates the use of the TimeSeries menu.

- 1. Set the TOI to the desired time span. The time span can be defined in absolute terms (Start Time and End Time) or in relative terms (last 24 hours, or last 12 months).
- 2. Set the desired ROI by drawing a box around the region in the image display screen.
- 3. Select the datasets for which the coverage information is desired, and click on the update button.

- 4. Now select the TimeSeries menu and select either Get Data in Box by Hours, or Days, or Months depending on the desired time increment. The time increment determines how the datasets will be grouped when the results table is formed. For example, selecting Get Data in Box by Months groups the datasets according to the month in which they were found.
- 5. The results will be shown in another browser window, and will be similar to that shown in the example figure below:




Figure 9 Sample output of TimeSeries, Get Data in Box by Months menu choice. The blue underlined numbers indicate that they are a hypertext link to an IDB applet which will display the datasets on that row.

Note the color coding of the cells in the table.

- Yellow indicates 1 or more data items found for that particular dataset.
- Green indicates a dataset that is time invariant (and would therefore be found regardless of the TOI)
- Black shows no coverage for that dataset at that particular time.

Dataset Manipulation in the HSLB

Make sure at least a portion of the dataset is shown in the IDS before continuing. The dataset manipulation in the HLSB is limited to selecting datasets and displaying the coverage areas of those datasets. However, one can also get more detailed information about the type of

datasets being displayed. In addition, the HLSB serves as the starting point for data content analysis by starting up the Interactive Data Browser(IDB).

- Click on the DATA menu in the HLSB Tool bar. A menu list should drop down.
- Select GET METADATA IN BOX. This will open a browser window displaying information about the type of dataset shown in the IDS. These include date and time, file format, area covered, and size of the dataset image.
- Close the Metadata window. Click on the DATA menu again, and select GET DATA IN BOX.

An ITERACTIVE DATA BROWSER applet will be started. The IDB will contain the datasets selected in the HLSB. This concludes the tutorial on basic HLSB operations. The image animation feature is covered in another tutorial, as it is common to both the HLSB and IDB.

Interactive Data Browser Tutorials

Interactive Data Browser Basic Operations

This tutorial covers basic IDB operations such as the selection of datasets for display, basic plotting functions, and use of the volumetric display methods. The Interactive Display Browser is executed when the user selects a dataset in the HLSB and clicks the "GET DATA IN BOX" menu item.

Dataset selection and Display Screen Manipulation

Dataset selection in the IDB refers to the selection of specific data images contained within the dataset. For example, a dataset could be "Satellite X sensor images" in the HLSB, and would contain hundreds of data images – the list of which would be contained in the IDB. This tutorial assumes the following:

- A valid dataset (one containing actual data) has been selected by the HLSB.
- The user has centered on a dataset polygon in the HLSB before executing the GET DATA IN BOX command.
- 1. The first thing to notice is that there should be a dataset already selected and displayed in the IDS (Image Display Screen).
- 2. Select another dataset by right-clicking on the list and click the UPDATE button. Note that this dataset will be displayed in addition to the previous one.
- 3. If the dataset selected has additional layers, they will be shown in the Layers List Box. Click on a layer to select it and click

- UPDATE. The layer should be displayed on the screen. If not, it may be obscured by other datasets and will be more visible in another display (such as a 3D plot).
- 4. Use the navigation arrows surrounding the image display to move the viewing window around the dataset. Experiment with the zoom buttons and see how they affect the IDS.

Basic Plotting Functions - IDB

The Interactive Data Browser allows the user to plot the data values and visualize the data in various 3-dimensional representations. This section will show the user how to access the plotting functions covered under the PLOT menu item on the IDB Tool Bar.

ROI LINE PLOT

The ROI Line PLOT is generally used to view data values along an arbitrary line for a given dataset and dataset layer (if more than 1 layer exists).

- First select LINE from the ROI pull-down menu. Center the dataset within the Interactive Display Screen if you have not already done so.
- 2. Click and hold the left mouse button down on a starting point in the display and drag a line across the image. This will be the line along which the IDB will extract values for the plot.
- 3. Click on PLOT in the IDB Tool bar, and select ROI LINE PLOT. This will bring up another window showing a plot of the data values.
- 4. The output window also displays a hypertext link below the plot which allows you to download an ASCII file containing the x,y values used in generating the plot.

ROI 3D PLOT

The ROI 3D Plot is used to view data values across a rectangular area for a given dataset and dataset layer.

- 1. Select RECTANGULAR from the ROI pull-down menu. Center a portion of the dataset within the IDS.
- Click and hold the left mouse button down on a starting point in the display and drag a rectangular box across the image. This will define the region from which data values will be extracted to form the plot.
- 3. Click on PLOT in the IDB Tool Bar, then ROI 3D PLOT. A window containing the 3D plot will be created.

LAYER PLOT

LAYER PLOT is used in instances where the dataset is composed of many layers (such as a dataset consisting of ocean temperature collected at different depths). WIPE will issue a warning message if this plotting method is used on a dataset containing only 1 layer. Layer Plot can be done using the LINE and POINTS ROI. In LINE ROI mode, LAYER PLOT shows a plot of data values along a user-defined line for each layer selected. In POINTS ROI mode, LAYER PLOT shows a plot of data values at each layer for each of the selected points.

- 1. Select ROI LINE or ROI POINTS from the ROI pull-down menu. Center the dataset within the IDS.
- Select the layers of interest from the Layer list. Hold down the SHIFT key and left-click to select consecutive layers or hold down the CNTRL key and left click to pick specific layers.
- Click and hold the left mouse button down to drag a line across the image or click at several points on the image, depending on whether ROI LINE or ROI POINTS is selected.
- 4. Click on PLOT in the Tool Bar menu and select LAYER PLOT. A window containing the layer plot will be created.

TOPO DRAPE

Topo drape is used in instances where it would be useful to visually reference the data to topological features. An example would be to map temperature data in order to visualize terrain dependencies. The dataset is geo-referenced to internal WIPE databases of terrain elevation and bathymetry data.

- 1. Select ROI RECTANGULAR from the ROI pull-down menu. Be sure to center the dataset region of interest in the IDS.
- 2. Click an hold the left mouse button down to drag a rectangular box across the image. This defines the ROI for the plot.
- 3. Click on PLOT in the Tool Bar menu and select TOPO DRAPE. The applet will create a window containing the plot.
- 4. Notice the drop down menu bars along the top of the plot. They show the current settings for various options (described in Topo Drape Options). Change them to suit various needs.

Volumetric Visualization Guide

There are many instances where several datasets may overlap a given region of interest. The Interactive Data Browser allows the user to view the different datasets in a volumetric representation where each dataset is displayed as a layer of a 3-D cube. This volumetric visualization lets the user quickly evaluate several datasets and see their relationships at the same or nearly the same time. Follow the steps below to learn the different visualization methods.

Create a NetCDF File

- 1. Click on the ROI selection menu and select RECTANGULAR
- 2. Center the region of interest (ROI) in the IDS

- Left-click and hold on a starting point in the IDS and drag a rectangular box around the ROI.
- Select the DATA item on the Tool Bar and click on VOLUMETRIC VISUALIZATION.
- Another window will pop up with the visualization choices. Select "Create a NetCDF file"
- 6. The WIPE server will process the data within the ROI and create a hypertext link to the NetCDF file containing the data
- 7. Click on the hypertext link to download the file.
- The NetCDF file will have embedded MSHELL code that will unpack the datasets and display them as separate images in ProVIEW.

Using Proview to View the NetCDF file

The NetCDF file format makes it very easy to store different data arrays as variables within a file, specify the units and have attributes attached to those variables. The file format can be easily visualized as a cube of data, where the length and width of the cube are the N X M dimensions of the data arrays, and the height of the cube is the number of NetCDF variables in the file. This leads to the use of special commands to read and write to the file, as well as commands needed to view the attributes attached to the variables themselves. To simply view the variables as image files, the user just needs to run the following code in ProVIEW:

```
[out] = xcodencdf[$fname]
```

where *xcodencdf* loads the NetCDF file *\$fname*, and executes the MSHELL code. The code is located in the *MSHELL_SCRIPT* attribute attached to the first variable contained in the file. Type out.text in ProVIEW to view the *MSHELL_SCRIPT* code.

Generate a 3D Layer Cube

- 1. Follow steps 1-4 in the "Create a NetCDF File"method to select the ROI and enter the Volumetric Visualization menu
- 2. Select "Generate a 3D Layer Cube" from the menu choices.
- The server will generate a 3D image cube that contains the datasets as images arranged in layers parallel to the top face of the cube.

Generate a Java Movie Sequence

- Follow steps 1-4 in the "Create a NetCDF File" method for the ROI and to enter the Visualization menu
- 2. Select "Generate a Java Movie Sequence" from the menu choices

- The server will launch the Animated Display Viewer and begin cycling through the different datasets. The Animated Display Viewer is a JavaScript application; details of the operation are contained in the Image Animation section of the WIPE Tutorial.
- 4. Click on the hypertext link at the bottom of the Viewer to download it to your local machine as a zip file. The zip file contains an html file and gif and jpeg images needed to view the animation.

Image Animation

Most of the Image Animation functions are available in either the HLSB or the IDB. The only animation option that is applet specific is the "Generate a Java Movie Sequence" option in the IDB. However, the animation controls are still the same and can be separated into two types: animation through the applet itself or by using the WIPE Animated Data Viewer.

Applet Based Animation

The following are the detailed steps to follow when creating the appletbased animation:

- First create the frames to be displayed. Frames are the images shown in the Image Display Window. They are cached every time the user updates the screen information with the UPDATE button, moves the viewing window, or zooms the viewing window in or out. Caching allows for quicker retrieval when going back and forth between previous and current applet states.
- Right-click while in the IDS to bring up the Pop-Up Menu. Select ITERATE ALL. This will place a check in the checkbox and start the animation.
- 3. The display screen should now cycle the frames. The frames cycle from first frame to last, and loop back to first.
- Once the user is done viewing, right-click to view the Pop-Up Menu and re-select ITERATE ALL. This will uncheck the menu item and stop the animation.
- 5. Pressing the RESET button will clear the frames from the cache and allow the user to create a new sequence of frames for animation.

JavaScript Animation

A JavaScript viewer is used to display the frames and allow the user finer control of the animation. The method used to create the images is the same as the one for applet-based animation.

- Once a sufficient series of images has been created click on the DATA button in the Tool Bar menu and select PLAY ANIMATED DATA.
- 2. The WIPE Animated Data Viewer will be shown and will immediately start playing the frames within the display screen.
- 3. Press the STOP button under the "Animate Frames" control to stop the animation.
- 4. Select the looping method. The left button sets the Viewer to loop back from the last frame to start from the initial frame. The right button sets the Viewer to loop back and forth from initial to end frame.
- 5. Select the dwell time (time spent paused on the frame) for the first and last frames in the frame list. Leave at the default setting to have these frames cycle at the same speed as the rest.
- Press the Forward Arrow button under the "Animate Frames" control to restart the animation.
- 7. There will also be a hypertext link at the bottom of the viewer which allows you to download the viewer and animation to your local machine as a zip file.

The user may also click on specific frames under the "Omit Frame" control to remove them from the frame cycle. The other controls let the user tune the speed of the animation and conduct a frame by frame cycle. A complete listing of the controls and their functions is provided in a table under the HLSB JavaScript Animation section.

Custom Script Examples

This section of the tutorial offers several example situations where the user would benefit from writing custom scripts within WIPE to perform operations. These custom scripts are written in MSHELL, which is the interpreter language used by ProVIEW. Thus most of the proVIEW commands are available to the WIPE user. This allows for full customization, data manipulation and processing through user-made custom MSHELL algorithms. Note that there are two interfaces where the user can write custom scripts. One is the 'Custom Script' tab in the HLSB. The other is the 'Dataset Control' tab in the IDB. The two initial script examples below assume a familiarity with programming code (C, C++, etc). The third example assumes more familiarity with ProVIEW commands.

 Basic code style convention in the examples is 9pt. Courier New font for example code and 10 pt. Times New Roman italics when referencing or explaining ProVIEW commands.

Basic Custom Script Example


This example is meant to show the process of entering custom scripts into WIPE for execution. This will serve as the basis for later, more

advanced scripting examples. NOTE: ProVIEW is case sensitive so commands should be entered exactly as shown in the examples and variables should have the same case throughout the code (i.e. variable 'x' is not the same as 'X')

- 1. Click on the Custom Script tab in the IDS.
- 3. Type the following code shown below:

```
print "Hello World"
x = randu(1,10)
y = sin(x)
plot(y)
```

4. Click on the EXECUTE button at the bottom of the Custom Script window. Another window should open with the results of the script execution, such as the figure shown below.



5. The window should show a very familiar example output — "Hello World" and a sine plot of 10 random points. The *print* command is a standard command for outputting text (and text strings) to the screen. The ProVIEW random number generator, *randu*, is told to generate a 1 X 10 row vector of random numbers. The sine function is called by *sin*.

Basic WIPE Extraction Example

This example illustrates the use of custom scripting to view datasets without using the applet controls. The example can be extended to automate the viewing of several dataset images, and to analyze several images using ProVIEW commands. This example assumes the user already running the Interactive Data Browser containing at least 1 dataset in the dataset list. If not, consult the HLSB tutorial on how to select a dataset and run IDB.


- 1. Click on the Custom Script tab in the IDS.
- 2. Select "ProVIEW Calculator (HTML preformatted >)"
 for output type
- 3. Type the following code. Substitute your own dataset, sensor, and layer names according to the following syntax (this should be the same syntax used in the IDB dataset list):

DatasetName|DatasetRegion@Layer

This should be similar to the format of the datasets shown in the IDB dataset list. The difference is "@layer" where layer is the value of the layer of interest. Enter "0" if the dataset contains no layers.

```
$dset = "NAVO_Temperature|test1@0"
[out] = getI[$dset]
out255 = scale255(out)
view out255
```

- 4. The output window should show an image retrieved by get1 (the 'get Image' function) and scaled from 0-255 via the scale255 function. The \$dset_layer variable specifies the data for get1 to retrieve. Notice how the get1 function utilizes brackets, which is the syntax for external functions, versus the parentheses for scale255- internal to ProVIEW.
- 5. The sample output from the above code is shown below:



Output of 'getI' function. The function applies a grayscale palette to the data. For more customization of the palette and other parameters, use the 'Wipe_Extraction' function, shown in a later example.

Wipe Extraction and Analysis Example

The *getI* function in the previous example can be used as part of a larger custom script. In this case it will be used to extract two datasets and perform a comparative analysis. The example will cover different analytical functions accessed through various ProVIEW commands and

is meant to illustrate the customization power available to the user. Because each WIPE server configuration is unique to the institution, the example is intended as a general showcase tutorial. However, the user is welcome to use any part of the code as a building block for custom scripts.

The two datasets in the example represent bathymetry data collected off the region of North Carolina. The "DBDB" dataset will be considered the baseline data, and it would be useful to compare it with the data in the "NAVO_Bathy" dataset. This example steps through one such custom script that performs that comparison.

The following is the example code entered in the Custom Script window:

```
// retrieve DBDB data
$DataSet_Layer = "DBDB|DBDB_V1.0@0"
[bathy]=getI[$DataSet_Layer]
bathy255 = bathy.scale255
view bathy255

// retrieve navo bathymetry data
$DataSet_Layer = "NAVO_Bathy|3sec_onslow@0"
[nbathy]=getI[$DataSet_Layer]
nbathy255 = nbathy.scale255
view nbathy255
```

The code generates two output arrays containing data from the NAVO_Bathy and DBDB datasets. It then scales the data values to 0-255 to create two image arrays. The output of the image arrays is shown below.



The output images are bathy255 on the left, and nbathy255 on the right. The images will be displayed vertically in the actual window, in the order of the 'view' commands.

The custom script can be extended (via the code below) to compute the percentage error between the two arrays. A figure containing the output image is also shown.

```
//correct for sign differences
bathy = bathy.abs
nbathy = nbathy.abs
//define region of bathy with pixel values > 0)
```

```
groi = gtindex(bathy,0)
//create error array with same size as bathy
error = zeros(bathy.nrows,bathy.ncols)
//assign %error between datasets to valid pixels
error(groi) = abs( (bathy(groi)-nbathy(groi)) //
/.bathy(groi) ) * 100
//clip error values above 255 to 255
error = gtclipto(error, 255, 255)
//find region of bathy where pixel values = 0
//and set the same region in error = 0
groi2 = eqindex(bathy,0)
error(groi2) = 0
//view the error image
"the percentage error between the two datasets is
shown below"
view error
```



The 'error' array viewed as an image. The large black area is a region of no dataset values (since it is over land). The gray area is the coverage of 'bathy', which is larger than 'nbathy'.

Note how WIPE is able to display the percent difference between the two data arrays as an image, for better visualization of the error. In addition, since the data for both datasets was already geo-referenced to lat-lon coordinates, WIPE was able to compare two different sized data arrays with a subset region common to both.

Building Blocks, System Variables, and Additions to the Applet

The ability to build upon other functions is what gives the user a tremendous power to customize WIPE features and build larger, simpler, or more detailed functions out of smaller function blocks. This

section of the tutorial shows the code contained within the *getI* function to illustrate the building block capability.

The following code makes up the *getI* function:

```
FUNCTION [out]=getI[$DataSet_Layer]
$GROI = ""
$Scaling = ""
$Palette = ""
[out,r_image,g_image,b_image]=Wipe_Extraction[
$DataSet_Layer,M_longlat_2d,M_longlat0,M_W,M_H,$GROI,$Scaling,$Palette]
```

Note that actual MSHELL syntax would require the parameters in the call to the *Wipe_Extraction* function to be on the same line, but it is separated into several lines for purposes of this example.

As seen from the code, *getI* is really a simple function which passes the \$DataSet_Layer variable into a more complicated external function Wipe_Extraction. Also, *getI* sets \$GROI, \$Scaling, and \$Palette to empty strings which tells Wipe_Extraction to use the default settings.

Suppose the user wants to be able to view a particular dataset, out of several selected datasets in the IDB, and have more control over the palette used. The following function code would serve this purpose. Note that for this example the datasets are assumed to have only 1 layer each.

```
FUNCTION [out] = getIselected[dset,paletteused]
$GROI = ""

$Scaling = ""

$Palette = int2str(paletteused)
$dsetsarray = smodify($SelDataSets_Layers,",","\n")
$datasetwanted = $datasetsarray[dset]
[out,r_image,g_image,b_image] = Wipe_Extraction[
$DataSet_Layer,M_longlat_2d,M_longlat0,M_W,M_H,$GROI,$Scaling,$Palette]
```

The \$GROI and \$Scaling variables are once again left as default. \$Palette is set to the value paletteused (specified by the user) after it has been converted to string format. The values for paletteused range from 0 (grayscale) to 4 (user-defined color look-up table). Paletteused could have been made a string variable but then the user would need to put double quotes "" around the palette number. Once the function is entered into the WIPE scripts subdirectory (ask the WIPE Server Administrator or consult the WIPE Server Manual for details), the user

can call the function using the Custom Script Window as shown in the example below:

```
//want first dataset in the selected datasets list
dset = 0
paletteused = 2 //use pseudocolor palette
[out] = getIselected[dset,paletteused]
view out
```

WIPE also maintains a series of system variables which are applied to any function being executed. An extremely powerful system variable is M_echo . Typing $M_echo = I$ in the beginning of any custom script sets the output display to echo the commands being executed. This is just a brief sample of the MSHELL commands, which can be used in building custom scripts. The ProVIEW manual has a detailed listing of all the system variables and MSHELL commands, most of which can be used in a WIPE server.

As a final note, a custom script can be sent to the WIPE Server Administrator for inclusion into the applet as a menu item. The *get1* function is a good example of a function that can be turned into an applet control, such that the user can select a dataset and then click on the a button to instantly browse dataset images. The advantage of this is the output will be shown in a separate window, leaving the IDS intact and bypassing the use of navigation arrows, zoom buttons, and other applet controls.