



.print Client Windows for ICA, RDP, and TCP/IP

(.print version 7.0)

Manual

ThinPrint GmbH
Alt-Moabit 91 a/b
10559 Berlin
Germany/Alemania

ThinPrint Pty. Ltd.
L 10, 275 Alfred Street
North Sydney / NSW / 2060
Australia

ThinPrint, Inc.
20525 Center Ridge Rd, Suite 630
Cleveland, Ohio 44116
USA/EEUU

ThinPrint, Inc.
8703 Yates Drive, Suite 200
Westminster, Colorado 80031
USA/EEUU



E-mail: info@thinprint.com
Web: www.thinprint.com
Issued: July 8, 2008 (v21)

© Copyright

This document is the intellectual property of ThinPrint GmbH. This document may be copied in whole or in part, provided this Copyright notice is included in every copy.

® Registered trade marks

All hardware and software names mentioned in this document are the registered trademarks of their respective companies or should be regarded as such.

Safety warning

All ThinPrint products are pure software solutions. Please note the safety warnings in the technical documentation from your hardware vendor and from the manufacturer of each device and component. Before beginning installation, we recommend closing all windows and applications and deactivating any virus scanner.

How to use this manual

The following conventions are used throughout this manual to represent recurring actions and text types.

Conventions

Note!	Important tip, explanation, exception
SMALL CAPS	Menu, command, dialog panel, option
<i>Italic</i> "Name"	Proper name, emphasis, variable
Courier	Keyboard input
→	Consecutive menu or command
■	Enumeration, head note
Example	Example
–	Procedural steps
1.	
2.	
Page 5	Links
www.cortado.com	


What is ThinPrint .print?	5
Overview	5
ThinPrint Output Gateway	6
 Installing .print Client under Windows NT, 2000/3, XP	7
Administrator permissions	7
Installation	7
Currently available .print Client Windows types	9
 Installing .print Client under Windows Vista	11
Administrator permissions	11
Installation	11
 Installing .print Client under Windows 9x/ME	13
 .print Client context menu	14
 Configuration with .print Client Manager	15
Setup tab	16
Assignment tab	16
Plug-and-play client installation	17
.print AutoConnect	17
Advanced tab	19
Connection Svc tab	20
SSL encryption	21
Importing SSL certificates	22
Registry entry CertName	23
Remote client configuration	24
.print Client Gateways and .print Connected Gateways	26
 Appendix	28
Customer service and technical support	28
Additional sources	28
License agreement	28

Distributing .print Client	31
Installing additional .print Client Windows types	31
Repairing .print Client Windows	32
Updating .print Client Windows	32
Uninstalling .print Client Windows	32
Relevant entries in Windows Registry	34
Registry entries of .print Client Windows	34
Additional Registry entries of .print Client Windows	36
 .print Clients and supported features	 38

What is ThinPrint .print?

Overview

ThinPrint .print is a software solution and consists of a server and a client component (Illus. 1).



Illus. 1 Using of ThinPrint .print with server and client components

Server component

The **.print Engine** is the actual core of the ThinPrint .print framework. It provides complete printer driver management including Driver Free Printing. The .print Engine performs the following main functions:

- Bandwidth control, encryption, and compression for print data
- Virtual printer driver ThinPrint Output Gateway
(replaces printer drivers on printing computers = Driver Free Printing).

Client component

A software component on the client side, **.print Client** is generally responsible for receiving print data, decompressing and decrypting it, and sending it to the print device. Many .print Clients are available for different end devices and areas of deployment: for all Windows versions incl. Windows CE and Windows Mobile, for Linux, Solaris, Dos, Win OS/2, and Java, for BlackBerry and Symbian as well as for internal and external print servers for network printers. The following .print Client types are available for Windows¹:

- .print Client Windows for ICA
- .print Client Windows for RDP
- .print Client Windows for TCP/IP (as a Windows application)
- .print Client Service Windows (as a Windows service)²

¹ Windows 95 and later


² Information on installing and configuring the .print Client Service Windows can be found in the relevant manual ([Page 28](#)).

ThinPrint Output Gateway

Output Gateway is a virtual printer driver which enables print jobs to be rendered only on clients with Windows as the operating system; an optional print preview is also available on the client.

Note! When printing over Output Gateway, the fonts used in the document must also be installed on the client.

Page setup Client-side printer properties such as paper sizes and sources, print resolution, color, and duplex will be displayed in Output Gateway's user interface (Illus. 2, left).



Illus. 2 Display of native printer driver's paper sources on a client (left) and of ThinPrint Output Gateway in a terminal session (right)

Installing .print Client under Windows NT, 2000/3, XP

Administrator permissions

Administrator permissions are required for all installation and configuration procedures. It is therefore best to log on under Windows always with the same account – e.g. as ADMINISTRATOR.


Installation

Note! Under Windows NT 4.0, the installation routine for .print Client Windows 5.0 SR-2 (5.2) and later requires **Service Pack 6**.

- Please note: Particular installation programs are provided for Windows Vista as well as for RDP printing to .print Clients running under Windows XP x64 or 2003 x64 (see [Page 11](#)), and the installation under Windows 9x/ME (see [Page 11](#)) differs a little from that under Windows NT 4.0/2000/XP/2003.
- Download of .print Client at: www.thinprint.com/?s=4316&lc=61 in particular: [Setup.exe](#), [TPTCPen.msi](#), [TPICAen.msi](#), [TPRDPen.msi](#)
- Please first delete any previously installed .print Client Windows (see [Page 32](#)).


*.print Client
Windows
installation*

1. Under Windows NT 4.0, 2000, XP, or 2003 start the installation program **Setup.exe** (Illus. 3) or the relevant **.msi file** (Illus. 4)³. The abbreviations in the .msi file names have the following meanings:
 - ICA = for printing via the Citrix ICA protocol
 - RDP = for printing via the Microsoft RDP protocol
 - TCP or SRV = for session-independent printing via TCP/IP (TCP = installation as an application; SRV = installation as a Windows service)
 - en or de = English or German




Illus. 3 Installing .print Client with Setup.exe

³ For the unattended installation see the [Preconfiguration and unattended installation of .print Client Windows](#) white paper.




Illus. 4 Installing .print Client with an .msi file under Windows NT 4.0, 2000, XP, or 2003

2. Select a language and click OK (Setup.exe only) and confirm the following window with NEXT.
3. Read the license agreement and accept its terms with NEXT (Illus. 5).




Illus. 5 Read and accept the license agreement; click NEXT

4. Choose the installation path (Illus. 6) and click NEXT.
5. Select an appropriate client type (Setup.exe only) and again confirm by clicking NEXT (Illus. 7).



Illus. 6 Changing installation path if necessary



Illus. 7 .print Client Windows type selection (Setup.exe only)

Note! Please note the check list in the “.print Server Engine” or “.print Application Server Engine” manual ([Page 28](#)).

Currently available .print Client Windows types

.print Client Windows for TCP/IP

A TCP/IP connection must exist between server and client machines. To run .print Client Windows for TCP/IP. It must also be possible to access the client machine's TCP port from the server. Connections with Network Address Translation (NAT) or with asynchronous connections require the .print Client Windows for ICA or RDP (below). In case of NAT .print Connection Service⁴ can also be used.

The .print Client is started by a shortcut that is automatically created in the Windows STARTUP folder during setup.

⁴ Additional licensing required (.print Connected Gateway)

- Click NEXT and continue with step 6., [Page 10](#).

.print Client Service Windows

See the “.print Client Service Windows” user manual ([Page 28](#)).


.print Client Windows for ICA

This .print Client can be run as long as there is an ICA connection to a Citrix server (the ICA client version must be 4.20.715 or higher).

The .print Client starts automatically when an ICA session is opened.

- Click NEXT and continue with step 6., [Page 10](#).

Note! To successfully complete .print Client installation, the correct path to the Citrix ICA client must be entered at the prompt (is usually automatically detected – Illus. 8).



Illus. 8 Path to the Citrix ICA client

.print Client Windows for RDP

This .print Client can be run as long as there is an RDP connection to a Microsoft terminal server (the Terminal Services client⁵ version must be 5.00.x or higher; the terminal server must be running Windows 2000/XP/2003).

The .print Client starts automatically when an RDP session is opened.

Completing installation

6. Confirm the remaining prompts with OK, YES, NEXT, or FINISH. An icon is displayed in the task bar when .print Client Windows is running (Illus. 9).



Illus. 9 .print Client Windows icon in the task bar

⁵ Other Microsoft denominations are: Remote Desktop Client and Remote Desktop Connection

Installing .print Client under Windows Vista

Administrator permissions

Administrator permissions are required for all installation and configuration procedures. It is therefore best to log on under Windows always with the same account – e.g. as ADMINISTRATOR.

Installation

- Please note: For other Windows versions than Vista as well as for RDP printing to .print Clients running under 32-bit Windows particular installation programs are provided (see Pages [7](#) and [13](#)).
- If you want to print via ICA under Windows Vista you need a Citrix ICA client version 10.0 or later (as well as the following .print Client Installer: TPICAven.msi; upper arrow in Illus. 10).
- Download of .print Client at: www.thinprint.com/?s=4316&lc=61 in particular: [TPTcpVen.msi](#), [TPTcpVenx64.msi](#), [TPICAven.msi](#), [TPRdpVen.msi](#), [TPRdpVenx64.msi](#)

*.print Client
Windows
installation*

1. Under Windows Vista start the relevant **.msi file** (Illus. 10)⁶. The abbreviations in the .msi file names have the following meanings:
 - TP = ThinPrint
 - Ica = for printing via the Citrix ICA protocol
 - Rdp = for printing via the Microsoft RDP protocol
 - Tcp or Srv = for (session-independent) printing via TCP/IP (Tcp = installation as an application; Srv = installation as a Windows service⁷)
 - en or de = English or German
 - V = .print Client for Windows Vista (and .print Client RDP type for Windows XP x64/2003 x64)
 - x64 = .print Client for Windows Vista x64 as well as for RDP printing to .print Clients running under Windows XP x64 or 2003 x64

⁶ For the unattended installation see the [Preconfiguration and unattended installation of .print Client Windows](#) white paper.

⁷ See the [.print Client Service Windows](#) manual.

Note! There are .print Client versions both for 32-bit Windows as well as for Windows x64.


- For printing via **ICA** to .print Clients running under Windows Vista x64, XP x64, or 2003 x64 you can only use the 32-bit version of .print Client, because there are only 32-bit versions of Citrix ICA client.
- For printing via **RDP** to .print Clients running under Windows Vista x64, XP x64, or 2003 x64 you can only use the x64 version of .print Client, because Microsoft delivers only a 64-bit version of its RDP client together with Windows.
- For printing via **TCP/IP** to .print Clients running under Windows Vista x64, XP x64, or 2003 x64 you can use both the 32-bit or the x64 version of .print Client.

Example 1: You intend to install the .print Client on a PC and print via ICA. On the PC runs the 32-bit version of Windows Vista or Windows Vista x64. Select in both cases the file: **TPICAven.msi** (upper arrow in Illus. 10).

Example 2: You intend to install the .print Client on a PC and print via RDP. On the PC runs the 32-bit version of Windows Vista. Therefore select the file: **TPRdpVen.msi** (middle arrow in Illus. 10).

Example 3: You intend to install the .print Client on a PC and print via RDP. On the PC runs Windows XP x64. Therefore select the file: **TPRdpVenx64.msi** (lower arrow in Illus. 10).


2. Continue with step 2 on [Page 8](#).



Illus. 10 Installing .print Client under Windows Vista

Installing .print Client under Windows 9x/ME

Installation of .print Client Windows for the Windows versions 9x/ME only differs from that for Windows NT/2000/XP/2003 (see [Page 7](#)) in the choice of available .print Client types (Illus. 11). For Windows versions 9x/ME, the .print Client Windows is not available as Windows service.




Illus. 11 .print Client Windows type selection under Windows 9x/ME (Setup.exe only)

.print Client context menu

.print Client version 6.2 and later has a context menu, which can be opened by clicking the .print icon in the task bar, that offers quick access to important functions.


- Right click the .print icon in the task bar. The context menu shown in Illus. 12 opens.



Illus. 12 .print Client context menu

The following options are available in context menu:

- **CONFIGURE:** Clicking CONFIGURE opens .print Client Manager (see also “Configuration with .print Client Manager”, [Page 15](#)).
- **RELOAD PRINTERS:** To read newly installed printers into the .print Client Windows printer list or remove deleted printers from the .print Client Windows printer list without closing and restarting the .print Client, use the RELOAD PRINTERS option. Selecting this option synchronizes the .print Client’s printer list with the system’s printer list.
If the relevant value in the Windows Registry has been set (see “Select all existing printers for AutoConnect” in “.print AutoConnect”, [Page 17](#)), these detected printers will also all be selected for .print AutoConnect.
- **ABOUT:** This option displays version information on the installed .print Client (Illus. 13).




Illus. 13 Information about .print Client

- **CLOSE:** Click CLOSE to close .print Client. This option is only available in TCP/IP versions (and not in the ICA and RDP version as well as in the .print Client Service Windows).
How to restart the .print Client? See the following chapter.

Configuration with .print Client Manager

Remember, several changes only take effect after restarting the .print Client Windows. Please follow the steps described below to do so.

- Close .print Client Windows (TCP/IP version only; see above and [Page 20](#)).
- Restart .print Client Windows:
 - TCP/IP: Select START→ PROGRAMS→ .PRINT CLIENT WINDOWS→ START CLIENT (Illus. 14).
 - ICA/RDP: Disconnect and reconnect each terminal session.




Illus. 14 Start .print Client Windows for TCP/IP

Starting .print Client Manager




.print Client Windows is configured with .print Client Manager:

- Open .print Client Manager
 - either by double clicking its icon in the task bar (see illustration left)
 - or with START→ PROGRAMS→ .PRINT CLIENT WINDOWS→ CONFIGURE (Illus. 14)
 - or by opening the context menu using the right mouse-button and selecting the CONFIGURE option.



Illus. 15 .print Client Windows context menu

- This opens the panel in Illus. 16.



Illus. 16 .print Client Manager: CURRENT PRINTER (Lexmark printer as example)

Setup tab


Current printer Select CURRENT PRINTER here (Illus. 16). Print jobs are printed from the current printer if the printer *ID* can't be determined (e.g., no printer ID is given in the printer name at the server).

Should you want to specify that the *current printer* of ThinPrint .print is the same as the local Windows default printer, simply leave the default setting INHERIT CLIENT'S DEFAULT PRINTER. Or select the current printer manually with USE THIS PRINTER; in this case, the current printer can be different than the local Windows default printer.

Furthermore, the current printer can be set as default printer in a session for .print AutoConnect (see Illus. 16).

Assignment tab

Printers and their IDs ASSIGNMENT lists available printers with their IDs and their classes (Illus. 17).



Illus. 17 Printers with assigned IDs and selection for .print AutoConnect

The ASSIGNMENT panel displays information about available printers. This is also where you find printer IDs, which are automatically assigned by the .print Client

Windows and are necessary for manually assigned printer names on the .print Engine (without AutoConnect; for more information, see the .print Engine manual; [Page 28](#)).

Note! If .print Client Windows recognizes a printer as new – e.g., after renaming a printer – it might assign the printer a new ID; in this case, .print Engine may need to be reconfigured.

*Enable sending
properties*

If this option is enabled and .print AutoConnect is used, the client printer's paper trays as well as duplex settings, paper formats, and print resolution will be applied to the printer created on the server. Please also observe the server side option APPLY CLIENT PRINTER PROPERTIES of the .print AutoConnect configuration (see manual of the respective .print Engine; [Page 28](#)). Default: enabled.

Plug-and-play client installation

Since .print version 5.3, the .print Client Windows is pre-configured at installation so that user input is no longer necessary. This, too, decisively simplifies administration. The following especially noteworthy settings are default properties:

- The “current printer” in .print Client Windows is selected for .print AutoConnect (and/or roaming service).
- The “current printer” in .print Client Windows is selected as default printer for the session (when running .print AutoConnect).
- “Sending properties” is enabled.

Please note that previous settings are still valid when updating or installing .print Client on a machine where it was installed before.

.print AutoConnect

It's also possible to select different printers by checking the box next to them. .print AutoConnect will automatically map all selected printers on a server and connect them with a ThinPrint Port – provided templates exist and .print AutoConnect is running on the server (= auto-created printers). When starting a terminal session all marked printers are created automatically in the session. For more information please refer to the .print AutoConnect chapter in the .print Engine manual ([Page 28](#)).

*Select all existing
printers for
AutoConnect*

By starting .print Client from the COMMAND PROMPT, you can enter a parameter for selecting all existing printers as well as all printers to be created in the future for AutoConnect. This option is only available in the .print Client for TCP/IP.

- Start .print Client Windows from the command prompt from its directory with

```
Thnclnt32 -e1
```


All printers listed on the ASSIGNMENT tab are now selected for AutoConnect.

Should you no longer wish to have all printers automatically selected for AutoConnect, you can disable this function by starting the .print Client Windows with the parameter **-e0**:

- Start .print Client Windows from the command prompt from its directory with


```
Thnclnt32 -e0
```

Printer class Double clicking a printer name opens an input box for specifying the printer class for .print AutoConnect (Illus. 18). The result is shown in Illus. 19.



Illus. 18 Enter class name (see .print Auto-Connect in the .print Engine manual; [Page 28](#))

Note! Unlike printer names, class names may not be longer than 7 characters and may not include blank spaces.




Illus. 19 Printers with ID and class

Advanced tab

The ADVANCED panel (Illus. 20) offers the following settings:

- Bandwidth* – Check this box and enter a bandwidth value. Note: If the value is larger or if CLIENT CONTROL is disabled at the server, server settings (see .print Engine manual; [Page 28](#)) are applied.
- TCP Port* – Enter here the port number where .print Client Windows should receive incoming connections. Be sure: Same TCP port number for both .print Client Windows and .print Engine printer port to which the client printer is connected.⁸ Otherwise, communication between the two .print components is impossible. The TCP port number is of course only relevant for printing over TCP/IP. Default port number is 4000.
- Use Connection Service* – If you want to use the .print Connection Service, enable its check box. Once it has been activated, the additional tab card called CONNECTION SVC will be added. This tab offers settings for using the Connection Service (see “Connection Svc tab” below). Default: disabled



Illus. 20 .print Client Manager for Windows: advanced options

- Print-to-Screen* This function of .print Client Windows 7.0 is a component of ThinPrint's Cortado Corporate Server⁹; see “Cortado Corporate” user manual ([Page 28](#)).
- Administrators only* Checking this box prevents users from making changes to .print Client Windows settings.
- OK* Changes are applied without quitting .print Client Windows – changes could, however, first be functional after restarting .print Clients or the terminal session ([Page 15](#)).
- CANCEL* Previous settings remain intact, all changes are ignored.

⁸ see also .print Engine manual ([Page 28](#))

⁹ formerly Content Beamer

CLOSE Quits .print Client Windows for TCP/IP. The .print Client icon disappears from the task bar. The .print Client Windows must be restarted before .print printing resumes ([Page 15](#)).


Restart could change printer IDs – if printers were deleted along with their Registry entries; in this case, the .print Engine may require reconfiguration.

Tip! The CLOSE button is only active for .print Client Windows for TCP/IP. The .print Clients for ICA and RDP automatically close when the session ends. The .print Client Service Windows is closed in the SERVICES folder.

Info line The info line displays the version numbers of the .print Client Windows files.

Connection Svc tab

The CONNECTION SVC tab (Illus. 21) offers settings for using the .print Connection Service. Please also note the information about installing and configuring the .print Connection Service in your .print Engine manual and in the “.print Connected Gateway” manual ([Page 28](#)).



Illus. 21 .print Client Manager started; CONNECTION SVC tab

- | | |
|----------------------------------|---|
| <i>Connection server address</i> | – Enter the IP address of the server on which the .print Connection Service has been installed. |
| <i>TCP port</i> | – Enter the number of the TCP port via which the .print Client connects to the Connection Service. Default port number is 4001. |
| <i>Authentication key</i> | – Enter the .print Client's authentication key for the Connection Service. |
| <i>Client ID</i> | – Here is where the client ID is entered. The Connection Service uses the client ID to forward print jobs to a client. Depending on the mode of communication, the client ID is given by the Connection Service (dynamic mode) or must be given by the client (static mode). In the latter case, the client ID must be saved in this box. |

*Connection retry
interval (s)*

- Enter the wait time (in seconds) after which a new attempt should be made to establish a connection if the .print Connection Service is not reachable.
Default: 0.

Status line

After successful connection to the Connection Service, the status line will display the server IP address as well as the TCP port number, client ID, and authentication key. If no connection could be established to the Connection Service, the status line shows the message “Not connected” (see Illus. 21).

SSL encryption

If you want a secure SSL connection between .print Engine and .print Client, you can encrypt print data (version 6.2 and later) with the SSL based TLS¹⁰ norm. To do so, Windows 2000 or higher is required as operating system on the client machine.

This print data encryption is based on client authentication. When using SSL encryption, two certificates are installed on the server where .print Engine is running, and a certificate signed by the server is installed on the client. More information is found in the [.print Server Engine](#) manual.

We recommend creating certificates with an individual certificate server or requesting them from an official source¹¹. Please note that the certificate must be a **x.509** certificate (file format *.cer or *.p12). See the [Creating SSL certificates for printing with .print](#) white paper.

¹⁰ TLS = Transport Layer Security; SSL = Secure Socket Layer


¹¹ e. g., www.verisign.com or www.trust-center.de

Importing SSL certificates

If the USE ENCRYPTION option is enabled in the ThinPrint Port configuration¹² on the server, a relevant SSL certificate, which has been signed by the server, must be imported to the machines on which a .print Client is running.

Note! Client certificates have to be imported in the client machine's certificate store. **Either** you import the certificates **individually for each user** (at MY USER ACCOUNT) **or one time per machine** (at COMPUTER ACCOUNT). Did you choose the Computer Account you have to assign permissions to the certificate afterwards, if the computer user(s) are not members of the Administrators group (to do so see the [Creating SSL certificates for printing with .print](#) white paper).


1. To install a client certificate, open the Microsoft Management Console (MMC) with **mmc.exe** from the COMMAND PROMPT.
2. Select **either** the following in MMC on the client PC **per user**:
FILE→ ADD/REMOVE SNAP-IN→ ADD→ CERTIFICATES→ ADD→ MY USER ACCOUNT→ FINISH→ CLOSE→ OK
Or select for the machine:
FILE→ ADD/REMOVE SNAP-IN→ ADD→ CERTIFICATES→ ADD→ COMPUTER ACCOUNT→ FINISH→ CLOSE→ OK
3. Now import the certificate by selecting ALL TASKS→ IMPORT in the context menu (Illus. 22) and then
NEXT→ BROWSE→ OPEN→ NEXT→ PASSWORD→ NEXT→ PLACE ALL CERTIFICATES IN THE FOLLOWING STORE→ NEXT→ FINISH→ OK




Illus. 22 Starting import of an SSL certificate
(example for MY USER ACCOUNT or CURRENT USER)

Illus. 23 and 24 show the results of import.

¹² see .print Engine manual ([Page 28](#))



Illus. 23 SSL certificate imported to a client machine
(example for MY USER ACCOUNT or CURRENT USER)



Illus. 24 SSL certificate imported to a client machine
(example for COMPUTER ACCOUNT or LOCAL COMPUTER)


Registry entry CertName

Before sending encrypted print data, the server checks whether the name of the imported certificate is included in the `CertName` entry in the client machine's Registry and whether the stored certificate is present on the client. The `CertName` entry in the Registry can be entered with the Custom Installation Wizard¹³ or manually as follows:

1. After the certificate has been imported, create the following Registry entry on the client machines with REGEDIT (Illus. 25; data type: `reg_sz`):

```
hkey_local_machine\software\thinprint\client\CertName
```

¹³ See the [Preconfiguration and unattended installation of .print Client Windows](#) white paper.



Illus. 25 Registry entry for SSL encryption on Windows clients (example for `tpclient` certificate)


2. Enter as value the name of the imported certificate as displayed in the column ISSUED TO of the MMC's certificate overview (`tpclient` as example in illus. 23 and 25).
3. Restart .print Client Windows ([Page 15](#)).

The `CertName` Registry entry is only needed for encrypting print data; receipt of unencrypted print data is still possible.


Remote client configuration

Remote configuration is possible for .print Client Windows printing with TCP/IP protocol. The entry `RmtConf` is needed in the Windows registry of all client machines you want to configure. This can be done manually (Illus. 26 or [Page 36](#)) or by using the Custom Installation Wizard 7.0 or 7.0 V (see the [Preconfiguration and unattended installation of .print Client Windows](#) white paper).


- Open the Windows registry of the client machine you want to configure. Add the entry `RmtConf` (`reg_mult_sz`) under `hkey_local_machine\software\thin-print\client`. Enter the IP addresses of all those machines from which the client should be configured (Illus. 26).
- Restart .print Client.
- Go to the machine on which .print Engine is installed. Open the MMC, select .print Client snap-in and enter the address of the client machine to configure (Illus. 27).
- Now, the selected machine is ready for remote configuration (Illus. 28).



Illus. 26 .print Client machine:
Registry entry RMTCONF added for remote configuration of .print Client



Illus. 27 .print Engine machine: Open the MMC, select .print Client snap-in and enter the address of the client machine to configure




Illus. 28 .print Engine machine: Remote configuration of a .print Client

.print Client Gateways and .print Connected Gateways

The .print Client Gateway can greatly simplify the introduction of ThinPrint .print because it can receive .print print jobs for an entire group of clients and printers, decompress and decrypt them, and then distribute them conventionally in a local network – like a local print server (Illus. 29). Then the .print Client is only necessary on the Client Gateway for this remote LAN. Otherwise, the .print client must be installed on each end device: rich clients, printers, print servers, thin clients, PDAs, etc. This could mean that with thin clients, for example, a BIOS update is necessary. Even mixed environments pose no problem: The .print client is installed onto all devices where simple installation is possible, and all others are served by a Client gateway.


More information can be found in the [Windows computer as a .print Client Gateway](#) white paper.



Illus. 29 Windows computer as a .print Client Gateway (example)

The .print Connected Gateway is a variation of the .print Client Gateway. The .print Client installed on the Client Gateway can connect to the .print Connection Service installed on the server. Print jobs can then be sent via TCP/IP, even where the Client Gateways are found in a masked network (e.g., behind a router with Network Address Translation; Illus. 30).

More information can be found in the [.print Connected Gateway](#) manual and in the [SEH TPG60/120 as a .print Client Gateway](#) white paper.



Illus. 30 Windows machine and SEH TPG60 as .print Connected Gateways (example)

Appendix

Customer service and technical support

Customer Service www.thinprint.com/?s=8&lc=61
support@thinprint.com

Additional sources

Further information about ThinPrint .print can be downloaded from our website.

Manuals The following manuals are available at www.thinprint.com/ → FIND PRODUCT
→ <product name> → MANUAL(S):

- .print Client Service Windows
- .print Application Server Engine
- Cortado Corporate
- .print RDP Engine
- .print Virtual Desktop Engine
- .print Desktop Blade Engine
- .print Tracking Service
- Remote Desktop Suite Standard
- Remote Desktop Suite Premium
- .print Server Engine
- .print Engine Unix
- .print Engine AS/400
- .print RDP Engine XP
- .print Queue Manager
- .print Connected Gateway

White papers The following white papers can be downloaded at www.thinprint.com/ → FIND PRODUCT → <product name> → WHITE PAPERS or www.thinprint.com/ → SUPPORT & SERVICES → WHITE PAPER DOWNLOAD:

- Preconfiguration and unattended installation of .print Client Windows
- Creating SSL certificates for printing with .print
- Tips for configuring ThinPrint .print
- .print addressing
- .print AutoConnect and .print Virtual Channel Gateway
- Windows computer as a .print Client Gateway
- Intermate IAPS ThinPrint as a .print Client Gateway
- SEH ISD200/300 as a .print Client Gateway
- SEH TPG60/120 as a .print Client Gateway
- Intermate 10x as a .print Client Gateway

License agreement

ThinPrint End User License Agreement (EULA)

".print Client Windows"

Important!

Please read the following ThinPrint End User License Agreement (hereinafter referred to as "EULA") carefully before installation and/or use of the Software ".print Client Windows", its possibly integrated add-on programs and any media, material, online or electronic documentation (hereinafter jointly referred to as "Software") as specified in section 4 of the EULA.

Upon installation, copying or any other use of the Software you are entering into a binding agreement to accept the conditions of the EULA and agree to adhere to them. If you install this Software as administrator or other member of staff of a company entitled to installation and/or if you make it available for use to Third Parties or persons afterwards, you also accept the conditions stipulated in the EULA and agree to adhere to them.

If you, however, do not agree with the conditions of the EULA, you are not entitled to install, make available and/or use the Software.

0. General terms

The EULA is agreed upon between ThinPrint GmbH, Alt-Moabit 91a/b, 10559 Berlin (hereinafter referred to as "ThinPrint") and a legal or natural person who themselves or their staff install and use the Software (hereinafter referred to as "End User"). It is a valid contract between the named parties finally defining all rights and duties of the End User and ThinPrint in regard to the Software.

1. Rights of use

1.1 Within the limits of the EULA, End User has – subject to the conditions of the EULA – the non-transferable, revocable, regionally limited and non-exclusive right to install and use the Software and its possibly integrated add-on programs. The Software may be used and installed on a computer, server or a server farm in accordance with the number of licenses included with the Software. End User is entitled to make a copy of this Software in accordance with the EULA after the installation or – instead of the copy – to create an image of the computer or server on which the Software has been installed. The copy or image may only be used and stored for archiving and reinstallation purposes of the Software on the same computer, server or server farm. All trademarks and copyrights and any other legal notes relating to the rights of ThinPrint must be included and remain in such copy or image.

1.2 End User is not entitled to make additional partial or complete copies or images of the Software and its add-on programs other than mentioned in 1.1, to copy in any way, to translate or to dismantle parts of the Software, to change the arrangement or to make any other changes and/or amendments or to make copies of such changes. End User is not allowed other than in the legally permitted boundaries to reverse engineer, to decompile or to disassemble the Software. End User is not entitled to distort the contents of the Software, to change its color, pattern and fonts or to split or in any other way alter the elements of the logo, copyright and trademark details.

1.3 End User is not entitled to surrender, sublicense, sell or in any other way pass on the rights and duties granted to him under the EULA.

1.4 If End User receives the Software on more than one storage system, End User is only entitled to install and use the Software contained on one of the mediums only. It is generally prohibited to install and use the Software contained on the second medium on another computer, server or server farm. The Restrictions in 1.2 and 1.3 also apply.

1.5 If the Software is an update version of a previous product ("original product") and End User has bought the update version as part of an update service, End User is only entitled to install and use the Software, if End User is in possession of a valid license for an original product marked available for upgrade by ThinPrint. End User must be aware that the update version replaces the original product and/or its supplements and may deactivate it.

1.6 If the Software is marked "School Version", End User is only entitled to the use described in 1.1–1.3, if End User uses the Software as "Entitled User in an Approved Educational Establishment". To obtain the entitlement mentioned in sentence 1, End User has to apply in writing to ThinPrint GmbH, Alt-Moabit 91a/b, 10559 Berlin, Germany.

1.7 If the Software has been marked "NFR" (Not For Resale), the use of the Software is limited to demo, test or evaluation purposes only. Any further use is prohibited. End User is especially not entitled to resell the Software or pass it on in any other way to a Third Party.

1.8 Any other rights of ThinPrint not explicitly asserted above remain unaffected.

2. Transmission of the Software onto 2nd Computer, Disclosure to Third Parties

2.1 The Software itself may at no time be sold, loaned, rented or passed on in any other way to Third Parties.

2.2 End User is only entitled to install the Software on a second computer, server or server farm, if the Software, after its transmission onto the second computer, server or server farm has been completely and permanently removed and/or cancelled from the first computer, server or server farm. Upon installation of the Software onto the second computer, server or server farm, all other parts of the Software, including but not limited to its add-on programs, descriptions, media and other printed materials, also must be transferred. All persons having access to the second computer, server or server farm and therefore to the Software must be sufficiently informed of the contents and the individual conditions of the EULA.

3. Licensing

It is not necessary to activate any license key in order to use the Software.

4. Software-components of the ".print Client Windows"

The ".print Client Windows" is an additional software component of the ".print"-product line that provides services and functions on a computer.

5. Intellectual Properties, Trademarks and Copyrights of the Software

The Software, its entire contents (including but not limited to pictures, photos, animations, video, audio, music, text and “Applets”), any contents accessible through the Software, and copies thereof are protected by any and all available national and international copyrights, commercial protection rights, especially patent rights, utility patent, design patent and trade rights and all other existing protection rights of the Software, its improvements, bug fixes and extensions or any other modifications to the Software, regardless of their origin. By accepting the EULA, End User is obliged to use and observe all of the aforementioned rights of the Software product which are entitled to ThinPrint or Third Parties only as stipulated and defined in the EULA and not to infringe or violate such rights including in particular that no content must be copied or in any other way multiplied, stored, sold or passed on in any way, nor – apart from the Software itself – be used. End User is entitled to print a documentation of the Software, if the documentation is only provided in electronic form. End User may multiple copies of all printed materials accompanying the Software for internal use.

6. Warranty

6.1 The Software only has to perform those functions mentioned and described in the manual without error.

6.2 Otherwise, the General Terms and Conditions of Business of ThinPrint governing the purchase of Software apply.

7. Liability

7.1 ThinPrint tests the Software and validates its general suitability. If damages occur to End User during the installation or use of the Software, ThinPrint is liable completely and to twice the value of the purchase price of said Software not exceeding in any case a total sum of EUR 50,000, if said damages are directly caused by improper and/or incomplete testing or improper or incomplete test of suitability. Liability for negligence and gross negligence of ThinPrint is limited to damages that have been foreseeable or should have been foreseeable. ThinPrint assumes no liability for indirect or atypical damages (consequential or otherwise) or for any financial losses such as loss of profits or savings.

7.2 If End User does not make any adequate (at least daily), reasonable and common to the current state-of-the-art backup of his data in the interest of data security, or – in case of suspected Software error – fails to take reasonable and adequate security measures, End User has to accept contributory negligence regarding resulting damages.

7.3 ThinPrint is only liable for damages arising to End User within the context of or due to the Software download process from the ThinPrint website or during the installation process. ThinPrint specifically does not guarantee freedom from computer viruses, so that ThinPrint can not be held liable for any damage arising from computer viruses. In fact, End User is specifically obliged to use sufficient and always up-to-date protection against computer viruses and to actively prevent infiltration by computer viruses, in particular before End User starts downloading the Software.

7.4 ThinPrint assumes no liability for the information and the Software “.print Client Windows” regarding defects of quality or title, particularly for the accuracy, correctness, freedom of third-party trademark rights and copyrights, completeness and/or usability, except for cases of gross negligence or malice traceable to ThinPrint. In case of proven gross negligence or intent of ThinPrint, ThinPrint is liable to a maximum sum of EUR 50,000.

7.5 The product liability of ThinPrint remains unaffected.

8. Forfeiture

If End User or his employees and/or representatives violate any rights and/or obligations arising from the EULA, especially rights of use, ThinPrint is entitled to request End User to immediately abandon the use of the Software and its copies and to delete or return the Software and its copies to ThinPrint. ThinPrint reserves any rights to claim for damages.

9. Transfer of Rights

Neither party may assign or transfer the EULA and the rights and obligations arising hereof to a Third Party without previous written permission of the respective other party, unless the Transferring Party and the Third Party are in a state of dependence as defined in § 17 of the German Stock Companies Act (AktG) or the Third Party takes over all or almost all assets of the transferring party by written contract. The permission as defined in sentence 1 may be denied given significant causes. Significant cause is particularly given, if the fulfillment of rights and obligations under the EULA are endangered due to such transfer.

10. Scope of the EULA

The EULA ultimately stipulates all rights of use of the Software as well as any other right and/or obligation of End User and ThinPrint, as long as deviant written agreements and conditions individually agreed between the Parties do not exist. The EULA supersedes any and all previous oral or written agreements, information or offers concerning the Software.

11. Place of Jurisdiction/Applicable Law

The EULA and its implementation shall be construed and interpreted in accordance with German Law and be subject to the exclusive jurisdiction of the Courts of Berlin, Germany. Any terms of the CISG (United Nations Convention on Contracts for the International Sale of Goods) are applicable, if and insofar as they include mandatory law.

12. Severability Clause

If any one or more of the provisions contained in the EULA shall, for any reason, be held invalid, illegal or unenforceable in any respect, such invalidity, illegality or unenforceability shall not affect the remaining provisions of the EULA, but the EULA shall be construed as if such invalid, illegal or unenforceable provision had never been contained herein, unless the deletion of such provision or provisions would result in such a material change so as to cause completion of the transactions completed herein to be unreason-

able. In lieu of such invalid, illegal or unenforceable provision shall be added a provision similar in terms to such provision as may be valid, legal and enforceable and suiting the Parties contractual interests best.
ThinPrint GmbH, 10559 Berlin
November 2007/v2.2

Distributing .print Client


The program “Custom Installation Wizard” can be used together with the [Preconfiguration and unattended installation of .print Client Windows](#) white paper for presetting .msi-versions of .print Client Windows.

Custom Installation Wizard The CUSTOM INSTALLATION WIZARD FOR .PRINT CLIENT WINDOWS .MSI FILES can be downloaded from: www.thinprint.com/→ SUPPORT & SERVICES→ SOFTWARE DOWNLOAD→ CONTINUE→ .PRINT CLIENT WINDOWS .MSI FILES.

Installing additional .print Client Windows types

It is possible to install several types of .print Client Windows on a single client machine. Thus you get a .print Client, that supports multiple protocols simultaneously (TCP/IP, ICA, and/or RDP).

1. Therefor run the .print Client installation program **Setup.exe** (not over CONTROL PANEL→ADD/REMOVE PROGRAMS). The menu in Illus. 31 appears. Or run the relevant **.msi file** (Pages 8 and 13).




Illus. 31 Modify or repair the .print Client Windows

2. If you run the **Setup.exe** select MODIFY afterwards. The menu in Illus. 32 appears.

3. Select additional .print Client Windows types for installation.

Note! It is not possible to install both TCP/IP clients (.print Client Windows and .print Client Service Windows) on the same computer. Removing the checkmark (Illus. 32) will uninstall the .print Clients.



Illus. 32 Installing additional (or uninstalling) .print Client Windows types (example)

Repairing .print Client Windows

Should .print Client Windows ever quit functioning, you don't have to reinstall it – you can repair it. .print Client Windows are repaired exactly as described above, except that REPAIR is selected instead of MODIFY (Illus. 31).

Updating .print Client Windows


Please note that previous settings are still valid when updating or installing .print Client on a machine where it was installed before.

1. Uninstall the present .print Client (see next chapter).
2. Install the new one (Page [7](#) or [13](#)).

Uninstalling .print Client Windows


1. Select CONTROL PANEL→ADD OR REMOVE PROGRAMS, select .PRINT CLIENT WINDOWS¹⁴, and click REMOVE (Illus. 33).

¹⁴ formerly ThinPrint Client



Illus. 33 Removing .print Client Windows (Example for Windows XP)

2. Did you use the Setup.exe for installation the menu in Illus. 34 appears. Select REMOVE and then NEXT.
3. Confirm the following windows with REMOVE and FINISH.



Illus. 34 Deleting .print Client(s) Windows

Relevant entries in Windows Registry

Registry entries of .print Client Windows

The .print Client creates the following Registry entries under:

hkey_local_machine\software\thinprint\client

Name	Menu item (.print Client Manager)	Description	Type	Default value
AdminOnly	ADMINISTRATORS ONLY	Restricts client configuration to administrators only	reg_dword	0
Bandwidth	BANDWIDTH	Client-side bandwidth setting (bit/s or bps)	reg_dword	none
ConnAuthKey	AUTHENTICATION KEY	Value can be defined by the admin on the connection server; otherwise it's irrelevant for the first logon, but may not be changed thereafter	reg_dword	0
ConnKeep-Alive	—	Interval for refreshing the connection; has to be lower or equal than .print Connection Service's "KeepAliveTO" (server side); (in seconds)	reg_dword	60
ConnMode	USE CONNECTION SERVICE	0 = Receiving print jobs without .print Connection Service (Listen Mode) 3 = Using .print Connection Service Static Mode 1 = both modes at the same time (0 + 3)	reg_dword	0
ConnPort	TCP PORT (CONNECTION Svc)	TCP port for communication with the .print Connection Service; be sure: same TCP port number as .print Connection Service's "ClientPort"	reg_dword	4001
ConnServer	CONNECTION SERVER ADDRESS	IP address of the computer on which .print Connection Service is running	reg_sz	127.0.0.1
ConnUID	CLIENT ID	Client ID for the static mode – an unambiguous ID must be assigned for all clients (TPUID)	reg_dword	0
ConnWait	CONNECTION RETRY INTERVAL	Wait time for connection retries if .print Connection Service is not reachable (in seconds)	reg_dword	300
DefaultState	DEFAULT AT SERVER	AutoConnect defines current printer as default printer at server; Page 16	reg_dword	1

Name	Menu item (.print Client Manager)	Description	Type	Default value
PName_ <i>n</i>	PRINTER (ASSIGNMENT)	Name(s) of client printer(s) as read from the system settings	reg_sz	none
Port	TCP PORT (ADVANCED)	TCP-Port for communication with the .print Engine; must be the same as .print Engine "port" with a normal ThinPrint port	reg_dword	4000
PrinterClasses	CHOOSE CLASS NAME	Names of the created printer classes	reg_sz	PCL5, PS, TXT
PTSPort	PRINT-TO-SCREEN	Print-to-Screen interface (e.g. COM2, RIM_USB); not .print Client Windows 7.0 V	reg_sz	none
PType_ <i>n</i>	CLASS (ASSIGNMENT)	Assigned printer class (<i>n</i> corresponds to <i>n</i> from PName_ <i>n</i>) plus printer driver name	reg_sz	none
Selected- Printer	CURRENT PRINTER	.print Client's default printer	reg_sz	UseWD efault
Send- Properties	ENABLE SENDING PROPERTIES	AutoConnect option for sending printer properties	reg_dword	1
UseWDefault	INHERIT CLIENT'S DEFAULT PRINTER	Set to use local Windows default printer as CURRENT PRINTER	reg_dword	1

Additional Registry entries of .print Client Windows

The following Registry entries can be created by the Custom Installation Wizard or have to be created manually under:

hkey_local_machine\software\thinprint\client

Name	Menu item (Custom Installation Wizard)	Description	Type	Default value
CertName (Windows 2000 and later)	SSL ENCRYPTION → CERTIFICATE NAME	Name of the imported SSL/TLS certificate; Page 23	reg_sz	none
CERTSTORE (.print Client Windows 7.0 V and later)	CERTIFICATE STORE	0 = use the user's certificate store 1 = use the computer's certificate store Note: Permissions has to be assigned to the certificate (see the Creating SSL certificates for printing with .print white paper).	reg_dword	0
DefPrintState	PRINTER SELECTION	Value for the automatic selection of all newly installed printers for Auto-Connect; 1 = enabled	reg_dword	none
HKCU	PRIORITY FOR SAVING SETTINGS	1 = .print Client configuration is user specific saved under: hkey_current_user\software\thinprint\client	reg_dword	0
NewID	ASSIGN PRINTER ID	Specifies the starting value for printer ID assignment	reg_dword	none
PreviewPrinter	PREVIEW PRINTER FOR OUTPUT GATEWAY	Specifies whether a preview should be displayed on the client computer when using ThinPrint Output Gateway,	reg_dword	none
RmtConf	REMOTE CONFIGURATION	IP address of the administration machine from which the .print Client remote configuration is allowed (it is possible to enter more than one address); Page 24	reg_multi_sz	none

Name	Menu item (Custom Installation Wizard)	Description	Type	Default value
SetIDList	MODIFYING THE PRINTER LIST	Specifies whether changes in the .print Client (new printers, classes, etc.) should be applied when client is restarted 1 = changes are applied (printer list is updated) 0 = changes are reset Note: The „Reload printers“ function (see Page 14) has a higher priority than these settings.	reg_dword	none
StartDelay	START DELAY	Specifies whether and how long (in seconds) .print Client startup should be delayed after user login (applies only to .print Client Windows TCP/IP)	reg_dword	none
WATCHPRINTERS (.print Client Windows 7.0 V and later)	PRINTER LIST UPDATE	1 = .print Client updates its printer list automatically (as soon as a printer is added to or deleted from the machine) 0 = .print Client updates its printer list only if it is restarted or its “Reload Printers” option is executed	reg_dword	0

hkey_local_machine\software\thinprint\tpviewture

Name	Menu item (Custom Installation Wizard)	Description	Type	Default value
Move	POSITION	Specifies whether the position of the screen is to be moved to the printable area of the client printer (for use with ThinPrint Output Gateway only)	reg_dword	none
Resize	SIZE	Specifies whether the position of the screen is to be scaled to the printable area of the client printer (for use with ThinPrint Output Gateway only)	reg_dword	none

Further information on the single entries can be found in the respective chapters of this manual and of the [Preconfiguration and unattended installation of .print Client Windows](#) white paper.

.print Clients and supported features

.print Client	Network protocol			.print AutoConnect	Compression and streaming	Bandwidth control	SSL/TLS encryption	Output Gateway	.print Viewture	Virtual Channel Gateway	Connection Service
	ICA	TCP/IP	RDP								
+ possible – not possible											
Windows (TCP/IP) ^a	–	+	–	+	+	+	+	+	+	–	+
Windows (ICA)	+	–	–	+	+	+	+	+	+	+	–
Windows (RDP) ^b	–	–	+	+	+	+	+	+	+	+	–
Service Windows (TCP/IP) ^a	–	+	–	+	+	+	+	+	–	–	+
ActiveX Windows (TCP/IP) ^a	–	+	–	+	+	+	+	+	+	–	+
Linux (TCP/IP) ^a	–	+	–	+	+	+	+	–	–	–	+
Linux (RDP)	–	–	+	+	+	+	+	–	–	+	–
Java (TCP/IP) ^a	–	+	–	+	+	+	+	–	–	–	+
Java as an applet (ICA)	+	–	–	+	+	+	+	–	–	+	–
Win16 (TCP/IP) ^a	–	+	–	+	+	+	–	–	–	–	–
Win OS/2 (TCP/IP)	–	+	–	+	+	+	–	–	–	–	–
MS-DOS (TCP/IP) ^a	–	+	–	+	+	+	–	–	–	–	–
Windows CE (TCP/IP) ^a	–	+	–	+	+	+	–	–	–	–	–
Windows CE (ICA)	+	–	–	+	+	+	–	–	–	+	–
Windows CE (RDP)	–	–	+	+	+	+	–	–	–	+	–
Windows Mobile (TCP/IP) ^a	–	+	–	+	+	+	–	–	–	–	–
Windows Mobile (ICA)	+	–	–	+	+	+	–	–	–	–	–
Windows Mobile (RDP)	–	–	+	+	+	+	–	–	–	–	–
ActiveX Windows Mobile (TCP/IP) ^a	–	+	–	+	+	+	–	–	–	–	+
LPD device	–	+	–	–	+	+	–	–	–	–	–

a Also usable for ICA/RDP sessions, provided a TCP/IP connection exists between server and client

b RDP 5.0 required

c If a decompression filter can be installed