


A PhAst Overview

Morgan Rehnberg & Robert Crawford

May 10, 2013



Contents

1	Introduction	3
1.1	Overview	3
1.2	What's different about PhAst	3
2	Installing PhAst	5
2.1	PhAst binary	5
2.2	Installing from source	5
2.2.1	Required packages	5
2.3	Optional packages	6
2.4	Directory structure	6
2.5	The configuration file	6
2.6	Checking for updates	7
2.7	Miscellaneous notes	7
3	Working with multiple images	8
3.1	Overview	8
3.2	Adding images	8
3.3	Removing images	8
3.4	Refreshing images	9
3.5	Navigating the stack	9
3.6	Blinking images	9
4	PhAst features	10
4.1	Overview	10
4.2	Image types	10
4.3	Mouse modes	10
4.3.1	Color	10
4.3.2	Zoom	11
4.3.3	Blink	11
4.3.4	ImExam	11
4.3.5	Vector	11
4.3.6	Label	11
4.4	WCS features	11

4.4.1	Star overlay	13
4.4.2	Search	13
4.4.3	Image alignment	13
4.5	Photometry	13
4.5.1	Overview	13
4.5.2	Aperture centering and sizing	14
4.5.3	Color terms	16
4.5.4	Multi-image photometry	16
4.6	Processing images	17
4.6.1	SExtractor integration	17
4.6.2	SCAMP integration	18
4.6.3	missFITS integration	18
4.6.4	Photometric zero-point	18
4.7	MPC reporting	19
5	Experimental features	22
5.1	SPICE	22
A	Keyboard shortcuts	23
B	Calibration process	24
B.1	Overscan correction	24
B.2	Bias subtraction	24
B.3	Dark subtraction	24
B.4	Flat division	25
B.5	Binning	25
B.6	Precession	25
C	Programming with PhAst	26
C.1	Overview	26
C.2	PhAst program structure	26
C.2.1	PhAst index	26
C.2.2	Compilation order	26
C.2.3	Execution order	26
C.3	Common blocks	27
C.3.1	phast_state	27
C.3.2	phast_images	27
C.4	The image object	27
C.5	The image stack	28

Chapter 1

Introduction

1.1 Overview

PhAst is an interactive astronomical image display program, built on ATV 2.3. It is written in IDL. PhAst allows the user to open, view, and process multiple images in the popular FITS format.

1.2 What's different about PhAst

PhAst is a fork of Aaron Barth's ATV project at the 2.3 release. The project aims to expand ATV in three ways:

1. Redesign the GUI for use with modern widescreen displays
2. Provide support for multi-image analysis
3. Integrate outside tools to streamline the data reduction process

ATV's GUI is vertically oriented, while modern displays have become increasingly horizontal. PhAst attempts to make use of this newfound horizontal real estate by moving the main control panel to the left of the display window. For example, maximizing ATV tends to simply expand the menu panel far beyond what is needed, while expanding the image an equal amount. In PhAst, the menu panel remains fixed at all times, and any change in the program's size is directly translated into an increased image size.

Although ATV provides rudimentary support for blinking up to three images, only a single image is retained in memory at any given time. For example, if a user opens an image, scales it for blinking, then opens a second image and stretches it, these changes are not applied back to the initial image, which is now lost from memory. This process is useful for images of different exposure, but many sets of astronomical images have identical exposure and a single adjustment should be applied to all of them. By storing all images in an expandable stack, PhAst allows the user to manipulate any number of images, adjust them as a group, and animate through them all.

Finally, although ATV offers a robust photometry tool, it does not address astrometry other than support for existing WCS coordinates. PhAst also does not include a dedicated astrometry package, but it integrates with Emmanuel Bertin's excellent SExtractor and SCAMP tools for solving images. Including this capability also allows PhAst to expand its use of WCS coordinates, since the user can always use the astrometry pipeline to add them to his images.

Chapter 2

Installing PhAst

2.1 PhAst binary

PhAst is available in binary form from <http://www.noao.edu/noao/staff/mighell/phast/>. The binary is required for any user who does not have a valid IDL license. Running the binary requires the IDL Virtual Machine, available from <http://www.exelisvis.com>.

2.2 Installing from source

If you wish to modify PhAst, you must install it from source. The latest stable version is available from <http://www.noao.edu/noao/staff/mighell/phast/>. There is also a Git repository located at <http://github.com/forceflow1049/phast>. This repository contains past code versions plus the latest in-development version, which is likely to be unstable.

Move the directory containing PhAst to the location in which you want it installed. Launch IDL and type 'phast.install'. This will add the current location to your IDL path and check for the presence of the NASA Astronomy User's Library and the Coyote Library, which are required for operation. Once PhAst is installed, you can run it from any directory by typing 'phast' at the IDL prompt.

NOTE: PhAst requires IDL 8.0 or later to run.

2.2.1 Required packages

The main PhAst application is contained in a single IDL procedure, *phast.pro*. The following packages are also required:

- The NASA IDL Astronomy User's Library
- The Coyote Library

2.3 Optional packages

PhAst also supports a pipeline of reduction tools, designed to expedite data analysis. The following packages are optional, but will extend PhAst's capabilities:

- SExtractor
- SCAMP
- missFITS
- *zeropoint.param*
- *read_vicar.pro*
- *vicgetpars.pro*

See section 4.6 for more information on the features involving these packages. If you are using the binary version of PhAst, the files *read_vicar.pro* and *vicgetpars.pro* are already included.

2.4 Directory structure

The PhAst directory structure should look like:

```
phast/
  phast.pro
  phast_install.pro
  lib/
  output/
                                catalogs/
                                images/
```

PhAst requires an output directory named *output* in the same directory as the main program. The directories *catalogs* and *images* must exist inside of *output*. If PhAst is started and these directories are not found, it will ask to create them. Not creating these directories will cause PhAst to behave incorrectly and possibly crash. The images sub-directory can always be cleared by selecting File>Remove and selecting to empty the output directory.

2.5 The configuration file

Since PhAst is a GUI application, no configuration file is required for operation. Support for a configuration file is provided, however, to allow the user to set commonly used parameters to a desired value. If a configuration file is desired, create the file *phast.conf* in the same directory as the main program. Parameters can be set in the form *parameter value*, where a single tab separates the parameter and its value. Do not place quotes around string

values. Naturally, not all program variables can be set via the configuration file. Allowable parameters are listed in tables throughout this manual.

2.6 Checking for updates

You can check for updates to PhAst from within the application. Simply choose Help>Check for updates. By default, PhAst will check for updates every time it is started. Automatic update checking is a silent process - you will only be notified when a new version is available.

Parameter	Default	Type	Description
check_updates	1	0/1	check for updates on startup?

2.7 Miscellaneous notes

Because PhAst deals with large data files (in the form of images), it is rather dependant on a high-bandwidth, low-latency connection. It is always best to run PhAst from the local machine, or a machine on the local network. If you absolutely must run the program over the public internet, please be patient! It can take up to ten seconds for certain actions to load completely (ie, examing a star's photometry).

Chapter 3

Working with multiple images

3.1 Overview

A major advantage of PhAst over ATV is the ability to examine and process multiple images at once. This greatly expands the user's image comparison options. Although only one image can be displayed on the screen at a time, all added images are stored in a stack, where they can be readily accessed.

3.2 Adding images

Images can be added either one-by-one, or in entire directories. Adding single images has one potential advantage: packed (i.e., .fz) files can be loaded. Directory adding is limited to uncompressed images. FITS files can be added to the stack by choosing File>Read and selecting either a single image or an entire directory. Images are always added to the end of the stack. If an entire directory has been added, the images are added in the order in which they appear in the directory.

3.3 Removing images

A currently displayed image can be easily removed from the image stack. This is useful for an accidental image selection or when a poor-quality image is identified. Images can be removed by selecting File>Remove and choosing either to remove the current image or all images. The image(s) will be removed, the stack will be collapsed, and the next available image will be displayed. If all images are removed, any loaded catalog data is erased (see section 4.4.1 for more information).

3.4 Refreshing images

If the user modifies an image while it is in the stack, such modifications may not automatically be reflected in the archived image. Refreshing an image reloads it from disk, which will update the archived image to the latest version. This can be done by selecting File>Refresh and selecting to refresh either the current image or all archived images. Some processes, such as computing the photometric zero-point will automatically refresh the image upon completion.

3.5 Navigating the stack

Images can be quickly skimmed through with the arrow buttons located directly under the pan and track mini-windows. The user can also jump to any desired image by selecting it from the drop down list. More advanced navigation options are available in the Blink Control toolset, discussed in section 3.6. The keyboard shortcuts Page Up / Page Down can also be used to move forward and backwards through the stack. The Home key will jump to the first image and the End key will jump to the last.

3.6 Blinking images

The arrangement of working images into the stack makes blinking easy. Simply add the images in the order you wish them to be animated. The blink control toolbox provides an easily-accessible method for controlling the blinking process. To start a blink, simply press the play button. The images will begin to animate through at their default rate. This rate can be controlled with the Animate Speed slider. Three animation types are offered: forward, backward, and bounce (where the images are played forwards and then backwards). The animation can be stopped by pressing the pause button.

Parameter	Default	Type	Description
animate_speed	0.4	float	time (in sec) per image on [0.1,1]
animate_type	forward	string	forward/backward/bounce
tb_blink_visible	1	0/1	draw the blink controls?
tb_blink_toggle	1	0/1	expand blink controls initially?

Chapter 4

PhAst features

4.1 Overview

The following is an incomplete list of notable, non-obvious features of PhAst. For a more complete listing of basic functionality, see the documentation for ATV.

4.2 Image types

PhAst is primarily designed to view FITS images. It does not currently support FITS spectra. As of version 1.1, there is experimental support for NASA's VICAR image format, used on some spacecraft missions. These images can be opened by going to File > Read and selecting *Read VICAR Image*. VICAR images can be opened in the same session as FITS images. Pipeline features such as SExtractor and SCAMP execution do not work with VICAR images.

4.3 Mouse modes

ATV is built around a series of mouse modes, which define the behavior of mouse clicks on the main images. PhAst adds an additional mouse mode, *Label*. PhAst also changes the default mouse mode from Color to ImExam.

4.3.1 Color

While in Color mode, click and drag to adjust the brightness and contrast of the displayed image. Image adjustments are carried through to all opened images.

Parameter	Default	Type	Description
<code>invert_colormap</code>	0	0/1	invert image by default?

4.3.2 Zoom

While in Zoom mode, left-clicking magnifies the image and right-clicking demagnifies the image. Middle-clicking will center the image on the clicked pixel.

4.3.3 Blink

PhAst places less emphasis on the blink mouse mode than does ATV, instead relying on the Blink Control toolbox on the left pane. Clicking the mouse in blink mode will rapidly blink through up to three images, defined by choosing Blink>SetBlink1, etc from the menu bar. This method of blinking does not take into account any further changes made to the images (see section 3.6).

4.3.4 ImExam

ImExam mode allows basic information about a given region of the image to be quickly viewed. Left-clicking in ImExam mode displays the photometry window (see section 4.5), while right-clicking displays basic statistics. Middle-clicking centers the clicked pixel on the display area.

4.3.5 Vector

Click and drag in Vector mode to generate a 1-D spectrum of pixel brightnesses.

4.3.6 Label

The label mouse mode is new to PhAst. It provides a simpler interface to commonly performed labeling tasks. Left clicking while in label mode brings up the label region dialog, usually accessed through Labels>Region. In label mode, this form is automatically populated with the coordinates of the mouse click. The user can either left-click or left-click and drag to activate this feature. If only a click is performed, the radius is set to 10 px, allowing small circles to be quickly placed. If the user also drags, the radius of the circle will be set as the distance from mouse-press to mouse-release.

If the right mouse button is pressed, a text label can be placed on the image. A dialog box will popup for input and the label will be placed at the location of the mouse click.

Figure 4.1 shows some of the available annotations.

4.4 WCS features

PhAst supports World Coordinate System coordinates encoded in the FITS header. As the user mouses over an image, the left panel displays the current cursor position in terms of RA and Dec, as well as x,y image coordinates. The coordinate system can be changed in the ImageInfo menu category. The current image rotation is indicated by arrows showing north




Figure 4.1: Images can be annotated with text labels and shapes.

and east on the overview image. PhAst also makes use of WCS for both reference catalog lookup and image alignment.

4.4.1 Star overlay

Any image with valid WCS can have known catalog stars overlaid on the image. This is controlled by the Overlay Stars toolset on the left panel. The user can select the limiting magnitude down to which stars will be overlaid, and whether or not the names should be displayed (as opposed to just the positions). The default catalog for reference stars is USNO-B1.0, which is an online catalog. The catalog can be changed by selecting ImageInfo>Select Catalog.

Parameter	Default	Type	Description
tb_overlay_visible	1	0/1	Draw star overlay toolbox?
tb_overlay_toggle	0	0/1	Expand star overlay toolbox initially?

4.4.2 Search

If you have valid WCS and access to a catalog, you can search the current image for a known catalog star. This is useful if you are searching a dense field for a particular star. To perform a search, simply type the catalog name into the search box at the bottom of the Overlay Stars toolbox and press search. If the specified star is present in the current image, it's position and name are overlaid on the screen, in the same fashion as the star overlay option.

4.4.3 Image alignment

Images with valid WCS can also be aligned (registered), so that the fixed stars remain in place. This is especially useful when blinking images. Aligning the images will help any moving object in the field stand out despite any field motion. Image alignment can be selected in the basic stack navigation toolbox, directly under the pan and track mini-windows.

Parameter	Default	Type	Description
align_toggle	0	0/1	align images? 1=yes

If an image does not have WCS coordinates, these features are unavailable. The proper pointing data, however, can be written to the FITS header of each image as part of the pipeline process.

4.5 Photometry

4.5.1 Overview

PhAst maintains ATV's aperture photometry package, modifying it only to facilitate photometry over multiple images. The photometry window can be opened either by choosing

ImageInfo>Photometry or left-clicking while in the ImExam mouse mode. Two new buttons have been added to the photometry window, allowing the user to cycle through the images in the image stack. Once a star is selected, these buttons can be used to examine the photometry of the same star in several images. Note that this feature currently makes use of ATV's ability to snap to a nearby star. If your field shifts dramatically from image to image, or your field is particularly dense, use this feature with caution. The snap-to radius can be adjusted with the *Centering box size* field.

4.5.2 Aperture centering and sizing

PhAst offers three methods for centering the photometric aperture on a target:

- *Snap to* centering (inherited from ATV) in which the apertures are re-centered on the brightest pixel within the measuring aperture before the centroid is computed. The method attempts to find the object nearest to the location of the users mouse click.
- *Flux* centering, based on the x-y centroid of the flux contained within the inner sky aperture (to account for all of the flux) after subtracting the median sky background from total counts. The calculation is performed twice: first, based on the user's manual positioning of the cursor; second, based on the centroid computed in the first pass. The two-pass approach largely eliminates the influence of the user's initial manual positioning on the calculated centroid.
- *Manual* centering (inherited from ATV) in which the center of the whole pixel on which the user has clicked is taken as the centroid of the object and used to center the apertures.

The default centering method is *snap to*. The x-y position of the center of the aperture is also the basis for any astrometric position computed by PhAst.

When the program starts, the photometry apertures are sized automatically to cover defined fractions of the flux in a 2D Gaussian profile using the current value of PhAsts estimate of FWHM in images. The default value is 1.3". The sizing algorithm is:

1. The measurement aperture is sized to contain 72% of the flux for a 2D Gaussian PSF. This is considered to be the optimum for aperture measurements, because the sky noise grows more rapidly than the object flux beyond this point, leading to deterioration in the SNR. Once measured, the flux value (and error) are grown to give a total flux coverage of 90% or 94%. A theoretical growth curve based on the integrated volume under a circular 2D Gaussian PSF is used for this purpose.
2. The inner sky aperture is set so that 99.9% of the flux for a Gaussian PSF is contained within it, and essentially no object flux contaminates the sky annulus.
3. The outer sky aperture is set so that the sky annulus contains at least 200 pixels from which to determine the sky contribution.




Figure 4.2: The photometry window in its default state.

4.5.3 Color terms

As discussed below, PhAst has the capability to determine the photometric zeropoint of an image and will include a color term in the determination by default. PhAst provides two methods for selecting the color of an observed object. The object's spectral type (B-M, 0-9) can be selected from the photometry window and the appropriate color terms will be retrieved from a standard table. Alternatively, the color terms can be explicitly provided. The default spectral type is K0.

4.5.4 Multi-image photometry

The *Do all* button allows you to perform a photometric measurement at this point on all images. This is useful for recording a lightcurve for an object. For example, to write photometric data for an object over a set of images, you would do the following (see Figure ??):

1. Set mouse mode to ImExam
2. Click on object of choice (use star name overlay to find, if necessary)
3. Click *Write results to file...* and choose a filename
4. Click *Do all*
5. Click *Close photometry file*

This file will contain the photometric readings and error estimates for the object in each of your images.

Parameter	Default	Type	Description
ccdgain	1.0	float	ccd gain
ccdrn	0.0	float	ccd readnoise
ccdrotangle	90.0	float	rotation of ccd in deg
innersky	10.0	float	inner sky radius
magunits	0	0/1	Units: 0=counts, 1=magnitudes
outersky	20.0	float	outer sky radius
photerrors	0	0/1	calculate photometric error? 1=yes
photfilename	phastphot.dat	string	filename of output photometry data file
phot_rad_plot_open	1	0/1	show radial plot of photometry by default?
pixelscale	1.0	float	pixel scale in arcseconds
seeing	2*pixelscale	float	seeing in arcseconds
skytype	0	int	sky subtraction type: 0=idlphot, 1=median, 2=none

4.6 Processing images

PhAst provides a flexible option for calibrating images. To access the calibration features, choose Pipeline>Process images from the top menu. The calibration window allows the user to select an image to be calibrated, as well as a dark, flat, and bias image, if desired. Check the tickboxes for the calibration types you wish to use, and then select an image to correspond to each. Checking the overscan correct box will subtract any present overscan region from each image and then trim this region from the file. Custom binning values can be supplied to resize an image. For a detailed description of the calibration process, see section B.

NOTE: Binning an image will change its plate scale, which must be accounted for in other configuration files!

Parameter	Default	Type	Description
<code>bias_file</code>	-	string	bias file to be used for calibration
<code>cal_file_name</code>	<code>./output/images/phast.fits</code>	string	default filename for calibrated image
<code>dark_file</code>	-	string	dark file to be used for calibration
<code>flat_file</code>	-	string	flat file to be used for calibration

4.6.1 SExtractor integration

The currently displayed image can be plate-solved with SExtractor to extract any objects present. To use this feature, you must have a version of SExtractor installed such that it can be called via the command line with the command `sex`. In addition, the appropriate configuration files must be configured and placed in the same directory as PhAst. A text box is also given to allow you to pass commands to SExtractor. These commands are passed in the form of `OPTION_NAME VALUE`. For more information regarding SExtractor options, see its manual.

NOTE: SExtractor requires a number of configuration files to run. These files must be present in the same directory as `phast.pro`. The purpose of these files is described in the SExtractor manual.

Parameter	Default	Type	Description
compute_astrometry	0	0/1	Compute astrometry?
sex_catalog_name	-	string	path to where SExtractor catalog is placed
sex_flags	-	string	list of SExtractor flags. Use one space between flags
fits_crota1	0	float	RA field rotation
fits_crota2	0	float	Dec field rotation
fits_cdelt1	-	float	RA plate scale
fits_cdelt2	-	float	Dec plate scale

4.6.2 SCAMP integration

If a source list has been created using SExtractor, PhAst runs SCAMP to find an astrometric solution and write those coordinates to the FITS header. If there is significant uncertainty in an image's pointing data, you may need to relax SCAMP's error tolerance. Consult the SCAMP manual for the exact procedure to make this change.

NOTE: If your images do not contain the CROTA and CDELTA keywords in their FITS headers (or the data is incorrect), SCAMP will not solve them correctly. Use the configuration file parameters listed below to provide or override the rotation and plate scale.

Parameter	Default	Type	Description
scamp_flags	-	string	list of SCAMP flags. Use one space between flags
fits_crota1	0	float	RA field rotation
fits_crota2	0	float	Dec field rotation
fits_cdelt1	-	float	RA plate scale
fits_cdelt2	-	float	Dec plate scale

4.6.3 missFITS integration

Once a SCAMP solution is found, PhAst will use missFITS to write this data to the header of the calibrated image.

Parameter	Default	Type	Description
missfits_flags	-	string	list of missFITS flags. Use one space between flags

4.6.4 Photometric zero-point

If an image has been solved, and its WCS coordinates written to the FITS header, PhAst can use an external catalog to calculate the photometric zero-point. To calculate the zero-point for the currently displayed image, choose Pipeline>Photometric zero-point and click start.

The photometric zero-point will be calculated based on data from the currently selected catalog and written to the FITS header with the keyword *MAGZERO*. By default, the GSC-2.3.2 star catalog is used during the zero-point computation.

To determine catalog magnitudes, the flux coverage of the measuring aperture must be coordinated with the size of SExtractor's elliptical apertures. This is done automatically based on the SExtractor parameter *PHOT_AUTOPARAMS[0]*. If the value is 2.0, then the flux is grown to 90% coverage. If the value is 2.5, then the flux is grown to 94% coverage. These choices will be made (and the coverage ratio set) even if the user will simply measure instrumental magnitudes with PhAst. The default for PhAst is *PHOT_AUTOPARAMS[0] = 2.5* and a flux coverage ratio of 94%.

PhAst offers the option to report measurements as calibrated or absolute magnitudes. PhAst will solve for the zero-point and color-term coefficient of the filter passband used in the image. The solution involves matching the objects detected in the image to entries in the GSC-2.3.2 catalog by position. The GSC-2.3.2 catalog is derived from the same all-sky Schmidt sky survey used by the USNO-B1.0 catalog, but has superior photometry in the photographic B and R bands. The B-R color term is used in the zero-point determination. This method requires that the image have a valid astrometric solution to support the match of image stars to the catalog. To determine the zeropoint, a weighted linear regression analysis is performed to relate instrumental magnitudes to the R band catalog magnitude, with outlier rejection at the 2.4-sigma level (2 percent chance of false positive). *Z0* (zeropoint) and *Zc* (color term) coefficients are estimated.

A limitation of PhAst's zeropoint determination at present is that it operates on images individually. It can account for varying instrumental zeropoints by image (e.g., due to non-photometric conditions) only in the fit to catalog magnitudes. If the ensemble of catalog stars varies by image in the fits, the varying zeropoints may not be completely controlled.

NOTE: The file *zeropoint.param* must be present in the same directory as *phast.pro* for zero-point calibration to work.

NOTE: For technical reasons, processing currently does not automatically compute the photometric zero-point for images. This must be performed separately on each image.

4.7 MPC reporting

If a set of images have been properly calibrated with WCS and photometric zero-point data, PhAst can generate an object report for the Minor Planets Center (MPC). To prepare an MPC report, select *ImageInfo>MPC report*. You will be presented with three tabs to walk you through the report creation process. The Info tab displays the site and observer information to be included in the report. This information can be specified using the configuration file (see end of section for appropriate keywords). The data tab allows the user to select the data points they wish to select. With *MouseMode ImExam* selected, click *Choose a data point* and then click on the object in the image. The photometry window will appear. Use



Figure 4.3: PhAst’s batch processing allows for the calibration of an entire directory of files, or all currently loaded files.

it to confirm you have selected the correct target and that the object's magnitude seems appropriate. When you are satisfied that the correct object has been selected, click *Add selected point* to store the point for reporting. Up to five points can be stored for reporting. After at least two points have been selected, clicking the Check Plots tab will display plots of RA, Dec, and Magnitude vs time, as well as the computed velocity and position angle. This information can be used to help determine whether a suspected detection is real.

Parameter	Default	Type	Description
mpc_ack	-	string	MPC report ACK line
mpc_code	-	char	single character code
mpc_com	-	string	MPC report comment
mpc_contact_address	-	string	Contact address
mpc_contact_email	-	string	Contact email
mpc_contact_name	-	string	Contact person's name
mpc_height	-	float	Observatory elevation (m)
mpc_lat	-	float	Observatory latitude (deg)
mpc_lat_dir	N	N/S	Is lat north or south?
mpc_lon	-	float	Observatory longitude (deg)
mpc_lon_dir	W	E/W	Is the lon east or west?
mpc_observers	-	string	Observers' names
mpc_m measurer	-	string	Measurer's name
mpc_net	USNO-B1.0	string	MPC NET line
mpc_note1	-	char	MPC note 1 (see standard)
mpc_note2	-	char	MPC note 2 (see standard)
mpc_site_code	-	int	MPC site code
mpc_telescope	-	string	Telescope name

Chapter 5

Experimental features

The features described in this section probably don't work. If they do work, they are probably riddled with bugs. Even if you survive the bugs, these features probably aren't useful to you. You have been warned!

5.1 SPICE

The SPICE system is a software suite developed to provide the location and trajectories of all major objects in the solar system, including planets, moons, and spacecraft.

SPICE integration in PhAst currently allows the user to check whether their VICAR image contains any moons of Saturn and plots their position and range on the image. To use this feature, you must enable it in *phast.conf* and have the IDL SPICE package (ICY) properly installed and configured. SPICE kernels to be loaded should be listed, one per line, in a file specified by the parameter *kernel_list*. The default is *kernels.txt*.

Parameter	Default	Type	Description
tb_spice_visible	0	0/1	draw the SPICE controls?
tb_spice_toggle	0	0/1	expand SPICE controls initially?
kernel_list	kernels.txt	string	file containing list of kernels to load

Appendix A

Keyboard shortcuts

Below is a table of keyboard shortcuts available in PhAst. Note that the image part of the main window must have focus for keyboard shortcuts to be recognized.

Key	Description
c	column plot
e	erase annotations
h	histogram of pixel values
i	image statistics
m	cycle mouse modes
p	photometry
q	quit PhAst
r	row plot
s	surface plot
t	contour plot
x	extract spectrum
Down	move mouse cursor down
End	last image
Home	first image
Left	move mouse cursor left
Page Down	previous image
Page Up	next image
Right	move mouse cursor right
Up	move mouse cursor up

Appendix B

Calibration process

The calibration process used by PhAst is described below. If any of the calibration images are omitted, then the corresponding calibration step is not performed. If the bias frame is omitted, the bias value is assumed to be 0.

B.1 Overscan correction

If the overscan correction tickbox has been selected, all the images have their overscan subtracted. The FITS keyword BIASSEC is found and parsed for the bias region. For every row in the image, the median value from that row's bias region is found and subtracted from each other element. This process occurs for the science, dark, flat, and bias images (or any that have been provided). The overscan is then trimmed from the images.

B.2 Bias subtraction

The bias image is now subtracted from the science image on a pixel-by-pixel basis. A floor of zero is placed on each resulting value, preventing negative counts.

B.3 Dark subtraction

The bias frame is first subtracted from the dark frame. Since the dark frame could have a different exposure length than the science image, it must then be scaled to reflect this different. The EXPTIME keyword is extracted from both FITS headers and the ratio is used to scale the dark frame. Once scaled, the dark is subtracted from the science on a pixel-by-pixel basis.

B.4 Flat division

The bias frame is first subtracted from the flat frame. The dark frame is then scaled to match the flat's exposure time as described in the previous section. This scaled dark is then subtracted from the flat. The median value of a region defined by the middle 50% of each dimension is then computed. A flat map is then created by dividing the flat by this median value. The science image is then divided by this flat map.

B.5 Binning

Images are binned in the x and y directions using the FREBIN procedure. Surface flux is conserved.

B.6 Precession

Images whose equinox or epoch is not J2000 will be precessed to J2000. The IDL Astronomy User's Library procedure *precess* is used to perform the precession and the FITS header is updated to reflect the new equinox.

Appendix C

Programming with PhAst

C.1 Overview

PhAst is open-source software and you are encouraged to modify it for your own purposes. To assist in this, this appendix will describe the basic internal structure of PhAst.

C.2 PhAst program structure

C.2.1 PhAst index

An index file, *index.txt*, is located in the `lib/` directory and lists the location of every PhAst procedure.

C.2.2 Compilation order

The main procedure, *phast.pro* compiles and calls a series of additional procedures located in the `lib/` directory. They are compiled in alphabetical order so prepending a filename with `aaax_` will set its compile order. Note that `aaaa`, `aaab`, and `aaac` are already reserved.

C.2.3 Execution order

Starting PhAst results in the following initial procedure calls:

1. *phast.pro*
2. *phast_compile_modules.pro*
3. *phast_startup.pro*
4. *phast_initcommon.pro*

5. *phast_read_config.pro*

Once these procedures are called, PhAst should be sitting idle on its launch screen.

C.3 Common blocks

C.3.1 *phast_state*

The *phast_state* common block holds the values of all program-wide variables. It includes things such as the number of images loaded, the current image displayed, and the current astrometric catalog as well as interface states, like whether the blink widget is currently visible. If you want to add a system-wide value, create a new line in the *state* structure definition in the procedure *phast_initcommon*. Variables that do not need global scope should not be placed here and should be confined to their respective procedure or function. This helps avoid namespace overlap and increases performance.

C.3.2 *phast_images*

This common block contains copies of all the images PhAst needs, including both the temporary display copies and stored stack version. The image stack is known as the *image_archive* in the code. The image archive is an array which holds all the image objects created from loaded images.

C.4 The image object

Images stored in the image stack are contained in objects. These objects are defined by the *phast_image_define* procedure and have the class name *phast_image*. Each object has local pointers to the following data:

- *image*: the array containing the image data
- *header*: contains the data from the FITS header
- *name*: a string containing the pathname to the file originally loaded into PhAst
- *size*: a two-element array containing the x-y size of the image in pixels
- *rotation*: a float containing the rotation of the image in degrees, measured from the image's initial orientation on loading
- *astr*: contains the astrometric data, if available

Data can be altered and retrieved from the image object through the typical set of helper functions.

C.5 The image stack

The image stack is an array which contains the image objects for all images loaded into PhAst. It is called the *image_archive* and located in the *phast_images* common block. Images can be added to the stack through the *phast_add_image* procedure and removed via the *phast_remove_image* procedure.