

ISOTROPY

Version 9.0

User's Manual

August 2007

Harold T. Stokes, Dorian M. Hatch, and Branton J. Campbell
Department of Physics and Astronomy
Brigham Young University

ISOTROPY is a program which displays information about space groups, irreducible representations, isotropy subgroups, and phase transitions. The concepts and algorithms used in ISOTROPY were developed by Harold T. Stokes, Dorian M. Hatch, and Branton J. Campbell. The actual computer source code was written by Harold T. Stokes. Questions about using ISOTROPY may be directed to Harold T. Stokes via e-mail at `stokesh@byu.edu`.

This software may be distributed without restriction, but if it is used in research that results in publications, the use of this program should be acknowledged with reference to H. T. Stokes, D. M. Hatch, and B. J. Campbell.

To run ISOTROPY, type `iso`. After a pause, the program will respond with a message and then a prompt character (`*`), indicating that it is ready for a command. The user then enters commands which causes ISOTROPY to display the desired data. All entered commands, as well as the displayed data, are copied into a file, `iso.log`, in the current default directory. This file can be later examined or printed out.

ISOTROPY has access to six different space-group settings, found in the following references:

1. *International Tables for Crystallography*, Vol. A, edited by T. Hahn (Reidel, Boston, 1983).
2. *International Tables for X-Ray Crystallography*, Vol. I, edited by N. F. M. Henry and K. Lonsdale (Kynoch Press, Birmingham, 1965).
3. S. C. Miller and W. F. Love, *Tables of Irreducible Representations of Space Groups and Co-Representations of Magnetic Space Groups* (Pruett, Boulder, 1967). This is essentially the same as A. P. Cracknell, B. L. Davies, S. C. Miller, and W. F. Love, *Kronecker Product Tables*, Vol. 1 (Plenum, New York, 1979).
4. O. V. Kovalev, *Representations of the Crystallographic Space Groups: Irreducible Representations, Induced Representations and Corepresentations* (Gordon and Breach, Amsterdam, 1993).
5. C. J. Bradley and A. P. Cracknell, *The Mathematical Theory of Symmetry in Solids* (Clarendon, Oxford, 1972).
6. *The Irreducible Representations of Space Groups*, edited by J. Zak (Benjamin, New York, 1969).

These references will be referred to as International Tables (new ed.), International Tables (old ed.), Miller-Love, Kovalev, Bradley-Cracknell, and Zak, respectively. ISOTROPY has access to the irrep labeling of Miller-Love, Kovalev, Bradley-Cracknell, and Zak for all physically irreducible representations arising from \mathbf{k} points of symmetry. Also, ISOTROPY has access to the irrep labeling of Miller-Love for all physically irreducible representations arising from *all* \mathbf{k} points, including \mathbf{k} lines and \mathbf{k} planes of symmetry and general \mathbf{k} vectors.

When ISOTROPY starts, the default space-group setting is International Tables (new ed.) and the default irrep labeling is Miller-Love. The user can set up his own defaults by creating a file `iso.ini` containing commands. If this file exists in the current default directory, ISOTROPY will execute these commands when it starts, before giving the initial prompt (`*`).

ISOTROPY Commands

A command consists of a series of keywords and parameters. Different keywords and parameters are separated by a space character in the command. All keywords may be entered using either upper or lower case letters. All keywords may be abbreviated to the first one or more characters, depending on the ambiguity of the meaning of different commands that start with the same letter(s). ISOTROPY tells the user when a keyword is ambiguous.

If a question mark (?) is entered in place of one of the keywords, all valid keywords that could be entered at the position of the question mark will be displayed. For example, if a simple ? is entered in place of a command, ISOTROPY will indicate that the valid keywords are CANCEL, DISPLAY, LABEL, PAGE, QUIT, SCREEN, SETTING, SHOW, and VALUE. This means that the first keyword in a command must be one of these words. As another example, if LABEL ? is entered as a command, ISOTROPY will indicate that the valid keywords are ELEMENT, IMAGE, LATTICE, POINTGROUP, SPACEGROUP, and VECTOR. This means that if the first keyword in a command is LABEL, then it must be followed by one of those three words.

In the following material, each command is denoted by keywords and parameters ($p1$, $p2$) which may be a number or another keyword. A parameter in brackets (eg., [$p2$]) is optional and does not need to be present for a command to be valid.

CANCEL $p1$ $p2$ [$p3$...]

The keyword CANCEL can be put in front of any SHOW or VALUE command below to cancel the effect of that command. These cancel commands will not be explicitly listed here, except for a few commands which require some additional explanation.

CANCEL SHOW ALL

Cancels the effect of all SHOW commands previously used.

CANCEL SHOW ELEMENT

This command also causes CANCEL SHOW CHARACTER and CANCEL SHOW MATRIX to be automatically executed.

CANCEL SHOW IRREP [$p1$]

Cancels the effect of SHOW IRREP. The parameter $p1$ is the name of the one the settings (MILLER-LOVE, KOVALEV, BRADLEY-CRACKNELL, or ZAK). If $p1$ is present, then only the notation specified by $p1$ is removed from the display. If $p1$ is not present, then all irrep symbols are removed from the display. (Note that the irrep symbol in the current setting can only be removed from the display by removing all irrep symbols with CANCEL SHOW IRREP).

CANCEL VALUE ALL

Cancels the effect of all VALUE commands previously used.

DISPLAY BUSH

Data about a bush of vibrational modes are displayed. The parent space group, irrep, direction of the order parameter, and Wyckoff positions of the atoms must be selected.

When used with `SHOW MODES`, the atomic displacements in each mode is displayed. When used with `SHOW INVARIANTS`, the invariant polynomials in the free-energy expansion of the bush of modes are displayed.

DISPLAY DIRECTION

The irreps and directions of order parameters are displayed, given the parent space group, subgroup, basis vectors of the subgroup lattice, and origin of the subgroup.

DISPLAY DISTORTION

Symmetry-allowed distortions are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands.

DISPLAY IMAGE

Data about images of the irreps are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands.

DISPLAY INVARIANTS

Invariant polynomials in the representation space of one or more coupled irreps are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands. A parent space group must be selected (using `VALUE PARENT`), and one or more irreps must be selected (using `VALUE IRREP`). Each invariant polynomial and its degree are displayed without needing to use any `SHOW` commands.

`VALUE GRADIENT` may be used to display invariant polynomials containing spatial derivatives. The value selected by this command determines the number of derivatives each polynomial will contain. (Note that polynomials which vanish in a volume integral are also displayed. The user must inspect these himself and discard them by hand.) The degree of the polynomial must be selected (using `VALUE DEGREE`).

DISPLAY IRREP

Data about irreps are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands.

DISPLAY ISOTROPY

Data about isotropy subgroups are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands. Isotropy subgroups for irreps associated with \mathbf{k} lines and \mathbf{k} planes of symmetry and general \mathbf{k} vectors are not stored in the data base since they depend on the parameters α, β, γ which define the exact location of the \mathbf{k} vector. The data for these subgroups are read from a file with a name of the form, `ixxxx_x.iso`. `ISOTROPY` looks for this file in the user's directory. If it is not found, the user is prompted, and, if desired, `ISOTROPY` will then proceed to calculate the requested subgroups and create the file. Depending on the order parameter selected by `VALUE DIRECTION`, other files may also be created without notifying the user. For example, if only the kernel has been selected, a file of the form, `kxxxx_x.iso`, will be created. If only subgroups arising from one arm of the star of \mathbf{k} has been selected, a file of the form, `axxxx_x.iso`, will be created. If the direction of the order parameter has been explicitly selected, then a file of the form, `vxxxx_x.iso`, will be created.

DISPLAY ISOTROPY COUPLED

Data about isotropy subgroups of coupled order parameters are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands. A parent space group must be selected (using `VALUE PARENT`), and two or more irreps must be selected (using `VALUE IRREP`). The data for these subgroups are read from a file with a name of the form, `xxxx_xx.iso`. `ISOTROPY` looks for this file in the user's directory. If it is not found, the user is prompted, and, if desired, `ISOTROPY` will then proceed to calculate the requested subgroups and create the file. Note that not commands implemented for `DISPLAY ISOTROPY` are implemented for `DISPLAY ISOTROPY COUPLED`.

DISPLAY KPOINT

Data about \mathbf{k} vectors in the first Brillouin zone are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands.

DISPLAY PARENT

Data about space groups are displayed. (The word `PARENT` refers to "parent space group".) The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands.

DISPLAY SETTING

The current space-group setting being used is displayed.

DISPLAY SHOW

All `SHOW` commands currently in effect are shown.

DISPLAY SUPERSPACEGROUP

Data about (3+1)-dimensional superspace groups are displayed. The displayed data are controlled by `VALUE`, `SHOW`, and `CANCEL` commands.

DISPLAY VALUE

All `VALUE` commands currently in effect are shown.

LABEL ELEMENT *p1*

The notation for the space-group elements is changed. This affects the label displayed whenever elements of a space group are displayed. It also affects the way in which elements are to be entered with the `VALUE ELEMENT` command. The parameter *p1* indicates the notation to be used: `INTERNATIONAL`, `MILLER-LOVE`, `KOVALEV`, `BRADLEY-CRACKNELL` and `ZAK` for the notations of the international tables, Miller and Love, Kovalev, Bradley and Cracknell, and Zak, respectively. See the `VALUE ELEMENT` command for an explanation of these notations. Note that the `SETTING` command does not change the notation of space-group elements. For example, it is possible to show elements of a space group in the setting of Zak using Bradley and Cracknell's notation for the space-group elements. When `ISOTROPY` is started, the default notation for elements is `BRADLEY-CRACKNELL`.

The parameters `X1X2X3X4` and `XYZT` affect the notation used for elements of the (3+1)-dimensional superspace groups. The parameter `X1X2X3X4` (default) causes them to be displayed in x_1, x_2, x_3, x_4 coordinates using the international notation only. The parameter `XYZT` causes them to be displayed in x, y, z, t coordinates using any of the available notations, `BRADLEY-CRACKNELL` by default.

LABEL IMAGE *p1*

LABEL IMAGE TOLEDANO adds the notation of Tolédano and Tolédano for images whenever image symbols are displayed. LABEL IMAGE NOTOLEDANO removes this notation.

LABEL LATTICE *p1*

The notation for Bravais lattices is changed. This affects the label displayed when SHOW LATTICE is used. The parameter *p1* indicates the notation to be used: SCHOENFLIES and PEARSON. See the VALUE LATTICE command for more explanation about these notations.

LABEL POINTGROUP *p1*

The notation for point groups is changed. This affects the label displayed when SHOW POINTGROUP is used. The parameter *p1* indicates the notation to be used: INTERNATIONAL and SCHOENFLIES. See the VALUE POINTGROUP command for more explanation about these notations.

LABEL SPACEGROUP *p1*

The notation for the space-group label is changed. This affects the label displayed when SHOW PARENT or SHOW SUBGROUP are used. The parameter *p1* indicates the notation to be used: INTERNATIONAL and SCHOENFLIES. Also the international notation can be changed to the full symbol or the short symbol using LABEL SPACEGROUP INTERNATIONAL SHORT or LABEL SPACEGROUP INTERNATIONAL FULL, respectively. The full symbol reflects the choice of cell and unique axis for the monoclinic space groups, while the short symbol does not. The INTERNATIONAL label also reflects the setting used. For example, space group #12 is C2/m, A2/m, B2/m, B2/m for the INTERNATIONAL, MILLER-LOVE, BRADLEY-CRACKNELL, ZAK settings, respectively. When using the KOVALEV setting, only the SCHOENFLIES labeling of space groups is shown.

LABEL VECTOR *p1*

LABEL VECTOR PRIMITIVE causes the components of vectors and coordinates of points to be displayed in terms of primitive basis vectors. LABEL VECTOR CONVENTIONAL causes the components of vectors and coordinates of points to be displayed in terms of conventional basis vectors. For example, a vector $\frac{1}{2}a\hat{i} + \frac{1}{2}a\hat{j}$ in a face-centered cubic lattice would be displayed as (1/2, 1/2, 0) using conventional basis vectors and as (0, 0, 1) using primitive basis vectors. (This vector happens to be chosen for the third primitive basis vector for that lattice.) LABEL VECTOR PRIMITIVE cannot be used with the INTERNATIONAL setting.

PAGE *p1*

This command sets the number of lines that can be displayed on the terminal screen at one time. When the output to a particular DISPLAY command requires more lines than *p1*, only *p1* lines are displayed at a time. When ISOTROPY starts, the default number of lines is 22. If *p1* is NOBREAK, the output does not stop until the next prompt * is issued.

QUIT

The program ISOTROPY exits.

SCREEN *p1*

The width of the crt screen is changed to *p1* characters wide. The default width of the screen is 80 characters. If the data to be displayed require more than *p1* characters in a

line, ISOTROPY first tries to arrange the last column of data to form more than one line on the screen. If this cannot be done, the line is truncated and an asterisk (*) appears at the right edge of the screen.

SETTING *p1*

The current space-group setting is changed. The parameter *p1* is the name of the setting: INTERNATIONAL NEW, INTERNATIONAL OLD, MILLER-LOVE, KOVALEV, BRADLEY-CRACKNELL, and ZAK refer to the setting of International Tables (new ed.), International Tables (old ed.), Miller and Love, Kovalev, Bradley and Cracknell, and Zak, respectively. The current setting can be displayed using the DISPLAY SETTING command. Additional options for the settings in International Tables are discussed under the command, SETTING INTERNATIONAL *p1*. If the SETTING INTERNATIONAL command is used (without the keywords NEW or OLD), then the setting is returned to whichever edition was used the last time the current setting was INTERNATIONAL. When ISOTROPY starts, the current setting is INTERNATIONAL NEW. The SETTING command changes the notation used for irreps, unless the setting is changed to INTERNATIONAL.

SETTING INTERNATIONAL *p1*

This command allows additional options for the setting of space groups in International Tables.

Some space groups have two choices of origin. When ISOTROPY is started, origin choice 2 is used. (This is the choice with the point of inversion at the origin.) To change the origin choice for a particular space group, use SETTING INTERNATIONAL *p1* ORIGIN *p2*, where *p1* is a space-group number or symbol and *p2* is 1 or 2. The origin choice for all space groups (with more than one origin choice) can be changed by using ALL for *p1*. (Note that the origin choice is changed only for the current setting, i.e., the new or old edition, not both.) For example, SETTING INTERNATIONAL 228 ORIGIN 1 changes the setting to origin choice 1 for space group #228 *Fd3c*. SETTING INTERNATIONAL ALL ORIGIN 1 changes the setting of all space groups (which have two origin choices) to origin choice 1.

The monoclinic space groups have two choices for the unique axis. When ISOTROPY is started, unique axis *b* is used for the new edition and unique axis *c* is used for the old edition. To change the choice of unique axis for a particular space group, use SETTING INTERNATIONAL *p1* AXIS *p2*, where *p1* is a space-group number or symbol and *p2* is B or C. The choice of unique axis for all monoclinic space groups can be changed by using ALL for *p1*. (Note that the axis choice is changed only for the current setting, i.e., the new or old edition, not both.) For example, SETTING INTERNATIONAL 5 AXIS C changes the setting to unique axis *c* for space group #5 *A2*. SETTING INTERNATIONAL ALL AXIS C changes the setting of all monoclinic space groups to unique axis *c*.

The base-centered monoclinic space groups in the new edition have three cell choices. When ISOTROPY is started, cell choice 1 is used. To change the cell choice for a particular space group, use SETTING INTERNATIONAL *p1* CELL *p2*, where *p1* is a space-group number or symbol and *p2* is 1, 2, or 3. The cell choice for all base-centered monoclinic space groups can be changed by using ALL for *p1*. (Note that the cell choice is changed only if the current setting is the new edition.) For example, SETTING INTERNATIONAL 5 CELL 3 changes the

setting to cell choice 3 for space group #5 $A2$. `SETTING INTERNATIONAL ALL CELL 3` changes the setting of all base-centered monoclinic space groups to cell choice 3.

The trigonal space groups have two choices for axes: hexagonal and rhombohedral. When `ISOTROPY` is started, the hexagonal axes are used. To change the choice of axes for a particular space group, use `SETTING INTERNATIONAL p1 AXIS p2`, where $p1$ is a space-group number or symbol and $p2$ is `HEXAGONAL` or `RHOMBOHEDRAL`. The choice of axes for all trigonal space groups can be changed by using `ALL` for $p1$. (Note that the axis choice is changed only for the current setting, i.e., the new or old edition, not both.) For example, `SETTING INTERNATIONAL 167 AXIS RHOMBOHEDRAL` changes the setting to rhombohedral axes for space group #167 $R\bar{3}c$. `SETTING INTERNATIONAL ALL AXIS RHOMBOHEDRAL` changes the setting of all trigonal space groups to rhombohedral axes.

SETTING MAGNETIC

Data about the isotropy subgroups of the grey magnetic space groups are displayed when `DISPLAY ISOTROPY` is used. All coordinates are expressed in terms of the primitive basis vectors in the setting of Miller and Love.

Magnetic space groups are displayed in the following format: (1) the number of the associated Fedorov space group in parentheses, (2) the Belov number, and (3) the symbol given in Miller and Love. Magnetic space groups are selected using the number or symbol of the corresponding Fedorov space group. For example, `VALUE PARENT 155` or `VALUE PARENT R32` selects the grey magnetic space group $R321'$. The command `VALUE SUBGROUP 155` selects any of the four space groups associated with $R32$, i.e., $R32$, $R321'$, $R32'$, R_I32 .

SETTING NOMAGNETIC

The command, `SETTING MAGNETIC`, is cancelled.

SHOW ACTIVE

Active images are indicated when `DISPLAY IMAGE` is used. Active irreps are indicated when `DISPLAY IRREP` or `DISPLAY ISOTROPY` is used. An irrep is active when both its Landau and Lifshitz frequencies are zero (the Landau and Lifshitz conditions). An image is active when at least one active irrep is mapped onto it. Note that not all irreps mapped onto active images are active irreps. Some of them may fail the Lifshitz condition.

SHOW BASIS

The basis vectors are shown. When `DISPLAY PARENT` is used, the primitive basis vectors of the parent space group are shown. If `LABEL VECTOR CONVENTIONAL` is used, primitive basis vectors with respect to the conventional unit cell are shown.

When `DISPLAY ISOTROPY` is used, the basis vectors of the isotropy subgroup are shown. When used with `LABEL VECTOR PRIMITIVE`, the primitive basis vectors of the subgroup are given in terms of the primitive basis vectors of the parent space group. When used with `LABEL VECTOR CONVENTIONAL`, the conventional basis vectors of the subgroup are given in terms of the conventional basis vectors of the parent space group.

SHOW CARTESIAN

Cartesian coordinates are displayed. The cartesian coordinates are defined by the `VALUE LATTICE PARAMETER` command. This is only implemented a few places in `ISOTROPY`:

(1) `DISPLAY PARENT`: basis vectors of the primitive lattice (`SHOW BASIS`), space-group elements, displayed as a rotation matrix followed by a translation (`SHOW GENERATORS` and `SHOW ELEMENT`), and Wyckoff positions (`SHOW WYCKOFF VECTOR`). (2) `DISPLAY ISOTROPY`: basis vectors of the primitive lattice (`SHOW BASIS`) and space-group elements (`SHOW GENERATORS` and `SHOW ELEMENT`). (3) `DISPLAY DISTORTION`: Wyckoff positions and displacement vectors (`SHOW MICROSCOPIC`). In the case of Wyckoff positions, the values of the parameters x, y, z must be selected by `VALUE WYCKOFF XYZ` if needed. Vectors must be given in terms of conventional basis vectors, not primitive. The cartesian coordinate system is chosen so that the x axis lies along the a axis, and the y axis lies in the ab plane.

`SHOW CHARACTER`

The irrep character for an element of the parent space group is shown when `DISPLAY IRREP` is used. The `SHOW ELEMENT` command is also automatically executed. The element is selected with the `VALUE ELEMENT` command. (The character is the trace of the matrix onto which the irrep maps the element of the space group.)

`SHOW COMPATIBILITY`

The compatibility relations for an irrep is shown when `DISPLAY IRREP` is used. The irrep of the little group of \mathbf{k} is decomposed into irreps of the little group of \mathbf{k}' , where \mathbf{k}' is some \mathbf{k} vector with more degrees of freedom than \mathbf{k} and contains \mathbf{k} as a subspace of its domain. For example, if \mathbf{k} is a point of symmetry, then \mathbf{k}' may be a line of symmetry which contains that point. \mathbf{k}' may be selected by the `VALUE COMPATIBILITY` command. If not selected, then relations for every possible \mathbf{k}' with one degree of freedom less than that of \mathbf{k} are shown.

`SHOW COMPLEX`

The complex form of an irrep is shown when `DISPLAY IRREP` is used.

`SHOW CONTINUOUS`

The phase transitions allowed to be continuous in Landau theory or in RG theory are indicated when `DISPLAY ISOTROPY` is used. In Landau theory, a phase transition to a particular subgroup is allowed to be continuous if the irrep is active and the order parameter is a possible minimum of the free energy expanded to fourth degree. RG theory imposes the additional constraint that the coefficients of the free-energy expansion lie within the attractor basin of a stable fixed point.

`SHOW DIMENSION`

The dimension of the image of the irrep is shown when `DISPLAY IMAGE`, `DISPLAY INVARIANTS`, `DISPLAY IRREP`, or `DISPLAY ISOTROPY` is used. In the cases of `DISPLAY INVARIANTS` and `DISPLAY ISOTROPY COUPLED`, the dimension of the *reducible* representation is shown (the sum of the dimensions of each of the irreps selected).

`SHOW DIRECTION [p1]`

The symbol for the direction of the order parameter is shown when `DISPLAY ISOTROPY` or `DISPLAY DISTORTION` is used. If $p1$ is `VECTOR`, then the vector form of the order parameter is also shown.

When `DISPLAY DISTORTION` is used, the direction is shown only when one has been selected by `VALUE DIRECTION`. Also, the parameter `p1` is ignored.

When `DISPLAY ISOTROPY COUPLED` is used, the symbol for the order parameter direction of each irrep is shown followed by a number in parentheses indicating which domain of the uncoupled isotropy subgroup is involved. For example, suppose we display the isotropy subgroups for the coupled order parameters of irreps X_3^+ and P_5 of space group D_{4h}^{17} . We would find that one of the subgroups is D_{2d}^4 with order parameter direction `P1(1)P4(3)`. This means that this subgroup is an intersection of the first domain of D_{4h}^{16} [irrep X_3^+ , direction $P_1 = (a, 0)$] and the third domain of D_{2d}^{11} [irrep P_5 , direction $P_4 = (a, 0, \bar{a}, 0)$]. The direction of the order parameter for D_{2d}^4 is denoted `(a,0,b,0,-b,0)`, the first two components associated with irrep X_3^+ and the remaining four components associated with irrep P_5 . The irreps associated with each part of the order parameter may be seen by using `SHOW IRREP`.

`SHOW DISTINCT`

The domains for distinct subgroups are shown when `DISPLAY ISOTROPY` is used.

`SHOW DOMAINS [GENERATORS]`

The possible domains arising from the phase transition are shown when `DISPLAY ISOTROPY` is used. The number of possible domains is equal to the index of the isotropy subgroup in the parent space group. When the parameter `GENERATORS` is present, the element of the parent space group which generates the domain is also shown.

When `DISPLAY DISTORTIONS` is used, `SHOW DOMAINS` will cause the domain selected by `VALUE DOMAIN` to be shown.

`SHOW DOMAIN SETS`

The possible multidomain structures (domain sets) are shown when `DISPLAY ISOTROPY` is used. See the tutorial on domains.

`SHOW DOMAIN SETS ALL`

Equivalent domain sets are shown when `DISPLAY ISOTROPY` is used and when a class has been selected with `VALUE DOMAIN SETS CLASS`. When used with `SHOW DOMAIN SETS DIRECTION`, equivalent directions are shown when a direction has been selected with `VALUE DOMAIN SETS DIRECTION`.

`SHOW DOMAIN SETS BASIS`

The basis vectors of the domain set group are shown when `DISPLAY ISOTROPY` is used. When used with `SHOW DOMAIN SETS INTERSECT`, the basis vectors of the intersection group are shown.

`SHOW DOMAIN SETS DIRECTION`

The directions of the domain set vectors \vec{s} are shown when `DISPLAY ISOTROPY` is used. See the tutorial on domains.

`SHOW DOMAIN SETS ELEMENTS`

The elements of the domain set group are shown when `DISPLAY ISOTROPY` is used. When used with `SHOW DOMAIN SETS INTERSECT`, the elements of the intersection group are shown.

SHOW DOMAIN SETS EQUIVALENT

Operators which take us to equivalent domain sets or equivalent directions are shown when DISPLAY ISOTROPY is used. This command is used with SHOW DOMAIN SETS ALL.

SHOW DOMAIN SETS GENERATORS

The generating elements of the domain set group are shown when DISPLAY ISOTROPY is used. When used with SHOW DOMAIN SETS INTERSECT, the generating elements of the intersection group are shown.

SHOW DOMAIN SETS GROUP

The space group symmetry of the domain set is shown when DISPLAY ISOTROPY is used.

SHOW DOMAIN SETS INTERSECT

The space group symmetry of the intersection of the symmetries of every domain in the set is shown when DISPLAY ISOTROPY is used.

SHOW DOMAIN SETS ORIGIN

The origin of the domain set group is shown when DISPLAY ISOTROPY is used. When used with SHOW DOMAIN SETS INTERSECT, the origin of the intersection group is shown.

SHOW ELEMENTS

When used with DISPLAY PARENT, the coset representatives of the parent space group with respect to its translation subgroup are shown.

When used with DISPLAY IMAGE, all of the matrices of the image are shown.

When used with DISPLAY IRREP, the element of the parent space group selected by VALUE ELEMENT is shown.

When used with DISPLAY ISOTROPY, the coset representatives of the subgroup with respect to its translation subgroup are shown.

When used with DISPLAY SUPERSPACEGROUP, the coset representatives of the (3+1)-dimensional superspace group with respect to its translation subgroup are shown.

SHOW FAINTNESS

The nonzero faintness indices for all of the other irreps of the parent space group are shown when DISPLAY IRREP is used. Invariant polynomials exist which linearly couple these irreps to the selected irrep. The minimum degree of the part of the polynomial associated with the selected irrep is the faintness index. For example, if the selected irrep is R4+, we find a faintness index 3 for irrep R2+. The form of the invariant polynomial in this case is $q_1\eta_1\eta_2\eta_3$ where q_1 is the order parameter associated with R2+ and η_1, η_2, η_3 are components of the order parameter $\boldsymbol{\eta}$ associated with R4+. The coupling is linear in q_1 , and the degree of the part of the polynomial containing components of $\boldsymbol{\eta}$ is 3, the faintness index.

SHOW FELIX

The Felix frequency of the image is shown when DISPLAY IRREP or DISPLAY ISOTROPY is used. The Felix frequency is the number of anisotropic gradient terms in the LGW Hamiltonian.

SHOW FERROIC

The ferroic species of the phase transition is shown when `DISPLAY ISOTROPY` is used. See `VALUE FERROIC` for an explanation of the symbols.

SHOW FREQUENCY [*p1*]

When `DISPLAY IRREP` is used, the point-group irreps of the Wyckoff positions which induce the space-group irrep are shown, along with the subduction frequency. If *p1* is `VECTOR`, only the point-group irreps which induce vector irreps of the space-group irrep are shown, along with the number vector irreps which can be induce. This number will be some multiple of the subduction frequency, since there may be more than one independent set of vector basis functions for the point group irrep.

When `DISPLAY ISOTROPY` is used, the irreps which subduce the isotropy subgroup are shown, along with the subduction frequency. For each irrep, there is a direction of an order parameter which remains invariant under the operation of each element in the isotropy subgroup. If *p1* is `DIR`, the direction of that order parameter is shown. In parentheses is shown the domain number where you can find that direction if you display the isotropy subgroups for that irrep. If *p1* is `GAMMA`, only the Γ ($\mathbf{k} = 0$) irreps are shown. If *p1* is `CLASSIFICATION`, the symbol `F` (for “full”) is shown when the distortions associated with the irrep fully classify the domains of the subgroup. Otherwise, the symbol `P` (for “partial”) is shown.

SHOW GENERATORS

When used with `DISPLAY PARENT`, the generators of the parent space group are shown. (Generators of the lattice are actually not shown explicitly.)

When used with `DISPLAY IMAGE`, the generating matrices of the image are shown.

When used with `DISPLAY IRREP`, elements of the parent space group which are mapped onto the generating matrices of the irrep’s image are shown.

When used with `DISPLAY ISOTROPY`, the elements of the parent space group which generate the isotropy subgroup are shown.

When used with `DISPLAY SUPERSPACEGROUP`, the generators of the (3+1)-dimensional superspace group are shown. (Generators of the lattice are actually not shown explicitly.)

SHOW IMAGE

The symbol of the image of the irrep is shown when `DISPLAY IMAGE`, `DISPLAY IRREP`, or `DISPLAY ISOTROPY` is used.

SHOW INDEX

The index of the isotropy subgroup in the parent space group is shown when `DISPLAY ISOTROPY` is used. The index is the size of the parent space group relative to the subgroup.

SHOW INVARIANTS

The invariant polynomials in the free-energy expansion of a bush of modes are displayed when `DISPLAY BUSH` is used.

SHOW IRREP [*p1*]

The symbol of the irrep is shown when `DISPLAY INVARIANTS`, `DISPLAY DISTORTION`, `DISPLAY IRREP`, or `DISPLAY ISOTROPY` is used. The symbol shown uses the irrep notation

of the current space-group setting. The parameter *p1* allows the irrep symbol to also be shown in other notations. *p1* can be MILLER-LOVE, KOVALEV, BRADLEY-CRACKNELL, or ZAK, referring to the irrep notations of Miller and Love, Kovalev, Bradley and Cracknell, and Zak, respectively. *p1* can also be POINTGROUP, in which case the conventional labels for point-group irreps are shown for irreps at the Γ point ($\mathbf{k} = 0$). Even when *p1* is present, this command causes the irrep to be shown in the notation of the current setting in addition to the setting specified by *p1*. When DISPLAY INVARIANTS or DISPLAY ISOTROPY COUPLED is used, the symbols of all irreps selected are shown in sequence on the same line.

SHOW KDEGREE

The degrees of freedom of the \mathbf{k} vector are shown. For example, a \mathbf{k} point of symmetry has 0 degrees of freedom, and a \mathbf{k} line of symmetry has 1 degree of freedom.

SHOW KERNEL

The generating elements of the kernel of the irrep are shown when DISPLAY IRREP is used. (The kernel is the set of all elements in the parent space group which map onto the unit matrix in the image.)

SHOW KPOINT

The coordinates of the \mathbf{k} vector are shown when DISPLAY KPOINT, DISPLAY IRREP or DISPLAY DIRECTION is used. The coordinates are given in terms of the reciprocal lattice vectors derived from the basis vectors of the direct lattice. The form depends on the space-group setting as well as the form of the vectors used, primitive or conventional.

SHOW LANDAU

The Landau frequency of the image is shown when DISPLAY IMAGE, DISPLAY IRREP, or DISPLAY ISOTROPY is used. The Landau frequency is the number of independent third-degree invariants.

SHOW LATTICE

When DISPLAY PARENT is used, the Bravais lattice of the space group is shown. When DISPLAY SUPERSPACEGROUP is used, the Bravais lattice of the (3+1)-dimensional super-space group is shown. When DISPLAY ISOTROPY is used, the Bravais lattices of both the parent space group and isotropy subgroup are shown.

SHOW LIFSHITZ

The Lifshitz frequency of the irrep is shown when DISPLAY IRREP or DISPLAY ISOTROPY is used. The Lifshitz frequency is the number of times that the vector representation is contained in the antisymmetrized cube of the irrep.

SHOW LOCAL [*p1*] [*p2*]

The local microscopic distortions at a point about a Wyckoff position are displayed when DISPLAY DISTORTION is used. The coordinates of the point must be selected with the command VALUE POSITION. If *p1* is not present, then the distortions are shown as linear combinations of basis functions of the irrep of the point group associated with the point. The command SHOW LOCAL SCALAR displays distortions of scalar functions, such as occupation probabilities. The command SHOW LOCAL VECTOR displays vector distortions, such as

atomic displacements. The command `SHOW LOCAL VECTOR PSEUDO` displays pseudo vector distortions, such as molecular rotations or magnetic moments.

`SHOW MACROSCOPIC [PSEUDO]`

The macroscopic distortions (tensor components) are displayed when `DISPLAY DISTORTION` is used. The type of tensor must be specified by the `VALUE RANK` command. The parameter `PSEUDO` indicates a pseudo-tensor, such as a magnetic moment. For hexagonal crystals, the tensors are given with respect to an orthogonal coordinate system where the y axis is chosen to lie along the hexagonal b axis.

`SHOW MATRIX`

The irrep matrix for an element of the parent space group is shown when `DISPLAY IRREP` is used. The command `SHOW ELEMENT` is also automatically executed. The element is selected with the `VALUE ELEMENT` command.

`SHOW MAXIMAL`

Maximal isotropy subgroups are indicated when `DISPLAY ISOTROPY` is used. An isotropy subgroup is maximal when it is not a subgroup of any other isotropy subgroup for the same irrep.

`SHOW MICROSCOPIC [p1] [p2]`

The microscopic distortions are displayed when `DISPLAY DISTORTION` is used. If $p1$ is not present, then the distortions are shown as linear combinations of basis functions of the irrep of the point group associated with the Wyckoff position. The command `SHOW MICROSCOPIC SCALAR` displays distortions of scalar functions, such as occupation probabilities. The command `SHOW MICROSCOPIC VECTOR` displays vector distortions, such as atomic displacements. The command `SHOW MICROSCOPIC VECTOR PSEUDO` displays pseudo vector distortions, such as molecular rotations or magnetic moments.

`SHOW MODES`

The atomic displacements in each vibration mode of a bush are displayed when `DISPLAY BUSH` is used.

`SHOW NEWFRACTIONALS`

The new fractionals in the unit cell of the isotropy subgroup are shown when `DISPLAY ISOTROPY` is used. These new fractionals are vectors which are lattice vectors in the parent space group but are not lattice vectors in the isotropy subgroup.

`SHOW ORDER`

The order of the image is shown when `DISPLAY IMAGE` is used.

`SHOW ORIGIN`

The origin of the isotropy subgroup with respect to the parent space group is shown when `DISPLAY ISOTROPY` is used. When used with `LABEL VECTOR PRIMITIVE`, the coordinates of the origin are given in terms of the primitive basis vectors of the parent space group. When used with `LABEL VECTOR CONVENTIONAL`, the coordinates of the origin are given in terms of the conventional basis vectors of the parent space group.

SHOW PAIRS [*p1*]

This command shows information about pairs of domains of isotropy subgroups when `DISPLAY ISOTROPY` is used. We denote a pair of domains by (P_i, P_j) , where P_i is the i th domain of an isotropy subgroup. The pair to be considered can be selected by the `VALUE DOMAIN PAIRS` command. If the pair has not been selected, then the pair (P_1, P_j) is considered for each domain j .

When the pair has not been selected, equivalence classes of domain pairs are displayed. Any class of pairs has an element of the form (P_1, P_j) . Each pair is considered for every domain j . The number in the pair column numbers the class of pairs to which the pair belongs. For example, domain 3, pair 2 means the pair (1,3) is in the second equivalence class of pairs.

If *p1* is `INTERSECT`, the intersection of the isotropy groups belonging to the two domains in the domain pair is displayed. We call this the pair intersection group. This group is always one of the other isotropy subgroups belonging to the same irrep. Therefore, we display simply the direction of that isotropy subgroup. The domain of that subgroup is also shown in parentheses if it is not the first domain.

If *p1* is `SWITCH`, an element of the space group which switches the two domains in the pair is displayed. For the domain pair (P_i, P_j) , this element takes P_i to P_j and it also takes P_j to P_i . When the two domains are identical, we consider the switching element to not exist.

If *p1* is `GROUP`, the space group label of the pair group is displayed. This group consists of all elements in the pair intersection group plus all elements that switch the two domains in the pair. If *p1* is `BASIS`, `ORIGIN`, `GENERATORS`, or `ELEMENTS`, then the basis vectors of the lattice, the origin of the space group, the generating elements, or the complete list of elements of the pair group are displayed, respectively. These commands are very similar to the `SHOW BASIS`, `SHOW ORIGIN`, `SHOW GENERATORS`, and `SHOW ELEMENTS` commands used with the `DISPLAY ISOTROPY` command.

SHOW PARENT

The parent space group is displayed when `DISPLAY PARENT`, `DISPLAY INVARIANTS`, `DISPLAY DISTORTION`, `DISPLAY IRREP`, `DISPLAY ISOTROPY`, or `DISPLAY KPOINT` is used.

SHOW POINTGROUP

When `DISPLAY PARENT` is used, the point group of the space group is displayed. When `DISPLAY SUPERSPACEGROUP` is used, the point group of the basic space group of the (3+1)-dimensional superspace group is displayed. When `DISPLAY ISOTROPY` is used, the point groups of both the parent space group and isotropy subgroup are shown.

SHOW POSITION IRREP

The irrep of the point group associated with a point about a Wyckoff position is shown when `DISPLAY DISTORTION` is used with `SHOW LOCAL`.

SHOW SIZE

The relative sizes of the primitive unit cells of the parent space group and the isotropy subgroup is shown when `DISPLAY ISOTROPY` is used.

SHOW STAR

When `DISPLAY KPOINT` or `DISPLAY IRREP` is used, the star of \mathbf{k} is displayed.

SHOW SUBGROUP

The space-group symbol of the isotropy subgroup is shown when `DISPLAY ISOTROPY` is used.

SHOW SUBGROUP ALTERNATE

An alternate basis vector and origin are shown when `DISPLAY ISOTROPY` is used. If the basis vectors selected by `VALUE BASIS` and the origin selected by `VALUE ORIGIN` are consistent with the subgroup-symmetry being displayed, the selected values will be shown instead of those in the data base. This provides a way for you to try some “nicer” choices of basis vectors and origins and find out whether these choices still describe the same subgroup-symmetry.

SHOW SUPERSPACEGROUP

The superspace group is displayed when `DISPLAY SUPERSPACEGROUP` is used.

SHOW TWIN $p1$ [$p2$]

This command displays information about twin intersection groups and twin groups when `DISPLAY ISOTROPY` is used. This information is shown for a particular domain pair if one has been selected by the `VALUE DOMAIN PAIR` command. Otherwise, the pair (P_1, P_j) for each domain j will be used. In order to display information about twins, a plane must be specified by selecting its normal position using the `VALUE NORMAL` command and a point on the plane using the `VALUE POSITION` command.

If $p1$ is `INTERSECT`, then information about the twin intersection group is displayed. Each element in this group must obey the following requirements: It must be a member of each of the two isotropy subgroups associated with the two domains in the pair. (This means that this group is a subgroup of the pair intersection group.) If the element operates on a point in the specified plane, the point must stay in the plane. (This means that the group must be diperiodic.) If the point operator part of the element operates on a vector perpendicular to the specified plane, the direction of the vector must stay the same. To display information about twin intersection groups, an additional keyword ($p2$) must also be present. If $p2$ is `GROUP`, `BASIS`, `ORIGIN`, `GENERATORS`, or `ELEMENTS`, then the diperiodic space group label, the basis vectors of the lattice, the origin of the space group, the generating elements, or the complete list of elements of the twin intersection group are displayed, respectively. These commands are very similar to the `SHOW SUBGROUP`, `SHOW BASIS`, `SHOW ORIGIN`, `SHOW GENERATORS`, and `SHOW ELEMENTS` commands used with the `DISPLAY ISOTROPY` command.

Information which is displayed about the twin group is controlled by $p1$. Each element in the twin group must obey the following requirements: It must either keep both domains in the pair invariant or switch them. (This means that this group is a subgroup of the pair group.) If the elements operates on a point in the specified plane, the point must stay in the plane. (This means that the group must be diperiodic.) If the point operator part of the element operates on a vector perpendicular to the specified plane, the direction of the vector either stays the same or reverses its direction. If $p1$ is `GROUP`, `BASIS`, `ORIGIN`,

GENERATORS, or ELEMENTS, then the diperiodic space group label, the basis vectors of the lattice, the origin of the space group, the generating elements, or the complete list of elements of the twin group are displayed, respectively. These commands are very similar to the SHOW SUBGROUP, SHOW BASIS, SHOW ORIGIN, SHOW GENERATORS, and SHOW ELEMENTS commands used with the DISPLAY ISOTROPY command.

If $p1$ is SWITCH, then a “switching” element is displayed. If $p2$ is SIDE, then the element switches the two domains but does not change the direction of the vector normal to the plane. If $p2$ is NORMAL, then the element reverses the direction of the vector normal to the plane but does not switch the two domains. If $p2$ is BOTH, then the element switches both the two domains and the direction of the vector normal to the plane.

SHOW TYPE

The irrep type (1,2,3) are shown when DISPLAY IMAGE or DISPLAY IRREP is used. A type-1 irrep is real. A type-2 irrep is complex but its characters are real. A type-3 irrep is complex and its characters are also complex.

SHOW UNITCELL

Only distortions in the unit cell of the parent are shown when DISPLAY DISTORTIONS is used with SHOW MICROSCOPIC.

SHOW WYCKOFF [$p1, p2$]

When DISPLAY PARENT is used, the symbol for the Wyckoff position is shown. If $p1$ is VECTOR, the coordinates of the Wyckoff position are shown. In addition, if $p2$ is ALL, the coordinates of all of the points associated with the Wyckoff position are shown. If $p1$ is POINTGROUP, the point group of the Wyckoff position is shown. If $p1$ is ELEMENTS, the space-group elements which belong to the point group of the Wyckoff position are shown. If $p1$ is CHARACTER, the characters of the point-group irreps are shown for each space-group element which belongs to the point group of the Wyckoff position.

When DISPLAY DISTORTION is used, the symbol for the Wyckoff position is shown. If $p1$ is IRREP, the irrep of the point group of the Wyckoff position is shown.

SHOW WYCKOFF SUBGROUP

When DISPLAY ISOTROPY is used, the Wyckoff positions of the atoms in the subgroup are shown.

SHOW XYZ

The x, y, z coordinates of a point in the unit cell of the isotropy subgroup are given in terms of the x, y, z coordinates of a point in the unit cell of the parent space group when DISPLAY ISOTROPY is used. The coordinates are given with respect to the origins of the space groups. When used with LABEL VECTOR PRIMITIVE, the coordinates are given in terms of primitive basis vectors. When used with LABEL VECTOR CONVENTIONAL, the coordinates are given in terms of conventional basis vectors. (In the case of centered Bravais lattices, the conventional basis vectors are not primitive.)

VALUE ACTIVE $p1$

When DISPLAY IMAGE is used, VALUE ACTIVE YES selects active images and VALUE ACTIVE NO selects images which are not active. When DISPLAY IRREP or DISPLAY ISOTROPY is

used, `VALUE ACTIVE YES` selects active irreps and `VALUE ACTIVE NO` selects irreps which are not active. An irrep is active when both its Landau and Lifshitz frequencies are zero (the Landau and Lifshitz conditions). An image is active when at least one active irrep is mapped onto it. Note that not all irreps mapped onto active images are active irreps. Some of them may fail the Lifshitz condition.

`VALUE BASIS p1 p2 p3`

The basis vectors of a subgroup are selected. This command affects the data displayed by `DISPLAY DIRECTION`. p_1, p_2, p_3 are the three vectors. Each vector is denoted by three numbers separated by commas. The three numbers are components of the vector in terms of the basis vectors of the lattice of the parent space group. See `VALUE CELL` below for examples.

When used with `DISPLAY ISOTROPY`, the alternate basis vectors are selected. See `SHOW SUBGROUP ALTERNATE`.

`VALUE CELL p1 p2 p3`

The basis vectors of a super cell are selected. This command affects the data displayed by `DISPLAY DISTORTION`. p_1, p_2, p_3 are the three vectors. Each vector is denoted by three numbers separated by commas. The three numbers are components of the vector in terms of the basis vectors of the lattice. For example, $2, 0, 0$ denotes a vector which is two times the first basis vector of the lattice. Components may be fractions if the conventional form of the vector has been chosen with `LABEL VECTOR CONVENTIONAL`. Each vector must be a vector of the primitive lattice. For example, $1/2, 1/2, 0$ would be a vector of a face-centered lattice. When a super cell has been selected, `DISPLAY DISTORTION` shows all atoms in the super cell.

`VALUE COMPATIBILITY p1`

The compatibility relations to be shown by `DISPLAY IRREP` are selected. p_1 is the label of a \mathbf{k} vector. See the `SHOW COMPATIBILITY` command.

`VALUE CONTINUOUS p1`

Phase transitions which may or may not be allowed to be continuous in Landau theory or in RG theory are selected when `DISPLAY ISOTROPY` is used. `VALUE CONTINUOUS RG` selects isotropy subgroups to which a phase transition is allowed to be continuous in RG theory, `VALUE CONTINUOUS LANDAU` selects isotropy subgroups to which a phase transition is also allowed to be continuous in Landau theory and `VALUE CONTINUOUS NO` selects isotropy subgroups to which a phase transition is not allowed to be continuous in either theory. In Landau theory, a phase transition to a particular subgroup is allowed to be continuous if the irrep is active and the order parameter is a possible minimum of the free energy expanded to fourth degree. RG theory imposes the additional constraint that the coefficients of the free-energy expansion lie within the attractor basin of a stable fixed point.

`VALUE DEGREE p1 [p2]`

The degrees of invariant polynomials are selected. This command affects the data displayed by `DISPLAY INVARIANTS`. The parameters, p_1 and p_2 , are numbers representing the degree of the polynomial. If they are both present, then degrees p_1 through p_2 are selected. If only p_1 is present, then only degree p_1 is selected. If this command has not been used yet,

or if the `CANCEL VALUE DEGREE` command has been used, `ISOTROPY` displays the invariant polynomials of degrees 1 through 4 by default.

`VALUE DIMENSION p1 [p2]`

The dimensions of matrices in the irrep's image are selected. This command affects the data displayed by `DISPLAY IMAGE`, `DISPLAY IRREP`, and `DISPLAY ISOTROPY`. The parameters, $p1$ and $p2$, are numbers representing the dimension of matrices in an image. If they are both present, then dimensions $p1$ through $p2$ are selected. If only $p1$ is present, then only dimension $p1$ is selected.

`VALUE DIRECTION p1 [p2 ...]`

The direction of the order parameter is selected. This command affects the data displayed by `DISPLAY ISOTROPY`, `DISPLAY DISTORTION`, `DISPLAY INVARIANTS`, `DISPLAY BUSH`, and `DISPLAY DIRECTION`. The parameters $p1, p2, \dots$ each represent the direction of an order parameter. If more than one direction is selected, then corresponding irreps must be selected first, and the number of directions selected must equal the number of irreps selected.

The direction of an order parameter can be represented in several ways. The most usual way is to simply enter for the parameter the symbol of the direction (for example `VALUE DIRECTION P1` to select the direction P1). `VALUE DIRECTION KERNEL` selects the order parameter in the most general direction. `VALUE DIRECTION ONEARM` selects order parameters which arise from only one arm of the star of \mathbf{k} . These are implemented only for non \mathbf{k} points of symmetry. In addition, `VALUE DIRECTION ONEARM,P1` selects the order parameter P1 among those which arise from only one arm of the star of \mathbf{k} . `VALUE DIRECTION VECTOR,A,0,0` selects the order parameter $(a, 0, 0)$, and `VALUE DIRECTION VECTOR,0.5A,0.866A` selects the order parameter $(\frac{1}{2}a, \frac{1}{2}\sqrt{3}a)$. Note that irrational coefficients (and sometimes rational coefficients such as $\frac{1}{3}$) must be given to three decimal places.

`VALUE DOMAIN p1 [p2 ...]`

The domain of the isotropy subgroup is selected. This command affects the data displayed by `DISPLAY ISOTROPY` when used with `SHOW DOMAIN`, by `DISPLAY DISTORTION` when a subgroup has been selected with `VALUE DIRECTION`, and by `DISPLAY INVARIANTS` when the direction of an order parameter has been selected with `VALUE DIRECTION`. $p1$ is a number indicating the domain. (The numbering of domains may be obtained by using `SHOW DOMAINS` with `DISPLAY ISOTROPY`.) Normally, `DISPLAY ISOTROPY` used with `SHOW DOMAIN` causes all domains to be displayed. `VALUE DOMAIN` causes only one domain to be displayed. Normally, `DISPLAY DISTORTION` uses the direction of the order parameter in the first domain. `VALUE DOMAIN` along with `VALUE DIRECTION` uses the direction of the order parameter in selected domain. When used with `DISPLAY INVARIANTS`, the number of domains selected must be equal to the number of irreps selected by the `VALUE IRREP` command.

`VALUE DOMAIN PAIR p1 p2`

A pair of domains of the isotropy subgroup is selected. This command affects the data displayed by `DISPLAY ISOTROPY` when used with `SHOW PAIRS` or `SHOW TWIN` commands.

VALUE DOMAIN SETS CLASS $p1$

The class of the domain set is selected. This command affects the data displayed by `DISPLAY ISOTROPY`. $p1$ is a number which is displayed in the “class” column when `SHOW DOMAIN SETS` is used.

VALUE DOMAIN SETS DIRECTION $p1$

The direction of the domain set vector \vec{s} is selected. This command affects the data displayed by `DISPLAY ISOTROPY`. $p1$ is a number which is displayed in the “dir” column when `SHOW DOMAIN SETS` is used with `SHOW DOMAIN SETS DIRECTION`.

VALUE DOMAIN SETS ORDER $p1$

The order of the domain set is selected. This command affects the data displayed by `DISPLAY ISOTROPY`. $p1$ is a number representing the number of domains present in the set.

VALUE DOMAIN SETS UNCONNECTED $p1$

The number of unconnected parts of the domain set is selected. This command affects the data displayed by `DISPLAY ISOTROPY`. $p1$ is a number.

VALUE ELEMENT $p1$

The element of the parent space group is selected. This command affects the data displayed by `DISPLAY IRREP`. $p1$ is a space-group element. The element is denoted by a symbol, using the notation of International Tables, Miller and Love, Kovalev, Bradley and Cracknell, or Zak. For example, $X\ 1/2\text{-}Y\ \text{-}Z$, $2\ 0\ 1/2\ 0$, $H2\ 0\ 1/2\ 0$, $C2X\ 0\ 1/2\ 0$, and $UX\ 0\ 1/2\ 0$ all refer to the same element (using each of the notations, respectively). In the notation of the International Tables, the x,y,z parts are separated by a space character. In the other notations, the point operation comes first, followed by the fractional, each part separated by a space character. The notation used for $p1$ must agree with the point-operation notation selected for elements. The `LABEL ELEMENT` command changes the notation selected.

VALUE FELIX $p1$ [$p2$]

The Felix frequency of the image is selected. This command affects the data displayed by `DISPLAY IRREP` and `DISPLAY ISOTROPY`. The parameters, $p1$ and $p2$, are numbers representing the Felix frequency of an irrep (the number of anisotropic gradient terms in the LGW Hamiltonian). If they are both present, then Felix frequencies $p1$ through $p2$ are selected. If only $p1$ is present, then only Felix frequency $p1$ is selected.

VALUE FERROIC $p1$

The ferroic species of the phase transition is selected. This command affects the data displayed by `DISPLAY ISOTROPY`. The parameter $p1$ is a symbol representing the ferroic species: `FC` (ferroelectric), `PF` (proper ferroelectric), `IFC` (improper ferroelectric), `FS` (ferroelastic), `PFS` (proper ferroelastic), `IFS` (improper ferroelastic), `NF` (nonferroic), `OTHER` (other ferroic).

VALUE FREQUENCY $p1$ [$p2$]

The subduction frequency of the isotropy subgroup is selected. This command affects the data displayed by `DISPLAY ISOTROPY`. The parameters, $p1$ and $p2$, are numbers representing the subduction frequency. If they are both present, then subduction frequencies

$p1$ through $p2$ are selected. If only $p1$ is present, then only subduction frequency $p1$ is selected.

VALUE GRADIENT $p1$

The number of spatial derivatives in invariant polynomials is selected. This command affects the data displayed by `DISPLAY INVARIANTS`. The parameter $p1$ is a number representing the number of derivatives to appear in each invariant polynomial.

VALUE IMAGE $p1$

The image of the irrep is selected. This command affects the data displayed by `DISPLAY IMAGE`, `DISPLAY IRREP`, and `DISPLAY ISOTROPY`. The parameter $p1$ is an image to be selected. The image is denoted by a symbol, using either the notation of Stokes and Hatch or the notation of Tolédano and Tolédano.

VALUE IRREP $p1$ [$p2 \dots$]

The irreps are selected. This command affects the data displayed by `DISPLAY INVARIANTS`, `DISPLAY DISTORTION`, `DISPLAY IRREP`, `DISPLAY ISOTROPY`, and `DISPLAY KPOINT`. The parameters $p1, p2, \dots$ are irreps to be selected. Only the first irrep listed ($p1$) is used by `DISPLAY DISTORTIONS`, `DISPLAY IRREP`, and `DISPLAY ISOTROPY`. This command cancels the effect of any `VALUE KPOINT` command previously used. The irrep is denoted by a symbol, using either the notation of Miller and Love, Kovalev, Bradley and Cracknell, or Zak. For example, $Y1+$, $K8T1$, $Z1+$, and $Z1$ all refer to the same irrep (using each of the notations, respectively) in space group #12 $A2/m$. Note that $Z1$ and $A1$ are the same irrep in the Zak notation for this space group. When there are more than one symbol for the same irrep, any of them may be used for $p1$. GM is used for Γ . When a physically irreducible representation is constructed from two complex conjugate irreps, the notation indicates this (for example, $Z1Z2$ or $K22T1T2$ in space group #30 $Pnc2/mc2$).

The irrep notation used for $p1$ must agree with the current space-group setting. The `SETTING` command changes the current setting. When `SETTING INTERNATIONAL` is used, the current irrep notation does not change. When `ISOTROPY` is first started, the irrep notation is Miller and Love. See the `SETTING` command for an explanation of how the command affects the irrep selected by `VALUE IRREP`.

VALUE KDEGREE $p1$

The degrees of freedom of the \mathbf{k} vector are selected. This command affects the data displayed by `DISPLAY IRREP` and `DISPLAY KPOINT`.

VALUE KPOINT $p1$

Irreps which arise from a given \mathbf{k} point are selected. This command affects the data displayed by `DISPLAY IRREP`, `DISPLAY ISOTROPY` and `DISPLAY DISTORTION`. This command also selects the \mathbf{k} vector displayed by `DISPLAY KPOINT`. The parameter $p1$ is the \mathbf{k} point to be selected. This command cancels the effect of any `VALUE IRREP` command previously used. The \mathbf{k} point is denoted by a symbol, using either the notation of Miller and Love, Kovalev, Bradley and Cracknell, or Zak. For example, Y , $K8$, Z , and Z all refer to the same \mathbf{k} point (using each of the notations, respectively) in space group #12 $A2/m$. Note that Z and A are equivalent \mathbf{k} points in the Zak notation for this space group. When there are equivalent \mathbf{k} points, any of them may be used for $p1$. GM is used for Γ . As with irrep

notation, the \mathbf{k} -point notation used for $p1$ must agree with the current space-group setting. See the `VALUE IRREP` command for a further discussion of this point.

`VALUE KVALUE p1 [p2 ...]`

The values of the parameters α, β, γ defining the \mathbf{k} vectors are selected. The parameters $p1, p2, \dots$ each represent a set of parameters for a \mathbf{k} vector. The number of sets selected must equal the number of irreps selected. These parameters need only be selected if one or more of the irreps are associated with \mathbf{k} vectors which are not at \mathbf{k} points of symmetry. For example, a \mathbf{k} vector on a \mathbf{k} line of symmetry is defined by a single parameter α which gives the position of the vector on the line. In that case, `VALUE KVALUE 1, 1/4` would select one value, $\alpha = \frac{1}{4}$. `VALUE KVALUE 2, 1/4, 3/8` selects two values, $\alpha = \frac{1}{4}$ and $\beta = \frac{3}{8}$. `VALUE KVALUE 0 1, 1/4` selects values for two \mathbf{k} vectors, the first one at a \mathbf{k} point of symmetry and the second one at a \mathbf{k} line of symmetry. Each value must be given as a ratio of two integers, as shown in the examples.

`VALUE LANDAU p1 [p2]`

The Landau frequency of the image is selected. This command affects the data displayed by `DISPLAY IMAGE`, `DISPLAY IRREP`, and `DISPLAY ISOTROPY`. The parameters, $p1$ and $p2$, are numbers representing the Landau frequency of an image (the number of independent third-degree invariants). If they are both present, then Landau frequencies $p1$ through $p2$ are selected. If only $p1$ is present, then only Landau frequency $p1$ is selected.

`VALUE LATTICE p1 [p2]`

When `DISPLAY PARENT` is used, the Bravais lattices of the space group are selected. When `DISPLAY ISOTROPY` is used, the Bravais lattices of the isotropy subgroup are selected. When `DISPLAY SUPERSPACEGROUP` is used, the Bravais lattices of the basic space group of the (3+1)-dimensional superspace group are selected. The parameters, $p1$ and $p2$ are lattices. If they are both present, then lattices $p1$ through $p2$ are selected (using the order shown in the table below). If only $p1$ is present, then only lattice $p1$ is selected. The lattices are denoted by a symbol, using either the Schoenflies notation or the Pearson notation (see table below). For example, `VALUE LATTICE TI` and `VALUE LATTICE Q-V` both select the body-centered tetragonal lattice.

Lattice	Symbols	Lattice	Symbols
1. triclinic	T AP	8. primitive tetragonal	Q TP
2. primitive monoclinic	M MP	9. body-centered tetragonal	Q-V TI
3. base-centered monoclinic	M-B MC	10. Trigonal	RH HR
4. primitive orthorhombic	O OP	11. Hexagonal	H HP
5. base-centered orthorhombic	O-B OC	12. primitive cubic	C CP
6. body-centered orthorhombic	O-V OI	13. face-centered cubic	C-F CF
7. face-centered orthorhombic	O-F OF	14. body-centered cubic	C-V CI

VALUE LATTICE PARAMETER *p1 p2 p3 p4 p5 p6*

The lattice parameters are selected. The parameters *p1* through *p6* are the values of *a, b, c, α, β, γ* , respectively. *a, b, c* are the lengths of the 3 basis vectors **a, b, c** of the conventional lattice, α is the angle between **b** and **c**, β is the angle between **a** and **c**, and γ is the angle between **a** and **b**.

VALUE LIFSHITZ *p1 [p2]*

The Lifshitz frequency of the irrep is selected. This command affects the data displayed by DISPLAY IRREP and DISPLAY ISOTROPY. The parameters, *p1* and *p2*, are numbers representing the Lifshitz frequency of an irrep (the number of times that the vector representation is contained in the antisymmetrized cube of the irrep). If they are both present, then Lifshitz frequencies *p1* through *p2* are selected. If only *p1* is present, then only Lifshitz frequency *p1* is selected.

VALUE MAXIMAL *p1*

When DISPLAY ISOTROPY is used, VALUE MAXIMAL YES selects maximal isotropy subgroups and VALUE MAXIMAL NO selects subgroups which are not maximal. An isotropy subgroup is maximal when it is not a subgroup of any other isotropy subgroup for the same irrep.

VALUE NORMAL *p1 p2 p3*

This command affects the data displayed by DISPLAY ISOTROPY when one of the SHOW TWIN commands is used. This command selects the orientation of the plane between a domain pair. *p1 p2 p3* are the Miller indices (*hkl*) of the plane. All three numbers must be integers. Note that if the primitive labeling of vectors is selected by the LABEL VECTORS PRIMITIVE command, these Miller indices may not have their usual meaning.

VALUE ORDER *p1 [p2]*

The orders of the image are selected. This command affects the data displayed by DISPLAY IMAGE. The parameters, *p1* and *p2*, are numbers representing the order of an image (number of distinct matrices in the image group). If they are both present, then orders *p1* through *p2* are selected. If only *p1* is present, then only order *p1* is selected.

VALUE ORIGIN *p1*

The origin of a subgroup is selected. This command affects the data displayed by DISPLAY DIRECTION. *p1* is the position of the origin, denoted by three numbers separated by commas. The three numbers are coordinates in terms of the basis vectors of the lattice of the parent space group.

When used with DISPLAY ISOTROPY, the alternate origin is selected. See SHOW SUBGROUP ALTERNATE.

VALUE PARENT *p1 [p2]*

The parent space groups are selected. This command affects the data displayed by DISPLAY PARENT, DISPLAY INVARIANTS, DISPLAY DISTORTION, DISPLAY IRREP, DISPLAY ISOTROPY, DISPLAY KPOINT, and DISPLAY SUPERSPACEGROUP. The parameters, *p1* and *p2*, are space groups. If they are both present, then space groups *p1* through *p2* are selected. If only *p1* is present, then only space group *p1* is selected. The space groups can be denoted by a number or by a symbol, using either the Schoenflies or international notation

(either short or full symbol). For example, VALUE PARENT 124 refers to space group #124 (D_{4h}^2 or $P4/mcc$ or $P4/m2/c2/c$). This command could have also been entered as VALUE PARENT D4H-2 or VALUE PARENT P4/MCC or VALUE PARENT P4/M2/C2/C. Note that since parameters are delimited by space characters, they should not contain any space characters themselves. In the international notation, bars over numbers are denoted by a preceding minus sign (eg., P-3C1 for $P\bar{3}c1$) and subscripts are denoted by a preceding underline character (eg., P4_2/MCM for $P4_2/mcm$).

When used with DISPLAY SUPERSPACEGROUP, the VALUE PARENT command selects the basic space groups of the (3+1)-dimensional superspace groups.

VALUE POINTGROUP *p1* [*p2*]

When DISPLAY PARENT is used, the point groups of the space group are selected. When DISPLAY ISOTROPY is used, the point groups of the isotropy subgroup are selected. When DISPLAY SUPERSPACEGROUP is used, the point groups of the basic space group of the (3+1)-dimensional superspace group are selected. The parameters, *p1* and *p2* are space groups. If they are both present, then point groups *p1* through *p2* are selected (using the order shown in the table below). If only *p1* is present, then only point group *p1* is selected. The point groups are denoted by a symbol, using either the Schoenflies or international notation (see table below). For example, VALUE POINTGROUP OH and VALUE POINTGROUP M-3M both refer to the point group O_h or $m\bar{3}m$. A bar over a number is denoted by a preceding minus sign (eg., -4 for $\bar{4}$).

Point Group Symbols

1. C1	1	9. C4	4	17. C3I	-3	25. C6V	6MM
2. CI	-1	10. S4	-4	18. D3	32	26. D3H	-62M
3. C2	2	11. C4H	4/M	19. C3V	3M	27. D6H	6/MMM
4. CS	M	12. D4	422	20. D3D	-3M	28. T	23
5. C2H	2/M	13. C4V	4MM	21. C6	6	29. TH	M3
6. D2	222	14. D2D	-42M	22. C3H	-6	30. O	432
7. C2V	MM2	15. D4H	4/MMM	23. C6H	6/M	31. TD	-43M
8. D2H	MMM	16. C3	3	24. D6	622	32. OH	M-3M

VALUE POSITION *p1* *p2* *p3*

The coordinates of a point are selected. This command affects the data displayed by DISPLAY DISTORTION when SHOW LOCAL is used. The coordinates are assumed to be in terms of the basis vectors of the lattice, using the setting chosen at the time when DISPLAY DISTORTION is used. Each coordinate must be given in terms of rational numbers. For example, 1/2 1/2 1/2 would denote the coordinates at $(\frac{1}{2}, \frac{1}{2}, \frac{1}{2})$. Also, irrational coordinates can be denoted by x, y, or z. For example, x 1/2-x 0 would denote coordinates at $(x, \frac{1}{2} - x, 0)$, where *x* is an arbitrary irrational number. The coordinates x y z would denote a general point.

The command `VALUE POSITION` also affects the data displayed by `DISPLAY ISOTROPY` when one of the `SHOW TWIN` commands are used. In this case, a point on the plane between the pair of domains is selected.

`VALUE RANK p1`

The rank of a macroscopic tensor is selected. This command affects the data displayed by `DISPLAY DISTORTION` when `SHOW MACROSCOPIC` is used. $p1$ shows the indices of the tensor in numerical order. For example, $p1 = 1234$ indicates a tensor of rank 4. Indices to be symmetrized are enclosed by square brackets. For example, $p1 = [12]$ indicates a totally-symmetrized tensor of rank 2. Indices to be antisymmetrized are enclosed by curly brackets. For example, $p1 = 1\{23\}$ indicates a tensor of rank 3 which is antisymmetric with respect to the 2nd and 3rd indices. The value of the rank cannot exceed 6.

`VALUE SIZE p1 [p2]`

The relative sizes of the primitive unit cells of the parent space group and the isotropy subgroup are selected. This command affects the data displayed by `DISPLAY ISOTROPY`. The parameters, $p1$ and $p2$, are numbers representing relative size. If they are both present, then sizes $p1$ through $p2$ are selected. If only $p1$ is present, then only size $p1$ is selected.

`VALUE SUBGROUP p1 [p2]`

The isotropy subgroup space groups are selected. This command affects the data displayed by `DISPLAY ISOTROPY`. The parameters, $p1$ and $p2$, are space groups. If they are both present, then space groups $p1$ through $p2$ are selected. If only $p1$ is present, then only space group $p1$ is selected. The space groups can be denoted by a number or by a symbol. See `VALUE PARENT` for an explanation of the symbols used.

`VALUE SUBGROUP MAXIMAL`

The maximal subgroups of the parent are selected. This command affects the data displayed by `DISPLAY ISOTROPY`.

`VALUE SUBGROUP SUPERSPACEGROUP`

For non \mathbf{k} points of symmetry, we consider isotropy subgroups which have the symmetry of (3+1)-dimensional superspace groups and allow incommensurate distortions. This command affects the data displayed by `DISPLAY IRREP`, `DISPLAY ISOTROPY`, and `DISPLAY DISTORTION`.

`VALUE SUPERSPACEGROUP p1 [p2]`

The (3+1)-dimensional superspace groups are selected. This command affects the data displayed by `DISPLAY SUPERSPACEGROUP`. The parameters, $p1$ and $p2$, are superspace groups. If they are both present, then superspace groups $p1$ through $p2$ are selected. If only $p1$ is present, then only superspace group $p1$ is selected. The superspace groups can be denoted by a number or by a symbol, using the notation in *International Tables*, Vol. C. For example, `VALUE SUPERSPACEGROUP 49.8` refers to superspace group #49.8 $Pmaa(0\frac{1}{2}\gamma)$. This command could have also been entered as `VALUE SUPERSPACEGROUP PMAA(01/2G)`. Note that since parameters are delimited by space characters, they should not contain any space characters themselves. In the international notation, bars over numbers are denoted by a preceding minus sign (eg., $P\bar{3}c1(00\gamma)$) and subscripts are denoted by a preceding underline character (eg., $P4_2/mcm(00\gamma)$).

VALUE TYPE $p1$

The irrep type (1,2,3) is selected. This command affects the data displayed by DISPLAY IRREP and DISPLAY IMAGE. A type-1 irrep is real. A type-2 irrep is complex but its characters are real. A type-3 irrep is complex and its characters are also complex.

VALUE WYCKOFF $p1$ [$p2$...]

Wyckoff positions are selected. This command affects the data displayed by DISPLAY PARENT, DISPLAY IRREP, and DISPLAY DISTORTION. The parameters $p1, p2, \dots$ are the single-letter symbols of the positions, as given in International Tables.

VALUE WYCKOFF IRREP $p1$ [$p2$...]

Irreps of the point group of a Wyckoff position are selected. This command affects the data displayed by DISPLAY PARENT, DISPLAY IRREP, and DISPLAY DISTORTION. The parameters $p1, p2, \dots$ are the irrep symbols, using the convention of Bradley and Cracknell.

VALUE WYCKOFF XYZ $p1$ $p2$ $p3$

The parameters x, y, z of the Wyckoff position are selected. $p1, p2, p3$ are the values of x, y, z , respectively.

Q	quit
SC <i>p1</i>	width of screen
PAGE <i>p1</i>	number of lines displayed at a time
C V ...	cancel a V command
C V ALL	cancel all previously used V commands
C SH ...	cancel a SH command
C SH ALL	cancel all previously used SH commands
D V	display all V commands in effect
D SH	display all SH commands in effect
?	help (can be inserted in place of any keyword)

D SET	display the current space-group setting
SET <i>p1</i>	change the setting (<i>p1</i> = I, I NEW, I OLD, MI, K, B, Z)
SET I <i>p1</i> OR <i>p2</i>	origin choice (<i>p1</i> = space group or ALL and <i>p2</i> = 1, 2)
SET I <i>p1</i> AX <i>p2</i>	axis choice (<i>p1</i> = space group or ALL and <i>p2</i> = B, C, HEX, RH)
SET I <i>p1</i> CELL <i>p2</i>	cell choice (<i>p1</i> = space group or ALL and <i>p2</i> = 1, 2, 3)
SET MAG	magnetic space groups
SET NOMAG	return to Federov space groups

L SP <i>p1</i>	change the labeling of space groups (<i>p1</i> = SCH, I, I SHORT, I FULL)
L EL <i>p1</i>	change the labeling of space group elements (<i>p1</i> = I, M, K, B, Z, X1, XYZT)
L VEC <i>p1</i>	change the form of the vectors (<i>p1</i> = CON, PRIM)
L IM <i>p1</i>	use image notation of Tolédano and Tolédano (<i>p1</i> = TOL, NOTOL)
L PO <i>p1</i>	change the labeling of point groups (<i>p1</i> = SCH, I)
L LAT <i>p1</i>	change the labeling of lattices (<i>p1</i> = SCH, P)

D PAR	display data on parent space group
V PAR <i>p1</i> [<i>p2</i>]	select space group(s)
V LAT PAR <i>p1</i> ... <i>p6</i>	select lattice parameters <i>a, b, c, α, β, γ</i>
V LAT <i>p1</i> [<i>p2</i>]	select lattice(s)
V POINT <i>p1</i> [<i>p2</i>]	select point group(s)
V WY <i>p1</i> [<i>p2</i> ...]	select wyckoff positions
V WY IR <i>p1</i> [<i>p2</i> ...]	select point-group irrep of wyckoff position
V WY XYZ <i>p1</i> ... <i>p3</i>	select parameters <i>x, y, z</i> of wyckoff position
SH PAR	show space group symbol
SH CART	show Cartesian coordinates
SH GEN	show generating elements of space group
SH EL	show coset representatives of space group
SH LAT	show lattice
SH POINT	show point group
SH BAS	show basis vectors of lattice
SH WY [<i>p1, p2</i>]	show Wyckoff positions (<i>p1</i> = VEC, POINT, ELE, CHAR, <i>p2</i> = ALL)

D SUP	display data on (3+1)-dimensional superspace group
V SUP <i>p1</i> [<i>p2</i>]	select superspace group(s)
V PAR <i>p1</i> [<i>p2</i>]	select basic space group(s)
V LAT <i>p1</i> [<i>p2</i>]	select lattice(s) of the basic space group
V POINT <i>p1</i> [<i>p2</i>]	select point group(s) of the basic space group
SH SUP	show superspace group symbol
SH GEN	show generating elements of superspace group
SH EL	show coset representatives of superspace group
SH LAT	show lattice of superspace group
SH POINT	show point group of basic space group

D KP	display data on k points
V PAR <i>p1</i> [<i>p2</i>]	select space group(s)
V IR <i>p1</i>	select irrep
V KP <i>p1</i>	select k point
V KDEG <i>p1</i>	select degrees of freedom of k point
SH PAR	show space group symbol
SH KP	show coordinates of k point
SH KDEG	show degrees of freedom of k point
SH STAR	show the star of k

D IM	display data on images of irreps
V IM <i>p1</i>	select image
V DIM <i>p1</i> [<i>p2</i>]	select dimension(s)
V ORD <i>p1</i> [<i>p2</i>]	select order(s)
V ACT <i>p1</i>	select active or non-active images (<i>p1</i> = Y, N)
V LAN <i>p1</i> [<i>p2</i>]	select Landau frequency/frequencies
V TYPE <i>p1</i>	select type of irrep
SH IM	show image symbol
SH GEN	show generating matrices
SH EL	show all matrices
SH DIM	show dimension
SH ORD	show order
SH ACT	show whether image is active or not
SH LAN	show Landau frequency
SH TYPE	show type of irrep

D IR	display data on irreps
V PAR <i>p1</i> [<i>p2</i>]	select space group(s)
V IR <i>p1</i>	select irrep
V KP <i>p1</i>	select k point
V KDEG <i>p1</i>	select degrees of freedom of k point
V KVAL <i>p1</i> [<i>p2</i> ...]	select parameters α, β, γ for the k point
V IM <i>p1</i>	select image of irrep
V EL <i>p1</i>	select space-group element (to display the character or matrix)
V DIM <i>p1</i> [<i>p2</i>]	select dimension(s)
V ACT <i>p1</i>	select active or non-active irreps (<i>p1</i> = Y, N)
V LAN <i>p1</i> [<i>p2</i>]	select Landau frequency/frequencies
V LIF <i>p1</i> [<i>p2</i>]	select Lifshitz frequency/frequencies
V FEL <i>p1</i> [<i>p2</i>]	select Felix frequency/frequencies
V TYPE <i>p1</i>	select type of irrep
V WY <i>p1</i> [<i>p2</i> ...]	select wyckoff positions
V WY IR <i>p1</i>	select point-group irrep of wyckoff position
V COMPAT <i>p1</i>	select k point for compatibility relation
V SUB SUP	show truncated irrep matrices used for incommensurate distortions
SH PAR	show space group
SH IR [<i>p1</i>]	show irrep (<i>p1</i> =other settings: M, K, B, Z, P)
SH ACT	show whether the irrep is active or not
SH IM	show image of irrep
SH GEN	show space-group elements that map onto the image generators
SH EL	show space-group element selected
SH CH	show character of selected space-group element
SH MAT	show matrix of selected space-group element
SH COMPLEX	show complex form of irrep matrix and character
SH KER	show generators of kernel

SH DIM	show dimension
SH LAN	show Landau frequency
SH LIF	show Lifshitz frequency
SH FEL	show Felix frequency
SH TYPE	show type of irrep
SH FAINT	show faintness index for linear coupling with other irreps
SH FR	show frequency and irreps of the Wyckoff-position point groups
SH KP	show coordinates of \mathbf{k} point
SH KDEG	show degrees of freedom of \mathbf{k} point
SH STAR	show the star of \mathbf{k}
SH COMPAT	show compatibility relations
<hr/>	
D IS	display data on isotropy subgroups
D IS COUP	display data on isotropy subgroups of coupled order parameters
V PAR $p1$ [$p2$]	select parent space group(s)
V SUB $p1$ [$p2$]	select isotropy subgroup(s)
V LAT $p1$ [$p2$]	select lattice(s) of subgroup
V POINT $p1$ [$p2$]	select point group(s) of subgroup
V IR $p1$ [$p2 \dots$]	select irreps
V KP $p1$	select \mathbf{k} point
V KVAL $p1$ [$p2 \dots$]	select parameters α, β, γ for the \mathbf{k} points
V IM $p1$	select image of irrep
V DIM $p1$ [$p2$]	select dimension(s) of irrep
V ACT $p1$	select active or non-active irreps ($p1 = Y, N$)
V CON $p1$	select continuous or discontinuous transitions ($p1 = LAN, RG, NO$)
V LAN $p1$ [$p2$]	select Landau frequency/frequencies
V LIF $p1$ [$p2$]	select Lifshitz frequency/frequencies
V FEL $p1$ [$p2$]	select Felix frequency/frequencies
V DIR $p1$ [$p2 \dots$]	select directions of order parameter
V FREQ $p1$ [$p2$]	select subduction frequency/frequencies
V DOM $p1$	select domain
V DOM P $p1$ $p2$	select domain pair
V DOM SET OR $p1$	select order of domain set
V DOM SET CL $p1$	select class of domain set
V DOM SET DIR $p1$	select direction of domain set vector
V DOM SET UN $p1$	select number of unconnected parts in domain set
V NORM $p1$ $p2$ $p3$	select Miller indices (hkl) of plane between twin domains
V POS $p1$ $p2$ $p3$	select point on plane between twin domains
V SIZ $p1$ [$p2$]	select size of subgroup's primitive unit cell relative to parent group's
V MAX $p1$	select maximal or non-maximal subgroups ($p1 = Y, N$)
V SUB MAX	select maximal subgroups of the parent
V SUB SUP	show superspace groups for incommensurate distortions
V LAT PAR $p1 \dots p6$	select lattice parameters $a, b, c, \alpha, \beta, \gamma$
V BAS $p1$ $p2$ $p3$	select alternate basis vectors
V ORI $p1$	select alternate origin
V FER $p1$	select ferroic species ($p1 = FC, IFS, NF, OTHER$)
SH PAR	show parent space group symbol
SH SUB	show isotropy subgroup symbol
SH DIR [$p1$]	show direction of order parameter ($p1=VEC$ to show the vector)
SH BAS	show basis vectors of subgroup
SH ORI	show origin of subgroup
SH SUB ALT	show alternate basis vectors and origin of subgroup
SH XYZ	show x, y, z in subgroup in terms of x, y, z in parent group
SH WY SUBG	show Wyckoff positions in subgroup

SH GEN	show elements of parent group which generate subgroup
SH EL	show elements of parent group which are elements of subgroup
SH NEW	show new fractionals in subgroup
SH SIZ	show relative size of subgroup's primitive unit cell to parent group's
SH IND	show index of subgroup in parent group
SH DOM [p1]	show domains (p1=GEN to show generators)
SH DOM SET [p1]	show domain sets (p1=GR to show set group, INT to show intersection group, BAS to show basis vectors, OR to show origin, GEN to show generators, ELE to show elements, ALL to show equivalent sets or directions, EQ to show equivalence operators, DIR to show domain set vectors)
SH DISTINCT	show which domains are distinct
SH PAIR	show which pairs of domains are equivalent
SH PAIR p1	show pair intersection group (p1 = I), pair group (p1 = GR) and its basis vectors (p1 = B), its origin (p1 = O), its generating elements (p1 = GE), and its elements (p1 = E).
SH TWIN INT p1	show twin intersection group: its label (p1 = GR), its basis vectors (p1 = B), its origin (p1 = O), its generating elements (p1 = GE), and its elements (p1 = E).
SH TWIN p1	show twin group: its label (p1 = GR), its basis vectors (p1 = B), its origin (p1 = O), its generating elements (p1 = GE), and its elements (p1 = E).
SH TWIN SW p1	show switching elements in twin group (p1 = SIDE, NORMAL, BOTH).
SH MAX	show whether or not the subgroup is maximal
SH LAT	show lattices of parent space group and of subgroup
SH POINT	show point groups of parent space group and of subgroup
SH IR [p1]	show irrep (p1=other settings: M, K, B, Z, P)
SH IM	show image of irrep
SH DIM	show dimension
SH ACT	show whether the irrep is active or not
SH CON	show whether or not the phase transition is continuous
SH LAN	show Landau frequency
SH LIF	show Lifshitz frequency
SH FEL	show Felix frequency
SH FR [p1]	show frequencies and irreps that subduce the subgroup (p1=DIR, GAM, CL)
SH CART	show Cartesian coordinates
SH FER	show ferroic species
<hr/>	
D DIST	display distortions
V PAR p1	select parent space group
V IR p1	select irrep
V KP p1	select k point
V KVAL p1 [p2...]	select parameters α, β, γ for the k point
V RANK p1	select rank and symmetries of macroscopic tensor
V DIR p1 [p2...]	select directions of order parameter
V DOM p1	select domain
V CELL p1 p2 p3	select super cell
V LAT PAR p1 ... p6	select lattice parameters $a, b, c, \alpha, \beta, \gamma$
V WY p1 [p2...]	select wyckoff positions
V WY IR p1 [p2...]	select point-group irrep of wyckoff position
V WY XYZ p1 ... p3	select parameters x, y, z of wyckoff position
V POS p1, p2, p3	select coordinates of point
V SUB SUP	show incommensurate distortions
SH MAC [p1]	show macroscopic distortion (p1=PSEUDO)
SH MIC [p1] [p2]	show microscopic distortion (p1=SC, VEC, p2=PSEUDO)
SH LOC [p1] [p2]	show local distortion (p1=SC, VEC, p2=PSEUDO)
SH PAR	show parent space group symbol
SH IR [p1]	show irrep (p1=other settings: M, K, B, Z, P)

SH DIR	show direction of order parameter
SH DOM	show domain
SH WY [<i>p1</i>]	show Wyckoff positions (<i>p1</i> =IR)
SH POS IR	show point group irrep of point about Wyckoff position
SH UNIT	show distortions in unit cell of parent
SH CART	show Cartesian coordinates
<hr/>	
D INV	display invariant polynomials
V PAR <i>p1</i>	select parent space group
V IR <i>p1</i> [<i>p2</i> ...]	select irreps
V KVAL <i>p1</i> [<i>p2</i> ...]	select parameters α, β, γ for the k point
V DIR <i>p1</i> [<i>p2</i> ...]	select directions of order parameter
V DOM <i>p1</i> [<i>p2</i> ...]	select domains
V DEG <i>p1</i> [<i>p2</i>]	select degree(s) of polynomials
V GRAD <i>p1</i>	select number of spatial derivatives
SH PAR	show parent space group symbol
SH IR [<i>p1</i>]	show irrep (<i>p1</i> =other settings: M, K, B, Z, P)
SH DIM	show dimension
<hr/>	
D BUSH	display data on bush of modes
V PAR <i>p1</i>	select parent space group
V IR <i>p1</i>	select irrep
V KVAL <i>p1</i> [<i>p2</i> ...]	select parameters α, β, γ for the k point
V DIR <i>p1</i>	select direction of order parameter
V WY <i>p1</i> [<i>p2</i> ...]	select Wyckoff positions
V DEG <i>p1</i> [<i>p2</i>]	select degree(s) of invariant polynomials
SH MODES	show atomic displacements
SH INV	show invariant polynomials in free energy
<hr/>	
D DIR	display directions of order parameters
V PAR <i>p1</i>	select parent space group
V SUBG <i>p1</i>	select subgroup
V BASIS <i>p1 p2 p3</i>	select basis vectors of subgroup lattice
V ORIGIN <i>p1</i>	select origin of subgroup
SH KPOINT	show k vectors
SH SUB	show subgroup symbol
SH SIZ	show relative size of subgroup's primitive unit cell to parent group's