

Old Gridding (T22)

[Top](#)

We have replaced with this tool with a new Java platform tool. See [Gridding \(T22a\)](#). The new tool has extended features and a superior user interface.

For a limited time we continue to support the older tool described in this chapter.

This tool enables you to convert point and traverse line data to a grid suitable for image processing and contouring. INTREPID divides the region being processed into a grid of square cells. Each grid cell will contain a value derived from an original data point (an **original data cell**) or interpolated from neighbouring cells or nearby points (an **interpolated cell**).

You can also use the INTREPID Gridding tool to enhance an existing grid dataset using LaPlace convolution and Minimum Curvature.

Beside the Gridding tool and the Spreadsheet Editor INTREPID has two special grid dataset processing tools and a grid rotation facility.

- The Grid Operations tool can resample the grid and change the cell size, See [Grid Operations \(T25\)](#) for information about this tool.
- The INTREPID Grid Stitch tool can combine overlapping or adjacent grid datasets, correcting for differences between them. It can also display data profile graphs along paths that you trace on the display. See [Grid Stitch—combining two grids \(T23\)](#) for a full description.
- The INTREPID Projection Conversion tool can rotate the cells of a grid so that the rows of cells are oriented differently. See [Old Datum and Projection Conversion \(T12\)](#) for instructions.

Recent changes to the Gridding tool


We have substantially rewritten the Gridding tool. You will notice some differences in its operation, but the new version has a similar user interface to the old one. We will rewrite the Reference Manual chapter for the new tool in the next edition.

This section summarises the changes to the tool. It has

- Rewritten internal coding to increase its efficiency and ease of modification.
- Tiling during bi-cubic spline (including trend spline) gridding and therefore use this process with grids of unlimited size.
- Rearranged grid enhancement options to allow you more control of the process.
- A choice of Akima or Cubic spline gridding (displays a dialog box for you to choose).
- Enhanced trend splining technique for line data. See [Enhanced trend splining](#).
- Gridding wizard. This simplifies the gridding process. It takes you through the stages of the process, requesting parameters and choices in the correct order. See [Gridding wizard](#).
- Gridding of potential field data plus observed gradients. See [Gridding of potential field data with observed gradients](#).
- Enhanced potential (TMI or Gravity) field grid, honouring observed gradients. See [Enhanced potential field gridding](#).

Enhanced trend splining

If you have selected Trend gridding, after you choose Apply, a dialog box appears for specifying trend gridding parameters.



The process finds maxima and minima in adjacent lines and associates them.

High Pass Window INTREPID applies a high pass filter to the data before examining trends. This filter is in the form of a moving average. INTREPID uses the residual values from this moving average filter. You can specify the size (in grid cells) of the window for the filter.


Minimum Amplitude for trending INTREPID will not process maxima or minima with amplitude less than the value¹ you specify here

Strike Angle Limit INTREPID will not record trends at angles closer to the line direction than the angle you specify here. Trends close to the line direction are too hard to follow using the trend gridding method because of the oblique distances between the lines. Trends in the line direction do not need enhancement, in any case.

Save Generated Trend Points To save the additional trend points, turn on this check box and specify the name for the additional trend points dataset.

This option replaces the use of the INTREPID_TREND_POINTS system parameter and the procedure described in [Recording the additional trend points](#).

Gridding wizard



1. in Z units, for example, nT

Gridding of potential field data with observed gradients

In the Gridding Wizard, specify Vector type input.

Sign convention for gradients from an aircraft

There is a local coordinate convention associated with acquisition. Since we are dealing with vector components of the potential field, this convention must be applied.

Assuming a moving platform for the acquisition vehicle such as an aeroplane:

- The local Y positive or length component is tail to tip positive.
- The cross component is left to right positive.
- The vertical component is upwards positive.

Storage of gradients in the source dataset

The gridding algorithm accepts any or all of these vector gradients.

Before gridding, convert the differences between readings to nT/m. Divide the difference by the distance between instruments

The local heading of the observation is also computed from the X, Y data and the components are stored with each scalar field observation as vector components in the E, N & Vertical projection system. That is, the observations are stored in a normalized coordinate frame for internal use.

Opportunities for using this extra gradient data

- Direct gridding of observed analytical signal

$$\sqrt{\left(\frac{\delta T}{\delta x}\right)^2 + \left(\frac{\delta T}{\delta y}\right)^2 + \left(\frac{\delta T}{\delta z}\right)^2}$$

- Direct gridding of observed total horizontal gradient, i.e.

$$\sqrt{\left(\frac{\delta T}{\delta x}\right)^2 + \left(\frac{\delta T}{\delta y}\right)^2}$$

- Enhanced potential (TMI / Gravity) field grid, honouring observed gradients. (see [Enhanced potential field gridding](#))
- For TMI, calculation of a short wavelength diurnal variation.

Enhanced potential field gridding

This has three stages:

Akima splines

These are able to take an observed gradient along the spline direction. The line direction gradient component is calculated for each observation point as required.

Minimum Curvature algorithm

Brigg's formulation is a first order finite difference approximation of La Place condition (13 point kernel). This went to considerable trouble to remove any observed horizontal gradient components.

This traditional formulation is revisited and redone as a second order finite difference approximation (25 point kernel). Provision for observed gradients has also been made.

Trend gridding

This allows the possibility of estimating key new pseudo observation points between flight lines. This estimation of observed value plus gradients is then available for the 2nd pass Akima spline.


Natural Neighbour gridding

This alternative method also allows for observed gradients. No implementation of this is available as yet.

Using the Gridding tool

>> *To use Gridding with the INTREPID graphic user interface*

- 1 Choose Gridding from the Grid menu in the Project Manager, or use the command **gridding.exe**. INTREPID displays the Gridding Main window.



- 2 If you have previously prepared file specifications and parameter settings for Gridding, load the corresponding task specification file using Load Options from the File menu. (See [Specifying input and output files](#) for detailed instructions.) If all of the specifications are correct in this file, go to step 10. If you wish to modify any settings, carry out the following steps as required.
- 3 If you are producing the grid from line data, ensure that INTREPID will be able to adequately identify the acquisition lines. See [Identifying acquisition lines](#) for details.
- 4 Specify the Z field for gridding from the line or point dataset, or the grid dataset to be reprocessed. Use Load Z Field for Gridding or Load Grid for Reprocessing from the File menu. See [Specifying input and output files](#) for detailed instructions.
- 5 If you wish to restrict the process to a specific region, specify the polygon dataset which defines the region. Use Load Polygon (Sub Region) from the File menu. See [Restricting the process to a specified region](#) for further information.
- 6 If you wish to save the resulting grid, or if INTREPID requires you to specify a file because the grid is too large for your computer's memory, specify the output grid dataset. Use Specify Output Grid from the File menu. If the grid is not too large for the computer's memory, you can complete the gridding process and decide to save the resulting grid afterwards if you wish. (See [Specifying input and output files](#) and [Storage of completed grids, memory limits, large grids, output files](#)).
- 7 If you are continuing an unfinished gridding process that involves tiling, or otherwise wish to specify a range of tiles to be processed, switch to the Gridding Tiling Control window (Choose Tiling from the Window menu), ensure that Manual Tiling Control is turned on, and specify the range of tiles to be processed. See [Specifying the range of tiles to be processed](#) for details.

- 8 If you are producing a grid from a line or point dataset, specify
 - Z Field Pre-processing (if required) (See [Pre-processing the Z data](#));
 - Precision of data in the output grid (See [Specifying the precision of data in the output grid](#));
 - Grid Cell Size (See [Specifying the grid size](#));
 - Cell extrapolation limit (See [Cell extrapolation limits](#));
 - Nominal Bearing of line data and grid rotation (if required) (See [Nominal Bearing and Producing a rotated grid](#));
 - Initial gridding method and required parameters (See [Initial Gridding](#)).
- 9 Specify the Image Refinement options (LaPlace convolution, Minimum Curvature, Smoothing, Masking) and corresponding parameters as required (See [Image Refinement](#) for details).
- 10 Turn Show Gridding on or off as required (Show Gridding is normally turned on). See [Viewing the gridding progress and clearing the display](#) for instructions.
- 11 When you have made specifications and settings according to your requirements, choose Apply. INTREPID will perform the Gridding process. If you have turned on Show Gridding and selected the Gridding Main window, INTREPID displays the new grid as it is produced.
 - If you are processing a small grid that fits into memory, and have specified an output grid file, INTREPID will save the grid at the end of the process.
 - If you are processing a small grid that fits into memory, and have not specified an output grid file, INTREPID will save the completed grid immediately if you now specify the output file. See [Specifying input and output files](#) for information about specifying files.
 - If you are processing a large grid and using the tiling process, INTREPID will save each tile on completion. See [Storage of completed grids, memory limits, large grids, output files](#) for information about memory and tiling.
- 12 If you wish to record the specifications for this process in a task specification (`.job`) file in order to repeat a similar task later or for some other reason, use Save Options from the file menu. (See [Specifying input and output files](#) for detailed instructions.)
- 13 If you wish to repeat the process, repeat steps 2–12, varying the parameters and/or data files as required.

14 To exit from Gridding, choose Quit from the File menu.

To view the current set of specifications and a report of the process and files involved, choose Report from the Window menu. INTREPID displays the Gridding Report window. See [Displaying options and using task specification files](#) for details and an example of a set of specifications.

After using Gridding you can carry out a more detailed inspection of the grid using INTREPID visualisation tools (see [Visualisation \(T26\)](#)).

You can clear the Gridding Main window display at any time using Clear from the Display menu.

You can view Help information by choosing options from the Help menu (See [Help](#)).

You can execute Gridding as a batch task using a task specification file that you have previously prepared. See [Displaying options and using task specification files](#) for details.

If you are executing Gridding as a batch task you can modify the task specification file to

- Disable the clipping of extrapolated cells from the outside the row and column limits of the grid (See [Clipping / Crew Cut](#) for details)
- Modify the relaxation factor (See [Minimum Curvature](#) for details).

Summary of the gridding process

- 1** If you are gridding line or point data, you specify the field of Z data
If you are enhancing an existing grid, you specify the grid dataset name and go to step 6.
- 2** You specify processes and parameters that you require.
- 3** INTREPID performs Z field pre-processing.
- 4** INTREPID calculates the number of cells in the grid, based on the extent of the line or point data.
- 5** INTREPID calculates centroid values for original data cells.
- 6** INTREPID calculates centroid values for interpolated cells (that do not contain original data), using the Nearest Neighbours, Bi-Cubic Spline, Trend Spline or Box Filter methods.
- 7** INTREPID performs LaPlace smoothing as required.
- 8** INTREPID performs the Minimum Curvature smoothing process as required.
- 9** INTREPID performs the Masking and/or Clipping process as required.
- 10** INTREPID saves the grid if required, or saves the current tile and goes back to repeat the process for the next selected tile.

Specifying input and output files

To create grids from point or traverse line data, you must specify the Z field to be gridded. To reprocess an existing grid, you will need to specify the name of the grid and the band number to be processed.

You may also wish to specify


- (If you wish to grid only a particular region), the polygon dataset (geographical region) required. (See [Restricting the process to a specified region](#)).
- (If you wish to save the results of the gridding process) the name for the output dataset (See [Storage of completed grids, memory limits, large grids, output files](#) for details).

INTREPID obtains the X, Y and line type data from the dataset aliases. You must have the following aliases identifying appropriate fields:

Alias	Field
X	East–West geographic location coordinate
Y	North–South geographic location coordinate
LineType	Line type
PointType	Point quality

See "[Vector dataset field aliases](#)" in INTREPID database, file and data structures (R05) for more information about aliases.

Choose the options as required from the File menu.



In each case INTREPID displays an Open or Save As dialog box. Use the directory and file selector to locate the file you require. (See "[Specifying input and output files](#)" in [Introduction to INTREPID \(R02\)](#) for information about specifying files).

Load Z Field for Gridding If you are gridding from a line or point dataset, use this to specify the Z field to be gridded.

If the alias does not exist, INTREPID displays Load X, Load Y and Load LineType (*line datasets only*) dialog boxes one after the other as required, for you to specify these fields. If there is no line type field, choose Cancel in the Load LineType dialog box.

For point datasets, if there is no **PointType** alias, then INTREPID does not use point type in selecting points for gridding.

Load Grid for Reprocessing If you are refining an existing grid, use this to specify the grid file name. INTREPID will only load and process band 0 of this grid (See [Output grid bands specification](#) for more information about bands).

Load Polygon (Sub Region) Use this to specify a polygon dataset which will act as a region of interest for the gridding process. INTREPID will only grid data within the polygon. See [Restricting the process to a specified region](#) for details.

Specify Output Grid If you wish to save the resulting grid, or if it is a large grid that requires tiling (See [Storage of completed grids, memory limits, large grids, output files](#) for details), use this option to specify the grid name. The output grid may be a new or existing grid. You can select the file name of an existing grid in the Save As dialog box, for example if you are

- Overwriting a grid,
- Processing selected tiles of an existing grid or
- Saving to a band of an existing grid.

After you specify the grid name INTREPID displays the Band Selection dialog box. Specify the band numbers and choose OK. See [Output grid bands specification](#) for details.

The origin of a grid saved by this tool is the centroid of the pixel/cell in the top left hand corner.

See [Storage of completed grids, memory limits, large grids, output files](#) for details about the timing of the save process.

Load Options If you wish to use an existing task specification file to specify the Gridding process, use this menu option to specify the task specification file required. INTREPID will load the file and use its contents to set all of the parameters for the Gridding process. (See [Displaying options and using task specification files](#) for more information).

Save Options If you wish to save the current Gridding file specifications and parameter settings as an task specification file, use this menu option to specify the filename and save the file. (See [Displaying options and using task specification files](#)).

Identifying acquisition lines

This section is for line dataset gridding only. It is normal practice to use only acquisition lines in the gridding process for line data.

Identifying acquisition lines using a line type field

If there is a **LineType** alias or if you specify a line type field in response to a prompt, INTREPID will use it to automatically exclude non-acquisition line data, processing types 2 and 3 only See ["Traverse line numbers and types" in INTREPID database, file and data structures \(R05\)](#) for a complete list of traverse line types and numbers.

If your dataset does not have a line type field but does have line numbers from which you can derive a line type field, you can use the INTREPID Spreadsheet Editor facility to create it. See ["Create new field example—Line Type field" in Spreadsheet Editor \(T15\)](#) for details about creating line type fields.

Identifying acquisition lines using Nominal Bearing

If you do not specify a line type field, but you do specify a Nominal Bearing (estimate of the strike (orientation) of the acquisition lines), INTREPID will identify the traverse lines oriented within $\pm 22\frac{1}{2}^\circ$ of the Nominal Bearing as acquisition lines. INTREPID uses the start and end points of a traverse line to calculate its strike.

If you wish to use the Nominal Bearing setting to identify the acquisition lines, but do not know their strike, INTREPID can calculate the average strike of the dataset for you. See [Nominal Bearing](#) for instructions.

If you do not identify acquisition lines

If you do not specify a line type field or a nominal bearing, INTREPID will grid all traverse line data.

Point quality

This section is for point dataset gridding only. If there is a **PointType** alias or you have specified a point type field, INTREPID will grid only those points for which the point type = 1. If you have not specified a point type field, INTREPID will grid using all points.

Output grid projection

The projection of the output grid is the same as that of the source dataset. See [Old Datum and Projection Conversion \(T12\)](#) for information about changing projection.

Output grid bands specification

Grids may have a number of sets of values, or **bands**. INTREPID stores multiband grid datasets in Band Interleaved by Pixel format¹³.

The Gridding tool can work with one band only at a time.

After you specify an output grid file name INTREPID displays the Band Selection dialog box.



Use this dialog box to specify the number of bands for the grid, and which band you intend to process (the current band). The band information consists of two numbers separated by /. The first number is number of bands in the grid. The second number is the band number for the current grid. The bands are numbered from 0. The default number of bands is 1, and the default current band is 0.

After you have specified the band numbers, choose OK. See ["Multiband grid datasets" in INTREPID database, file and data structures \(R05\)](#) for more information.

Note: If you are using Gridding to enhance an existing grid, the current version of INTREPID will load and process band 0 of the grid. You can still save the results of the process to any band of another grid.

^{1.3} For details about Band Interleaved formats contact our technical support service.

Storage of completed grids, memory limits, large grids, output files

For small grids, if you specify an output dataset, INTREPID will save it when the gridding process is complete. If you do not, INTREPID will simply retain the grid in memory until you perform another gridding process or exit from Gridding. If you specify an output dataset after the gridding process is complete, INTREPID will save the grid immediately.

For large grids you must specify a filename because your computer may not have room in memory for the whole dataset. In this case, INTREPID divides the grid up into sections (**tiles**), and processes them separately.

The criterion for a grid to be classified as large and require tiling is the value of the system parameter INTREPID_MEMORY. "[INTREPID Memory limits and tiling](#)" in [Configuring and using INTREPID \(R04\)](#) and [INTREPID system parameters and install.cfg \(R07\)](#) for further information.

Restricting the process to a specified region

You can specify a region of interest for the Gridding process using a polygon dataset. INTREPID will only grid data within the region defined by the polygon. You can use the Subsection tool to define the polygon (See [Subsections of datasets \(T21\)](#) for full instructions).

>> To specify a region of interest using a polygon dataset


Choose Load Polygon (Sub Region) from the File menu and select the polygon dataset required.

Specifying the range of tiles to be processed

If you are continuing an unfinished gridding process that involves tiling, or otherwise wish to specify a range of tiles to be processed, you can do this as follows.

>> To specify the range of tiles to be processed

- 1 Switch to the Gridding Tiling Control window (Choose Tiling Control from the Window menu).
- 2 Turn on Manual Tiling Control. INTREPID displays the tile range text boxes.



- 3 Specify the range of tiles to be processed in the corresponding text boxes.

Pre-processing the Z data

If you are gridding traverse line data you can apply a range of processes to the Z data before commencing the gridding process.


You can choose one of the following

- A Convolution filter for smoothing the data,
- A Naudy filter for noise reduction,
- Quadrature
- Instantaneous Phase
- Instantaneous Frequency
- Automatic Depth Estimation

An explanation of each of these processes appears below.

>> *To specify pre-processing*

- 1 Choose Z Field Pre-Process from the Pre-Process menu. INTREPID displays the Z Field Pre-Process dialog box.



Select the process you require from the Process option buttons. The default process is None.

- 2 If you have selected Convolve, specify the size of the convolution window in data points, using the Window Size (data points) text box. See [Convolve](#) for an explanation.
- 3 If you have chosen the Naudy filter, specify
 - The filter wavelength (in data points) using the Window Size (data points) text box,.
 - The filter tolerance (in Z units) using the Tolerance text box,
 - Whether you wish to produce the grid from the corrected data or from the data rejected by the filter (i.e., the noise).See [Naudy](#) for an explanation.
- 4 If you have chosen Automatic Depth Estimation, specify Window Size (data points). See [Automatic Depth Estimation](#) for an explanation.
- 5 Choose OK. INTREPID will note your choices and use them during the Gridding process.

The following sections describe each pre-process and its parameters in more detail.

Convolve

This is a filter for smoothing the data. For each point, INTREPID will compare each Z value with neighbouring values along the line. If there are sudden changes, INTREPID will adjust the current Z value to make the changes smooth. You need to specify the following:

Window Size (data points) Use this to specify the number of data points to be compared around the point being adjusted. For example, if you set the window to 4, INTREPID will examine two points on each side of the current point to calculate any adjustment. The default value of this parameter is 2.

Naudy

This filter reduces noise in your data by detecting sudden changes or spikes that are not characteristic of potential field data. You need to specify the following:

Window Size (data points) Use this to specify the wavelength (in data points) for the Naudy filter. The wavelength corresponds to the maximum width of noise anomalies to be removed. INTREPID will remove anomalies shorter than the wavelength you specify. The default value is 2.

Tolerance Use this to specify the filter tolerance (in Z units). The tolerance corresponds to the minimum amplitude of suspected noise anomalies to be removed. INTREPID will remove spikes with a amplitude higher than the tolerance you specify. The default value 0.1 corresponds to 0.1nT, the current documented accuracy of magnetometers. This ensures that INTREPID will only remove noise, and not waste time attempting to smooth out the normal fluctuations associated with the precision limits of the instrument.

Naudy Filter Options Select Use Corrected Data to produce the grid from the corrected data. Select Use Rejected Data (Noise) to produce the grid from data rejected by the filter (the 'noise').

Quadrature

This is an imaginary component of the Z field signal derived using the Hilbert transform 19 point finite difference operator. It is used to calculate instantaneous phase. This option is provided so that you can view the Quadrature results if required.

Instantaneous Phase

This is derived by combining the Z data (real component) and the Quadrature results (imaginary component) using the formula

$$\text{instantaneous phase} = \text{atan}\left(\frac{\text{imaginary}}{\text{real}}\right)$$

Instantaneous Phase can show continuity for subtle features often lost when you only examine the real component. See the articles Taner, Koehler and Sheriff (1979)¹⁴ and Fitzgerald, Yassi, and Dart (1997)²⁵ for further discussion of this technique.

1.⁴ Taner, M.T., Koehler, F. and Sheriff, R.E., 1979, Complex seismic trace analysis: *Geophysics* **44**, 1041–1063.

2.⁵ Fitzgerald, D., Yassi, N. and Dart, P., 1997, A case study on geophysical gridding techniques: INTREPID perspective: *Exploration Geophysics*, **28**, 1–

Instantaneous Frequency

This is a measure of change in the Instantaneous Phase (see previous section), comparing adjacent values of Instantaneous Phase results. It uses the formula

$$\text{instantaneous frequency} = \text{diff1}(\text{instantaneous phase})$$

See [DIFF function example](#) for an illustration of this function.

Automatic Depth Estimation


This process uses the Phillips method to estimate from the Z field signal the depth to a magnetic basement. INTREPID expresses the results in the same units as the X and Y fields of the dataset. Depth Estimate values are negative numbers with 0 corresponding to the survey height.

Window Size (data points) We suggest a value of 20 for this parameter.

Specifying the precision of data in the output grid

>> To specify the precision for the resulting gridded data

Choose the required option from the Precision menu.




The following table gives details of the Precision menu options

Menu Option	Detail
Byte	Byte
Integer (16 bit)	Single precision integer
Float (32 bit)	Single precision floating point
Double (64 bit)	Double precision floating point

See ["Data Types in INTREPID datasets"](#) in [INTREPID database, file and data structures \(R05\)](#) for general information about precision in INTREPID datasets.

Specifying the grid size

Use the Grid Cell Size text box in the Gridding Parameters area to specify the size of one grid cell in the distance units of the dataset.



Setting an appropriate Grid Cell Size is a balance between having a fine 'mesh' grid and having gaps or excessive interpolation between cells which may lead to inaccuracies.

If you are gridding from a line dataset we recommend a cell size greater than a quarter of the line spacing.

If you have a smaller cell size than recommended, we suggest that you increase the cell extrapolation limit (See [Cell extrapolation limits](#) for details).

Note: If your dataset is geodetic (latitude and longitude) you need to specify the grid cell size in degrees.


Cell extrapolation limits

You need to specify cell extrapolation limits for a number of Gridding processes:

- At the start of the gridding process INTREPID creates **edge regions** around the original data cells. These regions will contain extrapolated / interpolated data. The edge regions should ideally meet or overlap to satisfactorily fill gaps between original data points (e.g., the gap between traverse lines, or the gap between points of a point dataset). You need to specify appropriate cell extrapolation limits for filling these gaps.
- The image refinement processes also require an edge region containing data around the whole grid. See [Image Refinement](#) for details.
- The data in the edge region around the outside of the grid may be discarded after the image refinement processes. This process is called Clipping. See ([Clipping / Crew Cut](#)) for details.
- INTREPID interpolates values for all cells within regions fully enclosed by but outside the edge regions. The Masking process deletes (sets to **null**) these regions if required. Masking needs to know the extent of the edge regions. (See [Masking](#) for details).

>> To specify the cell extrapolation limit

Enter the limit (number of cells away from an original data point) into the Extrapolate Cell parameter.



You should normally use an extrapolate cell value of at least 2. The default value is 2.

Nominal Bearing

This section is for line dataset gridding only. If you are gridding a field from a line dataset using Bi-Cubic Spline or Trend Spline, INTREPID needs to know the orientation of the acquisition lines.

If you are gridding a field from a line dataset using Nearest Neighbours or Box Filter, you can specify the orientation of the acquisition lines for the purposes of quality control (i.e., rejecting lines that have different orientation) or to specify rotation for the grid.

INTREPID compares the Nominal Bearing parameter with acquisition line orientation. It uses the parameter for the following purposes:


- Determining the line direction for Bi-Cubic Spline and Trend Spline initial gridding. See [Initial gridding—Bi-Cubic Spline](#) and [Initial gridding—Trend Spline](#) below.
- Identifying acquisition lines if there is no line type field. See [Identifying acquisition lines using Nominal Bearing](#) for more information.
- Acquisition line quality control: INTREPID will only process traverse lines whose direction is within $\pm 22\frac{1}{2}^\circ$ of the specified Nominal Bearing. This rule applies irrespective of the acquisition line identification method (See [Identifying acquisition lines](#)).
- Specifying the required angle for a rotated grid if you have acquisition lines that do not lie North–South or East–West. See [Producing a rotated grid](#).

Using average strike for the Nominal Bearing

You can use the average strike of the lines as the Nominal Bearing. INTREPID can automatically calculate the average strike (orientation) of the traverse lines in the dataset for you .

>> To calculate the average strike for the current line dataset


- 1 Choose Report from the Window menu.
- 2 Choose Calculate Average Strike. INTREPID will calculate the average strike for the dataset and display the result under the Calculate Average Strike button. You can enter this result as the Nominal Bearing parameter.



Specifying Nominal Bearing

>> To specify Nominal Bearing

Use the Gridding Parameters area of the Gridding Main window.



Specify this parameter in the text box provided. Nominal Bearing can range from 0 to 180 and represents the bearing in degrees. 0° and 180° indicate North–South bearing and 90° indicates East–West.

Producing a rotated grid

You may be gridding a field from a line dataset with 'oblique' acquisition lines (that do not lie North–South or East–West). The survey may have been created like this, for example, so that the data is perpendicular to the strike of a feature of interest.


You may wish to produce a rotated grid from 'oblique' data with its rows or columns in the direction of the acquisition lines. After producing the grid you can rotate it so that the rows lie East–West. See ["Rotating a grid" in Grid Operations \(T25\)](#) for instructions.

If you are gridding an 'oblique' line dataset using the Bi-Cubic Spline or Trend Spline method in the gridding process, you must produce a rotated grid.

With the Nearest Neighbours and Box Filter methods producing a rotated grid from an 'oblique' line dataset is not compulsory. (See [Initial Gridding](#).)

>> To specify a rotated grid from 'oblique' acquisition lines

- 1 Specify the orientation for the grid rows as the Nominal Bearing parameter.
- 2 Turn on the Rotate Line Data check box in the Gridding Parameters area.



Grid initialisation

The first stage of gridding involves three processes.

- 1 INTREPID reads the input data. If it is a vector dataset, INTREPID creates a grid data structure and aligns it with the source dataset.
- 2 INTREPID identifies the grid cells that contain one or more original data points. It finds the nearest data point to the cell centroid and assigns its Z value to the cell. It also records the 'exact'¹⁶ position of the original data point within the cell for 'honour original points' processes.
- 3 INTREPID determines the row and column limits for the grid. INTREPID uses the cell extrapolation limit and the original data cells at the ends of each row and column in this process.

Note: The origin of a grid is the centroid of the pixel/cell in the top left hand corner.

Recording the cell centroid and original data point positions

You can save the cell centroids and the 'exact' positions of original data points selected for use (the **sample points**). We have provided this option for technical auditing of the gridding process.

>> To save the cell centroid and sample point exact positions

Assign a value to the system parameter INTREPID_HONOUR_ORIGINAL before processing. INTREPID will save a point dataset called

honour containing a record of each sample point. Each data point recorded will have two sets of coordinates:

- The coordinates of the corresponding cell centroid and
- The 'exact' coordinates of the original data.

If you are examining **honour**, edit its aliases to select the set of coordinates you require.

See [INTREPID system parameters and install.cfg \(R07\)](#) for further information about system parameters in INTREPID and "[Vector dataset field aliases](#)" in [INTREPID database, file and data structures \(R05\)](#) for more information about aliases.

^{1.6} To be more precise, the coordinates of the sub-cell containing the original data point. (There are 128 x 128 sub-cells in a grid cell.)

Calculation of the row and column limits

The row and column limits of the grid are lists of the locations of the outermost cells in each row and column which are to contain data.

In this discussion we will use the following notation

EC	= value of the Extrapolate Cell parameter
L_O	= cell position of the outermost original data cell at the current end of the current row or column
L_E	= cell position EC cells further out than L_O for the current end of the current row or column
$\{L_E^{\pm EC}\}$	= the set of L_E cell positions for the current end of the EC rows/columns before and EC rows/columns after the current row/column
$Max\{L_E^{\pm EC}\}$	= the outermost L_E position in the $L_E^{\pm EC}$ set
L	= row/column limit finally recorded

INTREPID calculates the row and column limits as follows.

For the left hand end of each row, INTREPID

- 1 Locates the leftmost original data cell (L_O);
- 2 Locates the cell EC cells further left than L_O (L_E);
- 3 Locates the L_E positions for the previous EC rows and the next EC rows $\{L_E^{\pm EC}\}$;
- 4 Finds the leftmost cell of the set $L_E^{\pm EC}$ ($Max\{L_E^{\pm EC}\}$)
- 5 Records the X coordinate of $Max\{L_E^{\pm EC}\}$ as the X coordinate of the left hand row limit for the current row (X coordinate of L). (The Y coordinate is, of course, the row number.)

INTREPID performs this process correspondingly for the right end of each row and for each end of the columns.

The overall effect of this process is to

- Produce a 'square ended' effect for groups of rows and columns, and
- Fill out rows/columns with 'inadequate' original data cells to a common grid edge.

Initial Gridding

Initial gridding uses a mathematical interpolation/extrapolation process to calculate values for the cells within the edge regions and also within enclosed gaps (fully enclosed by but outside the edge regions).

You can choose the Nearest Neighbours, Box Filter, Bi-Cubic Spline or Trend Spline method to calculate values for the interpolated cells in your grid. The sections below contain explanations of the processes.

Nearest Neighbours is our recommended general purpose method. It works well for a wide range of datasets. It uses two-point and three-point planar interpolation (triangulation).

Bi-Cubic Spline will *only work for line datasets*. It uses splining to assign cell centroid values.


Trend Spline uses the Bi-Cubic Spline method but first interpolates extra points between lines to ensure that anomalies at an oblique angle to the traverse line direction will be represented properly in the grid.

Box Filter is an alternative method, also successful with a wide range of datasets. It does not take account of gradients in the process, and will tend to reduce the magnitude and size of features in your results, compared with the other methods. It uses local averaging to assign cell centroid values (assuming that the original data point is at the centroid of the cell).

If you use Nearest Neighbours or one of the Spline methods, INTREPID uses the Box Filter to fill any gaps in the grid after your chosen process is complete.

>> To specify the initial grid process,

- 1 Choose the method required from the Initial Grid menu.



- 2 Specify the parameters required for the initial grid process. See below for process descriptions.

Initial gridding—Nearest Neighbours

You can produce grids from line and point dataset fields using this method. It has three stages.

1 Triangulation:

INTREPID makes a number of passes through the grid. It works along the rows of the grid one by one starting alternately at the most Northerly row working South and the most Southerly row working North.

For blank cells, INTREPID locates nearby original data cells and uses a triangulation process to calculate values.

When it locates a neighbouring original data cell, it records this for the blank cell. On the first pass through the grid, INTREPID searches for original data cells that are immediate neighbours. On subsequent passes, INTREPID searches for original data cells one cell further away each time from the blank cell. This process is called **shelling**. INTREPID searches a minimum of 20 shells around each cell.

When INTREPID has recorded three neighbouring original data cells for a blank cell, it immediately locates all blank cells whose centroids lie within the triangle formed by the three original data points.

INTREPID interpolates values for all cells within the triangle and marks all of the cells in the triangle as processed. INTREPID uses an 'honour original data' process for this interpolation, since it uses the actual positions of the original data points rather than their cell centroids.

Note: The honour original data process described here uses the same information but is otherwise not related to the honour original data options provided with minimum curvature image refinement (See [Minimum Curvature](#)).

After completing a pass in which it is unable to perform any interpolation, INTREPID moves to stage 2.

2 Linear interpolation:

INTREPID then passes through the grid examining all of the blank cells for which it has found only two nearby original data points.


INTREPID interpolates values for all blank cells on the line between the two original data points, once again using the position of the points rather than their cell centroids.

3 Box filtering:

INTREPID passes through the grid using the Box Filter method (See [Initial gridding—Box Filter](#)) and creates values for all remaining blank cells.

Nearest Neighbours parameters

If you choose the Nearest Neighbours method, the Gridding Parameters in the command area will appear as follows. Nearest Neighbours has no additional parameters to set.



Initial gridding—Bi-Cubic Spline

This section is for line dataset gridding only. You can produce grids from line dataset fields using this method, which is sometimes called 'fast grid'.

Note: This version of the Gridding tool does not use tiling, and so can only process grids that will fit into memory. The new Gridding tool now in beta release is able to use tiling with this method.


While using this method of calculating values for interpolated cells, INTREPID creates a located line structure that is closely related to the columns and rows of the grid being created. There are three stages of gridding with this method.

1 Pass along acquisition lines

INTREPID uses spline curves along the acquisition lines to calculate values that will correspond to all grid cells.

2 Pass across acquisition lines

In the second pass INTREPID examines each column or row of the located line structure perpendicular to the acquisition line direction. It notes the values obtained in the first pass (**nodes**) and uses them to calculate a spline curve perpendicular to the acquisition line direction. It uses the spline curve to calculate values in between the traverse lines. The following diagram illustrates the process.




3 Box filtering

INTREPID passes through the grid using the Box Filter method (See [Initial gridding—Box Filter](#)) and creates values for any remaining blank cells.

Bi-Cubic Spline parameters

If you are using the Bi-Cubic Spline method, the Gridding Parameters area in the Command Area looks like this:



Search Radius When interpolating a value for a group of cells during the second pass of the Bi-Cubic Spline process, INTREPID searches in both directions for nodes so that it can calculate a spline curve. It requires two nodes on each side of the cells. This parameter specifies a distance limit for this search. If INTREPID cannot find the nodes within this distance, it will not interpolate the cells.

Specify the Search Radius (in distance units) in the corresponding text box. We recommend a Search Radius larger than twice the line spacing, or 10 times the cell size (The recommended number of cells from one line to the next is 4).

Note: If your dataset is geodetic (latitude and longitude) you need to specify the Search Radius in degrees.

Nominal Bearing You must set this parameter. See [Nominal Bearing](#) for instructions.

Rotate Line Data If you are gridding 'oblique' acquisition lines (not oriented North–South or East–West), you must create a rotated grid aligned with the acquisition lines. If this is the case, turn on Rotate Line Data. See [Producing a rotated grid](#) for details.

Recording the original data points used

You can save a record of the data points selected for use by this gridding process (the sample points—selected because they were closest to the cell centroids).

>> *To save the sample points used by Bi-Cubic Spline gridding*

Assign a value to the system parameter INTREPID_FAST_POINTS before processing. INTREPID will save the sample points for the process as a point dataset called **fast**.

See [INTREPID system parameters and install.cfg \(R07\)](#) for further information about system parameters in INTREPID.

Initial gridding—Trend Spline

This section is for line dataset gridding only. You can produce grids from line dataset fields using this method.

Trend spline uses Bi-Cubic Spline gridding but includes a preliminary process which examines groups of lines together to find directional trends. Using this information in the gridding process can enhance the appearance of anomalies that lie at oblique angles to the traverse lines.

Note: We recommend that you only use this method with surveys that have regularly spaced lines.

The Trend Spline direction finding process involves two basic steps

- 1 INTREPID examines changes in all directions along groups of lines and calculates a trend direction for each data point (the direction in which there is the least change).
- 2 INTREPID uses this data to create sets of additional data points between the acquisition lines.

After the direction process, INTREPID creates the grid using the Bi-Cubic Spline method (See [Initial gridding—Bi-Cubic Spline](#))

For full details of these process see articles by Brindt and Hauska (1985)¹⁷ and Fitzgerald, Yassi and Dart (1997)²⁸.


It is possible to 'tune' Trend Spline gridding to accept or reject solutions based upon reliability of data in one direction versus another. If this capability is of interest to you, please contact our technical support service.

1.⁷ Brindt, L. and Hauska, H., 1985, Direction dependent interpolation of aeromagnetic data *Eleventh International Symposium on Machine Processing of Remotely Sensed Data*, Purdue University, Indiana, USA.

2.⁸ Fitzgerald, D., Yassi, N. and Dart, P., 1997, A case study on geophysical gridding techniques: INTREPID perspective: *Exploration Geophysics*, **28**, 1–

Trend spline parameters

If you are using the Trend Spline method, the Gridding Parameters area looks like this:



Gridding Parameters	
Grid Size	70.0nn
Extrapolate Cell	2
Nominal Bearing	
<input type="checkbox"/> Rotate Line Data	
Search Radius	2000

Search Radius See [Initial gridding—Bi-Cubic Spline](#) for an explanation of this parameter.

Nominal Bearing See [Initial gridding—Bi-Cubic Spline](#) for comments about this parameter.

Rotate Line Data See [Initial gridding—Bi-Cubic Spline](#) for comments about this parameter.

(Trend Variance Factor) The trend variance factor is the minimum level for significance of local variations. The number of trend points generated is very sensitive to the value of this parameter. Its default value is 1 (Z unit) You can change the value of the trend variance factor if you are using a task specification file for your gridding process. Edit the task specification (`.job`) file, changing the value in the `Trend_Variance_Factor =` line according to your requirements, e.g., `Trend_Variance_Factor = 2`. See [Displaying options and using task specification files](#) for further information.

Process reports for the Trend Spline method

You can inspect a report of the aspect ratio between line spacing and cell size during the gridding process. Under Unix this appears in the background window. Under *Windows* it is written to an `ntout` report file. See ["Diagnostic reporting options" in Configuring and using INTREPID \(R04\)](#) for more information.

Recording the additional trend points

You can save a record of the additional data points created between the acquisition lines (the additional trend points).

>> *To save the additional trend points*

Assign a value to the system parameter `INTREPID_TREND_POINTS` before processing. INTREPID will save the additional trend points as a point dataset called **trend**.

See [INTREPID system parameters and `install.cfg` \(R07\)](#) for further information about system parameters in INTREPID.

Initial gridding—Box Filter

You can produce grids from line and point dataset fields using this method. The Box filter progressively examines each empty cell in the grid in relation to its immediate neighbours and calculates a value for it based on an average value of its neighbours. The Box Filter process repeats until all cells have a value or until it has completed the maximum number of iterations you have specified.


The Box Filter assumes that the original data points are at the cell centroids. It does not take account of the actual position of data points within the cell (i.e., it has no 'honour original points' process) and therefore may not be as accurate as other methods.

Box Filter as a finishing process for other methods

If you use Nearest Neighbours or one of the Spline initial gridding methods, INTREPID uses the Box Filter after the process to fill any remaining gaps in the grid.

Box Filter parameters

If you choose the Box Filter method, the gridding parameters area will appear as follows.



Gridding Parameters	
Grid Size	70.0
Extrapolate Cell	2
Nominal Bearing	
<input type="checkbox"/> Rotate Line Data	
Box Iterations	100

Box iterations You can use this text box to specify the maximum number of Box filter iterations you wish INTREPID to perform before moving to the image refinement stage.

You do not need to specify Box Iterations if Box Filter is operating only as a final stage of another initial gridding method.

Gridding parameters summary

You can set the general Gridding Parameters in the top right corner of the Command area.

The various Gridding processes require different selections of these parameters. The following tables show Gridding parameters that are required for each method.

'Yes' means that you must specify a value.

Blank means that INTREPID does not use or require the parameter in the process at this stage, although its effect on the data may be carried through from a previous stage.

'ON' means that the option must be turned on for the process.

Gridding parameters for line datasets

Process	Grid Cell Size	Extrapolate Cell	Nominal Bearing	Rotate Line Data	Search Radius	Box Iterations
Grid initialisation	yes	yes	if required for acquisition line identification			
Nearest Neighbours	yes	yes				
Bi-Cubic Spline	yes	yes	yes	ON*	yes	
Trend Spline	yes	yes	yes	ON*	yes	
Box Filter	yes	yes	if required for acquisition line identification			yes

* for 'oblique' line datasets

Gridding parameters for point datasets


Process	Grid Cell Size	Extrapolate Cell	Box Iterations
Grid initialisation	yes	yes	
Nearest Neighbours	yes	yes	
Box Filter	yes	yes	yes

Image Refinement

After the initial gridding process, INTREPID can perform LaPlace convolution, Minimum Curvature and Masking image refinement processes.

If you are refining an existing grid, INTREPID can perform LaPlace convolution and Minimum Curvature Smoothing refinement. The Minimum Curvature process will not use the honour originals method in this case, since no original data is available.

You can specify the image refinement processes in the Image Refinement area of the Gridding Main window.



LaPlace iterations

This is a heavy smoothing convolution filter that INTREPID applies to all initial grid estimates. It leaves the original points alone. The process improves the condition of the grid for the Minimum Curvature process. If you perform LaPlace convolution, Minimum Curvature will require fewer iterations to achieve a satisfactory result.

The LaPlace formula appears below.

Where

Z_0 is the value in the cell being processed before the adjustment,

Z_0^1 is the value in the cell being processed after the adjustment,

R is the relaxation factor,

Z_1, Z_2, Z_3, Z_4 are the values in the surrounding cells as shown,

	Z_1	
Z_2	Z_0	Z_3
	Z_4	

If Z_0 does not contain original data, then

$$Z_0^1 = \left(\frac{Z_1 + Z_2 + Z_3 + Z_4}{4} - Z_0 \right) \times R + Z_0$$

Relaxation factor See [Minimum Curvature](#) for more information about this parameter.

Minimum Curvature

The Minimum Curvature method progressively examines each interpolated cell in the grid in relation to its immediate neighbours and changes its value based on the value of the neighbours.

The aim of the minimum curvature method is to produce a smooth surface of grid values. Working in both directions, it adjusts cell values using a second derivative calculation based on the differences between the values of the adjacent cells. It does not modify the original data points.

INTREPID uses a **relaxation factor** to accelerate the interpolation process. As INTREPID calculates a new value for each interpolated cell, it multiplies the difference between the old and adjusted value by the relaxation factor. The default value of the relaxation factor is 1.375.

Where

Z_0 is the value in the cell being processed before the Minimum Curvature adjustment,

Z_A is the adjusted value in the cell after the Minimum Curvature process has been applied,

R is the relaxation factor,


Z_1 is the new value in the cell being processed after the minimum curvature process and relaxation factor adjustment have been applied,

If Z_0 does not contain original data, then

$$Z_1 = (Z_A - Z_0) \times R + Z_0$$

INTREPID will repeat the process until it has completed the number of iterations you specify in the Maximum Iterations text box, or the maximum residual change for all cells is less than the value you specified in the Maximum Residual text box, whichever occurs first.

INTREPID normally uses the 12 cells immediately surrounding the target cell as comparison values in the Minimum Curvature process, as shown below.




The Minimum Curvature process can use an 'honour original data' system if required. If you choose this method, INTREPID allows for the actual position of the original data point in an original data cell (rather than the cell centroid) when calculating the weight (influence) of the cell in an adjustment of a neighbouring cell. If you are using the Gridding tool to enhance an existing grid, the grid will have no link with its original data, and therefore INTREPID cannot use any honour originals method. See below for additional explanation of the honour originals process.

At the end of the Minimum Curvature process, INTREPID can perform several further passes through the grid where it adjusts original data cells values in the same way as it has been adjusting interpolated cells. This process is called **smoothing**, and has the effect of further smoothing the grid near original data cells.

If you are using the Gridding tool to enhance an existing grid, INTREPID will only perform the Minimum Curvature process in Smoothing mode, since the original data can not be distinguished.

>> *To use Minimum Curvature image refinement*

- 1 Turn on the Minimum Curvature check box in the Image Refinement parameters area. INTREPID displays the Minimum Curvature parameters selection area.



- 2 Set the Honour Original Data (on or off, number of cells to use), Iterations, Maximum Residual, Smoothing, Smoothing Iterations according to your requirements.

Honour Original Data If you turn off Honour Original Data, INTREPID will assume that the original data points are located at the centroids of all original data cells, and calculate the same weight (influence) for the cell in all directions.

If you turn on Honour Original Data, INTREPID will allow for the actual position of the original data point in an original data cell (rather than the cell centroid) when calculating the weight (influence) of the cell in an adjustment of a neighbouring cell. This can improve the accuracy of the image refinement process. An original data point can have up to 128 x 128 different positions in a cell.

If you are using the Gridding tool to enhance an existing grid, original data is not available and INTREPID will automatically turn Honour Original Data off.

The Honour Original Data method has two variants: 1 cell and 2 cell. See the section immediately following for an explanation.

Note: The honour original data process described here uses the same information but is otherwise independent of the honour original data process used in Nearest Neighbours initial gridding (See [Initial gridding—Nearest Neighbours](#)).

Honour Original Data: 1 or 2 cell Choose the option button according to your requirements. The default option is 2 cell.

For 1 cell Honour Original Data, INTREPID simply calculates the weight (influence) of each original data cell on neighbouring cells based on the location of the original data point rather than the cell centroid, as explained above.

For 2 cell Honour Original Data, for each original data cell, INTREPID

- 1 Locates the quadrant of the original data cell in which the original data point lies;
- 2 Treats the 3 cells surrounding this quadrant as original data cells;
- 3 Locates the nearest original data points to the respective centroids of the 3 cells;
- 4 For each of the 3 cells, uses the value of its chosen data point and its position to calculate the weight (influence) of the cell for adjusting neighbouring cells.

When

- Every cell has changed during the last scan by less than the value that you specify (the **maximum residual** change), or
 - The maximum iterations have been performed,
- the Minimum Curvature process will stop.

Iterations You can use this text input box to specify the maximum number of times that INTREPID may scan through the grid (number of iterations) during the Minimum Curvature process.

Maximum Residual Each time INTREPID scans the grid in its attempt to smooth the grid, it may cause a change in the value of each interpolated cell. As it completes each progressive scan, the change in each cell becomes smaller—the interpolated values are becoming 'settled'.

You can use this text box to specify the stage at which you consider that the interpolated values are sufficiently 'settled' (leaving **residual** changes to be ignored).

Specify the Maximum Residual in the same units as your Z data.

If you are gridding magnetic data we recommend a value of 0.1nT to produce the best print quality.

Smoothing If you turn on Smoothing in the Refinements area, after INTREPID has completed the Minimum Curvature process, it will perform several further Minimum Curvature passes through the grid. During these passes it will adjust original data cell values in the same way as it has been adjusting interpolated cell values. This has the effect of further smoothing the grid.

Smoothing Iterations Use this text box to specify the number of smoothing iterations to perform.

(Relaxation factor) See above in this section for an explanation of the function of the relaxation factor. You can change the value of the relaxation factor if you are using a task specification (**.job**) file for your gridding process. Edit the **.job** file, changing the value in the **Relaxation_Factor =** line according to your requirements, e.g., **Relaxation_Factor = 1.325**. See [Displaying options and using task specification files](#) for information about batch mode.

Masking

Depending on the density of your original data, the cell size, and the value of the Extrapolate Cell parameter, INTREPID will fill gaps in the grid during the gridding process.

You may, on one hand, require a grid with no undefined regions, and require the Gridding tool to fill all gaps as best it can by interpolation.

On the other hand, you may

- Have one or more regions which should not have data at all, and for which interpolated data would be meaningless, or
- Require that the grid contain only data that is close to original data points.

In the Masking process, INTREPID sets to **null** all interpolated cells that are too far from an original data cell. INTREPID uses the value of the Extrapolate Cell parameter as the limit for the retaining or removing interpolated cells. For example, if Extrapolate Cell=2, then it sets to **null** all interpolated cells that are more than 2 cells away from an original data cell.

Whether you use Masking or not, if the Clipping process is enabled (See [\(Clipping / Crew Cut\)](#) for details below), INTREPID will sets to **null** all interpolated¹⁹ cells that are outside the row and column limits.

If you are using the Gridding tool to enhance an existing grid, INTREPID will not perform the Masking process.

>> *To use Masking*

Turn on the Masking check box in the Image Refinement parameters area.

The Extrapolate Cell parameter

INTREPID will use this parameter to specify the number of interpolated cells to retain around an original data cell. For example, if Extrapolate Cell is 3, INTREPID will mask (set to **null**) interpolated cells that are not within three cells of an original data cell. See [Cell extrapolation limits](#) for more information about this parameter.

(Clipping / Crew Cut)

The gradients at the edge of a grid can be extremely important in obtaining a good result from the gridding process. Keeping edge interpolation to a minimum is a desirable process. The Gridding tool has two processes which limit the number of interpolated cells at the edges of a grid.

Clipping

In the Clipping process, INTREPID sets to **null** all interpolated cells²⁰ on the edge of the grid that are outside the row and column limits.

By default, Clipping is enabled.

If you prefer extrapolated values around the border of the grid that are produced by Gridding to those produced by the Grid Filter tool (See

[Old spectral domain grid filters \(OldGridFFT\) \(T38\)](#)

[Spectral domain grid filters tool \(GridFFT\) \(T40\)](#)

[Spectral domain grid filters \(GridFFT\) wizard \(T39\)](#)

for details), you may wish to turn off Clipping.

1.⁹ Strictly speaking, these are extrapolated.

2.⁰ Strictly speaking these are extrapolated.

>> To disable Clipping

You must use Gridding in batch mode, and edit the task specification (`.job`) file accordingly. To turn Clipping off, edit the `Clipping =` line so that it reads `Clipping = No`. To turn Clipping on, edit the line so that it reads `Clipping = Yes`. See [Displaying options and using task specification files](#) for information about batch mode.

Crew Cut

The Crew Cut process is more stringent. If Crew Cut is enabled, both sides of an interpolated cell must be close to (within the value of the Extrapolate Cell parameter of) an original data cell, or the cell will be set to *null*.

By default, Crew Cut is disabled.

>> To enable Crew Cut

You must use Gridding in batch mode, and edit the task specification (`.job`) file accordingly. To turn Crew Cut off, edit the `CrewCut =` line so that it reads `CrewCut = No`. To turn Crew Cut on, edit the line so that it reads `CrewCut = Yes`. See [Displaying options and using task specification files](#) for information about batch mode.

The Extrapolate Cell parameter


If you disable Clipping, the value of this parameter will show the number of extrapolated cells retained around the original data cells at the edge of the grid. For example, if Extrapolate Cell is 3, there will be a border of three interpolated cells around the outside of the grid. See [Cell extrapolation limits](#) for more information about the Extrapolate Cell parameter.

Viewing the gridding progress and clearing the display

You can view the grid as INTREPID creates it.

>> To view the gridding process

- 1 Turn on Show Gridding in the Display menu



- 2 Choose the Gridding Main window from the Window menu.

INTREPID displays the progress of the gridding as a pseudocolour image in this display area. INTREPID represents one grid cell with one pixel up to 600 x 600 cells. For larger grids it subsamples the data to produce the screen image.

INTREPID automatically and dynamically adjusts the limits of the pseudocolour scale according to the data that it is representing, so that it uses the full range of the scale for the data concerned.

If you are working with a large dataset (See [Storage of completed grids, memory limits, large grids, output files](#)), INTREPID will use a tiling algorithm for the grid. Instead of expanding squares, you will see the image grow in strips)

>> To clear the display in the Gridding Main window


Choose Clear from the Display menu.

Viewing data in the early gridding stages


To examine your grid in the early stages when you can only see the cells containing data and possibly their immediate neighbours, choose Box Filter with Box Iterations set to 1 or some small number, LaPlace Iterations set to 0 and Minimum Curvature turned off. The process will stop after the number of iterations that you specify.

You can also view the cells containing original data at any time during the gridding process in the Gridding Original Data window. To view this page, choose Original Data from the Window menu.

Gridding progress display example—point dataset




Gridding progress display example—line dataset



Display example—Bi-Cubic Spline

This illustration shows the progress across the screen of the Bi-Cubic Spline process.




The Gridding Windows

INTREPID can use the Gridding windows to display the

- Gridding process (in pseudocolour),
- Original data (in pseudocolour)
- Gridding specifications and process reports (as text)
- Tiling control area and reports (as text)

>> To choose the display that you require

Use the Windows menu.




The Gridding Main Window

To view the Gridding Main window, choose Main from the Window menu.

The Gridding Main window contains


- A display area for the gridding process
- The gridding process status display area
- The Gridding parameters area
- The Image Refinement parameters area
- The Apply and Stop buttons



The Gridding Original Data window

After the gridding process commences, the Gridding Original Data window contains a pseudocolour display of the original data cells.

>> To view the Gridding Original Data window choose Original Data from the Window menu.



The Gridding Report window

The Gridding Report window has two columns of text.


The left hand column has a complete list of the current files, processes and parameters for Gridding. This text would become the Options file if you saved it (See [Displaying options and using task specification files](#) for details)

The right hand column contains reports of

- The source dataset and output grid statistics,
- The gridding process as it proceeds, and
- The Average Strike calculation button and report area (See [Using average strike for the Nominal Bearing](#) for details).

>> To view the Gridding Report window

Choose Report from the Window menu.



The Gridding Tiling Control window


The Gridding Tiling Control window has two columns of text.

The left hand column has a list of the current parameters for tiling process, a check box for turning on manual tiling control, and tile range text boxes if the check box is turned on. (See [Specifying the range of tiles to be processed](#) for details.)

The right hand column contains reports of the tiling process as it proceeds (See [Storage of completed grids, memory limits, large grids, output files](#)).

>> To view the Gridding Tiling Control window

Choose Tiling Control from the Window menu.



Apply

When you choose Apply INTREPID will carry out the Gridding process that you have specified.

Gridding status and progress reporting

Status and progress indicators

During each stage of the Gridding process, INTREPID displays progress information in the Status area at the bottom of the Gridding Main window.

Gridding Report

INTREPID reports information about the dataset and the gridding process, including

- The numbers of Rows and Columns and
- The Projection

>> To view the gridding report

Choose Report from the Window menu. INTREPID displays the Report window, which contains this information in its right half.

Tiling Report

INTREPID reports information about the tiling process,

>> To view the tiling report


Choose Tiling Control from the Window menu. INTREPID displays the Tiling Control window, which contains the report in its right half.

Trend Spline process reports

See [Process reports for the Trend Spline method](#).

Stop

If you wish to cancel the Gridding process before it is complete, choose Stop. INTREPID displays the Abort Gridding confirm dialog box. (With the current release of INTREPID, you may need to choose Stop several times in order for INTREPID to display this dialog box.)




Choose Yes to confirm that you wish to stop the process. Choose No to continue processing from where INTREPID suspended it.

Notes:

- If you are processing a small grid that fits into memory, all work on the grid will be lost, except for the initial statistics that INTREPID calculated for the input dataset.
- If you are processing a large grid using the tiling process, INTREPID will retain all tiles that have been completed, but all work on the current tile being processed will be lost (See [Storage of completed grids, memory limits, large grids, output files](#) for details).
- If you choose Apply again before you exit from Gridding, then
 - If you are processing a small grid that fits into memory, processing will commence from the beginning with the current set of parameters;
 - If you are processing a large grid using the tiling process, gridding will recommence at the start of the tile that INTREPID was processing when gridding stopped.

Help

You can use the Help menu to display help text on the topics shown in the menu illustration below.



Exit

To exit from Gridding choose Quit from the File menu.

Displaying options and using task specification files

Displaying options

To display the current file specifications and parameter settings, choose Report from the Window menu.

INTREPID displays the Gridding Report window containing the task specifications.

Using task specification files

You can store sets of file specifications and parameter settings for Gridding in task specification (**.job**) files.

>> To create a task specification file with the Gridding tool

- 1 Specify all files and parameters
- 2 If possible, execute the task (choose Apply) to ensure that it will work.
- 3 Choose Save Options from the File menu. Specify a task specification file (INTREPID will add the extension **.job**) INTREPID will create the file with the settings current at the time of the Save Options operation.

For full instructions on creating and editing task specification files see [INTREPID task specification \(.job\) files \(R06\)](#).

To use a task specification file in an interactive Gridding session

Load the task specification (**.job**) file (File menu, Load Options), modify any settings as required, then choose Apply.

>> To use a task specification file for a batch mode Gridding task

Type the command **gridding.exe** with the switch **-batch** followed by the name and path if necessary of the task specification file.

For example, if you had a task specification file called **surv329.job** you would use the command

```
gridding.exe -batch surv329.job
```

Task specification file notes and example

Here is an example of a Gridding task specification file

```
Process Begin
  Name = Gridding
  XIN = /disk1/survey/ebagoola_S/x
  YIN = /disk1/survey/ebagoola_S/y
  ZIN = /disk1/survey/ebagoola_S/raw_mag
  LineType = /disk1/survey/ebagoola_S/linetype
  OutputImage = /disk1/survey/raw_grid2
  Parameters Begin
    InitialMethod = BiSpline
    BoxOption5 = No
    Grid_Size = 70.0
    Search_Radius = 2000.0
    LineOrientation = -999
    MinimumCurvature = Yes
    ManualTilingControl = No
    Honour_Original = Yes
    Honour_2Cells = Yes
    Cells2Extrapolate = 2
    CellsInOverlap = 10
    MaximumIterations = 100
    CurrentBand = 0
    NumberOfBands = 1
    MaximumResidual = 2.0
    MinimumCurvatureTension = 0.0
    Relaxation_Factor = 1.375
    Trend_Variance_Factor = 1.0
    ZFilter = None
    ZPass = Pass
    Window = 5
    Tolerance = 0.1
    Masking = No
    Masking2 = No
    Clipping = Yes
    Smoothing = No
    Rotate_Lines = No
    SmoothingIterations = 4
    LaplaceIterations = 4
    StartTile = 1
    FinishTile = 1
  Parameters End
Process End
```


Notes

You can modify the following operations or parameters only by editing a task specification file:

You can disable the Clipping operation by editing the **Clipping =** line so that it reads **Clipping = No**. To enable Clipping, edit the line so that it reads **Clipping = Yes**. See (Clipping / Crew Cut) for details.

- You can enable the **CrewCut** option. See (Clipping / Crew Cut) for details.
- You can modify the relaxation factor in the minimum curvature process (See Minimum Curvature for details). Change the value in the **Relaxation_Factor =** line according to your requirements, e.g.,
Relaxation_Factor = 1.325.
- You can modify the **Trend_Variance_Factor**. See Initial gridding—Trend Spline for details.

Frequently asked questions

Q : Why doesn't Bispline gridding appear to fill the grid properly on a dataset with angled lines?

Splining only works in the NS or EW direction. It depends on the bearing entered. ie. if you enter a bearing of 90, it will spline (NS) for lines which have a bearing within 70°–110° ($\pm 20^\circ$ from 90°), or if you enter 0 it will spline EW for lines bearing 340°–20°. If you enter 45 you will need to select "rotate dataset" or else it will try and spline NS (as if lines were bearing 90°) and not find many node points, outputting a generally blank grid.

Q : What should I make the coarse grid Maximum scan distance for variable density gridding?

The coarse grid search radius (Max scan distance) should default to something very large in order to effectively scan the entire area.

It is in the same units as the X and Y coordinates.

Q : Can I grid a subsection of an area without having to define a bounding polygon dataset?

Gridding from INTREPID v3.7 supports a Clip Box with bounding co-ordinates directly defined in the job file.

Q : I want to grid the tie lines as well as the traverse lines. How do I do that?

Use the Nearest Neighbours option if you want to grid all the lines. If you have a Linetype field defined, re-number it to 2 for all lines, then grid.

Another way is to comment out the **Linetype** alias in the **.isi** file, then grid. The Nominal Bearing entry will then control what lines get gridded. If you leave it blank all lines get gridded.

Bi-splining won't grid all the lines because it ignores lines $> 22^\circ$ from the required nominal bearing.

Q : How can I change the null value in an INTREPID grid?

Edit the grid using the Spreadsheet Editor, and replace the **nulls** with the new value. Then edit the grid header file, and change **NullCellValue** to the new value.