

Abstract

This is the User Manual for the *MySQL™ Cluster Manager*, version 1.3.6. It documents the *MySQL Cluster Manager Agent* and *MySQL Cluster Manager Client* software applications which can be used to administer *MySQL Cluster*, a version of the *MySQL Database System* (referred to hereafter as "MySQL Server" or simply "MySQL") that incorporates the NDB storage engine for high availability and data redundancy in a distributed computing environment.

This Manual applies to MySQL Cluster Manager 1.3.6 and contains information that may not apply to older versions of the MySQL Cluster Manager software. For documentation covering previous MySQL Cluster Manager releases, see MySQL Documentation: MySQL Cluster, on the MySQL website.

MySQL Cluster Manager features. This manual describes features that may not be included in every version of MySQL Cluster Manager, and such features may not be included in the version of MySQL Cluster Manager licensed to you. If you have any questions about the features included in your version of MySQL Cluster Manager, refer to your MySQL Cluster Manager license agreement or contact your Oracle sales representative.

MySQL Cluster Manager, MySQL Server, and MySQL Cluster features. This manual contains certain basic information about MySQL Server and MySQL Cluster; however, it is not in any way intended as an exhaustive reference for either of these products.

Current versions of MySQL Cluster compatible with MySQL Cluster Manager are based on versions 7.2, 7.3, and 7.4 of the NDB storage engine; these versions of MySQL Cluster are known as "MySQL Cluster NDB 7.2," "MySQL Cluster NDB 7.3," and "MySQL Cluster NDB 7.4," respectively. MySQL Cluster functionality varies between MySQL Cluster releases; MySQL Cluster Manager cannot supply or emulate MySQL Cluster features that are not present in the version of the MySQL Cluster software in use.

For complete information about MySQL Server and MySQL Cluster, please refer to the appropriate version of the *MySQL Manual*:

- For information about MySQL Cluster NDB 7.2, see MySQL Cluster NDB 7.2.
- For information about MySQL Cluster NDB 7.3 and 7.4, see MySQL Cluster NDB 7.3 and MySQL Cluster NDB 7.4.

If you do not have the MySQL Server and MySQL Cluster documentation, you can obtain it free of charge from the MySQL Documentation Library, on the MySQL website.

For legal information, see the Legal Notices.

For help with using MySQL, please visit either the MySQL Forums or MySQL Mailing Lists, where you can discuss your issues with other MySQL users.

For additional documentation on MySQL products, including translations of the documentation into other languages, and downloadable versions in variety of formats, including HTML and PDF formats, see the MySQL Documentation Library.

Document generated on: 2015-12-15 (revision: 45883)

Table of Contents

Preface and Legal Notices	
1 Overview of MySQL Cluster Manager	
1.1 MySQL Cluster Manager Terminology	
1.2 MySQL Cluster Manager Architecture	
2 MySQL Cluster Manager Installation, Configuration, Cluster Setup	
2.1 Obtaining MySQL Cluster Manager	
2.2 Supported Platforms and MySQL Cluster Versions	. 5
2.3 MySQL Cluster Manager Installation	
2.3.1 Installing MySQL Cluster Manager on Unix Platforms	. 6
2.3.2 Installing MySQL Cluster Manager on Windows Platforms	. 9
2.3.3 Setting the MySQL Cluster Manager Agent User Name and Password	17
2.4 MySQL Cluster Manager Configuration File	18
2.5 Upgrading MySQL Cluster Manager	19
3 Using MySQL Cluster Manager	23
3.1 mcmd, the MySQL Cluster Manager Agent	23
3.2 Starting and Stopping the MySQL Cluster Manager Agent	31
3.2.1 Starting and Stopping the Agent on Linux	31
3.2.2 Starting and Stopping the MySQL Cluster Manager Agent on Windows	32
3.3 Starting the MySQL Cluster Manager Client	
3.4 Setting Up MySQL Clusters with MySQL Cluster Manager	37
3.4.1 Creating a MySQL Cluster with MySQL Cluster Manager	37
3.5 Importing MySQL Clusters into MySQL Cluster Manager	39
3.5.1 Importing a Cluster Into MySQL Cluster Manager: Basic Procedure	39
3.5.2 Importing a Cluster Into MySQL Cluster Manager: Example	40
3.6 MySQL Cluster Backup and Restore Using MySQL Cluster Manager	
3.6.1 Requirements for Backup and Restore	54
3.6.2 Basic MySQL Cluster Backup and Restore Using MySQL Cluster Manager	
3.7 Backing Up and Restoring MySQL Cluster Manager Agents	58
3.8 Setting Up MySQL Cluster Replication with MySQL Cluster Manager	60
4 MySQL Cluster Manager Client Commands	
4.1 Online Help and Information Commands	69
4.2 MySQL Cluster Manager Site and Agent Commands	
4.2.1 The add hosts Command	76
4.2.2 The remove hosts Command	
4.2.3 The change log-level Command	77
4.2.4 The rotate log Command	
4.2.5 The collect logs Command	78
4.2.6 The create site Command	79
4.2.7 The delete site Command	
4.2.8 The list sites Command	
4.2.9 The list hosts Command	
4.2.10 The show settings Command	
4.2.11 The stop agents Command	
4.2.12 The version Command	
4.2.13 The show warnings Command	
4.3 MySQL Cluster Manager Package Commands	
4.3.1 The add package Command	
4.3.2 The delete package Command	
4.3.3 The list packages Command	
4.4 MySQL Cluster Manager Cluster Commands	
4.4.1 The create cluster Command	
4.4.2 The delete cluster Command	
4.4.3 The list clusters Command	
4.4.4 The list nextnodeids Command	
4.4.5 The restart cluster Command	93

4.4.6 The show status Command	93
4.4.7 The start cluster Command	96
4.4.8 The stop cluster Command	98
4.4.9 The upgrade cluster Command	98
4.5 MySQL Cluster Manager Configuration Commands	100
4.5.1 The get Command	
4.5.2 The reset Command	. 111
4.5.3 The set Command	. 118
4.6 MySQL Cluster Manager Process Commands	. 124
4.6.1 The add process Command	124
4.6.2 The change process Command	127
4.6.3 The list processes Command	130
4.6.4 The start process Command	130
4.6.5 The stop process Command	131
4.6.6 The remove process Command	131
4.7 MySQL Cluster Manager Backup and Restore Commands	. 132
4.7.1 The abort backup Command	
4.7.2 The backup cluster Command	133
4.7.3 The list backups Command	
4.7.4 The restore cluster Command	
4.7.5 The backup agents Command	
4.8 MySQL Cluster Manager Cluster Importation Commands	
4.8.1 The import cluster Command	
4.8.2 The import config Command	
5 MySQL Cluster Manager Limitations and Known Issues	
5.1 MySQL Cluster Manager Usage and Design Limitations	
5.2 MySQL Cluster Manager 1.3.6 Limitations Relating to the MySQL Server	
5.3 MySQL Cluster Manager Limitations Relating to MySQL Cluster	
5.4 Syntax and Related Issues in MySQL Cluster Manager	
A Changes in MySQL Cluster Manager	
B Licenses for Third-Party Components Used in MySQL Cluster Manager 1.3.6	
B.1 GLib License (for MySQL Cluster Manager)	
B.2 GNU Lesser General Public License Version 2.1, February 1999	
B.3 libevent License	
B.4 libintl License	
B.5 LPeg Library License	
B.6 Lua (liblua) License	
B.7 LuaFileSystem Library License	
B.8 PCRE License	
B.9 SHA-1 in C License	
C Attribute Summary Tables	
C.1 Management Node Configuration Parameters	
C.2 Data Node Configuration Parameters	
C.3 API Node Configuration Parameters	
C.4 Other Node Configuration Parameters	
C.5 MySQL Server Option and Variable Reference for MySQL Cluster	
Index	203

Preface and Legal Notices

This is the User Manual for the *MySQLTM Cluster Manager*, version 1.3.6. It documents the *MySQL Cluster Manager Agent* and *MySQL Cluster Manager Client* software applications which can be used to administer *MySQL Cluster*, a version of the *MySQL Database System* (referred to hereafter as "MySQL Server" or simply "MySQL") that incorporates the NDB storage engine for high availability and data redundancy in a distributed computing environment.

This manual does contain certain basic information about MySQL and MySQL Cluster; however, it is not in any way intended as an exhaustive reference for either of these products.

Current versions of MySQL Cluster compatible with MySQL Cluster Manager are based on versions 7.2, 7.3, and 7.4 of the NDB storage engine; these versions of MySQL Cluster are known as "MySQL Cluster NDB 7.2," "MySQL Cluster NDB 7.3," and "MySQL Cluster NDB 7.4," respectively. MySQL Cluster functionality varies between MySQL Cluster releases; MySQL Cluster Manager cannot supply or emulate MySQL Cluster features that are not present in the version of the MySQL Cluster software in use.

For complete information about MySQL Server and MySQL Cluster, please refer to the appropriate version of the *MySQL Manual*:

- For information about MySQL Cluster NDB 7.2, see MySQL Cluster NDB 7.2.
- For information about MySQL Cluster NDB 7.3 and 7.4, see MySQL Cluster NDB 7.3 and MySQL Cluster NDB 7.4.

For license information, see the Legal Notices. This product may contain third-party code. For license information on third-party code, see Appendix B, *Licenses for Third-Party Components Used in MySQL Cluster Manager 1.3.6*.

Legal Notices

Copyright © 2009, 2015, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous

applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info or visit http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs if you are hearing impaired.

This documentation is NOT distributed under a GPL license. Use of this documentation is subject to the following terms:

You may create a printed copy of this documentation solely for your own personal use. Conversion to other formats is allowed as long as the actual content is not altered or edited in any way. You shall not publish or distribute this documentation in any form or on any media, except if you distribute the documentation in a manner similar to how Oracle disseminates it (that is, electronically for download on a Web site with the software) or on a CD-ROM or similar medium, provided however that the documentation is disseminated together with the software on the same medium. Any other use, such as any dissemination of printed copies or use of this documentation, in whole or in part, in another publication, requires the prior written consent from an authorized representative of Oracle. Oracle and/ or its affiliates reserve any and all rights to this documentation not expressly granted above.

Chapter 1 Overview of MySQL Cluster Manager

Table of Contents

1.1	MySQL	Cluster	Manager	Terminology	 1
1.2	MySQL	Cluster	Manager	Architecture	 2

This chapter provides a overview of MySQL Cluster Manager, as well as its architecture, purpose, and capabilities.

1.1 MySQL Cluster Manager Terminology

This section provides definitions of key terms used to describe MySQL Cluster Manager and its components in this manual and in other documentation relating to MySQL Cluster Manager and MySQL Cluster.

Site.

A set of hosts on which MySQL Cluster processes to be managed by MySQL Cluster Manager are located. A site can include one or more clusters.

Cluster.

A MySQL Cluster deployment. A cluster consists of a set of MySQL Cluster processes running on one or more hosts. A minimal cluster is usually considered to include one management node, two data nodes, and one SQL node. A typical production cluster may have one or two management nodes, several SQL nodes, and 4 or more data nodes. The exact numbers of data and SQL nodes can vary according to data size, type and rating of hardware used on the hosts, expected throughput, network characteristics, and other factors; the particulars are beyond the scope of this document, and you should consult MySQL Cluster NDB 7.3 and MySQL Cluster NDB 7.4, for more specific information and guidelines.

Host.

A computer. The exact meaning depends on the context:

• A computer where one or more MySQL Cluster processes are run. In this context, we sometimes refer more specifically to a *cluster host*.

The number of cluster processes and number of cluster hosts may be, but are not necessarily, the same.

• A computer where an instance of the MySQL Cluster Manager agent runs.

In order to run a MySQL Cluster using MySQL Cluster Manager, the MySQL Cluster Manager agent must be running on each host where cluster processes are to be run. In other words, when using MySQL Cluster Manager, all cluster hosts must also be MySQL Cluster Manager agent hosts (although the reverse is not necessarily true). Therefore, you should understand that anytime we use the term *host*, we are referring to a host computer in both of the senses just given.

Process.

In the context of MySQL Cluster, a process (more specifically, a cluster process) is a MySQL Cluster node, of one of the following 3 types: management node (ndb_mgmd), data node (ndbd or ndbmtd), or SQL node (mysqld). For more information about these node types and their functions in a cluster, see MySQL Cluster Core Concepts, and MySQL Cluster Nodes, Node Groups, Replicas, and Partitions.

Package.

A copy of the MySQL cluster software. This should include the binary executables needed to run the cluster processes of the desired types on a given host. The simplest way to make sure that this is done

is to place a copy of the entire MySQL Cluster distribution on each computer that you intend to use as a cluster host.

Configuration attribute.

A value whose setting affects cluster operations in a clearly defined and measurable way. When running MySQL Cluster manually, configuration is accomplished using cluster configuration parameters, MySQL server options, and MySQL system and status variables; MySQL Cluster Manager masks the differences between these, provides a unified view of them; see Configuration attributes, for more information.

Agent.

A MySQL Cluster Manager process that runs on each cluster host, responsible for managing the cluster processes running on that host.

Client.

The MySQL Cluster Manager client is a software application that allows a user to connect to MySQL Cluster Manager and perform administrative tasks, such as (but not limited to): creating, starting, and stopping clusters; obtaining cluster and cluster process status reports; getting cluster configuration information and setting cluster configuration attributes.

1.2 MySQL Cluster Manager Architecture

This section provides an architectural overview of MySQL Cluster Manager, its components, and their deployment.

MySQL Cluster Manager is a distributed client-server application consisting of two main components. The MySQL Cluster Manager agent is a set of one or more agent processes that manage MySQL cluster nodes, and the MySQL Cluster Manager client provides a command-line interface to the agent's management functions.

Agent.

The MySQL Cluster Manager agent is comprised of the set of all MySQL Cluster Manager agent processes running on the hosts making up a given management site. A MySQL Cluster Manager agent process is a daemon process which runs on each host to be used in the cluster. In MySQL Cluster Manager, there is no single central server or process; all agents collaborate in managing a cluster as a whole. This means that any connected agent can be used to carry out tasks that effect the entire cluster.

Each agent process is responsible for managing the MySQL Cluster nodes running on the host where the agent is located. MySQL Cluster management and SQL nodes are managed directly by the MySQL Cluster Manager agent; cluster data nodes are managed indirectly, using the cluster management nodes.

Management responsibilities handled by the MySQL Cluster Manager agent include the following:


- · Starting, stopping, and restarting cluster nodes
- Cluster configuration changes
- Cluster software upgrades
- · Host and node status reporting
- · Recovery of failed cluster nodes

Creating, performing initial configuration of, or starting a cluster, requires that agent processes be running on all cluster hosts. Once the cluster has been started, it continues to run even if one or more agent processes fail. However, any failed agent processes must be restarted before you can perform additional cluster management functions.

Client.

A MySQL Cluster Manager client is a software application used to access an MySQL Cluster Manager agent. In MySQL Cluster Manager, the client is actually nothing more than the mysql command-line client, started with the options that are necessary for it to connect to an MySQL Cluster Manager agent. MySQL Cluster Manager 1.3.6 and later releases include an mcm client for ease of use; this client consists of a script that acts as a wrapper for the mysql client with these options.

By way of example, we show how MySQL Cluster Manager would be deployed for use with a MySQL Cluster running on 4 host computers. This is illustrated in the following diagram:



In this example cluster, 2 of the hosts each house a management server and an SQL node; the other 2 hosts each house 2 data nodes. However, regardless of the distribution of cluster nodes among the hosts, a MySQL Cluster Manager agent process must be runnings on each host.

A MySQL Cluster Manager client can be used to access the agent from any of the hosts making up the management site to which the cluster belongs. In addition, the client can be used on any computer that has a network connection to at least 1 of the hosts where an agent process is running. The computer where the client itself runs is not required to be one of these hosts. The client can connect to and use different agent processes on different hosts within the management site, at different times, to perform cluster management functions.



Chapter 2 MySQL Cluster Manager Installation, Configuration, Cluster Setup

Table of Contents

2.1 Obtaining MySQL Cluster Manager	. 5
2.2 Supported Platforms and MySQL Cluster Versions	
2.3 MySQL Cluster Manager Installation	
2.3.1 Installing MySQL Cluster Manager on Unix Platforms	6
2.3.2 Installing MySQL Cluster Manager on Windows Platforms	. 9
2.3.3 Setting the MySQL Cluster Manager Agent User Name and Password	17
2.4 MySQL Cluster Manager Configuration File	18
2.5 Upgrading MySQL Cluster Manager	

This chapter discusses basic installation and configuration of the MySQL Cluster Manager Management Agent, connecting to the agent with the MySQL Cluster Manager client, and the basics of creating or importing a cluster using MySQL Cluster Manager.

2.1 Obtaining MySQL Cluster Manager

MySQL Cluster Manager is available only through commercial license. To learn more about licensing terms, and to obtain information about where and how to download MySQL Cluster Manager, visit http://www.mysql.com/products/cluster/mcm/, or contact your Oracle representative.

2.2 Supported Platforms and MySQL Cluster Versions

For a list of platforms supported by MySQL Cluster Manager 1.3.6, see *Supported Platforms: MySQL Cluster Manager* at http://www.mysql.com/support/supportedplatforms/cluster-manager.html, or contact your Oracle representative.

MySQL Cluster Manager 1.3.6 supports the following MySQL Cluster release versions:

- MySQL Cluster NDB 7.1 (see MySQL Cluster NDB 6.1 7.1), beginning with MySQL Cluster NDB 7.1.4
- MySQL Cluster NDB 7.2 (see MySQL Cluster NDB 7.2), beginning with MySQL Cluster NDB 7.2.4
- MySQL Cluster NDB 7.3 (see MySQL Cluster NDB 7.3 and MySQL Cluster NDB 7.4), beginning with MySQL Cluster NDB 7.3.2
- MySQL Cluster NDB 7.4 (see MySQL Cluster NDB 7.3 and MySQL Cluster NDB 7.4), beginning with MySQL Cluster NDB 7.4.4

Prior to installation, you must obtain the correct build of MySQL Cluster Manager for your operating system and hardware platform. For Unix platforms, MySQL Cluster Manager is delivered as a Unix .tar.gz archive, whose name is in the format of mcm-1.3.6-cluster-7.4.6-linux-distro-arch.tar.gz. For Windows platforms, an MSI installer file is provided. All MySQL Cluster Manager 1.3.6 packages include MySQL Cluster NDB 7.4.6.

When selecting the appropriate installer for your operating system and hardware, keep in mind that 32-bit programs can normally be run on 64-bit platforms, but that the reverse is not true.

2.3 MySQL Cluster Manager Installation

Installation of the MySQL Cluster Manager agent and client programs varies according to platform. On Unix platforms, you must extract the binaries and other files from a .tar.gz archive and copy them to the correct locations manually. For Windows platforms, an MSI installer is provided which

largely automates this process. Installation of MySQL Cluster Manager using each of these methods is covered in the next two sections.



Note

License keys were required in order to use some very early releases of MySQL Cluster Manager. They are not needed in order to use recent versions, including MySQL Cluster Manager 1.3.6.

2.3.1 Installing MySQL Cluster Manager on Unix Platforms

Install the MySQL Cluster Manager agent on Linux and similar platforms by following the instructions below.

Extract the MySQL Cluster Manager 1.3.6 program and other files from the distribution archive.

You must install a copy of MySQL Cluster Manager on each computer that you intend to use as a MySQL Cluster host. In other words, you need to install MySQL Cluster Manager on each host that is a member of a MySQL Cluster Manager management site. For each host, you should use the MySQL Cluster Manager build that matches that computer's operating system and processor architecture.

On Linux systems, you can unpack the archive using the following command, using mcm-1.3.6-cluster-7.4.6-linux-sles11-x86-64bit.tar.gz as an example (the actual filename will vary according to the MySQL Cluster Manager build that you intend to deploy):

```
shell> tar -zxvf mcm-1.3.6-cluster-7.4.6-linux-sles11-x86-64bit.tar.gz
```

This command unpacks the archive into a directory having the same name as the archive, less the .tar.gz extension. The top-level directory within the archive is named mcm-1.3.6.



Important

Because the Solaris version of tar cannot handle long filenames correctly, the MySQL Cluster Manager program files may be corrupted if you try to use it to unpack the MySQL Cluster Manager archive. To get around this issue on Solaris operating systems, you should use GNU tar (gtar) rather than the default tar supplied with Solaris. On Solaris 10, gtar is often already installed in the /usr/sfw/bin directory, although the gtar executable may not be included in your path. If gtar is not present on your system, please consult the Solaris 10 system documentation for information on how to obtain and install it.

In general, the location where you place the unpacked MySQL Cluster Manager directory and the name of this directory can be arbitrary. However, we recommend that you use a standard location for optional software, such as /opt on Linux systems, and that you name the directory using the 1.3.6 version number. (This facilitates subsequent upgrades.) On a typical Linux system you can accomplish this task like this:

```
shell> cd mcm-1.3.6-cluster-7.4.6-linux-sles11-x86-64bit shell> mv mcm-1.3.6 /opt/mcm-1.3.6
```

For ease of use, we recommend that you put the MySQL Cluster Manager files in the same directory on each host where you intend to run it.

Contents of the MySQL Cluster Manager Unix Distribution Archive.

If you change to the directory where you placed the extracted MySQL Cluster Manager archive and list the contents, you should see something similar to what is shown here:

```
shell> cd /opt/mcm-1.3.6
shell> ls
bin cluster etc lib libexec licenses share var
```

These directories are described in the following table:

Directory	Contents		
bin	MySQL Cluster Manager agent startup scripts		
cluster	Contains the MySQL Cluster NDB 7.4.6 binary distribution		
etc	Contains the agent configuration file (mcmd.ini)		
etc/init.d	Init scripts		
1ib and subdirectories	Libraries needed to run the MySQL Cluster Manager agent		
libexec	MySQL Cluster Manager agent and client executables		
licenses/lgpl	An archive containing source code (including licensing and documentation), for glib 2.1		
share/doc/mcmd	README.txt file		
var	XML files containing information needed by MySQL Cluster Manager about processes, attributes, and command syntax		

Normally, the only directories of those shown in the preceding table that you need be concerned with are the bin and etc directories.

For MySQL Cluster Manager 1.3.6 distributions that include MySQL Cluster, the complete MySQL Cluster NDB 7.4.6 binary distribution is included in the cluster directory. Within this directory, the layout of the MySQL Cluster distribution is the same as that of the standalone MySQL Cluster binary distribution. For example, MySQL Cluster binary programs such as ndb_mgmd, ndbd, ndbmtd, and ndb_mgm can be found in cluster/bin. For more information, see MySQL Installation Layout for Generic Unix/Linux Binary Package, and Installing a MySQL Cluster Binary Release on Linux, in the MySQL Manual.

If you wish to use the included MySQL Cluster software, it is recommended that you move the cluster directory and all its contents to a location outside the MySQL Cluster Manager installation directory, such as /opt/ndb-version. For example, on a Linux system, you can move the MySQL Cluster NDB 7.4.6 software that is bundled with MySQL Cluster Manager 1.3.6 to a suitable location by first navigating to the MySQL Cluster Manager installation directory and then using a shell command similar to what is shown here:

shell> mv cluster /opt/ndb-7.4.6



Note

The mcmd --bootstrap option uses the included MySQL Cluster binaries in the installation directory's cluster directory and does not work if they cannot be found there. To work around this issue, create a symbolic link to the correct directory in its place, like this:

shell> ln -s /opt/ndb-7.4.6 cluster

After doing this, you can use the mcm client commands add package and upgrade cluster to upgrade any desired cluster or clusters to the new MySQL Cluster software version.



Important

On Linux platforms, do not attempt to install the MySQL Cluster software by the RPM, Debian, or other installation packages for any package management

systems. They install MySQL Cluster differently than the binary distribution that comes with the MySQL Cluster Manager archive, and that will cause issue in the future when you try to upgrade your cluster with MySQL Cluster Manager.

The MySQL Cluster Manager agent by default writes its log file as mcmd.log in the installation directory. When the agent runs for the first time, it creates a directory where the agent stores its own configuration data; by default, this is /opt/mcm_data. The configuration data, log files, and data node file systems for a given MySQL Cluster under MySQL Cluster Manager control, and named cluster_name, can be found in clusters/cluster_name under this data directory (sometimes also known as the MySQL Cluster Manager data repository).

The location of the MySQL Cluster Manager agent configuration file, log file, and data directory can be controlled with mcmd start-up options or by making changes in the agent configuration file. To simplify upgrades of MySQL Cluster Manager, we recommend that you change the data repository to a directory outside the MySQL Cluster Manager installation directory, such as /var/opt/mcm. See Section 2.4, "MySQL Cluster Manager Configuration File", and Section 3.2, "Starting and Stopping the MySQL Cluster Manager Agent", for more information.

On Linux and other Unix-like systems, you can set up the MySQL Cluster Manager agent to run as a daemon, using the unit script that is supplied with the MySQL Cluster Manager distribution. To do this, follow the steps listed here:

 Copy the file /etc/init.d/mcmd under the MySQL Cluster Manager installation directory to your system's /etc/init.d/ directory (or equivalent). On a typical Linux system, you can do this using the following command in the system shell, where mcmdir is the MySQL Cluster Manager installation directory:

```
shell> cd mcmdir/etc/init.d
shell> cp mcmd /etc/init.d/mcmd
```

Make sure that this file has appropriate permissions and is executable by the user account that runs MySQL Cluster Manager. On a typical Linux system, this can be done by executing commands in your system shell similar to those shown here:

```
shell> chown mcmuser /etc/init.d/mcmd
shell> chmod 755 /etc/init.d/mcmd
```

Be sure to refer to your operating system documentation for exact information concerning the commands needed to perform these operations, as they may vary between platforms.

3. Open the file /etc/init.d/mcmd in a text editor. Here, we show a portion of this file, in which we have highlighted the two lines that need to be updated:

```
MCMD_SERVICE="mcmd"

MCMD_PSERVICE="MySQL Cluster Manager"

MCMD_ROOTDIR=@@MCMD_ROOTDIR@@

MCMD_BIN="$MCMD_ROOTDIR/bin/mcmd"

MCMD_CONFIG="$MCMD_ROOTDIR/etc/mcmd.ini"

# Run service as non-root user

MCMD_USER=@@MCMD_USER@@

SU="su --login $MCMD_USER --command"
```

In the first of these lines, replace the placeholder <code>@@MCMD_ROOTDIR@@</code> with the complete path to the MySQL Cluster Manager installation directory. In the second of these lines, replace the placeholder <code>@@MCMD_USER@@</code> with the name of the system user that runs the MySQL Cluster Manager agent (note that this must <code>not</code> be the system <code>root</code> account). Save the edited file.

The MySQL Cluster Manager agent should now be started automatically whenever the system is restarted.


When the agent is configured as a daemon, cluster processes are started automatically when the agent is restarted, as long as the cluster was running when the agent shut down. *Note that* <code>stopOnError</code> must be disabled (set to 0) for all data nodes in order for this to work. If the cluster was stopped when the agent shut down, it is necessary to supply a script which waits for the agent to complete its startup and recovery phases, and then, when the agent is ready, starts the cluster using a command such as <code>mcmdir/bin/mcm -e 'start cluster --background cluster_name;'.</code>

2.3.2 Installing MySQL Cluster Manager on Windows Platforms


To install MySQL Cluster Manager 1.3.6 on Windows platforms, you should first have downloaded the MSI installer file mcm-1.3.6-cluster-7.4.6-win32-x86.msi (see Section 2.1, "Obtaining MySQL Cluster Manager"). 1.3.6 for Windows is 32-bit, as is the bundled MySQL Cluster NDB 7.4.6; these run on both 32-bit and 64-bit versions of Windows.

As mentioned elsewhere (see, for example, Section 3.4.1, "Creating a MySQL Cluster with MySQL Cluster Manager"), you must install a copy of MySQL Cluster Manager on each computer where you intend to host a MySQL Cluster node. Therefore, the following procedure must be performed separately on each host computer. For ease of installations and upgrades on multiple machines, it is recommended that you install MySQL Cluster Manager to the same location on each host. This is C:\Program Files\MySQL\MySQL Cluster Manager 1.3.6\ or C:\Program Files (x86)\MySQL\MySQL Cluster Manager 1.3.6\ by default, but it is possible to install MySQL Cluster Manager to an alternate location such as C:\mcm\.


In the discussion that follows, we assume that you have downloaded the MySQL Cluster Manager 1.2.1 MSI installer as user jon to this user's Downloads directory (C:\Users\jon\Downloads\MCM) on a 64-bit Windows system. Navigate to this directory in Windows Explorer, as shown here:




To run the installer, double-click on the file icon in Windows Explorer. Some versions of Windows also provide an Install item in the Windows Explorer menu that can be used to run the installer. When you start the installer, you may see a Windows **Security Warning** screen. If you obtained the installer from a trusted source and know that it has not been tampered with, choose Run from the dialog, which allows the installer to continue to the **Welcome** screen, as shown here:




Click the Next button to continue to the License Agreement screen, as shown in the next figure:




You should read the license text in the text area, and when you have done so, check the box labelled **I accept the terms in the License Agreement**. Until you have checked the box, you cannot complete the MySQL Cluster Manager installation; it is possible only to go back to the previous screen, print the license, or cancel the installation (using the buttons labelled Back, Print, and Cancel, respectively). Checking the box enables the Next button, as shown here:




Click the Next button to continue to the **Destination Folder** screen, where you can choose the installation directory. The next figure shows the **Destination Folder** screen with the default location. On English-language 32-bit Windows systems, this is C:\Program Files\MySQL\MySQL Cluster Manager version\); on English 64-bit Windows systems, the default is C:\Program Files (x86)\MySQL\MySQL Cluster Manager version\. (In this example, we are installing MySQL Cluster Manager 1.2.1 on a 64-bit system, so the default is C:\Program Files (x86)\MySQL \MySQL Cluster Manager 1.2.1\.) You can click the **Change** button to change the directory where MySQL Cluster Manager should be installed; the default directory is adequate for most cases.



Once you have selected the destination directory, the installer has gathered all the information that it requires to perform the installation. Click Next to continue to the **Ready** screen, shown here:



Click the Install button to install MySQL Cluster Manager. As the installer begins to copy files and perform other tasks affecting the system, you may see a warning dialog from Windows User Access Control, as shown here:



If this occurs, click the Yes button to allow the installation to continue. A **Setup Wizard** screen with a progress bar is displayed while the installer runs, as shown in the next figure:




The **Setup Wizard** may require several minutes to copy all of the necessary files for MySQL Cluster Manager 1.3.6 and MySQL Cluster NDB 7.4.6 to the installation directory and to perform other required changes.



Note

The MySQL Cluster Manager 1.3.6 installer places MySQL Cluster NDB 7.4.6 in the cluster directory under the installation directory. (By default, this is C: \Program Files\MySQL\MySQL Cluster Manager 1.3.6\cluster or C:\Program Files (x86)\MySQL\MySQL Cluster Manager 1.3.6\cluster.) The location of the MySQL Cluster binaries is not separately configurable using the MySQL Cluster Manager installer.

When the **Setup Wizard** finishes, the installer displays the **Installation Completed** screen, as shown here:



MySQL Cluster Manager 1.3.6 has now been installed to the destination directory; click the Finish button to exit the installer.

2.3.2.1 Installing the MySQL Cluster Manager Agent as a Windows Service

After installing the MySQL Cluster Manager Agent as a Windows service, you can start and stop the agent using the Windows Service Manager. The installation also configures the agent to start automatically whenever Windows starts, and to shut down safely whenever Windows shuts down.




Note

The Windows service can be used to control the running of MySQL Cluster Manager agents on a single host only. To shut down agents on multiple hosts, you can use the stop agents command in the MySQL Cluster Manager client.

The installation is performed using the command prompt (cmd.exe); as with installing or removing any Windows service, it must also be done as a user having sufficient permissions, such the system Administrator account.

If the account you are currently using has Administrator privileges, you can simply start cmd.exe. Otherwise, you must run the command prompt program as the Administrator. To do this, first locate a shortcut to the command prompt. On most Windows systems, you can do this using the Start Menu. Find Programs (or All Programs, in some Windows versions), then navigate to Accessories. Under Accessories, right-click on the Command Prompt menu item. From the context menu that appears, select Run as Administrator. You can see how this looks on a typical Windows system in the next figure.



If a Windows UAC dialog referring to cmd.exe appears, click Yes to allow the command prompt to run as Administrator and thus to continue. You should now have a command prompt window open on your desktop, running a session with Administrator privileges.

To install the MySQL Cluster Manager agent as a service, we use the SC CREATE command. This command allows us to specify a name for the service (for use in NET START and NET STOP commands), a display name (to be shown in the Service Manager), a startup mode (automatic or manual start), and a path to the executable to be run as a service. (Use mcmd-svc.exe rather than mcmd.exe as the executable.) The path must also include any arguments needed by the program; in the case of MySQL Cluster Manager, mcmd-svc.exe must be told where to find its configuration file using the --defaults-file option. Both of these paths must be absolute.



Important

Installation of the MySQL Cluster Manager agent as a service is recommended. However, you should *not* install MySQL Cluster processes (ndb_mgmd.exe, ndbd.exe, ndbmtd.exe, mysqld.exe) as services on Windows hosts to be used as MySQL Cluster nodes under management by MySQL Cluster Manager, since the MySQL Cluster Manager agent itself controls MySQL Cluster nodes independently of the Windows Service Manager.

Assume that you have installed MySQL Cluster Manager to the default location for 64-bit Windows systems C:\Program Files (x86)\MySQL\MySQL Cluster Manager 1.3.6\ (C:\Program Files\MySQL\MySQL Cluster Manager 1.3.6\ on 32-bit Windows systems), and that its configuration file is located in C:\Program Files (x86)\MySQL\MySQL Cluster Manager 1.3.6\etc. Then the following command installs MySQL Cluster Manager as a service named mcm, with the display name "MySQL Cluster Manager 1.3.6":

```
C:\> SC CREATE

"MCM" DisplayName= "MySQL Cluster Manager 1.3.6" Start= "auto"

BinPath= "C:\Program Files (x86)\MySQL\MySQL Cluster Manager 1.3.6\bin\mcmd-svc.exe

--defaults-file=\"C:\Program Files (x86)\MySQL\MySQL Cluster Manager 1.3.6\etc\mcmd.ini\""

[SC] CreateService SUCCESS

C:\>
```

This command can be quite long. For enhanced legibility, we have broken it across several lines, but you should always enter it on a single line, allowing it to wrap naturally, similar to what is shown here:




In addition, you should keep in mind that the spaces after the equals signs following the DisplayName, Start, and BinPath arguments are required.


Starting and stopping the MySQL Cluster Manager agent Windows service. After installing the service successfully, you can start and stop the service manually, if the need arises, with the NET START and NET STOP commands, as shown here:



Once the service is installed, the MySQL Cluster Manager agent starts automatically whenever Windows is started. You can verify that the service is running with the Windows Task Manager. Open the Task Manager, and switch to the **Services** tab if it is not already displayed. If the MySQL Cluster Manager agent is running, you can find it in the list of services under MCM in the Name, column and MySQL Cluster Manager 1.3.6 in the Description column, as shown here:



You can also verify if the service is running using the Windows Service Manager, as shown here:



The Service Manager also allows you to start, stop, or pause the MySQL Cluster Manager agent service manually using a GUI.



Note

When first installing the MySQL Cluster Manager agent as a service, the service is not started automatically until Windows is started. If you do not wish to restart Windows, then you must start the service manually using either NET START on the command line or the graphical control provided in the Windows Service Manager.

You can remove the service using the SC DELETE command and the name of the service—in this case MCM—that was used in the SC CREATE command, as shown here:



If the service is running at the time that SC DELETE is executed, the removal of the service takes effect the next time the service is stopped. In such a case, you must stop the previous instance of the service manually, and allow it to be removed, before you can reinstall the service.

Once you have installed the MySQL Cluster Manager agent and the service is running correctly, you are ready to connect to it using the MySQL Cluster Manager client. See Section 3.3, "Starting the MySQL Cluster Manager Client", for information about how to do this.

2.3.3 Setting the MySQL Cluster Manager Agent User Name and Password

Normally it is not necessary to alter the user name or password used by the user agent to administer mysqld processes. However, if you should wish to do so, you can change either or both of these, using the procedure outlined here:

1. Stop all agents. (You can use stop agents for this purpose.)

- 2. Update the etc/mcmd.ini agent configuration file. Set a new password by uncommenting the line containing manager-password= and adding the new password as this value; set a new administrative user account name by uncommenting the line containing manager-username= and setting this to the new user name. See Section 3.1, "mcmd, the MySQL Cluster Manager Agent", for more information about these options.
- 3. For each mysqld do the following:
 - a. Log in (using the mysql client) as the MySQL root user
 - b. If you are changing the user name, do this first, using the following statement, where <code>olduser</code> is the current user name and <code>newuser</code> is the new <code>manager-user</code> that you set previously in <code>etc/mcmd.ini</code>:

```
RENAME USER 'olduser'@'127.0.0.1' TO 'newuser'@'127.0.0.1';
```

If you are changing the user name for the first time, use mcmd for olduser. In addition, you should use 127.0.0.1 for the host name (and not localhost).

c. Execute the following statement, where newuser is the new user name, and newpass is the new password:

```
SET PASSWORD FOR 'newuser'@'127.0.0.1' = PASSWORD('newpass');
```

Use mcmd for the user name if you have not changed it—that is, if manager-user has been left unset in mcmd.ini. Use 127.0.0.1 for the host name (and not localhost).

- d. Issue a FLUSH PRIVILEGES statement.
- 4. Restart the agents. All agents should now be using the new password for the mcmd accounts on the MySQL servers (mysqld processes).

2.4 MySQL Cluster Manager Configuration File

Before starting the MySQL Cluster Manager agent, you should make any necessary changes to the [mcmd] section of the agent configuration file, supplied with MySQL Cluster Manager as etc/mcmd.ini in the installation directory. On Linux and similar operating systems, you can edit this file in place; on Windows, it is recommended that you save a copy of this file to a convenient location for which the path does not contain any spaces, such as C:\mcm\data.

A # character in the MySQL Cluster Manager configuration file indicates the beginning of a comment; the comment continues to the end of the line.

The version of this file that is supplied with MySQL Cluster Manager reads similarly to what is shown here:

```
[mcmd]
plugins=manager

##manager-port=1862

##agent-uuid=
log-file=mcmd.log
log-level=message
##pid-file=
## Username and password for manager plugin
##manager-username=
##manager-password=
```

```
## Top-level directory for manager plugins information stored on disk
##manager-directory=
```

A minimal agent configuration file as used in production might look like this:

```
[mcmd]
plugins=manager
manager-port=1862
manager-directory=/var/opt/mcm-1.3.6
log-file=/var/opt/mcm/mcmd.log
log-level=warning
```

For more information about these and other options which can be set in the agent configuration file, see Section 3.1, "mcmd, the MySQL Cluster Manager Agent".

2.5 Upgrading MySQL Cluster Manager

This section discusses upgrading MySQL Cluster Manager from a previous release to the latest 1.3 release (currently 1.3.6), as well as providing basic guidance on upgrading the bundled MySQL Cluster software.

The basic steps for upgrading a MySQL Cluster Manager installation are listed here:

- 1. Install the new version of the MySQL Cluster Manager software in the desired location.
- 2. Create a configuration for the new installation such that it uses the previous installation's data.
- 3. Stop all running MySQL Cluster Manager agent processes on all hosts.
- 4. Start the new agent processes, ensuring that they use the new configuration created previously.

A more detailed explanation is provided of each of these steps in the next few paragraphs. For purposes of example, we assume an upgrade from an existing installation of MySQL Cluster Manager 1.2.4 to a new installation of MySQL Cluster Manager 1.3.6. For a Linux or other Unix-like system, we assume that these are installed in /opt/mcm-1.2.4 and /opt/mcm-1.3.6, respectively; on Windows, we assume the default directories C:\Program Files\MySQL\MySQL\MySQL Cluster Manager 1.2.4\ and C:\Program Files\MySQL\MySQL Cluster Manager 1.3.6\.

Step 1: Install new MySQL Cluster Manager version. You can obtain and install a new version of MySQL Cluster Manager in the same way as for a new installation (see Section 2.1, "Obtaining MySQL Cluster Manager", and Section 2.3, "MySQL Cluster Manager Installation"), with the additional requirement that you should not attempt to install the new version in the same location as the version which you are currently using.

Step 2: Configure new installation. In order for the new MySQL Cluster Manager agent binaries to manage the same MySQL Cluster instances, they must be able to find the data contained in the agent repository used by the old installation's binaries. This is /opt/mcm_data by default, but can be set using the manager-directory directive in mcmd.ini.

It is simplest for MySQL Cluster Manager software upgrades if the agent repository and the agent configuration file are located externally to the agent installation directory. Suppose the old version of the agent is installed to /opt/mcm-1.2.4, and that it uses the directory /var/opt/mcm for its agent repository and /etc/mcm/mcmd.ini for its configuration file. In this case, to make the new binaries use the same configuration and repository, it is necessary only to start the new mcmd processes such that they use the same configuration file (see Step 4). Otherwise, you should copy the default configuration file to a location outside the installation directory, such as /etc/mcm/mcmd.ini, as shown here:

```
shell> cp -r /opt/mcm-1.2.4/etc/mcmd.ini /etc/mcm/mcmd.ini
```

Then, add the following line to the new copy of the mcmd.ini file:

```
manager-directory=/var/opt/mcm
```

After this, you can save and close the file. See also Section 2.4, "MySQL Cluster Manager Configuration File".

Step 3: Stop all agents. Stop the agent processes using the old binaries on all hosts making up the management installation. You can stop all agents for a given site, for example mysite, using the stop agents command in the MySQL Cluster Manager client, as shown here:

```
mcm> stop agents mysite;
```

You should execute a stop agents command, similar to the one just shown, for each site listed in the output of list sites.

Step 4: Start new MySQL Cluster Manager binaries. Start the new mcmd agent binaries with the --defaults-file option so that it uses the correct configuration file, like this:

```
shell> mcmd --defaults-file=/etc/mcm/mcmd.ini &
```



Note

A majority of the agents (i.e., at least half of the total number plus one) should be started within a period of 10 seconds; otherwise, the lack of a quorum of nodes for decision making might cause the communication among the nodes to break down.

You should now be able to start the mcm client from the new installation and perform management tasks as usual. Once the client successfully starts and connects to the agent, you can verify that it is running the correct version of the MySQL Cluster Manager software using the version command, as shown here:

Next, check that all hosts, clusters, and processes on all sites are visible to the new mcm client, and are operational; for example:

Cluster Package									
mycluster mypackage yourcluster mypackage									
rows in	set	(2.07 s	sec)	'					
cm> show	stati	ısci	luster my	clus	ster;				
Cluster	5	Status		+	Comme		+		
mycluste	er 1	-	operation	+ al	• 		+		
row in s			ec)	+			+		
cm> show	stati	ısci	luster yo	urcl	luster	;			
 Cluster		 Stati	 ıs			mmen			
yourclus	ter	+ fully	y operati	 onal	+ L		+ 		
row in s	 set (().01 se	 ec)		+		+		
cm> show	statı	ıs -r m	mvcluster	· ;					
NodeId			+ Host	+-	Status	+ =	Nodegro	+	Package
			' +	+-		+		+	+
49		_mgmd	tonfisk		running				mypackag
1	ndbo		tonfisk		running		0		mypackag
2	ndbo		flundra		running		0		mypackag
50	mys	-	tonfisk		running				mypackag
51	mys	-	flundra	1	runniı	ng			mypackag
52	ndba	_	*tonfis		added				
53	ndba	api	*flundr	a	added	- 1			
·++									·
		(0.08 8	sec)						
rows in	bee								
		10 -r v	zouralust	er:				+	
rows in		ıs -r <u>y</u>	yourclust	er;	. – – – – -	+			
cm> show			yourclust ++ Host ++		atus	+ No +	degroup	Pa +	ackage
cm> show + NodeId	statı Prod	cess	++ Host ++	Sta		+ No +	degroup	+	+
cm> show	statu Prod	cess 	++ Host ++ alpha	Sta	nning	; 		m∑	+ /package
cm> show + NodeId + 50	stati Prod ndb	cess _mgmd	Host Host alpha beta	Sta run	ning ning	 n/	a	m2 m3 	/package /package
cm> show + NodeId +	statu Prod	cess _mgmd	++ Host ++ alpha	Sta run	nning	; 	a	m2 m3 	+ /package

See Chapter 3, *Using MySQL Cluster Manager*, for more information about performing common cluster management tasks with the mcm client.

Upgrading MySQL Cluster. Although the MySQL Cluster software typically comes bundled with the MySQL Cluster Manager distribution, it is important to keep in mind that upgrading the MySQL Cluster Manager software does *not* upgrade any existing MySQL Cluster installations. Since the new MySQL Cluster Manager installation uses the same configuration as the old one, the clusters under its control remain unchanged. If you wish to upgrade a cluster using the bundled MySQL Cluster software, you should move the cluster directory (see Contents of the MySQL Cluster Manager Unix Distribution Archive) and all of its contents to a location outside the MySQL Cluster Manager installation directory. After this, you can use add package and upgrade cluster to upgrade one or more clusters to the new version of the MySQL Cluster software.

22		

Chapter 3 Using MySQL Cluster Manager

Table of Contents

3.1 mcmd, the MySQL Cluster Manager Agent	23
3.2 Starting and Stopping the MySQL Cluster Manager Agent	31
3.2.1 Starting and Stopping the Agent on Linux	31
3.2.2 Starting and Stopping the MySQL Cluster Manager Agent on Windows	32
3.3 Starting the MySQL Cluster Manager Client	34
3.4 Setting Up MySQL Clusters with MySQL Cluster Manager	37
3.4.1 Creating a MySQL Cluster with MySQL Cluster Manager	37
3.5 Importing MySQL Clusters into MySQL Cluster Manager	39
3.5.1 Importing a Cluster Into MySQL Cluster Manager: Basic Procedure	39
3.5.2 Importing a Cluster Into MySQL Cluster Manager: Example	40
3.6 MySQL Cluster Backup and Restore Using MySQL Cluster Manager	54
3.6.1 Requirements for Backup and Restore	54
3.6.2 Basic MySQL Cluster Backup and Restore Using MySQL Cluster Manager	54
3.7 Backing Up and Restoring MySQL Cluster Manager Agents	58
3.8 Setting Up MySQL Cluster Replication with MySQL Cluster Manager	60

This chapter discusses starting and stopping the MySQL Cluster Manager agent and client, and setting up, backing up, and restoring MySQL Clusters using the MySQL Cluster Manager.

3.1 mcmd, the MySQL Cluster Manager Agent

mcmd is the MySQL Cluster Manager agent program; invoking this executable starts the MySQL Cluster Manager Agent, to which you can connect using the mcm client (see Section 3.3, "Starting the MySQL Cluster Manager Client", and Chapter 4, MySQL Cluster Manager Client Commands, for more information).

You can modify the behavior of the agent in a number of different ways by specifying one or more of the options discussed in this sections. Most of these options can be specified either on the command line or in the agent configuration file (normally etc/mcmd.ini). (Some exceptions include the --defaults-file and --bootstrap options, which, if used, must be specified on the command line, and which are mutually exclusive with one another.) For example, you can set the agent's cluster logging level to warning instead than the default message in either one of the following two ways:

• Include --log-level=warning on the command line when invoking mcmd.



Note

When specifying an agent configuration option on the command line, the name of the option is prefixed with two leading dash characters (--).

• Include the following line in the agent configuration file:

log-level=warning



Note

You can change the logging level at runtime using the ${\tt mcm}$ client change ${\tt log-level}$ command.

When used in the configuration file, the name of the option should not be prefixed with any other characters. Each option must be specified on a separate line. You can comment out all of a given line by inserting a leading hash character (#), like this:

#log-level=warning

You can also comment out part of a line in this way; any text following the # character is ignored, to the end of the current line.

The following table contains a summary of agent options that are read on startup by mcmd. More detailed information about each of these options, such as allowed range of values, can be found in the list following the table.

Table 3.1 MySQL Cluster Manager Agent (mcmd) Option Summary

Format	Description
agent-uuid	Set the agent's UUID; needed only when running multiple agent processes on the same host.
basedir	Directory to use as prefix for relative paths in the configuration
bootstrap	Bootstrap a default cluster on startup.
daemon	Run in daemon mode.
defaults-file	Configuration file to use
event-threads	Number of event handler threads to use.
help	Show application options.
help-all	Show all options (application options and manager module options).
help-manager	Show manager module options.
keepalive	Try to restart mcmd in the event of a crash.
log-backtrace-on-crash	Attempt to load debugger in case of a crash.
log-file	Name of the file to write the log to.
log-level	Set the cluster logging level.
log-use-syslog	Log to syslog.
manager-directory	Directory used for manager data storage.
manager-password	Password used for the manager account.
manager-port	Port for client to use when connecting to manager.
manager-username	User account name to run the manager under.
max-open-files	Maximum number of open files (ulimit -n).
pid-file	Specify PID file (used if running as daemon)
plugin-dir	Directory in which to look for plugins
plugins	Comma-separated list of plugins to load; must include "manager".
verbose-shutdown	Always log the exit code when shutting down.
version	Show the manager version.
xcom-port	Specify the XCOM port.

MySQL Cluster Manager Agent (mcmd) Option Descriptions

The following list contains descriptions of each startup option available for use with mcmd, including allowed and default values. Options noted as boolean need only be specified in order to take effect; you should not try to set a value for these.

• --agent-uuid=uuid

Command-Line Format	agent-uuid=uuid		
Permitted Values Type		string	

Default [set internally]

Set a UUID for this agent. Normally this value is set automatically, and needs to be specified only when running more than one mcmd process on the same host.

• --basedir=dir_name

Command-Line Format	basedir=dir_name			
Permitted Values	Type directory name			
	Default	•		

Directory with path to use as prefix for relative paths in the configuration.

• --bootstrap

Command-Line Format	bootstrap	
Permitted Values	Type boolean	
	Default	true

Start the agent with default configuration values, create a default one-machine cluster named <code>mycluster</code>, and start it. This option works only if no clusters have yet been created. This option is mutually exclusive with the <code>--defaults-file</code> option.

Currently, any data stored in the default cluster mycluster is not preserved between cluster restarts.

• --daemon

Command-Line Format	daemon	
Permitted Values	Type boolean	
	Default	true

Run mcmd as a daemon.

• --defaults-file=filename

Command-Line Format	defaults-file=file_name	
Permitted Values	Type file name	
	Default	etc/mcmd.ini

Set the file from which to read configuration options. The default is etc/mcmd.ini. See Section 2.4, "MySQL Cluster Manager Configuration File", for more information.

• --event-threads=#

Command-Line Format	event-threads=#	
Permitted Values	Туре	numeric
	Default	1
	Min Value	1
	Max Value	[system dependent]

Number of event handler threads to use. The the default is 1, which is sufficient for most normal operations.

• --help, -?

Command-Line Format	help	
Permitted Values	Type boolean	
	Default	true

mcmd help output is divided into *Application* and *Manager* sections. When used with mcmd, --help causes the *Application* options to be shown, as shown here:

```
shell> mcmd --help
Usage:
 mcmd [OPTION...] - MySQL Cluster Manager
Help Options:
  -?, --help
                                     Show help options
  --help-all
                                      Show all help options
  --help-manager
                                     Show options for the manager-module
Application Options:
  -V, --version
                                     Show version
  --defaults-file=<file>
                                     configuration file
                                     Always log the exit code when shutting down
  --verbose-shutdown
  --daemon
                                     Start in daemon-mode
  --basedir=<absolute path>
                                     Base directory to prepend to relative paths in the config
                                     PID file in case we are started as daemon
  --pid-file=<file>
  --plugin-dir=<path>
                                    Path to the plugins
                                    Plugins to load
  --plugins=<name>
  --log-level=<string>
                                     Log all messages of level ... or higher
                                    Log all messages in a file
  --log-file=<file>
  --log-use-syslog
                                     Log all messages to syslog
  --log-backtrace-on-crash
                                     Try to invoke debugger on crash
  --keepalive
                                      Try to restart mcmd if it crashed
  --max-open-files
                                      Maximum number of open files (ulimit -n)
  --event-threads
                                     Number of event-handling threads (default: 1)
```

• --help-all

Command-Line Format	help-all	
Permitted Values	Type boolean	
	Default	true

mcmd help output is divided into *Application* and *Manager* sections. When used with --help-all, mcmd displays both the *Application* and the *Manager* options, like this:

```
> mcmd --help-all
Usage:
 mcmd [OPTION...] - MySQL Cluster Manager
Help Options:
                                      Show help options
  --help-all
                                     Show all help options
  --help-manager
                                     Show options for the manager-module
manager-module
  --manager-port=<clientport>
                                   Port to manage the cluster (default: 1862)
                                     Xcom port (default: 18620)
  --xcom-port=<xcomport>
                                      Username to manage the cluster (default: mcmd)
  --manager-username=<username>
                                      Password for the manager user-account (default: super)
  --manager-password=<password>
  --bootstrap
                                      Bootstrap a default cluster on initial startup
  --manager-directory=<directory>
                                     Path to managers config information
Application Options:
  -V, --version
                                      Show version
  --defaults-file=<file>
                                      configuration file
```

```
--verbose-shutdown
                                    Always log the exit code when shutting down
--daemon
                                    Start in daemon-mode
--basedir=<absolute path>
                                    Base directory to prepend to relative paths in the config
--pid-file=<file>
                                    PID file in case we are started as daemon
--plugin-dir=<path>
                                   Path to the plugins
--plugins=<name>
                                   Plugins to load
--log-level=<string>
                                    Log all messages of level \dots or higher
--log-file=<file>
                                   Log all messages in a file
--log-use-syslog
                                   Log all messages to syslog
--log-backtrace-on-crash
                                    Try to invoke debugger on crash
                                    Try to restart mcmd if it crashed
--keepalive
--max-open-files
                                    Maximum number of open files (ulimit -n)
                                    Number of event-handling threads (default: 1)
--event-threads
```

• --help-manager

Command-Line Format	help-manager	
Permitted Values	Type boolean	
	Default	true

mcmd help output is divided into *Application* and *Manager* sections. When used with --help-manager, mcmd displays the *Manager* options, like this:

• --keepalive

Command-Line Format	keepalive	
Permitted Values	Type boolean	
	Default	true

Use this option to cause mcmd to attempt to restart in the event of a crash.

--log-backtrace-on-crash

Command-Line Format	log-backtrace-on-crash	
Permitted Values	Type boolean	
	Default	true

Attempt to load the debugger in the event of a crash. Not normally used in production.

• --log-file=filename

Command-Line Format	log-file=file	
Permitted Values	Type file name	
	Default	mcmd.log

Set the name of the file to write the log to. The default is mcmd.log in the installation directory. On Linux and other Unix-like platforms, you can use a relative path; this is in relation to the MySQL Cluster Manager installation directory, and not to the bin or etc subdirectory. On Windows, you

must use an absolute path, and it cannot contain any spaces; in addition, you must replace any backslash (\setminus) characters in the path with forward slashes (/).

• --log-level=*leve1*

Command-Line Format	log-level=level	
Permitted Values	Туре	enumeration
	Default	message
	Valid Values	message
		debug
		critical
		error
		info
		warning

Sets the cluster log event severity level; see MySQL Cluster Logging Management Commands, for definitions of the levels, which are the same as these except that ALERT is mapped to critical and the Unix syslog LOG_NOTICE level is used (and mapped to message). For additional information, see Event Reports Generated in MySQL Cluster.

Possible values for this option are (any one of) debug, critical, error, info, message, and warning. message is the default.

You should be aware that the debug, message, and info levels can result in rapid growth of the agent log, so for normal operations, you may prefer to set this to warning or error.

You can also change the cluster logging level at runtime using the change log-level command in the mcm client. The option applies its setting to all hosts running on all sites, whereas change log-level is more flexible; its effects can be constrained to a specific management site, or to one or more hosts within that site.

• --log-use-syslog

Command-Line Format	log-use-syslog	
Permitted Values	Type boolean	
	Default	true

Write logging output to syslog.

• --manager-directory=dir name

Command-Line Format	manager-directory=dir	
Permitted Values	Type directory name	
	Default	/opt/mcm_data

Set the location of the agent repository, which contains collections of MySQL Cluster Manager data files and MySQL Cluster configuration and data files. The value must be a valid absolute path. On Linux, if the directory does not exist, it is created; on Windows, the directory must be created if it does not exist. additionally on Windows, the path may not contain any spaces or backslash (\) characters; backslashes must be replaced with forward slashes (/).

The default location is /opt/mcm_data. If you change the default, you should use a standard location external to the MySQL Cluster Manager installation directory, such as /var/opt/mcm on Linux.

In addition to the MySQL Cluster Manager data files, the manager-directory also contains a rep directory in which MySQL Cluster data files for each MySQL Cluster under MySQL Cluster Manager control are kept. Normally, there is no need to interact with these directories beyond specifying the location of the manager-directory in the agent configuration file (mcmd.ini).

However, in the event that an agent reaches an inconsistent state, it is possible to delete the contents of the rep directory, in which case the agent attempts to recover its repository from another agent. In such cases, you must also delete the repchksum checksum file from the manager-directory. Otherwise, the agent reads this file and raises a checksum error due to the now-empty rep directory.

• --manager-password=password

Command-Line Format	manager-password=password	
Permitted Values	Type string	
	Default	super

Set a password to be used for the manager agent user account. The default is super.

Using this option together with manager-username causes the creation of a MySQL user account, having the username and password specified using these two options. This account is created with all privileges on the MySQL server including the granting of privileges. In other words, it is created as if you had executed GRANT ALL PRIVILEGES ON *.* ... WITH GRANT OPTION in the mysql client.

• --manager-port=#

Command-Line Format	manager-port=port	
Permitted Values	Type numeric	
	Default	localhost:1862

Specify the port used by MySQL Cluster Manager client connections. Any valid TC/IP port number can be used. Normally, there is no need to change it from the default value (1862).

Previously, this option could optionally take a host name in addition to the port number, but in MySQL Cluster Manager 1.1.1 and later the host name is no longer accepted.

• --manager-username=user_name

Command-Line Format	manager-username=name	
Permitted Values	Type string	
	Default	mcmd

Set a user name for the MySQL account to be used by the MySQL Cluster Manager agent. The default is memd.

When used together with manager-password, this option also causes the creation of a new MySQL user account, having the user name and password specified using these two options. This account is created with all privileges on the MySQL server including the granting of privileges. In other words, it is created as if you had executed GRANT ALL PRIVILEGES ON *.* ... WITH GRANT OPTION in the mysql client. The existing MySQL root account is not altered in such cases, and the default test database is preserved.

• --max-open-files=#

Command-Line Format	max-open-files=#

Permitted Values	Туре	numeric
	Default	1
	Min Value	1
	Max Value	[system dependent]

Set the maximum number of open files (as with ulimit -n).

• --pid-file=file

Command-Line Format	pid-file=file_name	
Permitted Values	Type file name	
	Default	mcmd.pid

Set the name and path to a process ID (.pid) file. Not normally used or needed. This option is not supported on Windows systems.

• --plugin-dir

Command-Line Format	plugin-dir=dir_name	
Permitted Values	Type directory name	
	Default	lib/mcmd

Set the directory to search for plugins. The default is lib/mcmd, in the MySQL Cluster Manager installation directory; normally there is no need to change this.

• --plugins

Command-Line Format	plugins=list	
Permitted Values	Type directory name	
	Default	

Specify a list of plugins to be loaded on startup. To enable MySQL Cluster Manager, this list must include manager (the default value). For other possibilities, see MySQL Proxy; however, you should be aware that we currently do not test MySQL Cluster Manager with any values for plugins other than manager. For this reason we recommend using the default the value in a production setting.

• --verbose-shutdown

Command-Line Format	verbose-shutdown	
Permitted Values	Туре	boolean
	Default	true

Force mcmd to log the exit code whenever shutting down, regardless of the reason.

• --version, -V

Command-Line Format	version	
Permitted Values	Type boolean	
	Default	true

Display version information and exit. Output may vary according to the MySQL Cluster Manager software version, operating platform, and versions of libraries used on your system, but should

closely resemble what is shown here, with the first line of output containing the MySQL Cluster Manager release number (emphasized text):

```
shell> mcmd -V
MySQL Cluster Manager 1.3.6 (64bit)
  chassis: mysql-proxy 0.8.3
  glib2: 2.16.6
  libevent: 1.4.13-stable
-- modules
  manager: 1.3.6
```

• --xcom-port

Command-Line Format	xcom-port=port				
Permitted Values	Туре	numeric			
	Default	18620			

Allows you to specify the XCOM port. The default in 18620.

3.2 Starting and Stopping the MySQL Cluster Manager Agent

Before you can start using MySQL Cluster Manager to create and manage a MySQL Cluster, the MySQL Cluster Manager agent must be started on each computer that is intended to host one or more nodes in the MySQL Cluster to be managed.

The MySQL Cluster Manager agent employs a MySQL user account for administrative access to <code>mysqld</code> processes. It is possible, but not a requirement, to change the default user name, the default password used for this account, or both. For more information, see Section 2.3.3, "Setting the MySQL Cluster Manager Agent User Name and Password".

3.2.1 Starting and Stopping the Agent on Linux

To start the MySQL Cluster Manager agent on a given host running a Linux or similar operating system, you should run mcmd, found in the bin directory within the manager installation directory on that host. Typical options used with mcmd are shown here:

```
mcmd [--defaults-file | --bootstrap] [--log-file] [--log-level]
```

See Section 3.1, "mcmd, the MySQL Cluster Manager Agent", for information about additional options that can be used when invoking mcmd from the command line, or in a configuration file.

mcmd normally runs in the foreground. If you wish, you can use your platform's usual mechanism for backgrounding a process. On a Linux system, you can do this by appending an ampersand character (&), like this (not including any options that might be required):

```
shell> ./bin/mcmd &
```

By default, the agent assumes that the agent configuration file is etc/mcmd.ini, in the MySQL Cluster Manager installation directory. You can tell the agent to use a different configuration file by passing the path to this file to the --defaults-file option, as shown here:

```
shell> ./bin/mcmd --defaults-file=/home/mcm/mcm-agent.conf
```

The --bootstrap option causes the agent to start with default configuration values, create a default one-machine cluster named mycluster, and start it. This option works only if no cluster has yet created, and is mutually exclusive with the --defaults-file option. Currently, any data stored in the default cluster mycluster is not preserved between cluster restarts; this is a known issue which we may address in a future release of MySQL Cluster Manager.

The use of the --bootstrap option with mcmd is shown here on a system having the host name torsk, where MySQL Cluster Manager has been installed to /home/jon/mcm:

```
shell> ./mcmd --bootstrap
MySQL Cluster Manager 1.3.6 started
Connect to MySQL Cluster Manager by running "/home/jon/mcm/bin/mcm" -a torsk:1862
Configuring default cluster 'mycluster'...
Starting default cluster 'mycluster' ...
Cluster 'mycluster' started successfully
       ndb_mgmd
                        torsk:1186
       ndbd
                        torsk
       ndbd
                        torsk
       mysqld
                       torsk:3306
       mysqld
                       torsk:3307
        ndbapi
Connect to the database by running "/home/jon/mcm/cluster/bin/mysql" -h torsk -P 3306 -u root
```

You can then connect to the agent using the mcm client (see Section 3.3, "Starting the MySQL Cluster Manager Client"), and to either of the MySQL Servers running on ports 3306 and 3307 using mysql or another MySQL client application.

The --log-file option allows you to override the default location for the agent log file (normally mcmd.log, in the MySQL Cluster Manager installation directory).

You can use --log-level option to override the log-level set in the agent configuration file.

See Section 3.1, "mcmd, the MySQL Cluster Manager Agent", for more information about options that can be used with mcmd.

The MySQL Cluster Manager agent must be started on each host in the MySQL Cluster to be managed.

To stop one or more instances of the MySQL Cluster Manager agent, use the stop agents command in the MySQL Cluster Manager client. If the client is unavailable, you can stop each agent process using the system's standard method for doing so, such as ^C or kill.

You can also set the agent up as a daemon or service on Linux and other Unix-like systems. (See Section 2.3.1, "Installing MySQL Cluster Manager on Unix Platforms".) If you also want data node failed processes from a running MySQL Cluster to be started when the agent fails and restarts in such cases, you must make sure that StopOnError is set to 0 on each data node (and not to 1, the default).

3.2.2 Starting and Stopping the MySQL Cluster Manager Agent on Windows

To start the MySQL Cluster Manager agent manually on a Windows host, you should invoke mcmd.exe, found in the bin directory under the manager installation directory on that host. By default, the agent uses etc/mcmd.ini in the MySQL Cluster Manager installation directory as its configuration file; this can be overridden by passing the desired file's location as the value of the --defaults-file option.

Typical options for mcmd are shown here:

```
mcmd[.exe] [--defaults-file | --bootstrap] [--log-file] [--log-level]
```

For information about additional options that can be used with mcmd on the command line or in an option file, see Section 3.1, "mcmd, the MySQL Cluster Manager Agent".

By default, the agent assumes that the agent configuration file is etc/mcmd.ini, in the MySQL Cluster Manager installation directory. You can tell the agent to use a different configuration file by passing the path to this file to the --defaults-file option, as shown here:

```
C:\Program Files (x86)\MySQL\MySQL Cluster Manager 1.1.4\bin>
mcmd --defaults-file="C:\Program Files (x86)\MySQL\MySQL Cluster
```

Manager 1.3.6\etc\mcmd.ini"

The --bootstrap option causes the agent to start with default configuration values, create a default one-machine cluster named mycluster, and start it. The use of this option with mcmd is shown here on a system having the host name torsk, where MySQL Cluster Manager has been installed to the default location:

```
C:\Program Files (x86)\MySOL\MySOL Cluster Manager 1.3.6\bin>mcmd --bootstrap
MySQL Cluster Manager 1.3.6 started
Connect to MySQL Cluster Manager by running "C:\Program Files (x86)\MySQL\MySQL
Cluster Manager 1.3.6\bin\mcm" -a TORSK:1862
Configuring default cluster 'mycluster'...
Starting default cluster 'mycluster'...
Cluster 'mycluster' started successfully
        ndb_mgmd
                       TORSK:1186
       ndbd
                       TORSK
        ndbd
                        TORSK
                        TORSK: 3306
       mysqld
       mysqld
                        TORSK:3307
       ndbapi
Connect to the database by running "C:\Program Files (x86)\MySQL\MySQL Cluster
Manager 1.3.6\cluster\bin\mysql" -h TORSK -P 3306 -u root
```

You can then connect to the agent using the mcm client (see Section 3.3, "Starting the MySQL Cluster Manager Client"), and to either of the MySQL Servers running on ports 3306 and 3307 using mysql or another MySQL client application.

When starting the MySQL Cluster Manager agent for the first time, you may see one or more Windows **Security Alert** dialogs, such as the one shown here:



You should grant permission to connect to private networks for any of the programs mcmd.exe, ndb_mgmd.exe, ndbd.exe, ndbmtd.exe, or mysqld.exe. To do so, check the **Private Networks...** box and then click the Allow access button. It is generally not necessary to grant MySQL Cluster Manager or MySQL Cluster access to public networks such as the Internet.



Note

The --defaults-file and --bootstrap options are mutually exclusive.

The --log-file option allows you to override the default location for the agent log file (normally mcmd.log, in the MySQL Cluster Manager installation directory).

You can use --log-level option to override the log-level set in the agent configuration file.

See Section 3.1, "mcmd, the MySQL Cluster Manager Agent", for more information about options that can be used with mcmd.

The MySQL Cluster Manager agent must be started on each host in the MySQL Cluster to be managed.

It is possible to install MySQL Cluster Manager as a Windows service, so that it is started automatically each time Windows starts. See Section 2.3.2.1, "Installing the MySQL Cluster Manager Agent as a Windows Service".

To stop one or more instances of the MySQL Cluster Manager agent, use the stop agents command in the MySQL Cluster Manager client. You can also stop an agent process using the Windows Task Manager. In addition, if you have installed MySQL Cluster Manager as a Windows service, you can stop (and start) the agent using the Windows Service Manager, CTRL-C, or the appropriate NET STOP (or NET START) command. See Starting and stopping the MySQL Cluster Manager agent Windows service, for more information about each of these options.

3.3 Starting the MySQL Cluster Manager Client

This section covers starting the MySQL Cluster Manager client and connecting to the MySQL Cluster Manager agent.

MySQL Cluster Manager 1.3.6 includes a command-line client mcm, located in the installation bin directory. mcm can be invoked with any one of the options shown in the following table:

Long form	Short form	Description
help	-3	Display mcm client options
version	-V	Shows MySQL Cluster Manager agent/client version.
_	-W	Shows MySQL Cluster Manager agent/client version, with version of mysql used by mcm.
address	-a	Host and optional port to use when connecting to mcmd, in host[:port] format; default is 127.0.0.1:1862.
mysql-help	-I	Show help for mysql client (see following).

The client-server protocol used by MySQL Cluster Manager is platform-independent. You can connect to any MySQL Cluster Manager agent with an mcm client on any platform where it is available. This means, for example, that you can use an mcm client on Microsoft Windows to connect to a MySQL Cluster Manager agent that is running on a Linux host.

mcm actually acts as a wrapper for the mysql client that is included with the bundled MySQL Cluster distribution. Invoking mcm with no options specified is equivalent to the following:

```
shell> mysql -umcmd -psuper -h 127.0.0.1 -P 1862 --prompt="mcm>"
```

(These -u and -p options and values are hard-coded and cannot be changed.) This means that you can use the mysql client to run MySQL Cluster Manager client sessions on platforms where mcm itself (or even mcmd) is not available. For more information, see Connecting to the agent using the mysql client.

If you experience problems starting an MySQL Cluster Manager client session because the client fails to connect, see Can't connect to [local] MySQL server, for some reasons why this might occur, as well as suggestions for some possible solutions.

To end a client session, use the exit or quit command (short form: \q). Neither of these commands requires a separator or terminator character.

For more information, see Chapter 4, MySQL Cluster Manager Client Commands.

Connecting to the agent with the mcm client. You can connect to the MySQL Cluster Manager agent by invoking mcm (or, on Windows, mcm.exe). You may also need to specify a hostname, port number, or both, using the following command-line options:

• --host=hostname or -h[]hostname

This option takes the name or IP address of the host to connect to. The default is localhost (which may not be recongized on all platforms when starting a mcm client session even if it works for starting mysql client sessions).

You should keep in mind that the mcm client does not perform host name resolution; any name resolution information comes from the operating system on the host where the client is run. For this reason, it is usually best to use a numeric IP address rather than a hostname for this option.

• --port=portnumber or -P[]portnumber

This option specifies the TCP/IP port for the client to use. This must be the same port that is used by the MySQL Cluster Manager agent. As mentioned eslewhere, if no agent port is specified in the MySQL Cluster Manager agent configuration file (mcmd.ini), the default number of the port used by the MySQL Cluster Manager agent is 1862, which is also used by default by mcm.

mcm accepts additional mysql client options, some of which may possibly be of use for MySQL Cluster Manager client sessions. For example, the --pager option might prove helpful when the output of get contains too many rows to fit in a single screen. The --prompt option can be used to provide a distinctive prompt to help avoid confusion between multiple client sessions. However, options not shown in the current manual have not been extensively tested with mcm and so cannot be guaranteed to work correctly (or even at all). See mysql Options, for a complete listing and descriptions of all mysql client options.



Note

Like the ${\tt mysql}$ client, ${\tt mcm}$ also supports ${\tt \ G}$ as a statement terminator which causes the output to be formatted vertically. This can be helpful when using a terminal whose width is restricted to some number of (typically 80) characters. See Chapter 4, ${\tt MySQL}$ Cluster Manager Client Commands, for examples.

Connecting to the agent using the mysql client. As mentioned previously, mcm actually serves as a wrapper for the mysql client. In fact, a mysql client from any recent MySQL distribution (MySQL 5.1 or later) should work without any issues for connecting to mcmd. In addition, since the client-server protocol used by MySQL Cluster Manager is platform-independent, you can use a mysql client on any platform supported by MySQL. (This means, for example, that you can use a mysql client on Microsoft Windows to connect to a MySQL Cluster Manager agent that is running on a Linux host.) Connecting to the MySQL Cluster Manager agent using the mysql client is accomplished by invoking mysql and specifying a hostname, port number, username and password, using the following command-line options:

• --host=hostname or -h[]hostname

This option takes the name or IP address of the host to connect to. The default is localhost. Like the mcm client, the mysql client does not perform host name resolution, and relies on the host operating system for this task. For this reason, it is usually best to use a numeric IP address rather than a hostname for this option.

• --port=portnumber or -P[]portnumber

This option specifies the TCP/IP port for the client to use. This must be the same port that is used by the MySQL Cluster Manager agent. Although the default number of the port used by the MySQL Cluster Manager agent is 1862 (which is also used by default by mcm), this default value is not known to the mysql client, which uses port 3306 (the default port for the MySQL server) if this option is not specified when mysql is invoked.

Thus, you *must* use the --port or -P option to connect to the MySQL Cluster Manager agent using the mysql client, even if the agent process is using the MySQL Cluster Manager default port, and even if the agent process is running on the same host as the mysql client. Unless the correct agent port number is supplied to it on startup, mysql is unable to connect to the agent.

• --user=username or -u[]username

Specifies the username for the user trying to connect. Currently, the only user permitted to connect is "mcmd"; this is hard-coded into the agent software and cannot be altered by any user. By default, the mysql client tries to use the name of the current system user on Unix systems and "ODBC" on Windows, so you *must* supply this option and the username "mcmd" when trying to access the MySQL Cluster Manager agent with the mysql client; otherwise, mysql cannot connect to the agent.

• --password[=password] or -p[password]

Specifies the password for the user trying to connect. If you use the short option form (-p), you *must not* leave a space between this option and the password. If you omit the *password* value following the --password or -p option on the command line, the mysql client prompts you for one.

Specifying a password on the command line should be considered insecure. It is preferable that you either omit the password when invoking the client, then supply it when prompted, or put the password in a startup script or configuration file.

Currently, the password is hard-coded as "super", and cannot be changed or overridden by MySQL Cluster Manager users. Therefore, if you do not include the --password or -p option when invoking mysql, it cannot connect to the agent.

In addition, you can use the --prompt option to set the mysql client's prompt. This is recommended, since allowing the default prompt (mysql>) to be used could lead to confusion between a MySQL Cluster Manager client session and a MySQL client session.

Thus, you can connect to a MySQL Cluster Manager agent by invoking the mysql client on the same machine from the system shell in a manner similar to what is shown here.

```
shell> mysql -h127.0.0.1 -P1862 -umcmd -p --prompt='mcm> '
```

For convenience, on systems where mcm itself is not available, you might even want to put this invocation in a startup script. On a Linux or similar system, this script might be named mcm-client.sh, with contents similar to what is shown here:

```
#!/bin/sh
/usr/local/mysql/bin/mysql -h127.0.0.1 -P1862 -umcmd -p --prompt='mcm> '
```

In this case, you could then start up a MySQL Cluster Manager client session using something like this in the system shell:

```
shell> ./mcm-client
```

On Windows, you can create a batch file with a name such as mcm-client.bat containing something like this:

```
C:\mysql\bin\mysql.exe -umcmd -psuper -h localhost -P 1862 --prompt="mcm> "
```

(Adjust the path to the mysql. exe client executable as necessary to match its location on your system.)

If you save this file to a convenient location such as the Windows desktop, you can start a MySQL Cluster Manager client session merely by double-clicking the corresponding file icon on the desktop (or in Windows Explorer); the client session opens in a new cmd. exe (DOS) window.

3.4 Setting Up MySQL Clusters with MySQL Cluster Manager

This section provides basic information about setting up a new MySQL Cluster with MySQL Cluster Manager. It also supplies guidance on migration of an existing MySQL Cluster to MySQL Cluster Manager.

For more information about obtaining and installing the MySQL Cluster Manager agent and client software, see Chapter 2, MySQL Cluster Manager Installation, Configuration, Cluster Setup.

See Chapter 4, MySQL Cluster Manager Client Commands, for detailed information on the MySQL Cluster Manager client commands shown in this chapter.

3.4.1 Creating a MySQL Cluster with MySQL Cluster Manager

In this section, we discuss the procedure for using MySQL Cluster Manager to create and start a new MySQL Cluster. We assume that you have already obtained the MySQL Cluster Manager and MySQL Cluster software, and that you are already familiar with installing MySQL Cluster Manager (see Chapter 2, MySQL Cluster Manager Installation, Configuration, Cluster Setup).

MySQL Cluster Manager 1.3.0 and later also supports importing existing, standalone MySQL Clusters; for more information, see Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager".

We also assume that you have identified the hosts on which you plan to run the cluster and have decided on the types and distributions of the different types of nodes among these hosts, as well as basic configuration requirements based on these factors and the hardware characteristics of the host machines.



Note

You can create and start a MySQL Cluster on a single host for testing or similar purposes, simply by invoking memd with the --bootstrap option. See Section 3.2, "Starting and Stopping the MySQL Cluster Manager Agent".

Creating a new cluster consists of the following tasks:

- MySQL Cluster Manager agent installation and startup. Install the MySQL Cluster Manager software distribution, make any necessary edits of the agent configuration files, and start the agent processes as explained in Chapter 2, MySQL Cluster Manager Installation, Configuration, Cluster Setup. Agent processes must be running on all cluster hosts before you can create a cluster. This means that you need to place a complete copy of the MySQL Cluster Manager software distribution on every host. The MySQL Cluster Manager software does not have to be in a specific location, or even the same location on all hosts, but it must be present; you cannot manage any cluster processes hosted on a computer where mcmd is not also running.
- MySQL Cluster Manager client session startup. Starting the MySQL Cluster Manager client and connect to the MySQL Cluster Manager agent. You can connect to an agent process running

on any of the cluster hosts, using the mcm client on any computer that can establish a network connection to the desired host. See Section 3.3, "Starting the MySQL Cluster Manager Client", for details

On systems where mcm is not available, you can use the mysql client for this purpose. See Connecting to the agent using the mysql client.

• MySQL Cluster software deployment. The simplest and easiest way to do this is to copy the complete MySQL Cluster distribution to the same location on every host in the cluster. (If you have installed MySQL Cluster Manager 1.3.6 on each host, the MySQL Cluster NDB 7.2.4 distribution is already included, in mcm_installation_dir/cluster.) If you do not use the same location on every host, be sure to note it for each host. Do not yet start any MySQL Cluster processes or edit any configuration files; when creating a new cluster, MySQL Cluster Manager takes care of these tasks automatically.

On Windows hosts, you should *not* install as services any of the MySQL Cluster node process programs, including ndb_mgmd.exe, ndbd.exe, ndbmtd.exe, and mysqld.exe. MySQL Cluster Manager manages MySQL Cluster processes independently of the Windows Service Manager and does not interact with the Service Manager or any Windows services when doing so.



Note

You can actually perform this step at any time up to the point where the software package is registered (using add_package). However, we recommend that you have all required software—including the MySQL Cluster software—in place before executing any MySQL Cluster Manager client commands.

- Management site definition. Using the create site command in the MySQL Cluster Manager client, define a MySQL Cluster Manager management site—that is, the set of hosts to be managed. This command provides a name for the site, and must reference all hosts in the cluster. Section 4.2.6, "The create site Command", provides syntax and other information about this command. To verify that the site was created correctly, use the MySQL Cluster Manager client commands list sites and list hosts.
- MySQL Cluster software package registration. In this step, you provide the location of the MySQL Cluster software on all hosts in the cluster using one or more add package commands. To verify that the package was created correctly, use the list packages and list processes commands.
- Cluster definition. Execute a create cluster command to define the set of MySQL Cluster nodes (processes) and hosts on which each cluster process runs, making up a the MySQL Cluster. This command also uses the name of the package registered in the previous step so that MySQL Cluster Manager knows the location of the binary running each cluster process. You can use the list clusters and list processes commands to determine whether the cluster has been defined as desired.

If you wish to use SQL node connection pooling, see Setup for mysqld connection pooling before creating the cluster.

- Initial configuration. Perform any configuration of the cluster that is required or desired prior to starting it. You can set values for MySQL Cluster Manager configuration attributes (MySQL Cluster parameters and MySQL Server options) using the MySQL Cluster Manager client set command. You do not need to edit any configuration files directly—in fact, you should *not* do so. Keep in mind that certain attributes are read-only, and that some others cannot be reset after the cluster has been started for the first time. You can use the get command to verify that attributes have been set to the correct values.
- **Cluster startup.** Once you have completed the previous steps, including necessary or desired initial configuration, you are ready to start the cluster. The start cluster command starts all

cluster processes in the correct order. You can verify that the cluster has started and is running normally after this command has completed, using the MySQL Cluster Manager client command show status. At this point, the cluster is ready for use by MySQL Cluster applications.

3.5 Importing MySQL Clusters into MySQL Cluster Manager

It is possible to bring a "wild" MySQL Cluster—that is, a cluster not created using MySQL Cluster Manager—under the control of MySQL Cluster Manager. The following sections provide an outline of the procedure required to import such a cluster into MySQL Cluster Manager, followed by a more detailed example.

3.5.1 Importing a Cluster Into MySQL Cluster Manager: Basic Procedure

The importation process consists generally of following the steps listed here:

- 1. Create and configure in MySQL Cluster Manager a "target" cluster whose configuration matches that of the "wild" cluster.
- 2. Prepare the "wild" cluster for migration.
- 3. Verify PID files for cluster processes.
- 4. Perform a test run, and then execute the import cluster command.

This expanded listing breaks down each of the tasks just mentioned into smaller steps; an example with more detail is also provided following the listing.

- 1. Create and configure "target" cluster under MySQL Cluster Manager control
 - a. Install MySQL Cluster Manager and start mcmd on all hosts; see Section 2.3, "MySQL Cluster Manager Installation", for more information.
 - b. Create a MySQL Cluster Manager site encompassing these hosts, using the create site command.
 - c. Add a MySQL Cluster Manager package referencing the MySQL Cluster binaries, using the add package command. Use this command's --basedir option to point to the correct location.
 - d. Create the target cluster using the create cluster command, including the same processes and hosts used by the wild cluster. Use the command's --import option to specify that the cluster is a target for import.

If the wild cluster adheres to the recommendation for node ID assignments given in the description for the create cluster command (that is, having node ID 1 to 48 assigned to data nodes, and 49 and above assigned to other node types), you need not specify the node IDs for the processes in the create cluster command.

Also, this step may be split into a create cluster command followed by one or more add process commands (see an example of such splitting in the description for the add process command).

e. MySQL Cluster Manager 1.3.1 and later. Use import config to copy the wild cluster's configuration data into the target cluster. Use this command's --dryrun option (short form: - y) to perform a test run that merely logs the configuration information that the command copies when it is executed without the option.

If any ndb_mgmd or mysqld processes in the wild cluster are running on ports other than the default, you must perform set commands to assign the correct port numbers for these in the target cluster. When all such processes are running on the correct ports, you can execute import config (without the --dryrun option) to copy the wild cluster's configuration data.

Following this step, you should check the log as well as the configuration of the target cluster to ensure that all configuration attribute values were copied correctly and with the correct scope. Correct any inconsistencies with the wild cluster's configuration using the appropriate set commands.

MySQL Cluster Manager 1.3.0: Since import config is not supported prior to the MySQL Cluster Manager 1.3.1 release, you must copy the wild cluster's configuration information to the target cluster manually, issuing set commands in the mcm client that duplicate the wild cluster's configuration in the target cluster, as discussed in the paragraphs immediately following.

MySQL Cluster global configuration data is stored in a file on the management node host which is usually (but not always) named <code>config.ini</code>. This global configuration file uses INI format which makes it simple to read or parse. For more information about this file, see MySQL Cluster Configuration Files, and MySQL Cluster Configuration: Basic Example

In addition, each mysqld process (SQL node) has its own configuration data in the form of system variables which are specific to that mysqld, and many of which can be changed at runtime. You can check their values using the SQL SHOW VARIABLES statement, and execute appropriate set commands for values differing from their defaults.

2. Prepare the "wild" cluster for migration

- a. Create a MySQL user named mcmd on each SQL node, and grant root privileges to this user.
- b. Kill each data node angel process using your system's facility for doing so. Do not kill any non-angel data node daemons.
- c. Kill and restart each management node process. When restarting ndb_mgmd, be sure to do so with the configuration cache disabled. Since the configuration cache is enabled by default, you must start the management node with --config-cache=false to deactivate it.
- d. Any cluster processes that are under the control of the system's boot-time process management facility, such as /etc/init.d on Linux systems or the Services Manager on Windows platforms, should be removed from its control.
- e. It is highly recommended that you take a complete backup of the "wild" cluster before proceeding any further, using the ndb_mgm client. For more information, see Using The MySQL Cluster Management Client to Create a Backup.
- 3. Verify cluster process PID files.
 - a. Verify that each process in the "wild" cluster has a valid PID file.
 - b. If a given process does not have a valid PID file, you must create one for it.

See Section 3.5.2.3, "Verify All Cluster Process PID Files", for a more detailed explanation and examples.

- 4. Test and perform migration of "wild" cluster.
 - a. Perform a test run of the proposed migration using import cluster with the --dryrun option, which causes MySQL Cluster Manager to check for errors, but not actually migrate any processes or data.
 - b. Correct any errors found using --dryrun. Repeat the dry run from the previous step to ensure that no errors were missed.
 - c. When the dry run no longer reports any errors, you can perform the migration using import cluster, but without the --dryrun option.

3.5.2 Importing a Cluster Into MySQL Cluster Manager: Example

As discussed previously (see Section 3.5.1, "Importing a Cluster Into MySQL Cluster Manager: Basic Procedure"), importing a standalone or "wild" cluster that was created without the use of MySQL Cluster Manager into the manager requires the completion of four major tasks: create a cluster in MySQL Cluster Manager and update its configuration such that this matches that of the "wild" cluster; prepare the "wild" cluster for MySQL Cluster Manager control; verify all PID files for cluster processes; and performing a dry run and then the actual import using the import cluster command. The example provided over the next few sections shows all steps required to perform the importation of a small, standalone MySQL Cluster into MySQL Cluster Manager.

Sample cluster used in example. The "wild" cluster used in this example consists of four nodes —one management node, one SQL node, and two data nodes running ndbd. Each of these nodes resides on one of four hosts, all of which are running a recent server release of a typical Linux distribution. The host names for each of these hosts is shown in the following table:

Node type (executable)	Host name
Management node (ndb_mgmd)	alpha
Data node (ndbd)	beta
Data node (ndbd)	gamma
SQL node (mysqld)	delta

We assume that these hosts are on a dedicated network or subnet, and that each of them is running only the MySQL Cluster binaries and applications providing required system and network services. We assume on each host that the MySQL Cluster software has been installed from a release binary archive (see Installing a MySQL Cluster Binary Release on Linux). We also assume that management node is using /var/lib/mysql-cluster/config.ini as the cluster's global configuration file, which is shown here:

```
[ndbd default]
DataMemory= 16G
IndexMemory= 12G
NoOfReplicas= 2
[ndb mamd]
HostName=alpha
NodeId=50
[ndbd]
NodeTd=5
HostName=beta
DataDir=/var/lib/mysql-cluster
[ndbd]
NodeTd=6
HostName=gamma
DataDir=/var/lib/mysql-cluster
[mvsald]
NodeId=100
HostName=delta
[ndbapi]
NodeId=101
```

The objective for this example is to bring this cluster, including all of its processes and data, under MySQL Cluster Manager control. This configuration also provides for a "free" SQL node or NDB API application not bound to any particular host; we account for this in the example.

3.5.2.1 Creating and Configuring the Target Cluster

The first task when preparing to import a standalone MySQL Cluster into MySQL Cluster Manager is to create a "target" cluster, Once this is done, we modify the target's configuration until it matches that of

the "wild" cluster that we want to import. At a later point in the example, we also show how to test the configuration in a dry run before attempting to perform the actual import.

To create and then configure the target cluster, follow the steps listed here:

- a. Install MySQL Cluster Manager and start mcmd on all hosts; we assume that you have installed MySQL Cluster Manager to the recommended location, in this case the directory /opt/mcm-1.3.6. (See Section 2.3, "MySQL Cluster Manager Installation", for more information.) Once you have done this, you can start the mcm client (see Section 3.3, "Starting the MySQL Cluster Manager Client") on any one of these hosts to perform the next few steps.
- b. Create a MySQL Cluster Manager site encompassing all four of these hosts, using the create site command, as shown here:

We have named this site newsite. You should be able to see it listed in the output of the list sites command, similar to what is shown here:

c. Add a MySQL Cluster Manager package referencing the MySQL Cluster binaries, using the add package command; this command's --basedir [83] option can be used to point to the correct location. The command shown here creates such a package, named newpackage:

You do not need to include the bin directory containing the MySQL Cluster executables in the --basedir path. Since the executables are in /usr/local/mysql/bin, it is sufficient to specify /usr/local/mysql; MySQL Cluster Manager automatically checks for the binaries in a bin directory within the one specified by --basedir.

d. Create the target cluster including at least some of the same processes and hosts used by the standalone cluster. Do not include any processes or hosts that are not part of this cluster. In order to prevent potentially disruptive process or cluster operations from interfering by accident with the import process, it is strongly recommended that you create the cluster for import, using the -import [89] option for the create cluster command.

You must also take care to preserve the correct node ID (as listed in the config.ini file shown previously) for each node. In MySQL Cluster Manager 1.3.1 and later, using the --import option allows you to specify node IDs under 49 for nodes other than data nodes, which is otherwise prevented when using create cluster (the restriction has been lifted since MySQL Cluster Manager 1.3.4).

The following command creates the cluster newcluster for import, and includes the management and data nodes, but not the SQL or "free" API node (which we add in the next step):

You can verify that the cluster was created correctly by checking the output of show status with the --process [95] (-r) option, like this:

e. If necessary, add any remaining processes and hosts from the "wild" cluster not included in the previous step using one or more add process commands. We have not yet accounted for 2 of the nodes from the wild cluster: the SQL node with node ID 100, on host delta; and the API node which has node ID 101, and is not bound to any specific host. You can use the following command to add both of these processes to newcluster:

Once again checking the output from show status -r, we see that the mysqld and ndbapi processes were added as expected:

You can also see that, since newcluster was created using the create cluster command's --import [89] option, the status of all processes in this cluster—including those we just added —is import. This means we cannot yet start newcluster or any of its processes, as shown here:

```
mcm> start process 50 newcluster;
ERROR 5317 (00MGR): Unable to perform operation on cluster created for import
mcm> start cluster newcluster;
```

```
ERROR 5317 (00MGR): Unable to perform operation on cluster created for import
```

The import status and its effects on newcluster and its cluster processes persist until we have completed importing another cluster into newcluster.

Following the execution of the add process command shown previously, the target newcluster cluster now has the same processes, with the same node IDs, and on the same hosts as the original standalone cluster. We are ready to proceed to the next step.

f. Now it is necessary to duplicate the wild cluster's configuration attributes in the target cluster. In MySQL Cluster Manager 1.3.1 and later, you can handle most of these using the import config command, as shown here:



Important

Before executing this command it is necessary to set any non-default ports for ndb_mgmd and mysqld processes using the set command in the mcm client.

As indicated by the output from import config --dryrun, you can see the configuration attributes and values that would be copied to newcluster by the unimpeded command in the agent log file (mcmd.log), which by default is created in the MySQL Cluster Manager installation directory. If you open this file in a text editor, you can locate a series of set commands that would accomplish this task, similar to what is shown here (emphasized text):

```
2014-03-14 16:05:11.896: (message) [T0xlad12a0 CMGR]: Got new message mgr_import_configvalues {84880f7
2014-03-14 16:05:11.896: (message) [T0xlad12a0 CMGR]: Got new message mgr_import_configvalues {84880f7
2014-03-14 16:05:11.896: (message) [T0xlad12a0 CMGR]: Got new message mgr_import_configvalues {84880f7
2014-03-14 16:05:13.698: (message) [T0x7f4fb80171a0 RECFG]: All utility process have finished
2014-03-14 16:05:13.698: (message) [T0x7f4fb80171a0 RECFG]: Process started : /usr/local/mysql/bin/mysq
2014-03-14 16:05:13.698: (message) [T0x7f4fb80171a0 RECFG]: Spawning mysqld --nodefaults --help --verbo
2014-03-14 16:05:13.904: (message) [T0x7f4fb80171a0 RECFG]: Successfully pulled default configuration f
2014-03-14 16:05:13.905: (warning) [T0x7f4fb80171a0 RECFG]: Failed to remove evsource!
2014-03-14 16:05:15.719: (message) [T0x7f4fb80171a0 RECFG]: All utility process have finished
2014-03-14 16:05:15.725: (message) [T0x7f4fb80171a0 RECFG]: Applying mysqld configuration to cluster...
2014-03-14\ 16:05:16.186:\ (\texttt{message})\ [\texttt{T0xlad12a0}\ \texttt{CMGR}\ ]:\ \texttt{Got}\ \texttt{new}\ \texttt{message}\ \texttt{mgr\_import\_configvalues}\ \big\{84880f7, \texttt{mgr}\big\}
2014-03-14 16:05:16.187: (message) [T0xlad12a0 CMGR ]: Got new message x_trans {84880f7a 39 0}
2014-03-14 16:05:16.286: (message) [T0x1ad12a0 CMGR ]: Got new message x_trans {84880f7a 40 0}
2014-03-14 16:05:16.286: (message) [T0x7f4fb80171a0 RECFG]: The following will be applied to the curren
set DataDir:ndb_mgmd:50="" newcluster
set IndexMemory:ndbd:5=1073741824 newcluster
set DataMemory:ndbd:5=1073741824 newcluster
set DataDir:ndbd:5=/usr/local/mysql/mysql-cluster/data newcluster
set ThreadConfig:ndbd:5="" newcluster
set IndexMemory:ndbd:6=1073741824 newcluster
set DataMemory:ndbd:6=1073741824 newcluster
set DataDir:ndbd:6=/usr/local/mysql/mysql-cluster/data newcluster
set ThreadConfig:ndbd:6="" newcluster
set basedir:mysqld:100=/usr/local/mysql newcluster
set character_sets_dir:mysqld:100=/usr/local/mysql/share/charsets newcluster
set datadir:mysqld:100=/usr/local/mysql/data newcluster
set general_log_file:mysqld:100=/usr/local/mysql/data/delta.log newcluster
set lc_messages_dir:mysqld:100=/usr/local/mysql/share newcluster
set log_error:mysqld:100=/usr/local/mysql/data/delta.err newcluster
set ndb_connectstring:mysqld:100=alpha newcluster
set ndb_mgmd_host:mysqld:100=alpha newcluster
set optimizer_trace:mysqld:100=enabled=off,one_line=off newcluster
set pid_file:mysqld:100=/usr/local/mysql/data/delta.pid newcluster
```

```
set plugin_dir:mysqld:100=/usr/local/mysql/lib/plugin newcluster
set report_port:mysqld:100=3306 newcluster
set slow_query_log_file:mysqld:100=/usr/local/mysql/data/delta-slow.log newcluster
set sql_mode:mysqld:100=STRICT_TRANS_TABLES,NO_ENGINE_SUBSTITUTION newcluster
```

Assuming that the dry run was successful, you should now be able to import the wild cluster's configuration into newcluster, with the command and a result similar similar to what is shown here:

You should check the log from the dry run and the resulting configuration of newcluster carefully against the configuration of the wild cluster. If you find any inconsistencies, you must correct these in newcluster using the appropriate set commands afterwards.

Manual configuration import (MySQL Cluster Manager 1.3.0). In MySQL Cluster Manager 1.3.0, which does not support the import config command, it is necessary to copy the wild cluster's configuration manually, using set commands in the mcm client (once you have obtained the values of any attributes that differ from their defaults). The remainder of this section applies primarily to MySQL Cluster Manager 1.3.0 and the process described here is generally not needed in MySQL Cluster Manager 1.3.1 and later.

MySQL Cluster global configuration data is stored in a file that is usually (but not always) named <code>config.ini</code>. Its location on a management node host is arbitrary (there is no default location for it), but if this is not already known, you can determine it by checking—for example, on a typical Linux system—the output of <code>ps</code> for the <code>--config-file</code> option value that the management node was started with, shown with emphasized text in the output:

```
shell> ps ax | grep ndb_mgmd

18851 ? Ssl 0:00 ./ndb_mgmd --config-file=/var/lib/mysql-cluster/config.ini

18922 pts/4 S+ 0:00 grep --color=auto ndb_mgmd
```

This file uses INI format to store global configuration information, and is thus easy to read, or to parse with a script. We start the setup of the target cluster configuration by checking each section of this file in turn. The first section is repeated here:

```
[ndbd default]
DataMemory= 16G
IndexMemory= 12G
NoOfReplicas= 2
```

The [ndbd default] heading indicates that all attributes defined in this section apply to all cluster data nodes. We can set all three attributes listed in this section of the file for all data nodes in newcluster, using the set command shown here:

You can verify that the desired changes have taken effect using the get command, as shown here:

```
mcm> get DataMemory:ndbd,IndexMemory:ndbd,NoOfReplicas:ndbd newcluster;
```

Name	Value	Process1	NodeIdl	Process2	NodeId2	Level	Comment
DataMemory	16G	ndbd	5			Process	
IndexMemory	12G	ndbd	5		İ	Process	İ
NoOfReplicas	2	ndbd	5		ĺ	Process	ĺ
DataMemory	16G	ndbd	6		ĺ	Process	ĺ
IndexMemory	12G	ndbd	6		ĺ	Process	ĺ
NoOfReplicas	2	ndbd	6		ĺ	Process	İ

The next section in the file is shown here:

```
[ndb_mgmd]
HostName=alpha
NodeId=1
```

This section of the file applies to the management node. We set its NodeId and HostName attributes previously, when we created newcluster. No further changes are required at this time.

The next two sections of the config.ini file, shown here, contain configuration values specific to each of the data nodes:

```
[ndbd]
NodeId=5
HostName=beta
DataDir=/var/lib/mysql-cluster

[ndbd]
NodeId=6
HostName=gamma
DataDir=/var/lib/mysql-cluster
```

As was the case for the management node, we already provided the correct node IDs and host names for the data nodes when we created newcluster, so only the DataDir attribute remains to be set. We can accomplish this by executing the following command in the mcm client:

You may have noticed that we could have set the <code>DataDir</code> attribute on the process level using the shorter and simpler command <code>set DataDir:ndbd=/var/lib/mysql-cluster newcluster</code>, but since this attribute was defined individually for each data node in the original configuration, we match this scope in the new configuration by setting this attribute for each <code>ndbd</code> instance instead. Once again, we check the result using the <code>mcm</code> client <code>get</code> command, as shown here:

 Name	+ Value			+ Process2			
	, +	, +	+	+	, +	, +	, +
	/var/lib/mysql-cluster		5				
DataDir	/var/lib/mysql-cluster	ndbd	6				

Configuration attributes for the SQL node are contained the the next section of the file, shown here:

```
[mysqld]
NodeId=100
HostName=delta
```

The NodeId and HostName attributes were already set when we added the mysqld process to newcluster, so no additional set commands are required at this point. Keep in mind that there may be additional local configuration values for this mysqld that must be accounted for in the configuration we are creating for newcluster; we discuss how to determine these values on the SQL node later in this section.

The remaining section of the file, shown here, contains a section defining attributes for a "free" API node that is not required to connect from any particular host:

```
[ndbapi]
NodeId=101
```

We have already set the NodeId and there is no need for a HostName for a free process. There are no other attributes that need to be set for this node.

For more information about the MySQL config.ini global configuration file, see MySQL Cluster Configuration Files, and MySQL Cluster Configuration: Basic Example.

As mentioned earlier in this section, each <code>mysqld</code> process (SQL node) may have, in addition to any attributes set in <code>config.ini</code>, its own configuration data in the form of system variables which are specific to that <code>mysqld</code>. These can be set in two ways:

- When the mysqld is started, by passing options to it on the command line when invoking it, by reading from an options file (usually named my.cnf, or my.ini on Windows), or both.
- At runtime using the SQL SET statement.

Because the initial values of many options can be changed at runtime, it is recommended that—rather than attempt to read the my.cnf or my.ini file—you check values for all system variables on each SQL node "live" in the mysql client by examining the output of the SHOW VARIABLES statement, and execute set commands setting each of these values where it differs from the default for that variable on that SQL node.

The mcm client can execute a script file containing client commands. The contents of such a script, named my-commands.mcm, which contains all commands we executed to create and configure newcluster, are shown here:

```
create cluster --import --package=newpackage --processhosts=ndb_mgmd:50@alpha,ndbd:5@beta,ndbd:6@gamma
add process --processhosts=mysqld:100@delta,ndbapi:101@* newcluster;
set DataMemory:ndbd=16G,IndexMemory:ndbd=12G,NoOfReplicas:ndbd=2 newcluster;
set DataDir:ndbd:5=/var/lib/mysql-cluster,DataDir:ndbd:6=/var/lib/mysql-cluster newcluster;
```

You can run such a script by invoking the client from the command line with a redirection operator, like this:

```
shell> mcm < my-commands.mcm
```

The name of the script file is completely arbitrary. It must contain valid mcm client commands or comments only. (A comment is delimited by a # character, and extends from the point in the line where this is found to the end of the line.) Any valid mcm client command can be used in such a file. mcm must be able to read the file, but the file need not be executable, or readable by any other users.

3.5.2.2 Preparing the Standalone Cluster for Migration

The next step in the import process is to prepare the "wild" cluster for migration. This requires creating an mcmd user account with root privileges on all hosts in the cluster; killing any data node angel processes that may be running; restarting all management nodes without configuration caching; removing cluster processes from control by any system service management facility. More detailed information about performing these tasks is provided in the remainder of this section.



Note

Before proceeding with any migration, the taking of a backup using the ndb_mgm client's BACKUP command is strongly recommended.

a. MySQL Cluster Manager acts through a MySQL user named mcmd on each SQL node. It is therefore necessary to create this user and grant root privileges to it. To do this, log in to the SQL node running on host delta and execute in the mysql client the SQL statements shown here:

```
CREATE USER 'mcmd'@'delta' IDENTIFIED BY 'super';

GRANT ALL PRIVILEGES ON *.* TO 'mcmd'@'delta' WITH GRANT OPTION;
```

Keep in mind that, if the "wild" cluster has more than one SQL node, you must create the mcmd user on every one of these nodes.

b. Kill each data node angel process using the system's facility for doing so. Do not kill any non-angel data node daemons. On a Linux system, you can identify angel processes by matching their process IDs with the owner IDs of the remaining ndbd processes in the output of ps excuted on host beta of the example cluster, as shown here, with the relevant process IDs shown in emphasized text:

```
shell> ps -ef | grep ndbd

jon 2023 1 0 18:46 ? 00:00:00 ./ndbd -c alpha

jon 2024 2023 1 18:46 ? 00:00:00 ./ndbd -c alpha

jon 2124 1819 0 18:46 pts/2 00:00:00 grep --color=auto ndbd
```

Use the kill command to terminate the process with the indicated process ID, like this:

```
shell> kill -9 2023
```

Verify that the angel process has been killed, and that only one of the two original ndbd processes remain, by issuing ps again, as shown here:

```
shell> ps -ef | grep ndbd

jon 2024 1 1 18:46 ? 00:00:01 ./ndbd -c alpha

jon 2150 1819 0 18:47 pts/2 00:00:00 grep --color=auto ndbd
```

Now repeat this process from a login shell on host gamma, as shown here:

The wild cluster's data nodes are now ready for migration.

c. Kill and restart each management node process. When restarting ndb_mgmd, its configuration cache must be disabled; since this is enabled by default, you must start the management server with --config-cache=false, in addition to any other options that it was previously started with.



Caution

Do not use 0 or OFF for the value of the --config-cache option when restarting ndb_mgmd in this step. Using either of these values instead of false at this time causes the migration of the management node process to fail at later point in the importation process.

On Linux, we can once again use ps to obtain the information we need to accomplish this, this time in a shell on host alpha:

The process ID is 16005, and the management node was started with the -f option (the short form for --config-file). First, terminate the management using kill, as shown here, with the process ID obtained from ps previously:

```
shell> kill -9 16005
```

Verify that the management node process was killed, like this:

```
shell> ps -ef | grep ndb_mgmd
jon 16532 1819 0 19:03 pts/2 00:00:00 grep --color=auto ndb_mgmd
```

Now restart the management node as described previously, with the same options that it was started with previously, and with the configuration cache disabled. Change to the directory where ndb_mgmd is located, and restart it, like this:

```
shell> ./ndb_mgmd -f /etc/mysql-cluster/config.ini --config-cache=false
MySQL Cluster Management Server mysql-5.6.24-ndb-7.4.6
2013-12-06 19:16:08 [MgmtSrvr] INFO -- Skipping check of config directory since config cache is disabled.
```

Verify that the process is running as expected, using ps:

```
shell> ps -ef | grep ndb_mgmd
jon 17066 1 1 19:16 ? 00:00:01 ./ndb_mgmd -f
/etc/mysql-cluster/config.ini --config-cache=false
jon 17311 1819 0 19:17 pts/2 00:00:00 grep --color=auto ndb_mgmd
```

The management node is now ready for migration.



Important

While our example cluster has only a single management node, it is possible for a MySQL Cluster to have more than one. In such cases, you must stop and restart *each* management node process as just described in this step.

- d. Any cluster processes that are under the control of a system boot process management facility, such as /etc/init.d on Linux systems or the Services Manager on Windows platforms, should be removed from this facility's control. Consult your system operating documentation for information about how to do this. Be sure not to stop any running cluster processes in the course of doing so.
- e. It is highly recommended that you take a complete backup of the "wild" cluster before proceeding any further, using the ndb_mgm client's START BACKUP command:

```
ndb_mgm> START BACKUP
Waiting for completed, this may take several minutes
Node 5: Backup 1 started from node 1
Node 5: Backup 1 started from node 1 completed
StartGCP: 1338 StopGCP: 20134
#Records: 205044 #LogRecords: 10112
Data: 492807474 bytes Log: 317805 bytes
```

It may require some time for the backup to complete, depending on the size of the cluster's data and logs. For START BACKUP command options and additional information, see Using The MySQL Cluster Management Client to Create a Backup.

3.5.2.3 Verify All Cluster Process PID Files

- a. You must verify that each process in the "wild" cluster has a valid PID file. For purposes of this discussion, a valid PID file has the following characteristics:
 - The filename is ndb_node_id.pid, where node_id is the node ID used for this process.
 - The file is located in the data directory used by this process.
 - The first line of the file contains the process ID, and only the process ID.

To check the PID file for the management node process, log into the system shell on host alpha, and change to the management node's data directory. If this is not specified, the PID file should be created in the same directory that ndb_mgmd runs in; change to this directory instead. Then check to see whether the PID file is present using your system's tools for doing this. On Linux, you can use the command shown here:

```
shell> ls ndb_1*
ndb_1_cluster.log ndb_1_out.log ndb_1.pid
```

Check the content of the matching .pid file using a pager or text editor. We use more for this purpose here:

```
shell> more ndb_1.pid
17066
```

The number shown should match the ndb_mgmd process ID. We can check this on Linux as before, using ps:

```
shell> ps -ef | grep ndb_mgmd
jon 17066 1 1 19:16 ? 00:00:01 ./ndb_mgmd -f /etc/mysql-cluster/config.ini --config-cache=fal
jon 17942 1819 0 19:17 pts/2 00:00:00 grep --color=auto ndb_mgmd
```

The management node PID file satisfies the requirements listed at the beginning of this section. Next, we check the PID files for the data nodes, on hosts beta and gamma. Log into a system shell on beta, then obtain the process ID of the ndbd process on this host, as shown here:

We observed earlier (see Section 3.5.2.1, "Creating and Configuring the Target Cluster") that this node's node ID is 5 and that its <code>DataDir</code> is <code>/var/lib/mysql-cluster</code>. Check in this directory for the presence of a file named <code>ndb_5.pid</code>:

```
shell> ls /var/lib/mysql-cluster/ndb_5.pid
ndb_5.pid
```

Now check the content of this file and make certain that it contains the process ID 2024 on the first line and no other content, like this:

```
shell> more /var/lib/mysql-cluster/ndb_5.pid
2024
```

Similarly, we locate and check the content of the PID file for the remaining data node (node ID 6, data directory /var/lib/mysql-cluster/) on host gamma:

The PID file for this data node also meets our requirements, so we are now ready to proceed to the mysqld binary running on host delta. We handle the PID file for this process in the next step.

b. If a given process does not have a valid PID file, you must create one for it, or, in some cases, modify the existing one. This is most likely to be a concern when checking PID files for mysqld processes, due to the fact that the MySQL Server is customarily started using the startup script mysqld_safe, which can start the mysqld binary with any number of default options, including the --pid-file option. We see that is the case when we check on host delta for the running mysqld process there (emphasized text):

```
shell> ps -ef | grep mysqld
jon 8782 8520 0 10:30 pts/3 00:00:00 /bin/sh ./mysqld_safe --ndbcluster
--ndb-connectstring=alpha
jon 8893 8782 1 10:30 pts/3 00:00:00 /usr/local/mysql/bin/mysqld
--basedir=/usr/local/mysql --datadir=/usr/local/mysql/data
--plugin-dir=/usr/local/mysql/lib/plugin --ndbcluster --ndb-connectstring=alpha
--log-error=/usr/local/mysql/data/delta.err --pid-file=/usr/local/mysql/data/delta.pid
jon 8947 8520 0 10:30 pts/3 00:00:00 grep --color=auto mysqld
shell> more /usr/local/mysql/data/delta.pid
8893
```

The PID for the SQL node is in an acceptable location (the data directory) and has the correct content, but has the wrong name.

You can create a correct PID file in either of two locations—in the process data directory, or in the directory $mcm_dir/clusters/cluster$ name/pid/ on the same host as the process, where mcm_dir is the MySQL Cluster Manager installation directory, and $cluster_name$ is the name of the cluster. In this case, since the existing PID file is otherwise correct, it is probably easiest just to copy it to a correctly named file in the same directory incorporating the node ID (100), like this:

```
shell> cp /usr/local/mysql/data/delta.pid /usr/local/mysql/data/ndb_100.pid
```

Another alternative is to create and write a completely new PID file to the proper location in the MySQL Cluster Manager installation directory, as shown here:

```
shell> echo '8893' > /opt/mcm-1.3.6/clusters/newcluster/pid/ndb_100.pid
shell> more /opt/mcm-1.3.6/clusters/newcluster/pid/ndb_100.pid
8893
```

ndbapi processes running under MySQL Cluster Manager do not require PID files, so we have completed this step of the import, and we should be ready for a test or "dry run" of the migration. We perform this test in the next step.

3.5.2.4 Testing and Migrating the Standalone Cluster

Testing and performing and performing the migration of a standalone MySQL Cluster into MySQL Cluster Manager consists of the following steps:

1. Perform a test run of the proposed import using import cluster with the --dryrun option. When this option is used, MySQL Cluster Manager checks for mismatched configuration attributes, missing or invalid processes or hosts, missing or invalid PID files, and other errors, and warns of any it finds, but does not actually perform any migration of processes or data.

```
mcm> import cluster --dryrun newcluster;
ERROR 5302 (00MGR): No access for user mcmd to mysqld 100 in cluster newcluster.
Please verify user access and grants adhere to documented requirements.
```

We omitted a crucial step earlier: we apparently neglected to create the mcmd superuser account needed on all SQL nodes in the "wild" cluster to bring them under control of MySQL Cluster Manager. In this case, there is only one SQL node, running on delta. Log into this SQL node as the MySQL root user, and create the mcmd account in the mysql client, as shown here:

```
shell> ./mysql -uroot -p
Enter password: *****
Welcome to the MySQL monitor. Commands end with ; or \g.
Your MySQL connection id is 3
Server version: 5.6.24-ndb-7.4.6 Source distribution
Copyright (c) 2000, 2013, Oracle and/or its affiliates. All rights reserved.
Oracle is a registered trademark of Oracle Corporation and/or its
affiliates. Other names may be trademarks of their respective
Type 'help;' or '\h' for help. Type '\c' to clear the current input statement.
mysql > CREATE USER 'mcmd'@'localhost' IDENTIFIED BY 'super';
Query OK, 0 rows affected (0.00 sec)
mysql> GRANT ALL PRIVILEGES ON *.*
   -> TO 'mcmd'@'localhost' IDENTIFIED BY 'super'
          WITH GRANT OPTION;
Query OK, 0 rows affected (0.00 sec)
mysql> SHOW GRANTS FOR 'mcmd'@'localhost'\G
Grants for mcmd@localhost: GRANT ALL PRIVILEGES ON *.* TO 'mcmd'@'localhost'
IDENTIFIED BY PASSWORD '*F85A86E6F55A370C1A115F696A9AD71A7869DB81' WITH GRANT OPTION
1 row in set (0.00 sec)
```

Having corrected this issue on the SQL node, we repeat the dry run in the mcm client:

```
mcm> import cluster --dryrun newcluster;
ERROR 5310 (00MGR): Process ndb_mgmd 50 reported 6 processes, while 5 processes
are configured for cluster newcluster
```

This error means that there are one or more cluster processes not accounted for the configuration for the target cluster. Checking the contents of the file /etc/mysql-cluster/config.ini on host alpha, we see that we overlooked a section in it earlier. This section is shown here:

```
[mysqld]
NodeId=102
```

To address this discrepancy, we need to add another "free" ndbapi process to newcluster, which we can do by executing the following add process command in the mcm client:

You can verify this by checking the output of show status -r [95] command, as shown here:

```
mcm> show status -r newcluster;
| NodeId | Process | Host | Status | Nodegroup | Package
                                                   newpackage
newpackage
newpackage
  50
         | ndb_mgmd | alpha | import |
                     | beta | import | n/a
| gamma | import | n/a
         ndbd
ndbd
  5
  6
 100 | mysqld
                     | delta | import |
                                                    newpackage
  101
         ndbapi
                     | * | import |
         ndbapi
                              | import |
 102
6 rows in set (0.11 sec)
```

Now we can run another test, using import cluster with the --dryrun as we did previously:

```
mcm> import cluster --dryrun newcluster;
```

- 2. Continue to correct any errors or other discrepancies found using --dryrun, repeating the dry run shown in the previous step to ensure that no errors were missed. The following list contains some common errors you may encounter, and their likely causes:
 - MySQL Cluster Manager requires a specific MySQL user and privileges to manage SQL nodes. If
 the mcmd MySQL user account is not set up properly, you may see No access for user...,
 Incorrect grants for user..., or possibly other errors. See Section 3.5.2.2, "Preparing
 the Standalone Cluster for Migration".
 - As described previously, each cluster process (other than a process whose type is ndbapi) being brought under MySQL Cluster Manager control must have a valid PID file. Missing, misnamed, or invalid PID files can produce errors such as PID file does not exist for process..., PID ... is not running ..., and PID ... is type See Section 3.5.2.3, "Verify All Cluster Process PID Files".
 - Process version mismatches can also produce seemingly random errors whose cause can sometime prove difficult to track down. Ensure that all nodes are supplied with the correct release of the MySQL Cluster software, and that it is the same release and version of the software.
 - Each data node angel process in the standalone cluster must be stopped prior to import. A running angel process can cause errors such as Angel process pid exists ... or Process pid is an angel process for See Section 3.5.2.2, "Preparing the Standalone Cluster for Migration".
 - The number of processes, their types, and the hosts where they reside in the standalone cluster must be reflected accurately when creating the target site, package, and cluster for import.

 Otherwise, errors such as Process id reported # processes ..., Process id ... does not match configured process ..., Process idnot configured ..., and Process iddoes not match configured process See Section 3.5.2.1, "Creating and Configuring the Target Cluster".

- Other factors that can cause specific errors include processes in the wrong state, processes that were started with unsupported command-line options or without required options, and processes having the wrong process ID, or using the wrong node ID.
- 3. When import cluster --dryrun no longer warns of any errors, you can perform the import with the import cluster command, this time omitting the --dryrun option.

3.6 MySQL Cluster Backup and Restore Using MySQL Cluster Manager

This section describes usage of the NDB native backup and restore functionality implemented in MySQL Cluster Manager, to perform a number of common tasks.

3.6.1 Requirements for Backup and Restore

This section provides information about basic requirements for performing backup and restore operations using MySQL Cluster Manager.

Requirements for MySQL Cluster backup. Basic requirements for performing MySQL backups using MySQL Cluster Manager are minimal. At least one data node in each node group must be running, and there must be sufficient disk space on the node file systems. Partial backups are not supported.

Requirements for MySQL Cluster restore. Restoring a MySQL Cluster using MySQL Cluster Manager is subject to the following conditions:

- A complete restore requires that all data nodes are up and running, and that all files belonging to a given backup are available.
- A partial restore is possible, but must be specified as such. This can be accomplished using the restore cluster client command with its --skip-nodeid option.
- In the event that data nodes have been added to the cluster since the backup was taken, only those data nodes for which backup files exist are restored. In such cases data is not automatically distributed to the new nodes, and, following the restore, you must redistribute the data manually by issuing an ALTER ONLINE TABLE ... REORGANIZE PARTITION statement in the mysql client for each NDB table in the cluster. See Adding MySQL Cluster Data Nodes Online: Basic procedure, for more information.

3.6.2 Basic MySQL Cluster Backup and Restore Using MySQL Cluster Manager

This section describes backing up and restoring a MySQL Cluster, with examples of complete and partial restore operations. Note that the backup cluster and restore cluster commands work with NDB tables only; tables using other MySQL storage engines (such as InnoDB or MyISAM) are ignored.

For purposes of example, we use a MySQL Cluster named mycluster whose processes and status can be seen here:

mcm> show	status -r m	nycluster;			
NodeId	Process	Host	Status	Nodegroup	Package
49 1 2 50 51 52	ndb_mgmd ndbd ndbd mysqld mysqld ndbapi	tonfisk tonfisk tonfisk tonfisk tonfisk *tonfisk	running running running running running added	 0 0 	mypackage mypackage mypackage mypackage mypackage

You can see whether there are any existing backups of mycluster using the list backups command, as shown here:

Simple backup. To create a backup, use the backup cluster command with the name of the cluster as an argument, similar to what is shown here:

backup cluster requires only the name of the cluster to be backed up as an argument; for information about additional options supported by this command, see Section 4.7.2, "The backup cluster Command". To verify that a new backup of mycluster was created with a unique ID, check the output of list backups, as shown here (where the rows corresponding to the new backup files are indicated with emphasized text):

If you attempt to create a backup of a MySQL Cluster in which each node group does not have at least one data node running, backup cluster fails with the error Backup cannot be performed as processes are stopped in cluster cluster_name.

Simple complete restore. To perform a complete restore of a MySQL Cluster from a backup with a given ID, follow the steps listed here:

- 1. Identify the backup to be used.
 - In this example, we use the backup having the ID 4, that was created for mycluster previously in this section.
- 2. Wipe the MySQL Cluster data.

The simplest way to do this is to stop and then perform an initial start of the cluster as shown here, using mycluster:

3. Restore the backup.

This is done using the restore cluster command, which requires the backup ID and the name of the cluster as arguments. Thus, you can restore backup 4 to mycluster as shown here:

Partial restore—missing images. It is possible using MySQL Cluster Manager to perform a partial restore of a MySQL Cluster—that is, to restore from a backup in which backup images from one or more data nodes are not available. This is required if we wish to restore mycluster to backup number 6, since an image for this backup is available only for node 1, as can be seen in the output of list backups in the mcm client (emphasized text):

To perform a restore of only those nodes for which we have images (in this case, node 1 only), we can use the <code>--skip-nodeid</code> option when executing a <code>restore cluster</code> command. This option causes one or more nodes to be skipped when performing the restore. Assuming that <code>mycluster</code> has been cleared of data (as described earlier in this section), we can perform a restore that skips node 2 as shown here:

```
mcm> restore cluster --backupid=6 --skip-nodeid=2 mycluster; +-----+
```

Because we excluded node 2 from the restore process, no data has been distributed to it. To cause MySQL Cluster data to be distributed to any such excluded or skipped nodes following a partial restore, it is necessary to redistribute the data manually by executing an ALTER ONLINE TABLE ... REORGANIZE PARTITION statement in the mysql client for each NDB table in the cluster. To obtain a list of NDB tables from the mysql client, you can use multiple SHOW TABLES statements or a query such as this one:

```
SELECT CONCAT('' TABLE_SCHEMA, '.', TABLE_NAME)
FROM INFORMATION_SCHEMA.TABLES
WHERE ENGINE='ndbcluster';
```

You can generate the necessary SQL statements using a more elaborate version of the query just shown, such the one employed here:

Partial restore—data nodes added. A partial restore can also be performed when new data nodes have been added to a MySQL Cluster following a backup. In this case, you can exclude the new nodes using --skip-nodeid when executing the restore cluster command. Consider the MySQL Cluster named mycluster as shown in the output of the following show status command:

The output of list backups shows us the available backup images for this cluster:

```
mcm> list backups mycluster;
```

	BackupId	NodeId	Host	Timestamp	Comment
+	1	+ 1	tonfisk	2012-12-04 12:03:52	
	1	2	tonfisk	2012-12-04 12:03:52	
1	2	1	tonfisk	2012-12-04 12:04:15	
Ì	2	2	tonfisk	2012-12-04 12:04:15	
	3	1	tonfisk	2012-12-04 12:17:41	
Ì	3	2	tonfisk	2012-12-04 12:17:41	
Ì	4	1	tonfisk	2012-12-12 14:24:35	
Ì	4	2	tonfisk	2012-12-12 14:24:35	
+		+	+	+	
8	rows in se	et (0.06 s	sec)		

Now suppose that, at a later point in time, 2 data nodes have been added to mycluster using an add process command. The show status output for mycluster now looks like this:

NodeId	Process	Host	Status	Nodegroup	Package
49	ndb_mgmd	tonfisk	running		mypackage
1	ndbd	tonfisk	running	0	mypackage
2	ndbd	tonfisk	running	0	mypackage
50	mysqld	tonfisk	running		mypackage
51	mysqld	tonfisk	running		mypackage
52	ndbapi	*tonfisk	added		
53	ndbapi	*tonfisk	added		
3	ndbd	tonfisk	running	1	mypackage
4	ndbd	tonfisk	running	1	mypackage

Since nodes 3 and 4 were not included in the backup, we need to exclude them when performing the restore. You can cause restore cluster to skip multiple data nodes by specifying a comma-separated list of node IDs with the --skip-nodeid option. Assume that we have just cleared mycluster of MySQL Cluster data using the mcm client commands stop cluster and start cluster --initial as described previously in this section; then we can restore mycluster (now having 4 data nodes numbered 1, 2, 3, and 4) from backup number 4 (made when mycluster had only 2 data nodes numbered 1 and 2) as shown here:

No data is distributed to the skipped (new) nodes; you must force nodes 3 and 4 to be included in a redistribution of the data using ALTER ONLINE TABLE ... REORGANIZE PARTITION as described previously in this section.

3.7 Backing Up and Restoring MySQL Cluster Manager Agents

This section explains how to back up configuration data for mcmd agents and how to restore the backed-up agent data. Used together with the backup cluster command, the backup agents command allows you to backup and restore a complete cluster-plus-manager setup.

If no host names are given with the backup agents command, backups are created for all agents of the site:

```
| Agent backup created successfully |
+-----+
1 row in set (0.07 sec)
```

To backup one or more specific agents, specify them with the --hosts option:

If no site name is given, only the agent that the mcm client is connected to is backed up.

The backup for each agent includes the following contents from the agent repository (mcm_data folder):

- The rep subfolder
- The metadata files high water mark and repchksum

The repository is locked while the backup are in progress, to avoid creating an inconsistent backup. The backup for each agent is created in a subfolder named rep_backup/timestamp under the agent's mcm_data folder, with timestamp reflecting the time the backup began. If you want the backup to be at another place, create a soft link from mcm_data/rep_backup to your desired storage location.

To restore the backup for an agent:

- Wipe the contents of the agent's mcm_data/rep folder
- Delete the metadata files high_water_mark and repchksum from the mcm_data folder
- Copy the contents in the mcm_data/rep_backup/timestamp/rep folder back into the mcm_data/rep folder
- Copy the metadata files high_water_mark and repchksum from the mcm_data/rep_backup/timestamp folder back into the mcm_data folder
- · Restart the agent

The steps are illustrated below:

```
mysql@tonfisk$ cd mcm_data
mysql@tonfisk$ cp mcm_data/rep_backup/timestamp/rep/* ./rep/
mysql@tonfisk$ cp mcm_data/rep_backup/timestamp/high_water_mark ./
mysql@tonfisk$ cp mcm_data/rep_backup/timestamp/repchksum ./
mysql@tonfisk$ mcml.3.6/bin/mcmd
```

The backup may be manually restored on just one, or more than one agents. If backup is restored for only one agent on, say, host A, host A will contact the other agents of the site to make them recover their repositories from host A using the usual mechanism for agent recovery. If all agents on all hosts are restored and restarted manually, the situation will be similar to the normal restarting all agents after stopping them at slightly different points in time.

If configuration changes has been made to the cluster since the restored backup was created, the same changes must be made again after the agent restores have been completed, to ensure that

the agents' configurations match those of the actual running cluster. For example: sometime after a backup was done, a set MaxNoOfTables:ndbmtd=500 mycluster command was issued and soon afterward, something happened and corrupted the agent repository; after the agent backup was restored, the same set command has to be rerun in order to update the momd agents' configurations. While the command does not effectively change anything on the cluster itself, after it has been run, a rolling restart of the cluster processes using the restart cluster command is still required.

3.8 Setting Up MySQL Cluster Replication with MySQL Cluster Manager

This section provides sample steps for setting up a MySQL Cluster replication with a single replication channel using the MySQL Cluster Manager.

Before trying the following steps, it is recommended that you first read MySQL Cluster Replication to familiarize yourself with the concepts, requirements, operations, and limitations of MySQL Cluster replication.

1. Create and start a master cluster:

Create and start a slave cluster (we begin with creating a new site called "ssite" just for the slave cluster; you can also skip that and put the master and slave cluster hosts under the same site instead):

```
mcm> create site --hosts=flundra ssite;

mcm> add package --basedir=/usr/local/cluster-mgt/cluster-7.3.2 7.3.2;

mcm> create cluster -P 7.3.2 -R \
```

```
ndb_mgmd@flundra,ndbmtd@flundra,ndbmtd@flundra,mysqld@flundra,mysqld@flundra,ndbapi@*,ndbapi@
slave;

mcm> set portnumber:ndb_mgmd=4000 slave;

mcm> set port:mysqld:50=3306 slave;

mcm> set port:mysqld:51=3307 slave;

mcm> set server_id:mysqld:50=101 slave;

mcm> set ndb_connectstring:mysqld:50=flundra:4000 slave;
```

3. Create a slave account (with the user name "myslave" and password "mypw") on the master cluster with the appropriate privilege by logging into the master replication client (mysqlM) and issuing the following statements:

```
mysqlM> GRANT REPLICATION SLAVE ON *.* TO 'myslave'@'flundra'
   -> IDENTIFIED BY 'mypw';
```

4. Log into the slave cluster client (mysqls) and issue the following statements:

mcm> set slave_skip_errors:mysqld=all slave;

mcm> start cluster slave;

```
mysqlS> CHANGE MASTER TO
   -> MASTER_HOST='tonfisk',
   -> MASTER_PORT=3306,
   -> MASTER_USER='myslave',
   -> MASTER_PASSWORD='mypw';
```

5. Start replication by issuing the following statement with the slave cluster client:

```
mysqls> start slave;
```

The above example assumes that the master and slave clusters are created at about the same time, with no data on both before replication starts. If the master cluster has already been operating and has data on it when the salve cluster is created, after step 3 above, follow these steps to transfer the data from the master cluster to the slave cluster and prepare the slave cluster for replication:

1. Back up your master cluster using the backup cluster command of MySQL Cluster Manager:

mcm> backup cluster master;



Note

Only \mathtt{NDB} tables are backed up by the command; tables using other MySQL storage engines are ignored.

2. Look up the backup ID of the backup you just made by listing all backups for the master cluster:

From the output, you can see that the latest backup you created has the backup ID "2", and backup data exists for node "1" and "2".

3. Using the backup ID and the related node IDs, identify the backup files just created under / mcm_data/clusters/cluster_name/node_id/data/BACKUP/BACKUP-backup_id/ in the master cluster's installation directory (in this case, the files under the /mcm_data/clusters/master/1/data/BACKUP/BACKUP-2 and /mcm_data/clusters/master/2/data/BACKUP/BACKUP-2), and copy them over to the equivalent places for the slave cluster (in this case, / mcm_data/clusters/slave/1/data/BACKUP/BACKUP-2 and /mcm_data/clusters/slave/2/data/BACKUP/BACKUP-2 under the slave cluster's installation directory). After the copying is finished, use the following command to check that the backup is now available for the slave cluster:

4. Restore the backed up data to the slave cluster (note that you need an unused ndbapi slot for the restore cluster command to work):

```
mcm> restore cluster --backupid=2 slave;
```

5. On the master cluster client, use the following command to identify the correct binary log file and position for replication to start:

```
mysqlM> SHOW MASTER STATUS\G;

***************************
    File: binlog.000017
    Position: 2857
    Binlog_Do_DB:
Binlog_Ignore_DB:
Executed_Gtid_Set:
```

6. On the slave cluster client, provide to the slave cluster the information of the master cluster, including the binary log file name (with the MASTER_LOG_FILE option) and position (with the MASTER_LOG_POS option) you just discovered in step 5 above:

```
mysqls> CHANGE MASTER TO
    -> MASTER_HOST='tonfisk',
    -> MASTER_PORT=3306,
    -> MASTER_USER='myslave',
    -> MASTER_PASSWORD='mypw',
    -> MASTER_LOG_FILE='binlog.000017',
    -> MASTER_LOG_POS=2857;
```

7. Start replication by issuing the following statement with the slave cluster client:

```
mysqlS> START SLAVE;
```

As an alternative to these steps, you can also follow the steps described in MySQL Cluster Backups With MySQL Cluster Replication to copy the data from the master to the slave and to specify the binary log file and position for replication to start.

Chapter 4 MySQL Cluster Manager Client Commands

Table of Contents

4.1 Online Help and Information Commands	
4.2 MySQL Cluster Manager Site and Agent Commands	75
4.2.1 The add hosts Command	76
4.2.2 The remove hosts Command	76
4.2.3 The change log-level Command	77
4.2.4 The rotate log Command	
4.2.5 The collect logs Command	
4.2.6 The create site Command	
4.2.7 The delete site Command	
4.2.8 The list sites Command	
4.2.9 The list hosts Command	
4.2.10 The show settings Command	
4.2.11 The stop agents Command	
4.2.17 The stop agents command	
4.2.13 The show warnings Command	
4.3 MySQL Cluster Manager Package Commands	
4.3.1 The add package Command	
4.3.2 The delete package Command	
4.3.3 The list packages Command	
4.4 MySQL Cluster Manager Cluster Commands	
4.4.1 The create cluster Command	
4.4.2 The delete cluster Command	
4.4.3 The list clusters Command	92
4.4.4 The list nextnodeids Command	92
4.4.5 The restart cluster Command	93
4.4.6 The show status Command	93
4.4.7 The start cluster Command	96
4.4.8 The stop cluster Command	
4.4.9 The upgrade cluster Command	
4.5 MySQL Cluster Manager Configuration Commands	
4.5.1 The get Command	
4.5.2 The reset Command	
4.5.3 The set Command	
4.6 MySQL Cluster Manager Process Commands	
4.6.1 The add process Command	
4.6.2 The change process Command	
4.6.3 The list processes Command	
4.6.4 The start process Command	
4.6.5 The stop process Command	
4.6.6 The remove process Command	
4.7 MySQL Cluster Manager Backup and Restore Commands	
4.7.1 The abort backup Command	
4.7.2 The backup cluster Command	
4.7.3 The list backups Command	134
4.7.4 The restore cluster Command	134
4.7.5 The backup agents Command	
4.8 MySQL Cluster Manager Cluster Importation Commands	
4.8.1 The import cluster Command	
4.8.2 The import config Command	

Identifiers in client commands

Case-sensitivity rules for client commands

Options common to client commands

The sections in this chapter describe commands used in the MySQL Cluster Manager 1.3.6 client for tasks such as defining sites, packages, and MySQL Cluster instances ("clusters"); configuring a MySQL Cluster; and getting the status of a running MySQL Cluster. These commands are issued to the management agent using the mysql client program included with the MySQL Cluster distribution (for information about the mysql client not specific to using MySQL Cluster Manager, see mysql — The MySQL Command-Line Tool). Each MySQL Cluster Manager client command takes the form shown here:

Consider the following MySQL Cluster Manager command, which starts a MySQL Cluster named mycluster and backgrounds the deletion process so that the client can be used to execute other commands in the meantime, without having to wait on the start cluster command to complete:

```
start cluster --background mycluster;
```

In this example, the command contains a start cluster instruction. An instruction consists of one or two keywords, such as set, or show status. This instruction is modified by the --background option which follows it; however, this option assigns no values.

Most command options have short forms, consisting of single letters, in addition to their long forms. Using the short form of the --background option, the previous example could also be written like this:

```
start cluster -B mycluster;
```

The long form of an option must be preceded by a double dash (--), and is case insensitive (lower case being the canonical form). The short form of an option must be preceded by a single dash (-), and is case sensitive. In either case, the dash character or characters must come immediately before the option name, and there must be no space characters between them. Otherwise, the MySQL Cluster Manager client cannot parse the command correctly. More information about long and short forms of options is given later in this section.



Important

Do not confuse options given to MySQL Cluster Manager client commands with mysql client options. A MySQL Cluster Manager client command option is always employed as part of a MySQL Cluster Manager client command; it is *not* passed to the mysql client when invoking it.

In addition, you cannot issue queries or other SQL statements in the MySQL Cluster Manager client. These are not recognized by the client, and are rejected with an error. The converse of this is also true: MySQL Cluster Manager client commands are not recognized by the standard mysql client.

The instruction just shown takes the argument mysite. The argument is usually an identifier that names the object to be effected; in this case, the command deletes the site whose name matches the argument. (For more information, see Section 4.2.6, "The create site Command".)

Changes in client commands in version 1.3.4. An additional --verbose option has been added in version 1.3.4 to the create cluster and add process commands. In both cases, using the option causes the command to return a list of the MySQL Cluster processes affected by the command; this includes their node IDs, process types, and the hosts where they are located.

Identifiers in client commands.

A legal MySQL Cluster Manager identifier consists of any sequence of characters from among the following:

- The letters a through z and A through Z
- The digits 0 through 9
- The dash (-), period (.), and underscore (_) characters

A MySQL Cluster Manager identifier must begin with a letter or digit.

Case-sensitivity rules for client commands.

The rules for case-sensitivity of MySQL Cluster Manager identifiers, commands, command options, process names, and configuration attributes are as follows:

- *Identifiers are case-sensitive*. For example, delete site mycluster cannot be used to delete a site named myCluster.
- Command keywords and the long forms of command options are case-insensitive. For example, any of the three commands delete cluster mycluster, DELETE CLUSTER mycluster, and DeLeTe cLuster mycluster works to delete the MySQL Cluster instance named mycluster.

In this manual, we show command keywords and the long forms of command options in lowercase, but you are not required to follow this convention if you do not wish to do so.

- The short forms of command options are case-sensitive. For example, -b (lowercase) is the short form of the --basedir option, but -B (uppercase) is the short form of the --background option.
- Names of MySQL Cluster processes are case-insensitive. For example, either of the commands get --include-defaults DataMemory:ndbd mycluster or get --include-defaults datamemory:NDBD mycluster reports the data memory allocated for each ndbd process in the cluster named mycluster.

In this manual, we show names of MySQL Cluster processes in lowercase. You are not required to follow this convention if you do not wish to do so; however, since the corresponding executables are named and must be invoked in lowercase, we suggest that you use lowercase.

Configuration attribute names are case-insensitive. For example, either of the commands get --include-defaults DataMemory:ndbd mycluster or get --include-defaults datamemory:ndbd mycluster returns the data memory allocated for each ndbd process in the cluster named mycluster; either of the commands set engine-condition-pushdown:mysqld:4=0 mycluster or set Engine-Condition-Pushdown:mysqld:4=0 mycluster disables the condition pushdown optimization in the mysqld process having the node ID 4 in the MySQL Cluster named mycluster.



Note

Configuration attributes in the MySQL Cluster Manager derive from two different sources: MySQL Cluster configuration parameters, and MySQL Server options. MySQL Cluster configuration parameters are case-insensitive, but their canonical forms use upper camelcase (that is, medial capitalization including the first letter). This means that whether you set a value for data memory using the MySQL Cluster Manager client or in the config.ini file, you can refer to it as DataMemory, datamemory, or dATAMEMORY without any negative impact. However, MySQL Server command-line options are case-sensitive and use only lowercase. This means that, for example, set Engine-Condition-Pushdown:mysqld:4=0 mycluster in the MySQL Cluster Manager client works to disable condition pushdown in the indicated mysqld process, but if you invoke the mysqld executable from a system prompt using --Engine-Condition-Pushdown=0, mysqld fails to start.

In this manual, for easy recognition, we show configuration attribute names as having the same lettercase used in other MySQL documentation; thus, we always refer to <code>DataMemory</code>, rather than <code>datamemory</code> or <code>DATAMEMORY</code>, and <code>engine-condition-pushdown</code>, rather than <code>Engine-Condition-Pushdown</code> or <code>ENGINE-CONDITION-PUSHDOWN</code>. While you are not required to do this when using MySQL Cluster Manager, we suggest that you also follow this convention.



Note

Values that contain space characters must be quoted using single quote (') characters. For example, if you wish to define a package named mypackage for a site named mysite using /usr/local/mysql cluster/7.3 (where a space occurs between mysql and cluster) as the path to the base directory on all hosts, the correct command would be add package --basedir='/usr/local/mysql cluster/7.3' mypackage.

To decrease the possibility of errors in reading and entering MySQL Cluster Manager commands, we recommend avoiding the use of space characters whenever possible.

Each command must end with a terminator character. By default, this is the semicolon (i) character. However, the sequences g and g are also supported as command terminators. The g terminator causes the output to be vertically formatted (the same as in the standard g client), as shown in this example:

```
mcm> get DataMemory mycluster\G
       ***************** 1. row *****************
   Name: DataMemory
  Value: 500M
Process1: ndbd
    Id1: 2
Process2:
    Td2:
  Level: Process
Comment:
   ******************* 2. row ****************
   Name: DataMemory
  Value: 500M
Process1: ndbd
    Id1: 3
Process2:
    Id2:
  Level: Process
Comment:
2 rows in set (0.22 sec)
```

By convention (for reasons of readability), we do not normally include the command terminator when showing the syntax for a command in Backus-Naur format or when including a MySQL Cluster Manager command inline in this text. However, if you do not use a statement terminator when you enter the command in the MySQL Cluster Manager client, the client displays a special "waiting..." prompt -> until you supply a terminator, as shown here:

```
mcm> list sites
->
->
->
->
->
[Empty set (1.50 sec)]
```

(The is the same as the behavior of the mysql client when you fail to end a statement with a terminator.)

A command option can also in many cases accept (or even require) a set of one or more *values*. The next example includes such an option, and also demonstrates setting of multiple values in a single option by passing them to the option as a comma-separated list:

The command just shown creates a site named mysite, consisting of two hosts named tonfisk and flundra. (See Section 4.2.6, "The create site Command", for more information about this command.) Since we used the long form of the --hosts option, we were required to use an equals sign (=) to mark the end of the option name and the beginning of the values list. You must not insert any space characters before or after the equal sign; doing so causes an error, as shown here:

```
mcm> create site --hosts =grindval,haj yoursite;
ERROR 7 (00MGR): Option --hosts requires a value
mcm> create site --hosts= grindval,haj yoursite;
ERROR 7 (00MGR): Option --hosts requires a value
```

The short form of an option does not use an equal sign. Instead, the value-list is separated from the option by a space. Using the -h option, which is the short form of the --hosts option, the previous create site command can be entered and executed like this:

The short forms of options actually accept multiple spaces between the option name and the values list; however, a single space is sufficient. If you omit the space, or try to use an equals sign, the command fails with an error, as shown here:

```
mcm> create site -htonfisk,flundra mysite;
ERROR 6 (00MGR): Illegal number of operands
mcm> create site -h=tonfisk,flundra mysite;
ERROR 3 (00MGR): Illegal syntax
```

Any option value containing one or more whitespace characters, one or more dash characters (-), or both, must be quoted using single quotation marks. Multiple values should be separated by commas only; do not insert spaces before or after any of the commas. Using spaces before or after the commas in a list of values causes the command to fail with an error, as shown here:

```
mcm> create site --hosts=tonfisk, flundra mysite;
ERROR 6 (00MGR): Illegal number of operands
```

As you can see from the examples just shown, a MySQL Cluster Manager client command returns a result set, just as an SQL statement does in the standard mysql client. The result set returned by a MySQL Cluster Manager client command consists of one of the following:

- A single row that contains a message indicating the outcome of the command. The create site command in the last example returned the result Site created successfully, to inform the user that the command succeeded.
- One or more rows listing requested objects or properties. An example of such a command is list processes, as shown here:



In the case of list processes, each row in the result contains the ID and type of a node in the MySQL Cluster named mycluster, together with the name of the host on which the process is running.

• An empty result set. This can occur with one of the list commands when there is nothing to report, such as when list sites is used before any sites have been created:

```
mcm> list sites;
Empty set (0.72 sec)
```

Each command must be entered separately; it is not possible to combine multiple commands on a single line.

Options common to client commands.

The following three options are common to most MySQL Cluster Manager client commands:

- 1. --help (short form: -?): Common to all client commands. Provides help output specific to the given command. See Section 4.1, "Online Help and Information Commands", for more information about this option.
- --force (short form -f): Causes any safety checks to be bypassed when executing the
 command. For example, delete cluster mycluster normally fails if any of the MySQL Cluster
 processes in the MySQL Cluster named mycluster are running; however, delete cluster -force mycluster forces the shutdown of mycluster, followed by the deletion of mycluster
 from MySQL Cluster Manager's inventory.

The --force option is supported for the following MySQL Cluster Manager client commands:

- delete site
- start cluster
- restart cluster
- stop cluster
- delete cluster
- add process

- start process
- stop process
- remove process
- set
- reset
- 3. --background (short form -B): Rather than waiting for the command to complete, the MySQL Cluster Manager client immediately returns the command prompt, allowing you to perform additional tasks in the client while that command continues to execute in the background. This can be useful when executing commands that might require some time to complete (such as starting a cluster with a great many nodes).

This option is supported by all client commands except for create site, delete site, add hosts, add package, and delete package.

4.1 Online Help and Information Commands

Online help is available in the MySQL Cluster Manager client for MySQL Cluster Manager client commands. The client can provide both general and command-specific information. In addition, you can obtain information about mysql client commands that are independent of the MySQL server and thus are also available for use when connected to the MySQL Cluster Manager agent.

Listing MySQL Cluster Manager client commands.

For a list of all commands with brief descriptions, use the list command, as shown here:

Obtaining information about specific MySQL Cluster Manager client commands.

To obtain more detailed help specific to a given command, invoke the command using the --help option, as shown in this example:

```
mcm> create site --help;
| Help
 create site [options] <sitename>
       Creates a site from the hosts listed in --hosts.
       Required options:
       --hosts|-h
                           Comma separated list of hostnames.
                           Format: --hosts = <host>[,<host>]*.
       Valid options:
       --background|-B
                           Run command in background, and return prompt
                           to the user immediately.
       --hosts | -h
                           Comma separated list of hostnames.
                           Format: --hosts = <host>[,<host>]*.
13 rows in set (0.00 sec)
```

For any MySQL Cluster Manager client command, the --help option may be abbreviated to -?:

As mentioned elsewhere in this manual (see Chapter 4, *MySQL Cluster Manager Client Commands*), many other MySQL Cluster Manager command options have short forms as well. These are included in the documentation for each command. You can also find out what these are for a given command by invoking it with the --help or -? option.

You can obtain the release version of the MySQL Cluster Manager software in use from the output of the version command.

mysql client commands in the MySQL Cluster Manager client.

You can also use most standard <code>mysql</code> client commands in the MySQL Cluster Manager client (but not SQL statements, which depend on being connected to a MySQL server), such as <code>prompt</code>, <code>quit</code>, and <code>status</code>. For example, the output of the status command when connected to the MySQL Cluster Manager agent looks something like this (depending on the exact version of the client and agent which you are using and possibly other factors):

```
mcm> status
/home/jon/bin/mcm/libexec/../cluster/bin/mysql
Ver 14.14 Distrib 5.6.24-ndb-7.4.6, for linux2.6 (x86_64) using EditLine wrapper
Connection id:
Current database:
                       <n/a>
Current user:
                      admin
                      Not in use
less
SSL:
Current pager:
Using outfile:
                      ;
Using delimiter:
Server version:
                       1.3.6 MySQL Cluster Manager
Protocol version:
                      10
Connection:
                      127.0.0.1 via TCP/IP
                       <n/a>
Server characterset:
     characterset:
                       <n/a>
Client Characterset: <n/a> <n/a> <n/a> 1862
Client characterset:
                       <n/a>
                       <n/a>
```



Note

You may use the command delimiter with mysql client commands, but you are not required to do so. For instance, assuming that the delimiter in use was the default semicolon (;) character, we could have executed the status command like this:

```
mcm> status;
-----/home/jon/bin/mcm/cluster/bin/mysql Ver 14.14 Distrib 5.6.24-ndb-7.4.6,...
```

A particularly useful <code>mysql</code> client command that you can also employ with <code>mcm</code> is the <code>source</code> command (short form: \.), which you can use for executing scripts containing MySQL Cluster Manager client commands. On a Linux system, you might have a text file in your home directory named <code>get-attributes.mcm</code>, whose contents are shown here:

```
get :ndb_mgmd mycluster\G
get :ndbd mycluster\G
get :mysqld mycluster\G
```

Assuming that you have created a cluster named mycluster, you can run this script in the client; the results vary according to how this cluster is actually configured, but should be similar to this:

```
Value: flundra
Process1: ndb_mgmd
NodeId1: 49
Process2:
NodeId2:
 Level:
Comment: Read only
Name: NodeId
  Value: 49
Process1: ndb_mgmd
NodeId1: 49
Process2:
NodeId2:
 Level:
Comment: Read only
Name: PortNumber
 Value: 1186
Process1: ndb_mgmd
NodeId1: 49
Process2:
NodeId2:
 Level: Process
Comment:
4 rows in set (0.09 sec)
mcm> get :ndbd mycluster\G
************************ 1. row ******************
  Name: DataDir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/1/data
Process1: ndbd
NodeId1: 1
Process2:
NodeId2:
 Level:
Comment:
Name: HostName
 Value: tonfisk
Process1: ndbd
NodeId1: 1
Process2:
NodeId2:
 Level:
Comment: Read only
Name: NodeId
 Value: 1
Process1: ndbd
NodeId1: 1
Process2:
NodeId2:
 Level:
Comment: Read only
              ****** 4. row ****************
  Name: DataDir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/2/data
Process1: ndbd
NodeId1: 2
Process2:
NodeId2:
 Level:
Comment:
Name: HostName
 Value: grindval
Process1: ndbd
NodeId1: 2
Process2:
NodeId2:
 Level:
```

```
Comment: Read only
                ****** 6. row **************
  Name: NodeId
  Value: 2
Process1: ndbd
NodeId1: 2
Process2:
NodeId2:
  Level:
Comment: Read only
6 rows in set (0.10 sec)
mcm> get :mysqld mycluster\G
        ************ 1. row ****************
  Name: datadir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/50/data
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
  Level:
Comment:
Name: HostName
  Value: hai
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
 Level:
Comment: Read only
                ****** 3. row ****************
  Name: log_error
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/50/data/mysqld_50_out.err
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
 Level:
Comment:
Name: ndb_nodeid
 Value: 50
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
  Level:
Comment: Read only
Name: ndbcluster
  Value:
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
  Level:
Comment: Read only
*********************** 6. row *****************
  Name: NodeId
  Value: 50
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
 Level:
Comment: Read only
*********************** 7. row *****************
  Name: port
 Value: 3306
Process1: mysqld
NodeId1: 50
```

```
Process2:
NodeId2:
  Level:
Comment:
Name: socket
  Value: /tmp/mysql.mycluster.50.sock
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
 Level:
Comment:
Name: tmpdir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/50/data/tmp
Process1: mysqld
NodeId1: 50
Process2:
NodeId2:
  Level:
Comment:
************************* 10. row ******************
  Name: datadir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/51/data
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
 Level:
Comment:
************************* 11. row *****************
  Name: HostName
  Value: torsk
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
 Level:
Comment: Read only
               ******* 12. row ****************
  Name: log_error
 Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/51/data/mysqld_51_out.err
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
Comment:
************************* 13. row ******************
  Name: ndb_nodeid
  Value: 51
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
  Level:
Comment: Read only
Name: ndbcluster
  Value:
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
 Level:
Comment: Read only
               ******* 15. row ***************
  Name: NodeId
 Value: 51
Process1: mysqld
NodeId1: 51
```

```
Process2:
NodeId2:
  Level:
Comment: Read only
               ******* 16. row ****************
  Name: port
  Value: 3307
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
  Level:
Comment:
 Name: socket
  Value: /tmp/mysql.mycluster.51.sock
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
  Level:
Comment:
             ******* 18. row ***************
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/51/data/tmp
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
  Level:
Comment:
18 rows in set (0.05 sec)
```



Note

You are not returned to the client prompt until the script has finished executing.

Similarly, on Windows, you can create a batch file using Notepad or another text editor, copy the same get commands as shown previously into it, and save it as get-attributes.bat in a convenient location such as the Windows desktop.

You can view a list of available mysql client commands using the help command. For more information about these, view the help output or see mysql Commands, in the MySQL Manual.

4.2 MySQL Cluster Manager Site and Agent Commands

In this section, we discuss commands used to work with MySQL Cluster Manager management sites. In addition, the stop agents, show settings, version, and show warnings commands, which relate to management agents, are also covered in this section.

A *site*, in terms of MySQL Cluster and MySQL Cluster Manager, is a collection of one or more host computers where MySQL Cluster Manager agents are running. Each agent is identified by the combination of two pieces of information:

- The hostname or IP address of the machine where the agent is running
- The number of the port used by the agent for communications



Note

MySQL Cluster makes extremely intensive use of network connections, and DNS lookups can contend with MySQL Cluster and MySQL Cluster Manager for bandwidth, resulting in a negative impact on the performance of MySQL Cluster and the applications using it. For this reason, we recommend that you use

numeric IP addresses rather than hostnames for MySQL Cluster and MySQL Cluster Manager host computers whenever feasible.

4.2.1 The add hosts Command

```
add hosts --hosts=host_list site_name
host_list:
   host[, host[, ...]]
```

This command adds one or more hosts to an existing management site. Agents using the same port as the management site must be running on any hosts added using this command. This command takes to mandatory arguments: a list of hosts (using the --hosts option), and the name of the site to which the hosts are to be added.

The --hosts takes a comma-separated list of one or more hosts to be added to the site.

For example, the following command adds two hosts named torsk and kolja to management site mysite:

None of the hosts added by this command may already be members of management site <code>site_name</code>. Do not attempt to add again a host that is already a member of the management site using its secondary (or alternate) IP address—the <code>mcmd</code> process on the host is already bound to the IP address that was supplied when the host was first added, and it cannot be bound again to another IP address.



Notes

- This command does not support the --force option.
- Do not use localhost in the host list, as MySQL Cluster Manager relies on the operating system for host name resolution, and localhost might be resolved differently on different systems. Use proper host names for the host list or, preferably, use the IP addresses for the hosts instead.
- When IPv6-enabled Windows systems are used as MySQL Cluster hosts under MySQL Cluster Manager, you must reference these hosts using IPv4 addresses. Otherwise, MySQL Cluster Manager will be unable to connect to the agent processes on those hosts. See Section 5.1, "MySQL Cluster Manager Usage and Design Limitations".

4.2.2 The remove hosts Command

```
remove hosts --hosts=host_list site_name

host_list:
    host[, host[, ...]]
```

This command removes one or more hosts from an existing management site. It takes as arguments a required option --hosts, whose value is a comma-separated list of one or more hosts to be removed, and the name of the site from which the hosts are to be removed. A number of limitations apply:

• The name of the host to be removed must not be localhost or 127.0.0.1.

- The host to be removed must not have any managed processes from any clusters assigned to them (remove those processes first with the remove process command); it can have unmanaged processes assigned to them though (typically, ndbapi@hostname or mysqld@*hostname).
- There should not be any packages defined with explicit paths pointing to the host to be removed.
- A quorum consists of a majority of hosts (i.e., half of the total number of hosts plus one) must exist
 for the site both before and after the host's removal, or it will not be possible to execute the remove
 host command.
- You cannot remove the last host from a site; use the delete site command instead.

The following command removes two hosts named tonfisk and flundra from the management site mysite:

4.2.3 The change log-level Command

```
change log-level [{--hosts=|-h }host_list] log_level site_name
host_list:
   host[,host[,...]]
```

Set the management agent's cluster logging level. This has the same effect as using the --log-level option; however, unlike the option, this command can be used at run time and does not require a restart of mcmd. Issuing this command overrides any value for --log-level set on the command line or in the agent configuration file.

When used with the <code>log_level</code> alone without a <code>host_list</code> and a <code>site_name</code>, this command applies only to the agent the <code>mcm</code> client is connected to. In the following example, the logging level is set to <code>warning</code> only on the host managed directly by the agent to which the <code>mcm</code> client is connected:

You can specify the name of a site to be affected by the command. For example, the following invocation of the command applies to the site named mysite:

You can also restrict the change to one or more hosts in a given site using the --hosts option, with multiple host names separated by commas. The following command changes the logging level to debug on the hosts named tonfisk and haj, but not on any other hosts in mysite:

You must specify a site when using the --hosts option; trying to use --hosts alone results in an error

Accepted values for <code>log_level</code> are the same as for the <code>--log-level</code>: one of <code>debug</code>, <code>critical</code>, <code>error</code>, <code>info</code>, <code>message</code>, or <code>warning</code>. For more detailed information about the meanings and effects of these values, see <code>MySQL</code> Cluster Logging Management Commands.

4.2.4 The rotate log Command

```
rotate log [--hosts=host_list] [site_name]
host_list:
  host[,host[,...]]
```

Rotate mcmd logs for the connected MySQL Cluster Manager agent, for agents running on certain hosts, or for agents on all hosts in a management site.

For example, to rotate logs for the agent to which the client session is connected:

A new log file, with a timestamp in its name, is created as a result:

```
-rw-r---- 1 mcmd cluster 74265 Jul 15 22:45 mcmd.log
-rw-r---- 1 mcmd cluster 1197573 Jul 15 22:45 mcmd.log.2014-07-15T22-45-28
```

To rotate logs for agents on hosts nanna12 and nanna13:

```
mcm> rotate log --hosts=nanna12,nanna13 mysite;
```

To rotate logs on all agents in the management site mysite:

```
mcm> rotate log mysite;
```

4.2.5 The collect logs Command

```
collect logs [cluster_name]
```

This command collects log files and other related files from all hosts. When the name of a cluster (cluster_name) is supplied with the command, it collects all the log files (.log) as well as the configuration files (.ini, .cnf), error files (.err), and option files (.opt) used by all processes belonging to the cluster, and also all the agent log files.

The collected files are put under the MySQL Cluster Manager data repository (/opt/mcm_data/ by default, or specified by the option --manager-directory) inside a folder named collected_files, under which the files are organized under a hierarchy of timestamps [for the file

collections] and then host names; below the host name level, the file organization mimics that on the host. For example, the agent log for the host tonfisk, collected on 2014-07-31 at 07:44:05, is found at:

/opt/mcm_data/collected-files/2014-07-31T07:44:05Z/tonfisk/opt/mysql/logs/mcmd-tonfisk-19001.log

If *cluster_name* is omitted, only the agent log files are collected.

4.2.6 The create site Command

```
create site {--hosts=|-h }host_list site_name
host_list:
   host[,host[,...]]
```

The create site command is used to create a MySQL Cluster Manager management site; that is, a set of MySQL Cluster Manager management agents running on one or more host computers. The command requires a list of one or more hosts where management agents are running and a name for the site. The host list is passed as the value of the --hosts option (short form: -h).

This is an example of a create site command that creates a site named mysite, consisting of the hosts tonfisk and flundra:



Tip

You can verify that the site was created as intended, using the list sites command, as shown here:

```
mcm> list sites;
+-----+----+
| Site | Port | Local | Hosts |
+-----+----+
| mysite | 1862 | Local | tonfisk,flundra |
+-----+----+
1 row in set (0.06 sec)
```

(See Section 4.2.8, "The list sites Command", for more information about this command.)

Agents must be running on all hosts specified in the --hosts option when create site is executed; otherwise, the command fails with the error Agent on host host:port is unavailable. The host where the agent used to issue the command is running must be one of the hosts listed. Otherwise, the command fails with the error Host host_name is not a member of site site_name.

A given agent may be a member of one site only; if one of the management agents specified in the host_list already belongs to a site, the command fails with the error Host host is already a member of site site.



Notes

• Do not use localhost in the host list, as MySQL Cluster Manager relies on the operating system for host name resolution, and localhost might be

resolved differently on different systems. Use proper host names for the host list or, preferably, use the IP addresses for the hosts instead.

 When IPv6-enabled Windows systems are used as MySQL Cluster hosts under MySQL Cluster Manager, you must reference these hosts using IPv4 addresses. Otherwise, MySQL Cluster Manager will be unable to connect to the agent processes on those hosts. See Section 5.1, "MySQL Cluster Manager Usage and Design Limitations".

4.2.7 The delete site Command

```
delete site site_name
```

The delete site command deletes an existing management site. The command does not stop or remove any agents making up the deleted site; instead, these agents continue to run, and remain available for use in other sites.

The command takes a single argument, the name of the site to be deleted. This example shows the deletion of a management site named mysite:

If the site to be deleted does not exist, the command fails with the error Command requires a site to be defined. If there are any packages referencing hosts belonging to the site, delete site fails with the error Packages exist in site site_name. The command also fails if there are defined any clusters that include hosts belonging to the site.



Note

The management client must be connected to a site in order to be able to delete it.

In addition, if you execute a delete site command with the --force option using one management agent while a different management agent is not running, you must remove the "missing" management agent's site files manually. For more information on site files, see Section 2.4, "MySQL Cluster Manager Configuration File".

4.2.8 The list sites Command

```
list sites
```

This command returns a list of the sites known to the management agent. It does not require any arguments. An example is shown here:

```
mcm> list sites;
+-----+
| Site | Port | Local | Hosts |
+-----+
| mysite | 1862 | Local | tonfisk,flundra |
+-----+
1 row in set (0.06 sec)
```

The output of list sites contains the following columns:

- Site. The name of the site.
- Port. The TCP/IP port used for communications between clients and management agents.
- Local. Either one of Local or Remote.
- Hosts. A comma-separated list of the hosts making up the site.

4.2.9 The list hosts Command

```
list hosts site_name
```

The list hosts command is used to obtain a list of the hosts comprising a given management site. The command requires a single argument, the name of the site to be examined. For each host listed, the information returned includes the hostname, status, and version of the management agent software in use, as shown in this example:

If you omit the site_name argument, the command fails with an error, as shown here:

```
mcm> list hosts;
ERROR 6 (00MGR): Illegal number of operands
```

Using the --verbose option (short form : -v) causes the command to print additional information on the hosts:

4.2.10 The show settings Command

```
show settings
```

This command lists the current values of a number of mcmd options:

The show settings command takes no arguments.

4.2.11 The stop agents Command

```
stop agents [[--hosts=host_list] site_name]
```

This command stops one or more MySQL Cluster Manager agents on one or more hosts.

When used without any arguments, stop agents stops the agent to which the client is currently connected.

When used with the name of a management site, the command stops all agents running on hosts making up the site. The following stops all MySQL Cluster Manager agents running on hosts in mysite:

```
mcm> stop agents mysite;
```

You can also stop a subset of the agents in a given management site by listing the hosts where they are running with the --hosts option, along with the name of the site to which they belong. The result of the following command is to stop MySQL Cluster Manager agents running on hosts kolja and torsk, both of which are members of the management site mysite:

```
mcm> stop agents --hosts=kolja,torsk mysite;
```

Multiple host names following the --hosts option should be separated by commas, with no intervening spaces. Invoking stop agents with this option without supplying a <code>site_name</code> causes a syntax error. Using an undefined <code>site_name</code> or names of hosts not belonging to the site with this command also results in an error.



Note

When IPv6-enabled Windows systems are used as MySQL Cluster hosts under MySQL Cluster Manager, you must reference these hosts using IPv4 addresses. Otherwise, MySQL Cluster Manager will be unable to connect to the agent processes on those hosts. See Section 5.1, "MySQL Cluster Manager Usage and Design Limitations".

4.2.12 The version Command

version

This command displays the version of the MySQL Cluster Manager software in use by the MySQL Cluster Manager agent to which this client is connected, as shown here:

The version command takes no arguments.

4.2.13 The show warnings Command

Using the show warnings command (available for MySQL Cluster Manager 1.3.4 and after), you can check the warnings (up to the last five) issued to the agent log (mcmd.log). For example:

4.3 MySQL Cluster Manager Package Commands

This section contains information about MySQL Cluster Manager client commands used to register, extend, unregister, and obtain information about the software packages making up instances of MySQL Cluster that are to be managed using the MySQL Cluster Manager.

4.3.1 The add package Command

```
add package {--basedir=|-b }path
  [{--hosts=|-h }host_list] package_name
host_list:
  host[,host[,...]]
```

This command creates a new package, or, if the package named <code>package_name</code> already exists, this command extends the package definition.

The --basedir option (short form: -b) indicates the location of the MySQL Cluster installation directory on the listed hosts, and is required. This must be the path to the top-level directory where the MySQL Cluster software is located (for example, /usr/local/mysql), and should *not* include the MySQL Cluster bin, libexec, or other subdirectory within the installation directory.

Hosts may be specified as a comma-separated list, using the --hosts option (short form: -h); however, this option is not required. If --hosts is omitted, the *path* is assumed to be valid for all hosts in the cluster that is created using this package (see Section 4.4.1, "The create cluster Command").



Important

- You cannot perform add package if you have not yet defined any sites
 (each host referenced in an add package command must be associated
 with a site). See Section 4.2.6, "The create site Command", for more
 information about defining sites.
- When a package is first added for a site with the add package command, whenever the --hosts option is used, the host list must contain the host for the mcmd agent to which the mcm client is currently connected, in order to allow the MySQL Cluster Manager to access the version information of the package.

Suppose we have two Linux hosts named tonfisk and flundra, and the MySQL Cluster software is installed in /usr/local/mysql on both hosts. In this case, you can create a package named mypackage that accounts for both hosts as shown here:

When this package is used to create a cluster, the MySQL Cluster Manager knows that it should find the MySQL Cluster software in the /usr/local/mysql directory on each of the hosts.

For options to MySQL Cluster Manager client command options having Windows paths as values, you must use forward slashes (/) in place of backslashes (\), so if tonfisk and flundra are Windows hosts where MySQL Cluster has been installed to the directory C:\mysql, the corresponding add package command would look like this (with the --basedir option highlighted):

In the example just given, we could also have issued the command as add package --basedir=/usr/local/mysql --hosts=tonfisk,flundra mypackage (or add package --basedir=c:/mysql --hosts=tonfisk,flundra mypackage on Windows) with the same result, but the --hosts option was not required, since the MySQL Cluster software's location is the same on each host. Let us suppose, however, that the software is installed in /usr/local/ndb-host-10 on host tonfisk and in /usr/local/ndb-host-20 on host flundra. In this case, we must issue 2 separate commands, specifying the host as well as the base directory in each case, as shown here:

Assuming that both hosts belong to a site called mysite, you can verify that these packages have been created as desired using the list packages command, as shown here:

(For more information about this command, see Section 4.3.3, "The list packages Command".)

It is possible to assign the same base directory (or directories) on the same host (or hosts) to multiple packages, as shown in this example, in which we assume that hosts tonfisk and flundra have previously been assigned to a site named mysite:



Note

When IPv6-enabled Windows systems are used as MySQL Cluster hosts under MySQL Cluster Manager, you must reference these hosts using IPv4 addresses. Otherwise, MySQL Cluster Manager will be unable to connect to the agent processes on those hosts. See Section 5.1, "MySQL Cluster Manager Usage and Design Limitations".

4.3.2 The delete package Command

```
delete package [{--hosts=|-h }host_list] package_name
host_list:
    host[,host[,...]]
```

This command is used to unregister a package. More specifically, it removes any references to MySQL Cluster software installations added to the agent's repository when the package was created. delete package does not remove any MySQL Cluster installations; the command removes only references to the installations. Once a package has been unregistered, it can no longer be used for a create cluster command. The MySQL Cluster binaries remain, but cannot be used in a MySQL Cluster administered using the MySQL Cluster Manager unless and until the base directory containing them has been registered with another package. (It is possible to register a base directory with multiple packages; see Section 4.3.1, "The add_package Command", for more information and an example.)

If the --hosts option (short form: -h) is used with this command, the base directory settings for the host or hosts named by the option are removed as well. All hosts given in the <code>host_list</code> must be members of the site to which the package is registered. Otherwise, the command fails.

A package that is in use by a cluster cannot be unregistered; the cluster must first be deleted (see Section 4.4.2, "The delete cluster Command").

Here is an example that demonstrates how to unregister a package named mypackage:

```
mcm> delete package mypackage;
```

You can also verify that the package was unregistered using the list packages command; the package name should no longer appear in the output of this command. If you attempt to use the unregistered package in a create cluster command, the command fails, as shown here:

```
mcm> create cluster --package=mypackage
    > --processhosts=ndb_mgmd@tonfisk,ndbd@grindval,ndbd@flundra,mysqld@tonfisk mycluster;
ERROR 4001 (00MGR): Package mypackage not defined
```

An upgrade cluster command that references an unregistered package also fails.



Note

When IPv6-enabled Windows systems are used as MySQL Cluster hosts under MySQL Cluster Manager, you must reference these hosts using IPv4 addresses. Otherwise, MySQL Cluster Manager will be unable to connect to the agent processes on those hosts. See Section 5.1, "MySQL Cluster Manager Usage and Design Limitations".

4.3.3 The list packages Command

```
list packages [package_name] site_name
```

This command lists registered packages. It requires a single argument, that being the name of the site with which the packages are registered, as shown in this example:

Package	Path	Hosts
i	/usr/local/ndb-host-10 /usr/local/ndb-host-20 /usr/local/mysql	tonfisk flundra tonfisk,flundra

If tonfisk and flundra are Windows hosts, the list of packages might look something like this:

Package	Path	Hosts
yourpackage		tonfisk flundra
mypackage	c:/mysql	tonfisk,flundra

In the example just shown, yourpackage uses the MySQL Cluster binaries installed at C:\cluster \ndb-host-10 on host tonfisk, and at C:\cluster\ndb-host-20 on flundra; mypackage uses MySQL Cluster binaries installed at C:\mysql on both hosts.

The output contains three columns; these are described in the following list:

• Package. The name of the package. This can sometimes be empty when a package includes MySQL Cluster installations that are in different locations on different hosts (see next example).

• Path. The path to the MySQL Cluster installation directory (base directory) on the indicated host or hosts. This is the same as the value given for the --basedir option in the add package command that was used to create or augment the package.

On Windows, paths shown in this column have any backslash characters converted to forward slashes, just as must be done for the --basedir option (see the earlier example in this section).

• Hosts. The host or hosts where the MySQL Cluster installation or installations are located.

You can filter the results so that information relating to only a single package is displayed by supplying the package name before the site name, as shown here:

(See Section 4.3.1, "The add package Command", for the add package commands that were used to create yourpackage.)

When a package contains MySQL Cluster installations using different base directories on different hosts, each unique combination of path and host is shown in its own row. However, the name of the package is displayed in the first row only; all rows that immediately follow this row and that do not contain the package name also relate to the same package whose name is shown in the first preceding row to display a package name. For example, consider the list packages command and output shown here:

This output shows that there are two packages defined for the site named mysite; these packages are named yourpackage and mypackage. The package yourpackage consists of the MySQL Cluster binaries in the directory /usr/local/ndb-host-10 on host tonfisk, and in the directory /usr/local/ndb-host-20 on host flundra. The package named mypackage consists of the MySQL Cluster binaries in the directory /usr/local/mysql on host tonfisk, and in the directory /usr/local/bin/mysql on host flundra.

If you omit the site_name argument, the command fails with an error, as shown here:

```
mcm> list packages;
ERROR 6 (00MGR): Illegal number of operands
```

4.4 MySQL Cluster Manager Cluster Commands

This section contains descriptions of MySQL Cluster Manager commands used to perform operations on clusters. These include creating and deleting a cluster; starting, stopping, and restarting a cluster; upgrading a cluster (that is, upgrading the MySQL Cluster software used by a given cluster); and listing clusters known to MySQL Cluster Manager.

4.4.1 The create cluster Command

```
create cluster {--package=|-P }package_name
    {--processhosts=|-R }process_host_list cluster_name
    [(--import|-m) cluster_name] [--verbose | -v]

process_host_list:
    process_name[:node_id]@host[,process_name@host[,...]]

process_name:
    {ndb_mgmd|ndbd|ndbmtd|mysqld|ndbapi}
```

This command creates a cluster to be managed by the MySQL Cluster Manager. However, it does not start the cluster (see Section 4.4.7, "The start cluster Command").

This command can also be used to create a cluster earmarked specifically as a target for importing another cluster that is not already under MySQL Cluster Manager control, as described later in this section, by employing the --import option. See also Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager".

create cluster requires the following arguments:

- A package_name, supplied as the value of the --package option (short form: -P). This must be the name of a package previously registered using add_package.
- A list (process_host_list) of MySQL Cluster processes, the hosts on which they are to run, and
 —optionally—their node IDs, supplied as the value of the --processhosts option (short form: -R),
 with list items separated by commas. As with other lists passed as option values in MySQL Cluster
 Manager commands, you must not use spaces before or after the commas.

Each item in the <code>process_host_list</code> consists of the name of a MySQL Cluster process—possibly suffixed with a colon (:) character followed by the process node ID—joined with the name of the host on which it is located using an amphora (@) sign (also sometimes known as the "at" sign). Permitted values for processes are <code>ndb_mgmd</code>, <code>ndbd</code>, and <code>mysqld</code>. When the cluster employs MySQL Cluster NDB 7.0 or later, you can also use <code>ndbmtd</code> as process name; in other words, a valid process name is the name of a MySQL Cluster process daemon binary. If node IDs are specified, they must be within the allowed range for the type of node defined.

To support running your own NDB API applications with a cluster under MySQL Cluster Manager, it is also possible to use ndbapi as a process type. Such applications can be connected to a managed cluster. Currently, MySQL Cluster Manager recognises only that an NDB API application is connected to the cluster; the NDB API application itself must be started, stopped, and configured manually.

It is also possible to specify one or more "free" mysqld and ndbapi processes without any hosts. To do this, simply use the wildcard * (asterisk character) in place of the hostname or IP address, as shown in the following table:

"Free" mysqld process:	mysqld@*
"Free" ndbapi process:	ndbapi@*

It is also possible to specify a node ID for a "free" process. (If this is not specified, MySQL Cluster Manager assigns a suitable node ID automatically.)

A mysqld process or ndbapi process that is specified without a host in this fashion is permitted to connect to the cluster from any host that can access the cluster over the network. Otherwise, the process may connect to the cluster only from the specified host.

By convention, items in the *process_host_list* are listed according to the process type, in the following order:

- Management node processes (ndb_mgmd)
- 2. Data node processes (MySQL Cluster NDB 6.3: ndbd; MySQL Cluster NDB 7.0 and later. ndbd, ndbmtd)
- 3. SQL node processes (mysqld)
- 4. Custom NDB API applications (ndbapi)

For information about writing your own NDB API applications, see The NDB API, in the *MySQL Cluster API Developer Guide*.

While the order in which the items are listed does not affect whether the create cluster command succeeds, we suggest that you follow this convention for readability, as well as compatibility with other MySQL Cluster management tools such as ndb mgm.

create cluster causes cluster node IDs to be assigned consecutively, in the order that the nodes are specified in the <code>process_host_list</code>, with node IDs for data node processes starting with 1, and node IDs for processes other than data node processes starting with 49. For MySQL Cluster Manager 1.3.3 and earlier, trying to manually assign node IDs less than 49 for ndb_mgmd, mysqld, or ndbapi fails with an error; the restriction, however, has been relaxed in two ways:

- For MySQL Cluster Manager 1.3.1 and later, the --import [89] option causes this restriction to be ignored, as discussed later in this section.
- For MySQL Cluster Manager 1.3.4 and later, the restriction has now been totally lifted. However, you are still recommended to follow the best practice of reserving node ID 1 to 48 for data nodes.

Each host referenced in the list must be part of the site for which the package used in create cluster is defined.

For processes of types <code>mysqld</code> and <code>ndbapi</code>, the hostname is required, but not enforced in the running cluster. In other words, an <code>[api]</code> section is created in the cluster <code>config.ini</code> file, but no <code>HostName</code> parameter is specified; thus, the <code>mysqld</code> or <code>ndbapi</code> can connect from any host. (Currently, there is no way using <code>MySQL</code> Cluster Manager to specify that a <code>mysqld</code> or <code>ndbapi</code> process is restricted to connecting from a single host.)

• A name for the cluster. Once the cluster has been created, this name is used to refer to it in other cluster management commands such as delete cluster, start cluster, and stop cluster. Like other object names used with MySQL Cluster Manager, the cluster_name must be valid according to the rules given elsewhere in this document for identifiers (see Chapter 4, MySQL Cluster Manager Client Commands).

An additional --verbose option for this command causes create cluster to output extra information as it is executed, as shown later in this section.

The --import option, introduced in MySQL Cluster Manager 1.3.0, flags the cluster as being created as a target for importing a cluster created outside MySQL Cluster Manager. This option causes the cluster's status to appear as import in the output of show status, as shown here:

+	statusp	+	·	+	·
NodeId	Process	Host	Status	Nodegroup	Package
1 5 6 10 11	ndb_mgmd ndbd ndbd mysqld ndbapi	alpha beta gamma delta *	import import import import import	n/a n/a	newpackage newpackage newpackage newpackage
6 rows in	rows in set (0.04 sec)				

Having the import status causes any of the commands start cluster, restart cluster, start process, and stop process to fail if they are executed before an import cluster command has been executed against this cluster. It is also not possible to execute upgrade cluster on a cluster having processes with import status. Other operations on this cluster continue to be performed normally.

Beginning with MySQL Cluster Manager 1.3.1, the --import option also overrides the usual requirement (effective until MySQL Cluster Manager 1.3.4) that node IDs assigned to processes other than data nodes must be greater than 48. (Bug #18181039)



Caution

While it is possible to import into a cluster that was created without this option, it is not advisable, since the cluster is not protected against accidentally performing any of the operations listed previously, which may result in confusing or misleading errors, and possibly other problems. For this reason, it is strongly recommended that you always use the --import option for creating the cluster in such cases.

For more information about importing clusters into MySQL Cluster Manager, including examples, see Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager".

Example

Consider the following command issued in the MySQL Cluster Manager client, which creates a cluster named mycluster:

As defined by the command just shown, mycluster consists of four nodes: a management node on host flundra; two data nodes—one on each of the hosts tonfisk and grindval; and one SQL node, also on host flundra.

Using the --verbose option causes the command to print output similar to that produced by the list processes command, as shown here:

You can also create this cluster in such a way that the mysqld process is permitted to connect to the cluster from any host able to reach the other cluster hosts over the network as shown here:

```
mcm> create cluster --package=mypackage
   -> --processhosts=ndb_mgmd@flundra,ndbd@tonfisk,ndbd@grindval,mysqld@*
   -> mycluster;
+-----+
```



Note

In the case of a "free" ndbapi process, it is not necessary to have the MySQL Cluster Manager software installed on the host where the ndbapi process is running.

Configuration changes to the newly-created cluster can be made using the set command prior to starting the cluster. This is often preferable to doing after the cluster has been started, since set commands used to make configuration changes in a running cluster can require a rolling restart, and rolling restarts of clusters having many nodes or large quantities of data (or both) may take a great deal of time to complete.



Note

When creating a cluster having more than one mysqld process on the same host machine, MySQL Cluster Manager assigns the MySQL default port (3306) to each of them. Therefore, you must assign a unique port for each mysqld process in the cluster.

4.4.2 The delete cluster Command

```
delete cluster [--removedirs] cluster_name
```

This command deletes the cluster named *cluster_name*, removing it from the list of clusters managed by MySQL Cluster Manager.

delete cluster does *not* remove any MySQL Cluster binaries from hosts. However, it *does* remove the cluster configuration, data, and log files that reside in the MySQL Cluster Manager data repository (which is usually at /opt/mcm_data/).

This example demonstrates how to delete a cluster named mycluster:

A look at the MySQL Cluster Manager data repository (at /opt/mcm_data/ in this case) shows that the folder that used to host the configuration, data, and log files for mycluster (/opt/mcm_data/clusters/mycluster) no longer exists:

```
shell> ls -l /opt/mcm_data/clusters
total 0
```

To remove the configuration and data files outside of the MySQL Cluster Manager data repository, delete cluster must be invoked with the --removedirs option, like this:

For example, if one of the data node on mycluster has its data directory outside of the MySQL Cluster Manager data repository:

Deleting mycluster without using --removedirs does not remove the data directory for node 1:

```
shell> ls -1 /home/dso/mycluster
total 4 drwxr-xr-x. 3 dso dso 4096 Sep 10 18:00 cdata
```

However, if the --removedirs option is used, the data directory for node 1 also gets removed:

```
shell> 1s -1 /home/dso/mycluster
total 0
```

delete cluster fails if the cluster to be deleted is running, as shown here:

```
mcm> delete cluster mycluster;
ERROR 5010 (00MGR): All processes must be stopped to delete cluster mycluster
```

You must shut down the cluster first, using stop cluster.

4.4.3 The list clusters Command

```
list clusters site_name
```

This command lists all clusters defined for a given management site named <code>site_name</code>, together with the package used by each cluster. For example, the command shown here displays a list of all clusters defined for the site named <code>mysite</code>:

If site_name is omitted, the command fails with an error, as shown here:

```
mcm> list packages;
ERROR 6 (00MGR): Illegal number of operands
```

4.4.4 The list nextnodeids Command

```
list nextnodeids cluster_name
```

MySQL Cluster Manager normally assigns IDs to new node processes automatically (although this can be overridden when issuing the create cluster or add process command). The list nextnodeids command can be used to see the next node ID that MySQL Cluster Manager has reserved for the next new process (of each possible process type) to be added to the cluster named cluster_name, which is required.

4.4.5 The restart cluster Command

```
restart cluster cluster_name
```

This command performs a rolling restart (see Performing a Rolling Restart of a MySQL Cluster) of the cluster named <code>cluster_name</code>. The cluster must already be running in order for this command to succeed. (For information about how to determine the operation state of the cluster, see Section 4.4.6, "The show status Command".)

For example, the command shown here performs a rolling restart of the cluster named mycluster:

If the cluster is not already running, restart cluster fails with an error, as shown here:



Note

Depending on the number of nodes and the amount of data stored in the cluster, a rolling restart can take a considerable amount of time, up to several hours for a cluster with a great many data nodes and a large amount of data. For this reason, you may want to execute this command with the --background option (short form -B) to allow it to run in the background, freeing the MySQL Cluster Manager client for other tasks.

Currently, there is no mechanism in MySQL Cluster Manager for performing system initial restarts of a cluster. This means that attributes that require an initial restart to be changed must be set before the cluster is started for the first time.

4.4.6 The show status Command

```
show status --cluster|-c cluster_name
show status --operation|-o cluster_name
show status --backup|-b cluster_name
show status --process|-r cluster_name
```

This command is used to check the status of clusters, cluster processes, backups, and commands issued in the MySQL Cluster Manager client. The type of status returned depends on which of the four

options of --cluster (short form: -c), --operation (short form: -o), --backup (short form: -b), or --process (short form -r) is used with the command. (If none of these is used, --cluster is assumed.) These options are described in more detail in the next few paragraphs.

--cluster

When this option is used, show status reports on the status of the cluster named <code>cluster_name</code>, as shown in this example:

	mcm> show statuscluster mycluster;		
Cluster		Comment	
mycluster	fully operational	İ	
1 row in set		r	

When used with the --cluster option (short form: -c), the output of this command consist of two columns. The Cluster column contains the name of the cluster. The Status column contains a description of the cluster's status; possible values and their meanings are shown in the following table:

Status Value	Meaning
fully operational	All cluster processes are running.
operational	All node groups are up and running, but at least one data node process (ndbd or ndbmtd) is not running. The cluster is online, but you should determine why any "missing" data nodes are not running and correct the problem as soon as possible.
non-operational	The cluster is not operational, because at least one node group is offline. You must investigate and fix the problem or problems, then restart the cluster, before the cluster can be used for data storage and retrieval operations.
stopped	The cluster is not running, because it has been stopped by the user. This normally does not indicate any problem as such, but you must restart the cluster before it can be used by any applications.
created	The cluster has been created successfully using the create cluster command, but has never been started. You must start the cluster using the start cluster command before you can make use of it.
unknown	The MySQL Cluster Manager was unable to determine the cluster's status. This may or may not indicate a problem with the cluster; it is possible that the problem lies with one or more MySQL Cluster Manager agents or the MySQL Cluster Manager client. You should attempt to determine the status of the cluster by other means, such as using show statusprocess in the MySQL Cluster Manager client (described later in this section), or employing one of the commands available in the ndb_mgm client (see ndb_mgm — The MySQL Cluster Management Client) such as SHOW or ALL STATUS.

--operation option

When the --operation option (short form: -o) is used, it causes SHOW STATUS to display the status of the latest command to be executed. This includes commands that were issued using the --background option (short form -bg). An example of this command is shown here:

mcm> show status -		•
Command	Status	Description
restart cluster		

```
+----+
1 row in set (1.60 sec)
```

The output contains 3 columns, described in the following list:

- Command. The text of the command last issued (previous to the show status --operation command), less any options or arguments.
- Status. The current state of the command. Possible values and their meanings are listed later in this section.
- **Description.** In some cases, depending on the command and its status, this column may contain additional information. Otherwise, <no message> is displayed here.

Possible values for the Status column, together with descriptions of these values, are shown in the following table:

Status Value	Description
executing	MySQL Cluster Manager is executing the command, but has not yet completed doing so.
finished	The command has executed (and completed) successfully.
failed	The command failed to execute. The Description column may contain information about the reason for the failure.
unknown	MySQL Cluster Manager was unable to determine the status of this command.

--backup option

When this option is used, show status reports on the status of the backup process for the cluster named <code>cluster_name</code>, as shown in the following examples:

--process option

When run with this option, show status returns information about each process in the cluster named <code>cluster_name</code>, as shown in this example:

When the --process option (short form: -r) is used with show status, the output contains 5 columns, described in the following list:

- Id. This is the node ID of the process as a node in cluster cluster_name.
- Process. The type of process, that is, the name of the corresponding MySQL Cluster executable. Allowed values are ndb_mgmd, ndbd, ndbmtd, and mysqld.
- Host. The hostname or IP address of the computer where the process is running.
- Status. The state or condition of this process. Possible values for this column are given later in this section.
- Nodegroup. If the Process is ndbd or ndbmtd—that is, if the process is a data node process—then this column shows the ID of the node group to which the process belongs. For any other value of Process, this column is empty.

Possible values for the Status column are shown in the following table, together with a description of what this value represents:

Status Value	Meaning
running	The process is running normally.
stopped	The process has been stopped by the user.
added	The process has been added to the cluster, but not yet started.
starting	The process has been started, but is not yet fully running. (For data nodes, you can determine which start phase the node is currently in by using the status command in the ndb_mgm client.)
stopping	The process has received a command to stop, and is now shutting down.
failed	The process has shut down unexpectedly (likely to have crashed). You should determine the cause for this unplanned shutdown, fix the problem, and restart the process as soon as possible.
import	The process is part of a cluster that was created for import, but the actual migration of processes and data from the original cluster has not yet taken place. start process and stop process commands fail for this process until this migration has occurred.
unknown	MySQL Cluster Manager is unable to establish the current status of this process. You should try to determine its status using other means.

You must supply the name of an existing cluster with this command, or else show status fails with an error, as shown here:

```
mcm> show status;
ERROR 6 (00MGR): Illegal number of operands
mcm> show status -c nosuchcluster;
ERROR 5001 (00MGR): Cluster nosuchcluster not defined
```



Important

Do not confuse this command with the MySQL SHOW STATUS statement, which has a different syntax, and which can be used only in the standard ${\tt mysql}$ client. The MySQL Cluster Manager client command accepts only those options shown at the beginning of this section, and does not accept a LIKE or WHERE clause.

4.4.7 The start cluster Command

```
start cluster [--initial|-i] cluster_name
```

This command starts the cluster named cluster_name, as shown in this example:

In order for the command to succeed, the cluster named in the command must already exist; otherwise the command fails with the error Cluster cluster name not defined, as shown here:

In addition, the cluster must not already be running, as shown here:

A cluster created for import cannot be started until the import has been completed. See Section 4.4.1, "The create cluster Command", and Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager", for more information.

```
--initial
```

The --initial option (short form: -i) causes all cluster data node processes to be started as if start process --initial had been used, which means that all data nodes wipe their data and start with clean data node file systems. NDB tables that were previously stored in the cluster are lost.

Under normal circumstances, you should use this option to start a cluster only when either you do not wish to preserve any of its data (and want to make a clean start), or you intend to restore the cluster from backup to a known good state (see Section 4.7.4, "The restore cluster Command"). You should also be aware that no special warnings are printed by the mcm client when --initial is used with start cluster; the command is immediately executed.

For information about creating cluster backups, see Section 4.7.2, "The backup cluster Command". If you need to know which backups are available (if any), use list backups.

Using the --initial option with start cluster does not cause mysql_install_db to be executed, or the mysql system database to be altered or removed, on any SQL nodes. This option also does not remove MySQL Cluster Disk Data tablespace files; if their removal is needed, it must be performed manually.

4.4.8 The stop cluster Command

```
stop cluster cluster_name
```

This command stops the cluster named cluster_name, if it is running, as shown in this example:

stop cluster fails if the cluster is not in an operational state (see Section 4.4.6, "The show status Command", for information about obtaining the cluster's status):

stop cluster cannot be used on a cluster created for import until the import has been completed. See Section 4.4.1, "The create cluster Command", and Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager", for more information.

4.4.9 The upgrade cluster Command

```
upgrade cluster {--package=|-P }package_name
[--set=attribute_assignment_list] cluster_name
attribute_assignment_list:
   attribute_assignment[,attribute_assignment][,...]
attribute_assignment:
   attribute_name:process_name[=value]
```

This command upgrades the cluster named *cluster_name* to the software package *package_name*. It accomplishes this by performing a rolling restart of the cluster.

The new package must be registered using add package before you can use it for an upgrade; otherwise, upgrade cluster fails with an error.

To use the command to perform an upgrade, the cluster must be in the fully operational status (you can check that using the command show status --cluster [94] cluster_name). A cluster created for import cannot be upgraded until the import has been completed. See Section 4.4.1, "The create cluster Command", and Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager", for more information.

Suppose mycluster is using MySQL Cluster NDB 7.1.17, and the binaries are registered with a package named 7.1.17, as shown by this list clusters command:

```
mcm> list clusters mysite;
+------+
| Cluster | Package |
+-----+
| mycluster | 7.1.17 |
+-------+
1 row in set (1.80 sec)
```

Now you wish to upgrade mycluster to MySQL Cluster NDB 7.1.19. Assuming that you have placed the NDB 7.1.19 binaries in the same directory on each host, the add package command to create a new package named 7.1.19 that contains these binaries might look something like this:



Note

On Windows, you must replace any backslash (\) characters in the path used for the add package command's --basedir option with forward slashes (/). See Section 4.3.1, "The add package Command", for additional information and examples.

Both packages should now be listed in the output of the command list packages mysite. To perform the upgrade to the 7.1.19 package, use the upgrade cluster command as shown here:

Once the upgrade cluster command has been successfully executed, you can verify that mycluster is now using the 7.1.19 package from the output of the appropriate list clusters command:

The command can perform major as well as minor series upgrades. Despite the name of this command, upgrade cluster can also be used to perform MySQL Cluster downgrades.

Not all upgrades and downgrades between different versions of MySQL Cluster are supported by the command. Three criteria must be met:

- The upgrade or downgrade must be supported by the MySQL Cluster versions involved. See the following sections in the MySQL Cluster manuals for lists of allowed upgrades and downgrades:
 - For MySQL Cluster 7.1: See Upgrading and Downgrading MySQL Cluster.
 - For MySQL Cluster 7.2: See Upgrading and Downgrading MySQL Cluster NDB 7.2.
 - For MySQL Cluster 7.3 and 7.4: See Upgrading and Downgrading MySQL Cluster.

- Both the versions you upgrade or downgrade to and from must be supported by the version of MySQL Cluster Manager you are using (for example, upgrade from MySQL Cluster 6.3.8 to 7.3.8 must be performed manually, because MySQL Cluster Manager no longer supports MySQL Cluster 6.3).
- For MySQL Cluster 7.2.13 and before, the Cluster must NOT have user privileges distributed across its SQL nodes, or the upgrade will have to be performed manually.

Starting from MySQL Cluster Manager 1.3.5, when using the upgrade cluster command, you can use the --set option to reconfigure your MySQL Cluster at the same time. This is particularly helpful when the upgrade requires configuration changes to your cluster. This option takes as its argument an attribute assignment list similar in format to that used with the get and set commands; see description of the set command on the proper way to formulate an attribute assignment list. For example: if you want to change the memory assigned to each data node for storing database records to 750M, specify that with the --set option in your upgrade cluster command:



Note

Unlike the way you use the set command, an equals sign (=) immediately following the --set option is required.

4.5 MySQL Cluster Manager Configuration Commands

This section covers the commands used in the MySQL Cluster Manager for getting and setting values of various types used in MySQL Cluster configuration. We begin with a discussion of what we mean by the term "configuration attribute", and how this relates to the manual configuration of a MySQL Cluster using MySQL Cluster configuration parameters and MySQL Server options and variables that you may already be familiar with.

Configuration attributes.

Traditionally, when administering MySQL Cluster, it has been necessary to distinguish between 3 types of configuration data:

- Configuration parameters set in the MySQL Cluster global configuration file read by the management server (or servers), by convention named config.ini
- Configuration variables set in a running MySQL server (SQL node) by using the SQL SET statement in the mysql command-line client (or in another MySQL client application)
- Configuration options passed to MySQL Cluster executable programs when invoking them



Note

Configuration options passed to mysqld often have the effect of setting values for configuration variables, many—but not all—of which can be overridden in a running MySQL server using a MySQL client application such as mysql.

MySQL Cluster Manager simplifies this configuration scheme by treating all 3 types of configuration data as *attributes*, where the term "attribute" refers to a MySQL Cluster configuration parameter, a MySQL Server variable, or a command-line option used with one or more MySQL Cluster binary programs. It does this transparently, handling all necessary changes in a unified interface.

Suppose that you wish to know how much data memory is allocated to the data nodes in a given MySQL Cluster. Rather than having to determine that this is controlled using the <code>DataMemory</code> configuration parameter that is written in the <code>config.ini</code> file and then reading that file to find the value, you merely invoke the MySQL Cluster Manager <code>get</code> command, and MySQL Cluster Manager handles reading from the file for you, and displays the value without the necessity of opening the file in a separate application such as <code>more</code> or <code>less</code>. If you wish to change the amount of data memory allocated to the data nodes, you can issue a MySQL Cluster Manager <code>set</code> (or <code>reset</code>) command; MySQL Cluster Manager then writes the desired value to <code>config.ini</code>. If—as is the case with <code>DataMemory</code>—updating a configuration value in a running MySQL Cluster requires a rolling restart to be performed, MySQL Cluster Manager can perform this operation automatically so that the configuration change takes effect without further intervention required on the part of the operator.

Configuration attribute levels.

A configuration attribute value applies at one of the three levels, described here:

- Default: This value is always used by any MySQL Cluster process of the type or types (such as ndbd or mysqld) to which the attribute applies, unless this value is overridden by the user.
- Process: This value is used for all instances of a given type of MySQL Cluster process.
- Instance: This value is used for a specific instance of a MySQL Cluster process, the instance being identified by its MySQL Cluster node ID.

Default values are hard-coded into MySQL Cluster; you can override a default value for a given configuration attribute (using the set command) or reset a given attribute value to its default (using the reset command), but you cannot change a default value itself. You can set or reset an configuration attribute's value on either the process level or the instance level using a single set or reset command. Once you have set or reset the value of a configuration attribute, this value persists until it is changed by executing another set or reset command.



Note

When setting or resetting a configuration attribute value, you must specify the level at which the setting applies.

MySQL Cluster Manager determines what value to use for a configuration attribute relating to a given process by following these steps for each MySQL Cluster process:

(For each configuration attribute:)

1. Is an attribute value defined for the node ID of this process?

Yes: Use the value that was defined for this node ID, and exit.

No: Proceed to the next step.

2. Is an attribute value specified on the process level, that is, for all processes of this type?

Yes: Use the value that was specified for all processes of this type, and exit.

No: Use the default value that applies to processes of this type, and exit.

(In the steps just shown, "exit" can be taken to mean "If there are more configuration attributes applicable to this process that have not yet been set, proceed to the next attribute until there are no more attributes to be set for this process".)



Note

The most recently specified value takes precedence. This means that if you set a configuration attribute for a specific process, then later specify a process-level value for this attribute, the process-level value is used for all processes of that type, including the instance for which you earlier set an instance-specific value.

Mandatory attributes.

Some attributes must be defined in the MySQL Cluster Manager at the process type or instance level for all processes of the applicable type or types for the cluster configuration to be valid. Such *mandatory attributes* may be changed, but not reset; in other words, the definition can be changed, but the definition itself cannot be removed entirely. Another way of stating this is that a mandatory attribute has no default value.

An example of a mandatory attribute is Nodeld. If you try to reset a mandatory attribute, the attempt fails with an error, as shown here:

```
mcm> reset NodeId:ndb_mgmd:1 mycluster;
ERROR 6007 (00MGR): Config attribute NodeId is mandatory and cannot be reset
mcm> reset NodeId:ndbd:2 mycluster;
ERROR 6007 (00MGR): Config attribute NodeId is mandatory and cannot be reset
mcm> reset NodeId:mysqld:4 mycluster;
ERROR 6007 (00MGR): Config attribute NodeId is mandatory and cannot be reset
```

Read-only attributes.

A *read-only attribute* is an attribute that must be defined by the MySQL Cluster Manager when a cluster is created. A read-only attribute can be neither changed nor reset by the user. This means that a read-only attribute is always a mandatory attribute.

One such attribute is HostName, which is read only for any type of MySQL Cluster process. Any attempt to change or reset a read-only attribute fails, as shown here:

```
mcm> reset HostName:ndb_mgmd mycluster;
ERROR 6008 (00MGR): Config attribute HostName is readonly and cannot be changed
mcm> reset HostName:ndbd mycluster;
ERROR 6008 (00MGR): Config attribute HostName is readonly and cannot be changed
mcm> reset HostName:mysqld mycluster;
ERROR 6008 (00MGR): Config attribute HostName is readonly and cannot be changed
mcm> set HostName:ndb_mgmd mycluster;
ERROR 6008 (00MGR): Config attribute HostName is readonly and cannot be changed
mcm> set HostName:ndbd mycluster;
ERROR 6008 (00MGR): Config attribute HostName is readonly and cannot be changed
mcm> set HostName:mysqld mycluster;
ERROR 6008 (00MGR): Config attribute HostName is readonly and cannot be changed
mcm> set HostName:mysqld mycluster;
ERROR 6008 (00MGR): Config attribute HostName is readonly and cannot be changed
```

An attribute that is mandatory or read only is set when a cluster is created. Neither a mandatory attribute nor a read-only attribute can be reset. (Neither type of attribute has a default value other than what is set for it when the cluster is created.) A mandatory attribute can be changed at any time by the user; a read-only attribute cannot be changed once the cluster has been created. You can obtain a listing of mandatory and read-only attributes using the get command.

A listing of attribute properties also can be found in the output of ndb_config --configinfo -- xml (see ndb_config -- Extract MySQL Cluster Configuration Information); for more complete information, see Configuration of MySQL Cluster.

MySQL Cluster Manager determines internally which attributes are considered read-only for reasons of cluster stability and performance. You can use the get command to see which attributes are read only.

4.5.1 The get Command

```
get [--include-defaults|-d] [filter_specification_list] cluster_name

filter_specification_list:
    filter_specification[,filter_specification][,...]

filter_specification:
    [attribute_name][:process_specification][+process_specification]]

process_specification:
    [process_name][:process_id]
```

```
process_name:
    {ndb_mgmd|ndbd|ndbmtd|mysqld|ndbapi}
```

This command is used in the MySQL Cluster Manager client to obtain configuration attribute values from a MySQL Cluster. (See Section 4.5, "MySQL Cluster Manager Configuration Commands", for a definition of the term "attribute" as it applies in the MySQL Cluster Manager.) The output includes the following columns:

- Name: This column contains the name of the configuration attribute.
- Value: This column shows the attribute's current value.
- Process1: This column holds the process type to which the attribute applies. This is one of ndb_mgmd, ndbd, ndbmtd (MySQL Cluster NDB 7.0 and later), or mysqld.
- Id1: This is the process ID of the process to which the attribute applies.
- Process2: For attributes that require specifying two nodes, such as those relating to TCP/IP connections, this column shows the process type of the second node.
- Id2: For attributes that require specifying two nodes, this column shows the process ID for the second node.
- Level: This is the attribute process level. This value in this column can be Default, Process, or empty; if this column is empty, it means that the attribute applies on the instance level.
- Comment: This column is used to show whether the attribute is Mandatory, Read only, Default attribute, or user defined (in which case the Comment column is empty).

By default, get returns only those attributes that have been set explicitly, either by the MySQL Cluster Manager itself, or by the user. In other words, it shows only attributes that are mandatory (including read-only attributes), or that have been set by the user after the cluster was created. Hereafter in this discussion, we refer to these as "non-default attributes".

Thus, prior to setting any configuration attributes, you can obtain a list of all mandatory and read-only attributes by running the simplest possible form of this command, as shown here:

```
mcm> get mycluster;
mcm> get mycluster\G
                 ****** 1. row ***************
  Name: DataDir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/1/data
Process1: ndbmtd
NodeId1: 1
Process2:
NodeId2:
  Level:
            ******** 2. row ***************
  Name: HostName
  Value: torsk
Process1: ndbmtd
NodeId1: 1
Process2:
NodeId2:
  Level:
Comment: Read only
Name: NodeId
  Value: 1
Process1: ndbmtd
NodeId1: 1
Process2:
NodeId2:
  Level:
Comment: Read only
```

```
Name: DataDir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/2/data
Process1: ndbmtd
NodeId1: 2
Process2:
NodeId2:
 Level:
Comment:
************************ 5. row *****************
 Name: HostName
 Value: torsk
Process1: ndbmtd
NodeId1: 2
Process2:
NodeId2:
  Level:
Comment: Read only
Name: NodeId
  Value: 2
Process1: ndbmtd
NodeId1: 2
Process2:
NodeId2:
 Level:
Comment: Read only
              ****** 7. row ****************
  Name: DataDir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/49/data
Process1: ndb_mgmd
NodeId1: 49
Process2:
NodeId2:
  Level:
Name: HostName
 Value: torsk
Process1: ndb_mgmd
NodeId1: 49
Process2:
NodeId2:
 Level:
Comment: Read only
Name: NodeId
  Value: 49
Process1: ndb_mgmd
NodeId1: 49
Process2:
NodeId2:
 Level:
Comment: Read only
*********************** 24. row *****************
  Name: ndbcluster
  Value:
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
 Level:
Comment: Read only
              ******* 25. row ****************
  Name: NodeId
  Value: 51
Process1: mysqld
NodeId1: 51
Process2:
```

```
NodeId2:
  Level:
Comment: Read only
 ******************* 26. row *****************
  Name: port
  Value: 3307
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
 Level:
Comment:
 ******************* 27. row *****************
  Name: socket
  Value: /tmp/mysql.mycluster.51.sock
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
  Level:
Comment:
*********************** 28. row *****************
  Name: tmpdir
  Value: /home/jon/bin/mcm/mcm_data/clusters/mycluster/51/data/tmp
Process1: mysqld
NodeId1: 51
Process2:
NodeId2:
  Level:
Comment:
Name: NodeId
  Value: 52
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
  Level:
Comment: Read only
29 rows in set (0.05 sec)
```

On Windows, no substitutions for backslashes or other characters used in values of paths reported by the get command is performed. However, it is possible to see forward slashes used in such paths if the values were set using the set command. See Setting Attributes Containing Paths on Windows [121], for more information.

Although a socket attribute is shown for mysqld nodes in the get output from the previous example and is not marked Read only, MySQL Cluster Manager does not support socket files on Windows. For this reason; you should not attempt to set socket attributes for Windows mysqld processes using MySQL Cluster Manager.

To include default values for attributes that have not (or not yet) been set explicitly, you can invoke this command with the --include-defaults option (short form: -d), as shown here (in part):

```
NodeId1: 1
Process2:
NodeId2:
 Level: Default
Name: __ndbmt_lqh_workers
 Value: NULL
Process1: ndbmtd
NodeId1: 1
Process2:
NodeId2:
 Level: Default
Comment:
Name: Arbitration
 Value: Default
Process1: ndbmtd
NodeId1: 1
Process2:
NodeId2:
 Level: Default
Comment:
Name: ArbitrationTimeout
 Value: 7500
Process1: ndbmtd
NodeId1: 1
Process2:
NodeId2:
 Level: Default
Comment:
. . .
Name: DefaultOperationRedoProblemAction
 Value: queue
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
 Level: Default
Comment:
Name: ExecuteOnComputer
 Value: NULL
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
 Level: Default
Comment:
Name: HeartbeatThreadPriority
 Value: NULL
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
 Level: Default
Comment:
************************ 1097. row *****************
 Name: HostName
 Value:
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
 Level: Default
```

```
Name: MaxScanBatchSize
  Value: 262144
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
  Level: Default
Comment:
Name: NodeId
  Value: 52
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
  Level:
Comment: Read only
                ******* 1100. row ***************
  Name: TotalSendBufferMemory
  Value: 0
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
  Level: Default
Comment:
 ************************ 1101. row *****************
  Name: wan
  Value: false
Process1: ndbapi
NodeId1: 52
Process2:
NodeId2:
  Level: Default
Comment:
1101 rows in set (0.09 sec)
```

As you can see, the output from this get command is quite long (and the number of rows generated increases with the number of nodes in the cluster.) However, it is possible to filter the output so that you can view only the attribute or attributes in which you are interested. This can be done by using a comma-separated list of one or more filter specifications. A filter specification is defined as shown here (condensed from that given at the beginning of this section, but effectively the same):

```
[attribute_name][:[process_name][:process_id]]
```

Filtering can be applied per attribute, per process type, and per process instance. We now provide some examples illustrating the use of such filters.

To obtain the value of a given attribute for all processes to which it applies in the cluster, you need only use the name of the attribute as a filter. For example, to obtain the HostName of all processes in the cluster named mycluster, you can execute the command shown here:

Name	Value	•	NodeId1	Process2	NodeId2	Level	Comment
HostName	flundra	ndbd	1				Read only
HostName	tonfisk	ndbd	2		İ	İ	Read only
HostName	grindval	ndb_mgmd	49		ĺ	İ	Read only
HostName	haj	mysqld	50		İ		Read only
HostName	torsk	mysqld	51		ĺ		Read only

To obtain the value of a given attribute for all processes of a given type, you can specify a filter of the form attribute_name:process_name. The following command retrieves the HostName of all ndbd processes (only) in the cluster mycluster:

mcm> get Hos							
	Value	Process1	Id1	Process2	ld2	Level	Comment
HostName HostName	flundra tonfisk	ndbd ndbd	1 2		 		Readonly Readonly
2 rows in se				,			

To retrieve the value of a given attribute for a particular instance of a process, you can use a filter that takes the form attribute_name:process_name:process_id. For example, you can use the following command to obtain the hostname for the process having 2 as its process ID:

mcm> get Hos		-					
•	Value	Process1	Id1	Process2	Id2	Level	Comment
·	tonfisk	ndbd	2				Readonly
1 row in set							

The command works the same if the process type is omitted:

mcm> get Hos		-					
· ·	Value	Process1	Id1	Process2	ld2	Level	Comment
HostName	tonfisk	ndbd	2	 			Readonly
1 row in set	•						

You can obtain information about multiple attributes within a single get command by specifying a list of filters, separated by commas. *Each filter in the list must be a complete, valid filter*. The command shown here retrieves the HostName and DataDir for all processes in mycluster:

Name	Value	Process1	NodeId1	Process2	NodeId2	Level	Comment
DataDir	/opt/cldata	ndbd	1	,			
HostName	flundra	ndbd	1	ĺ			Read only
DataDir	/opt/c2data	ndbd	2				
HostName	tonfisk	ndbd	2				Read only
DataDir	/opt/c49data	ndb_mgmd	49	ĺ			
HostName	grindval	ndb_mgmd	49				Read only
datadir	/opt/c50data	mysqld	50	ĺ			
HostName	haj	mysqld	50				Read only
datadir	/opt/c51data	mysqld	51				
HostName	torsk	mysqld	51				Read only

To retrieve the values of <code>HostName</code> and <code>DataDir</code> for only the data nodes in <code>mycluster</code>, you can use the <code>get</code> command shown here:

_	stName:ndbd,Da		-				
Name	Value 	Process1	Id1	Process2	Id2	Level	Comment
DataDir HostName DataDir HostName	/ /opt/c2data tonfisk /opt/c3data flundra	ndbd ndbd ndbd ndbd	1 1 1 2 2	 			Read only Read only

```
4 rows in set (1.36 sec)
```

In the example just shown, each filter includes a process type specifier. If you omit this specifier from one of the filters, you obtain a result that you might not expect:

Name	Value	Process1	Id1	Process2	'	Comment
HostName	grindval	ndb_mgmd	49			Read only
DataDir	/opt/c2data	ndbd	1			
HostName	tonfisk	ndbd	1			Read only
DataDir	/opt/c3data	ndbd	2			
HostName	flundra	ndbd	2			Read only
HostName	haj	mysqld	50			Read only
HostName	torsk	mysqld	51			Read only

The filter list HostName, DataDir:ndbd is perfectly valid. However, it actually consists of the filters HostName and DataDir:ndbd—in other words, it means "the HostName for all processes, and the DataDir for ndbd processes".

Suppose you wish to obtain the values for HostName for just the ndb_mgmd and mysqld processes in mycluster. You might be tempted to try using something like HostName:ndb_mgmd, mysqld for the filter list, but this does not work, as you can see here:

```
mcm> get HostName:ndb_mgmd,mysqld mycluster;
ERROR 6003 (00MGR): No such config variable mysqld for process
```

This is due to the fact that each filter in the filter list must be a valid filter, and must include an attribute name. (In the filter list just shown, MySQL Cluster Manager tries to interpret the first string following the comma as an attribute name.) The correct filter list to use in a get command for retrieving the HostName for the ndb_mgmd and mysqld processes in mycluster is shown in this example:

Name	Value	Process1		+ Process2		Level	Comment
HostName	+ grindval	+ ndb_mgmd	+ 49	+ 	+ 	+ 	Read only
HostName	haj	mysqld	50	İ			Read only
HostName	torsk	mysqld	51	İ			Read only

It is also possible to obtain a list of attributes and their values for a given process type or instance of a process. For a given process type, use a filter having the form : process_name. For example, to retrieve all non-default attributes applying to ndbd processes in a cluster named mycluster, you can use the filter :ndbd, as shown here:

Name	Value	Process1	Id1	Process2	Id2	Level	Comment
DataDir	/opt/c2data	ndbd	1				
HostName	tonfisk	ndbd	1				Read only
NodeId	1	ndbd	1				Read only
DataDir	/opt/c3data	ndbd	2				ĺ
HostName	flundra	ndbd	2				Read only
NodeId	2	ndbd	2				Read only

(The example just shown assumes that no attributes are set to non-default values.)

To get a list of all non-default attributes for a single instance of a process, use a filter having the form : process_name: process_id, as shown in this example, which retrieves all non-default attributes for the ndbd process having 2 as its process ID:

Name	+ Value	Process1	Id1	Process2	Id2	Level	Comment
DataDir HostName NodeId	/opt/c2data flundra 2	ndbd ndbd ndbd	2 2 2				Read only Read only

If you try to obtain values for an attribute which you know is supported by your MySQL Cluster version, but the result is empty, this almost certainly means that it is a default attribute which either has not been changed since the cluster was created or has been reset. In order to view default attributes using get, you must execute the command using the --include-defaults option (short form: -d).

Suppose you want to see how much <code>DataMemory</code> is configured for the <code>ndbd</code> processes in the cluster named <code>mycluster</code>, and you execute what appears to be the correct <code>get</code> command, but an empty result is returned, as shown here:

```
mcm> get DataMemory:ndbd mycluster;
Empty set (1.19 sec)
```

This means that the <code>DataMemory</code> attribute has its default value for all data nodes in the cluster. If you do not recall what this value is, you can determine it easily by repeating the same command with the addition of the <code>--include-defaults</code> (-d) option:

Now suppose that you increase the DataMemory to 500 megabytes per data node, then repeat the get command to verify the new value:

You can see that, not only has the Value column in the get command output been updated to the new value, but the Level column has also been updated from Default to Process. This means that you no longer need the --include-defaults option to view this attribute, as shown here:

mcm> get Data		_	- 1				
Name	Value	Process1	Id1	Process2	Id2	Level	Comment
DataMemory DataMemory	500M 500M	ndbd ndbd	1 2			Process Process	
2 rows in set	•	•		+			+

However, if you reset <code>DataMemory</code> (also on the process level), this is no longer the case. Then, <code>DataMemory</code> once again assumes its default value, after which you must use the <code>--include-defaults</code> option to retrieve it, as shown in this example:

For more information about these commands, see Section 4.5.3, "The set Command", and Section 4.5.2, "The reset Command".

Starting from MySQL Cluster Manager 1.3.4, the get command also tags multi-entry replication attributes as so in the Comment column; for example:

<pre>mcm> get replicate_ignore_</pre>	_table:mysqld m	ycluster;					
Name	Value	Process1	NodeId1	Process2	1	Level	Comment
replicate_ignore_table replicate_ignore_table replicate_ignore_table replicate_ignore_table replicate_ignore_table	mydb.t1 mydb.t50 mydb.mytable mydb.t51 mydb.mytable	mysqld mysqld mysqld mysqld mysqld	50 50 50 51 51	 		 Process Process	Multi-end Multi-end Multi-end Multi-end Multi-end
5 rows in set (0.05 sec)							

On how to reset multi-entry attributes, see Section 4.5.2, "The reset Command".

The get command does not normally display configuration attributes applying to TCP, SHM, or SCI connections. However, such attributes can be set in the MySQL Cluster Manager client (using the set command); and once they have been set, they are displayed by applicable get commands. See Setting TCP Connection Attributes, which provides an example of this.

4.5.2 The reset Command

```
reset filter_specification_list cluster_name

filter_specification_list:
    filter_specification[,filter_specification][,...]
```

```
filter_specification:
    attribute_name[:process_specification][+process_specification]]

process_specification:
    [process_name][:process_id]

process_name:
    {ndb_mgmd|ndbmtd|mysqld|ndbapi}
```

This command resets an attribute to its default value. Attributes can be set on either the process level or instance level. To reset an attribute on the process level, use a filter specification having the form <code>attribute_name:process_name</code>, where <code>attribute_name</code> is the name of the attribute to be reset, and <code>process_name</code> is the name of a MySQL Cluster process. To reset a configuration attribute on the instance level, use a filter specification of the form <code>attribute_name:process_name:process_id</code>, where <code>process_id</code> is the process ID.

You cannot issue a reset command that resets all values for a given configuration attribute regardless of process type; each reset command must specify a process type or instance of a process. Otherwise, the command fails, as shown here:

```
mcm> reset DataMemory mycluster;
ERROR 3 (00MGR): Illegal syntax
```

You also cannot revert all configuration attributes for a given process type or instance of a process using a single filter specification; you must always include the name of the attribute to be reset. Otherwise, the reset command fails, as shown here:

```
mcm> reset :ndbd mycluster;
ERROR 3 (00MGR): Illegal syntax

mcm> reset :ndbd:3 mycluster;
ERROR 3 (00MGR): Illegal syntax
```

Suppose that the data memory for all ndbd processes in the cluster named mycluster has been set to 500 MB, as shown in the output of this get command:

We can see from the entries in the Level column that the DataMemory setting for both ndbd processes applies on the process level. A process-level setting cannot be reset on the instance level, as shown here:

```
mcm> reset DataMemory:ndbd:2 mycluster;
ERROR 6010 (00MGR): No matching user defined setting was
found for config attribute DataMemory
mcm> reset DataMemory:ndbd:3 mycluster;
ERROR 6010 (00MGR): No matching user defined setting was
found for config attribute DataMemory
```

The following reset command also does not work, although you might think that it would do so, since it attempts to reset the attribute's value for both ndbd processes:

```
mcm> reset DataMemory:ndbd:2,DataMemory:ndbd:3 mycluster;
ERROR 6010 (00MGR): No matching user defined setting was
```

```
found for config attribute DataMemory
```

The previous command fails because MySQL Cluster Manager regards this as an attempt to apply two instance-level configuration changes. Because the <code>DataMemory</code> setting is a process-level setting, you must instead reset <code>DataMemory</code> to its default value on the process level; you can do this by using the filter specification <code>DataMemory:ndbd</code> in the <code>reset</code> command, as shown here:

If you execute the same get command as shown previously, the result is now empty:

```
mcm> get DataMemory mycluster;
Empty set (0.74 sec)
```

This is because the get command by default does not report default values. To retrieve the DataMemory values after resetting them, you must invoke get using the --include-defaults (short form: -d) option:

The DataMemory values are now included in the output, and are marked with the word Default in the Comments column.

Now suppose that the <code>mysqld</code> configuration attribute <code>wait_timeout</code> for the <code>mysqld</code> process having the ID 4 in the cluster named <code>mycluster</code> has previously been set to the value 200 as shown here, and that no other changes have been to this attribute:

Because the Level column is empty, we know that this setting applies on the instance level. If you try to reset it on the process level, the attempt fails, as shown here:

```
mcm> reset wait_timeout:mysqld mycluster2;
ERROR 6010 (00MGR): No matching user defined setting was
found for config attribute wait_timeout
```

If you wish to reset this attribute to its default value, you must use the reset command with the instance-level filter specification wait_timeout:mysqld:4, as shown here:

Once you have reset wait_timeout, it no longer appears in the output of the earlier get command:

```
mcm> get wait_timeout:mysqld mycluster;
Empty set (1.42 sec)
```

This is because the default behavior of the <code>get</code> command is to display only those values that have been set either by the MySQL Cluster Manager or by the user. Since <code>wait_timeout</code> has been allowed to revert to its default value, you must use the <code>--include-defaults</code> (short form: <code>-d</code>) option to retrieve it, as shown here:

Now consider a situation in which process-level and instance-level settings have been made to a configuration attribute; in this example, we use IndexMemory. First, verify that IndexMemory is set to its default value for all data node processes (in this case, there are two of them):

Now apply both a process-level change and an instance-level change to this attribute. You can do this with a single set command, as shown here:

Because the process-level change was specified first, it is overridden for the ndbd process by the instance-level change specified second. The output from the following get command confirms that this is the case:

mcm> get Index		•					
Name	Value	Process1	Id1	Process2	Id2	Level	Comment
IndexMemory IndexMemory	500M 750M	ndbd ndbd	2 3			Process	

If the instance-level IndexMemory setting for the ndbd process with process ID 3 is reset, the process-level setting still applies, as shown here:

Now, re-apply the instance-level IndexMemory setting, and verify using get that it has taken effect:

If you reset the process-level setting, the instance-level setting remains, and only the ndbd process having process ID 2 has its IndexMemory reset to the default value; the instance-level setting remains in effect, as you can see from the following sequence of commands:



Note

If the order of the specifiers in the original command that set IndexMemory had been reversed as IndexMemory:ndbd:3=750M,IndexMemory:ndbd=500M,

the instance-level change would have been overridden by the process-level change, and the resulting IndexMemory setting for both ndbd processes would be 500M. As discussed elsewhere, a process-level setting made after an instance-level setting that affects the same process completely removes the instance-level setting; the instance-level setting is not preserved, and resetting the attribute on the process level merely restores the default setting for all processes of that type. See Section 4.5, "MySQL Cluster Manager Configuration Commands", for more information.

Starting from MySQL Cluster Manager 1.3.4, the get and reset commands fully support multi-entry replication attributes; for example, if the replicate_ignore_table attribute has multiple entries:

Name	Value	Process1	NodeId1		NodeId2	Level	Comment
replicate_ignore_table	+ mydb.t1	+ mysqld	 50	+ 	+ 	+ 	+ Multi-entr
replicate_ignore_table	mydb.t50	mysqld	50	ĺ	İ	İ	Multi-enti
replicate_ignore_table	mydb.mytable	mysqld	50	ĺ	İ	Process	Multi-enti
replicate_ignore_table	mydb.t51	mysqld	51	İ	İ	İ	Multi-enti
replicate_ignore_table	mydb.mytable	mysqld	51	İ	İ	Process	Multi-enti

Without specifying a node ID, all the attribute's entries associated with the specified process type are reset with the following command:

With a node ID specified, only the instance entries associated with the node ID are reset by the following command:

Resetting TCP Connection Attributes. Certain configuration attributes, such as those relating to TCP connections, apply to connections between processes rather than to individual processes

or individual process types. As shown elsewhere (see Setting TCP Connection Attributes), when you set such an attribute on the process level using MySQL Cluster Manager, this means that the attribute applies to all connections between the two types of processes specified when issuing the set command. It is also possible to set such an attribute on the instance level, in which case it applies only to a single connection between two process instances.

Similarly, it is possible to reset such an attribute on either the process or instance level, depending on the level or levels at which it was set. In either case, an extended form of the process specifier is required, just as it is when setting an attribute that applies to a connection between processes. Assume that the SendBufferMemory attribute has previously been set for all connections between the two ndbd processes and the two mysqld processes that are found in a MySQL Cluster named mycluster2, as shown in the output of this get command:

ncm> get SendBufferN		•					
Name	Value	Process1	Id1	Process2	Id2	Level	Comment
SendBufferMemory	4M	ndbd	2	mysqld	4	Process	
SendBufferMemory	4M	ndbd	2	mysqld	5	Process	
SendBufferMemory	4M	ndbd	3	mysqld	4	Process	
SendBufferMemory	8M	ndbd	3	mysqld	5		
		+	+	+	·	·	+

Suppose that you wish to reset SendBufferMemory only for the connection between the ndbd process having process ID 3 and the mysqld process having process ID 5. The SendBufferMemory setting that applies to this connection is specified on the instance level, as you can see because the Level column value corresponding to this connection is empty; this means that it is possible to reset this value on the instance level. You can do this using the reset command shown here:

You can verify that the attribute was reset using the get command. However, as noted previously, once the instance-level setting has been removed, the process-level setting for this attribute again takes effect, so that the same setting applies to all connections between ndbd and mysqld processes, as shown here:

Name	Value	Process1	Id1	Process2	Id2		Comment
SendBufferMemory	+ 4M	+ ndbd	2	mysqld	+ 4	Process	
SendBufferMemory	4M	ndbd	2	mysqld	5	Process	
SendBufferMemory	4M	ndbd	3	mysqld	4	Process	
SendBufferMemory	4M	ndbd	3	mysqld	5	Process	

To reset this attribute on the process level, you can use the following reset command:

```
1 row in set (8.01 sec)
```

You can verify that the attribute has been reset for all connection between ndbd processes and mysqld processes, by using the get command, as shown here:

```
mcm> get -d SendBufferMemory mycluster2;
Empty set (1.39 sec)
```

As noted elsewhere in this manual (see Section 4.5.1, "The get Command"), the empty result set is to be expected in this case, even when get is invoked using the <code>--include-defaults</code> (or -d) option, because the MySQL Cluster Manager client does not display attributes that appear in the <code>[tcp]</code>, <code>[shm]</code>, or <code>[sci]</code> sections of the <code>config.ini</code> configuration file if they have not been explicitly set by the user.

4.5.3 The set Command

```
set attribute_assignment_list cluster_name
attribute_assignment[.ist:
    attribute_assignment[.attribute_assignment][....]
attribute_assignment:
    attribute_name:process_specification[+process_specification][=value]
process_specification:
    [process_name][:process_id]
process_name:
    {ndb_mgmd|ndbd|ndbmtd|mysqld|ndbapi}
```

This command is used to set values for one or more configuration attributes. Attributes can be set on either the process level or instance level.

set commands are executed whether or not the cluster has been started. In a cluster that is not running, the MySQL Cluster Manager merely updates the configuration files. However, in a running cluster, the MySQL Cluster Manager in addition automatically performs any node restarts or rolling restarts (see Performing a Rolling Restart of a MySQL Cluster) that are required to cause the attribute changes to take effect. However, since restart operations—particularly rolling restarts, where each process in the cluster must be stopped and restarted in turn—can take a great deal of time, it is preferable to make configuration changes before starting the cluster and putting it into use.

To set an attribute on the process level, use a set statement that contains an attribute assignment having the form attribute_name:process_name=value.

For example, to set <code>DataMemory</code> to 500 MB on the <code>ndbd</code> process level, so that the new value applies to all <code>ndbd</code> processes in the cluster, you can issue a <code>set</code> command containing the attribute assignment <code>DataMemory:ndbd=500M</code>, as shown here:

To verify that the new setting is being used, you can issue the following get command:

DataMemory 500M ndb DataMemory 500M ndb		+ 	+ Process Process
+2 rows in set (0.79 sec)	+	+	+



Note

For more information about this command, see Section 4.5.1, "The get Command".

To set an attribute for a specific process instance, include the process ID in the attribute assignment; the form of such an attribute assignment is attribute_name:process_name:process_id=value. For example, to set the wait_timeout attribute for the mysqld process that has process ID 50 to 200, you would issue a set command that contains the attribute assignment wait_timeout:mysqld: 51=200, like this:

You can verify that the setting has taken effect using an applicable get command:

Attributes which are marked Read only cannot be set. Attempting to do so fails with an error, as shown here:

Name	Value	Process1	Id1	Process2	Id2	Level	Comment
DataDir	/opt/c2data	ndbd	1	 			
HostName	tonfisk	ndbd	1				Read only
NodeId	2	ndbd	1				Read only
DataDir	/opt/c3data	ndbd	2				
HostName	grindval	ndbd	2				Read only
NodeId	3	ndbd	2				Read only
rows in set (1 cm> set HostNam		-	:Name	is read only	and o	cannot be	changed

However, you can set mandatory attributes, such as in the example shown previously in this section where the <code>DataDir</code> configuration attribute was set to a user-defined value.



Warning

The mandatory NoOfReplicas attribute must be set on the process level only. Attempting to set it on the instance level may leave the cluster, the MySQL Cluster Manager, or both in an unusable configuration.

Unlike the case with the get command, you cannot issue a set acting on a "global" scope—that is, you cannot, in a single attribute assignment, set a single value for an attribute such that the new attribute value applies to all processes regardless of process type, even if the attribute having that name can be applied to all process types. Nor can you specify multiple process types in a single attribute assignment. Attempting to do either of these things causes an error, as shown here:

```
mcm> set DataDir=/var/cluster-data mycluster;
ERROR 3 (00MGR): Illegal syntax

mcm> set DataDir:ndb_mgmd,ndbd,mysqld=/var/cluster-data mycluster;
ERROR 3 (00MGR): Illegal syntax
```

Instead, you must use a process-level attribute assignment for each process type. However, you are not necessarily required to issue a separate set command for each process type. Instead, you can also make multiple attribute assignments in a single set command, supplying the assignments as a comma-separated list. This set command assigns /var/cdata as the data directory (DataDir) for all MySQL Cluster processes in the cluster named mycluster:

As you can see from the get command just shown, the attribute assignments were successful, and took effect on the process level.



Note

In MySQL Cluster Manager, configuration attribute names are not casesensitive. See Case Sensitivity in String Searches for more information about case-sensitivity issues in MySQL Cluster Manager.

Similarly, you cannot reference multiple process IDs in a single attribute assignment, even if they are processes of the same type; the following command does *not* work:

```
mcm> set DataMemory:ndbd:1,2=750M mycluster;
ERROR 3 (00MGR): Illegal syntax
```

Instead, you would need to use the following command:

```
1 row in set (7.70 sec)
```

(Of course, if these are the only two data nodes in mycluster, then the command set DataMemory:ndbd=750M mycluster also accomplishes the same task.)



Note

A few configuration attributes apply to connections between processes and so require you to refer to both processes in the course of setting them. In such cases, you must use a special process specification syntax; see Setting TCP Connection Attributes, for information about how this is done.

You also cannot set values for multiple attributes in a single attribute assignment; this means that the following commands do *not* work:

```
mcm> set UndoDataBuffer=32M,UndoIndexBuffer=8M:ndbd mycluster;
ERROR 3 (00MGR): Illegal syntax

mcm> set DataMemory,IndexMemory:ndbd=1G mycluster;
ERROR 3 (00MGR): Illegal syntax
```

However, if you write a complete and valid attribute assignment for each attribute whose value you wish to update, you can rewrite these two commands so that they execute successfully, as shown here:

In fact, there is no reason that you cannot perform all four assignments in a single set command, using a list of four attribute assignments, like this:

However, it a good idea not to perform too many attribute assignments in any single set command, since this makes it more difficult to spot errors.

On Windows, when setting attributes whose values contain paths (such as <code>DataDir</code>), you must replace any backslash characters in the path with forward slashes. Suppose that you want to use <code>C:\temp\node50</code> for the <code>tmpdir</code> attribute of the <code>mysqld</code> process having node ID 50 in a MySQL Cluster named <code>mycluster</code> which is running on Windows. The original value for this attribute can be seen using the appropriate <code>get</code> command:

The correct set command to make the desired configuration change is shown here:

When you check the value using get—even though it was originally shown using backslashes—the forward slashes are used when displaying the new value:

However, if you try to use backslashes in the path when issuing the set command, the command fails:

```
mcm> set tmpdir:mysqld:4=c:\temp\4 mycluster;
Outfile disabled.
ERROR:
Unknown command '\4'.
ERROR 6014 (00MGR): Path name for parameter tmpdir must be absolute.
The value 'c:mp4' is illegal.
```

Setting TCP Connection Attributes. For a few attributes that apply only when using TCP connections (such as the <code>SendBufferMemory</code> and <code>ReceiveBufferMemory</code> attributes), it is necessary to use a modified syntax for attribute value assignments. In this case, the attribute assignment contains two process specifications, one for each process type or instance to which the setting applies, joined with a plus sign (+). For the following example, consider the cluster named <code>mycluster2</code>, consisting of the processes shown here:

(See Section 4.6.3, "The list processes Command", for more information about this command.)

TCP connection attributes are not shown in the output from the get command unless they have been set. This means that, prior to setting SendBufferMemory for the first time, you obtain an empty result if you try to retrieve its value, as shown here:

```
mcm> get SendBufferMemory mycluster2;
Empty set (0.18 sec)

mcm> get --include-defaults SendBufferMemory mycluster2;
Empty set (0.93 sec)
```

To set the SendBufferMemory to 4 MB for all TCP connections between data nodes and SQL nodes, you can use the command shown here:

If you check the attribute's value afterwards using get, you can see that the value is applied to all possible connections between each of the two ndbd processes and each of the two mysqld processes in mycluster2, thus there are four rows in the output:

To override this setting for only the connection between the data node with process ID 2 and the mysqld process (process ID 4), you can include the process ID in each of the two parts of the process specification, as shown here:

When you check the result using a get command, you can see that the new setting applies on the instance level, and only to the connection between processes having IDs 2 and 4; the process-level setting made previously still applies to the remaining 3 connections:

Name	Value	+ Process1	Id1	Process2	Id2	Level	Comment
SendBufferMemory	8M	ndbd	2	mysqld	50		
SendBufferMemory	4M	ndbd	2	mysqld	51	Process	
SendBufferMemory	4M	ndbd	3	mysqld	50	Process	
SendBufferMemory	4M	ndbd	3	mysqld	51	Process	

You cannot set a connection attribute on the process level in one part of the process specification (that is, for one end of the connection) and on the instance level in the other. Attempting to do so fails with an error, as shown here:

```
mcm> set SendBufferMemory:ndbd+mysqld:4=2M mycluster2;
ERROR 3 (00MGR): Illegal syntax
mcm> set SendBufferMemory:ndbd:2+mysqld=2M mycluster2;
ERROR 3 (00MGR): Illegal syntax
```

Setting Attributes for mysqld nodes. Before MySQL Cluster Manager 1.3.4, using the set command to set any attribute of a mysqld process always causes the process to restart. Since MySQL Cluster Manager 1.3.4, when a dynamic variable is set, mcmd sends out a SET GLOBAL statement instead to the mysqld to apply the value and also saves the value to the mysqld configuration file, so the value can be applied again at the next mysqld restart; however, an immediate restart is still triggered when a non-dynamic variable is set.

Setup for mysqld connection pooling. Enabling connection pooling for mysqld can be done by setting the ndb-cluster-connection-pool attribute to the desired number of connections, but also requires an extra step in creating the cluster.

Because the <code>mysqld</code> process attempts to make multiple connections to the cluster when connection pooling is enabled, the cluster must be configured with "spare" or "empty" connections. You can do this by adding (otherwise) unused <code>ndbapi</code> entries in the process_host list used in the <code>create cluster</code> command, as shown here:

After this, you can use a set command like this one to set the size of the connection pool according to the number of excess connections available in the config.ini file:

```
mcm> set ndb_cluster_connection_pool:mysqld=4;
```

user attribute not supported for mysqld. Trying to set the user attribute for a mysqld process is not currently supported, and results in a warning being written to the MySQL Cluster Manager log.

4.6 MySQL Cluster Manager Process Commands

This section contains information about MySQL Cluster Manager client commands used to start and stop MySQL Cluster processes, and to determine which processes are currently running.

MySQL Cluster Manager, ndb_mgm, and starting or stopping processes. For a MySQL Cluster under MySQL Cluster Manager control, it is recommended *not* to use the ndb_mgm command-line client that comes with the MySQL Cluster distribution to perform operations that involve starting or stopping nodes. These include but are not limited to the following ndb_mgm client commands (Commands in the MySQL Cluster Management Client):

- START
- STOP
- RESTART
- SHUTDOWN

4.6.1 The add process Command

```
add process {--processhosts=|-R }process_host_list
    [--set=attribute_assignment_list] cluster_name

process_host_list:
    process_name[:node_id]@host[,process_name@host[,...]]

process_name:
    {ndb_mgmd|ndbd|ndbmtd|mysqld|ndbapi}

attribute_assignment_list:
    attribute_assignment[,attribute_assignment][,...]

attribute_assignment:
    attribute_name:process_name[=value]
```

This command adds to an existing cluster one or more processes, which are specified using a process_host_list with the --processhosts [125] option, the format of which is the same as that used with the create cluster command. Any hosts referenced in the list must be members of the site to which the cluster belongs. In addition, all hosts must be resolvable.

Any new processes added by this command must be started explicitly using the command start process --added.

For example, the following add process command adds two mysqld processes on hosts tonfisk and flundra to the cluster named mycluster:

You can also manually assign a node ID to the new process you are adding to the cluster by adding ":node_ID." after the process_name. For MySQL Cluster Manager 1.3.3 and earlier, trying to manually assign node IDs less than 49 for ndb_mgmd, mysqld, or ndbapi fails with an error; the restriction, however, has been lifted since MySQL Cluster Manager 1.3.4. Nevertheless, you are still recommended to follow the best practice of reserving node ID 1 to 48 for data nodes. The following command adds two ndbd processes with node IDs 10 and 11 on hosts tonfisk and flundra, respectively, to mycluster:

Adding Free Processes

Using the add process command, you can add unmanaged mysqld processes, or ndbapi slots for ndbapi applications such as ndb_restore. To add an unmanaged mysqld process, prefix the hostname with the wildcard * (asterisk character):

```
1 row in set (2 min 3.14 sec)
```

To allow the unmanaged mysqld nodes to connect from any host, use the wildcard * (asterisk character) in place of the hostname or IP address:

The same applies to ndbapi slots for ndbapi applications such as ndb_restore: prefix the hostname with the wildcard character to limit connectivity to a specific host, or use only a wildcard, without hostname, to allow ndbapi applications from any host:

Because "free" processes are not managed by MySQL Cluster Manager, there is no need to run the start process --added command after they have been successfully added to the cluster.

Using add process to Simplify create cluster Commands

Processes added before the cluster is started for the first time are started with the cluster. This makes it possible to use this command to break down what would otherwise be very long create cluster commands. Consider the following set of commands which creates and then starts a cluster named mycluster:

```
create cluster --processhosts=ndb_mgmd@host1,ndbd@host1,ndbd@host2, \
  mysqld@host3,mysqld@host4 mycluster;
start cluster mycluster;
```

The long create cluster command can be divided into a shorter (and more manageable) version of itself, plus several add process commands. This set of commands performs the same task as the previous set, creating mycluster with exactly the same processes and hosts as before, and then starting it:

```
create cluster --processhosts=ndb_mgmd@host1 mycluster;
add process --processhosts=ndbd@host1,ndbd@host2 mycluster;
add process --processhosts=mysqld@host3,mysqld@host4 mycluster;
start cluster mycluster;
```

Because mycluster was never started before the ndbd and mysqld processes were added to it using the add process commands shown, it is not necessary to use the --added option with the start cluster command in this case; all 5 processes are started.

A process that is added to a cluster that was created using create cluster --import and before the import takes place is added with status import, which means it cannot be started or stopped using start process or stop process before an import has taken place.

Configuring a New Process when Adding it

A newly added process inherits its configuration attribute settings from those in effect for its process type on the parent cluster, or assume the default settings for that process type if none apply. Existing

attribute settings in the cluster must have process-level scope to be inherited by new processes added later; instance-level settings set for existing process instances prior to adding any new ones do not apply to any of the added processes. (See Configuration attributes, for more information about the scope of attribute settings.)

Inherited attribute settings can be overridden when adding processes; to do this, use the add process command's --set option. This option takes as its argument an attribute assignment list similar in format to that used with the get and set commands. Suppose that the current ndbd process-level setting in the cluster named mycluster for the DataDir attribute is /home/users/ndb/cluster-data, but you wish to add two new ndbd processes that use /tmp/cluster/data instead. You can do this using the following command:

```
mcm> add process --set=ndbd:DataDir=/tmp/cluster/data
> --processhosts=mysqld@tonfisk,mysqld@flundra
> mycluster;
```



Note

Unlike the way you use the set command, a equals sign (=) immediately following the --set option is required.

When setting attributes in this way which contain paths for processes running on Windows, you must replace any backslashes (\) used with forward slashes (/), just as with the set command. See Setting Attributes Containing Paths on Windows [121], for more information.

After a process has been added using add process, you can also use the set command to modify its configuration attribute settings (or specify additional ones) as you would with any other cluster process being managed with MySQL Cluster Manager.



Note

When IPv6-enabled Windows systems are used as MySQL Cluster hosts under MySQL Cluster Manager, you must reference these hosts using IPv4 addresses. Otherwise, MySQL Cluster Manager is unable to connect to the agent processes on those hosts. See Section 5.1, "MySQL Cluster Manager Usage and Design Limitations".

4.6.2 The change process Command

```
change process old_proc_type[:proc-id]=new_proc_type cluster_name

old_proc_type | new_proc_type:
    {ndbd|ndbmtd}
```

This command is used (MySQL Cluster NDB 7.0 and later) to change the process type for a given MySQL Cluster process or group of MySQL Cluster processes from one process type (old-process-type) to another process type (new-process-type).

Currently, the only two process types available for use with this command are ndbd and ndbmtd. This means that change process can be used to change the data node process running on one or more data nodes from the single-threaded data node daemon (ndbd) to the multi-threaded data node daemon (ndbmtd) or vice versa.

By default, change process affects all data nodes running the *old-process-type*. By specifying an optional *process_id*, its action can be restricted to the data node having that process ID.

Suppose you have a cluster which is named mycluster and which has two data nodes using ndbd processes, as reflected in the output of the following show status command:

NodeId
49 1 2 50 51 52

To change both data nodes to so that they use multi-threaded (ndbmtd) processes, issue the command shown here, without any process id specifier:

After the command has executed, you can verify that both data nodes are now using ndbmtd by checking the output of the appropriate show status command, as shown here:

		+	+	+
NodeId	Process	Host	Status	Nodegroup
 49	ndb mgmd	+ flundra	+ running	+
1	ndbmtd	tonfisk	running	n/a
2	ndbmtd	grindval	running	n/a
50	mysqld	haj	running	
51	mysqld	torsk	running	
52	ndbapi	*	running	



Note

The change process command can be used whether or not the cluster or the data node or data nodes to be changed are running. However, the command executes much more quickly if the data node or data nodes to be changed are not running. The next set of examples illustrates this.

It is possible (and sometimes desirable) to use ndbd and ndbmtd data node processes concurrently; thus, it is also possible using the change process command to change a single data node process from single-threaded to multi-threaded, or from multi-threaded to single-threaded. To do this, you must specify the data node process using its process ID.

First, we stop the cluster and verify that all processes are no longer running, as shown here:

+	+ ndb_mgmd	+ flundra	+ stopped	+	+
1	ndbmtd	tonfisk	stopped	n/a	
2	ndbmtd	grindval	stopped	n/a	
50	mysqld	haj	stopped		
51	mysqld	torsk	stopped		
52	ndbapi	*	stopped		I
+	+	+	+	+	+
6 rows in	set (0.05 s	sec)			

The following command changes only the node having the process ID 2 from using the multi-threaded data node daemon to the single-threaded version:

As you can see, change process operates much more quickly when the process to be changed is not running. As before, you can verify that the command succeeded using show status:

To complete the example, we start the cluster again, using start cluster, then change node number 2 back from ndbd (single-threaded) to ndbmtd (multi-threaded) using change process, then verify the change using show status:

```
6 rows in set (0.11 sec)
```

You can see that it can require much less time to stop the cluster, change a data node process, and then start the cluster again than it is to change the process while the cluster is running. However, if you do this, the cluster is not available while it is stopped.

As noted previously, change process works only with ndbd and ndbmtd processes; attempting to use any other process type causes the command to fail with an error, as shown here:

```
mcm> change process ndb_mgmd=mysqld mycluster;

ERROR 7009 (00MGR): Processes ndb_mgmd and mysqld are not interchangeable in this package
mcm> change process ndbd=mysqld mycluster;

ERROR 7009 (00MGR): Processes ndbd and mysqld are not interchangeable in this package
```

4.6.3 The list processes Command

```
list processes cluster_name
```

This command displays all processes making up a given cluster. The following example demonstrates how to list all processes that are part of the cluster named mycluster:

The *cluster_name* argument is required. If this argument is omitted, the command fails with an error, as shown here:

```
mcm> list processes;
ERROR 6 (00MGR): Illegal number of operands
```

4.6.4 The start process Command

```
start process {[--initial|-i] process_id | --added} cluster_name
```

This command starts the MySQL Cluster process having the process ID $process_id$ in the cluster named $cluster_name$. The status of the process to be started, as shown by show status -- process, must be added or stopped.

This example demonstrates how to start the process having the process ID 1 belonging to the cluster mycluster:

When the --initial option (short form: -i) is used, MySQL Cluster Manager starts a data node process with the --initial option, causing the data node to rebuild its file system.

Invoking this command with the --added option rather than with a process ID starts all nodes previously added to the cluster using add process, but not yet started.

You can obtain process IDs for all processes in a given cluster using show status --process or list processes. These are the same as the node IDs for these processes as shown in the output of other mcm client commands such as get or in the output of ndb_mgm -e "show" (see ndb_mgm — The MySQL Cluster Management Client).

You cannot use this command to start a mysqld process in a cluster that is stopped or otherwise unavailable; in MySQL Cluster Manager 1.3.0 and later, trying to do so fails with an error. (Bug #17073352) This includes a cluster created for import where the import has not yet been completed (see Section 4.4.1, "The create cluster Command", and Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager").

4.6.5 The stop process Command

```
stop process process_id cluster_name
```

This command stops the running MySQL Cluster process with the process ID $process_id$ in the cluster named $cluster_name$. The status of the process as shown by show status --process must be running.

Suppose that the process ID of a data node in the cluster named mycluster is 3. Then this data node can be stopped as shown here:

You can use show status --process or list processes to obtain process IDs for all processes in a given cluster.

In the event of a disk failure where MySQL Cluster Manager loses its manager directory (including its repository), the agent is able to recover information from other agents, but it does not actually control processes any longer, although it can detect them. This is due to the fact that the MySQL Cluster Manager agent cannot access the PID files. In this case, stop process no longer works, and you must kill such processes manually. Keep in mind that, if StopOnError is set to 0, the MySQL Cluster Manager agent restarts the data node process automatically; if StopOnError is 1 (the default), then you must execute the start process command manually.

This command does not work with processes in a cluster created for import where the import has not yet actually been completed. See Section 4.4.1, "The create cluster Command", and Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager", for more information.

4.6.6 The remove process Command

```
remove process [--removedirs] process_id_list cluster_name
process_id_list:
    process_id[, process_id[, ...]]
```

This command removes permanently the processes in the *process_id_list* from the cluster named *cluster name*. It provides a means to scale down a cluster offline.

If the --removedirs option is used, all data for the specified processes will be deleted.

The following restrictions apply when using this command:

- 1. The cluster must be in the status of created or stopped.
- 2. The processes to be removed must be in the status of stopped, added, or import.
- 3. The command cannot remove all processes from a cluster in the <u>created</u> status; at least one process must be left.
- 4. The command cannot remove all process of the same type from a cluster in the stopped status; at least one process must be left in the cluster for each type of nodes (management, data, and API).
- 5. The command cannot remove a data node that is in the stopped status if it is already a member of a node group (i.e., if it has ever been started and was fully functional).

You can use the show status --process or list processes command to obtain the process IDs for all the processes in a given cluster:

NodeId	Process	Host	Status	Nodegroup	Package
49 1	ndb_mgmd ndbmtd	flundra flundra	added added	 n/a	mypackage mypackage
2	ndbmtd	flundra	added	n/a	mypackage
50 51	mysqld mysqld	flundra flundra	added added		mypackage mypackage
52	ndbapi	*	added		
53	ndbapi	*	added		

The process IDs are the same as the node IDs for the processes shown in the output of the above or some other mcm client commands, or in the output of the ndb_mgm -e "show" command (see ndb_mgm — The MySQL Cluster Management Client). In the above example, the SQL node with the process ID 50 in mycluster can be removed by the following command:

And in this case, since the cluster was never started, we may also remove both data nodes:

4.7 MySQL Cluster Manager Backup and Restore Commands

This section contains information about MySQL Cluster Manager client commands relating to backing up a MySQL Cluster and restoring it from backup.

4.7.1 The abort backup Command

```
abort backup --backupid=backup_id cluster_name
```

This command aborts a backup, having the specified <code>backup_id</code>, of cluster <code>cluster_name</code>. You can obtain a list of backups and their IDs known to this MySQL Cluster Manager instance using the <code>list backups</code>. If the backup is not actually in progress, the command has no effect.

4.7.2 The backup cluster Command

```
backup cluster
  [--backupid]
  [--snapshotstart | --snapshotend]
  [--waitstarted | --waitcompleted]
  cluster_name
```

This command creates a backup of the MySQL Cluster named <code>cluster_name</code>. backup <code>cluster</code> takes a backup of the cluster's NDB tables only; tables using other MySQL storage engines (such as <code>InnoDB</code> or <code>MyISAM</code>) are ignored.

By default, this command assigns a backup ID to each backup automatically; you can override this behavior by specifying a backup ID using the --backupid option.

The --snapshotstart option causes the backup to match the state of the cluster when the backup began.

The --snapshotend option causes the backup to reflect the state of the cluster when the backup was finished. If neither option is specified, the MySQL Cluster Manager client acts as though --snapshotend had been used.

When the --waitstarted option is used, the MySQL Cluster Manager client waits until the backup has started before returning control to the user, after which the user can check the backup process' status with the show status command and the --backup option.

Using --waitcompleted causes the MySQL Cluster Manager client to wait until the backup process is complete before returning control to the user. If neither of these options is specified, the client behaves as if --waitcompleted had been used.

You can verify that the backup was performed by checking the output of list backups, as shown here:

Each row in the output represents a backup *image*—that is, a set of backup files specific to a given backup of a named cluster on a given data node. Timestamp values are UTC. By default, each image

is stored as a directory named /mcm_data/clusters/cluster_name/node_id/data/BACKUP/BACKUP-backup_id/ in the MySQL Cluster Manager installation directory.

It is possible to remove an unwanted backup from a given node by deleting this image directory and its contents. To remove a given backup completely, you must remove the corresponding image from each data node's BACKUP directory. You can do this as long as a backup or restore operation is not in progress; it is not necessary to stop the cluster or MySQL Cluster Manager agent prior to removing the images.

The Backup Id is used with abort backup and restore cluster.

The backup cluster command was added in MySQL Cluster Manager 1.2.1.

4.7.3 The list backups Command

```
list backups cluster_name
```

This command lists all backups of the MySQL Cluster named <code>cluster_name</code> that are known to this instance of MySQL Cluster Manager. The output includes the backup and node ID as well as a UTC timestamp for each backup, as shown here:

4.7.4 The restore cluster Command

```
restore cluster
    {--backupid=|-I }backup_id
    [--disable-indexes|-x]
    [--disable-metadata|-M]
    [--epoch|-e]
    [--exclude-databases=db_name]
    [--exclude-intermediate-sql-tables]
    [--exclude-missing-columns]
    [--exclude-missing-tables]
    [--exclude-tables=db_name.tbl_name[,db_name.tbl_name][,...]]
    [--include-databases=db_name]
    [--include-tables=db_name.tbl_name[,db_name.tbl_name][,...]]
    [--lossy-conversions]
    [--no-binlog|-1]
    [--no-restore-disk-objects]
    [{--parallelism=|-p }#]
    [--privilege-tables|-P]
    [--progress-frequency]
    [--rewrite-database]
    [--skip-broken-objects]
    [{--skip-nodeid=|-s }id_list]
    [--skip-table-check]
    [--skip-unknown-objects]
   cluster_name
```

This command restores a cluster from a backup having the specified backup ID (--backupid option; short form: -I) to the MySQL Cluster named <code>cluster_name</code>. In its simplest form, it can be used as shown here, to restore the cluster named <code>mycluster</code> to the state saved in the backup having backup ID 3:

If you are restoring an existing cluster to a known good state, you must wipe any existing data first. Stop the cluster using stop cluster, then restart it using start cluster with the --initial option, which causes the data node file systems to be cleared. (Note that Disk Data files must be removed manually.) Following this, you can restore the cluster from the desired backup using restore cluster.



Important

In order to restore a backup using restore cluster, the cluster must have an unused slot for an ndbapi process in its configuration. Otherwise, the command fails with the error Unable to perform restore – no vacant ndbapi slots in config for cluster cluster_name. See Adding Free Processes, for information on how to add a free ndbapi slot to your cluster.

Additional options that can be employed with this command include:

- --disable-indexes and --disable-metadata. To cause indexes to be ignored when restoring the table data, use the --disable-indexes option (short form: -x). Doing this can decrease the time required to restore a large data set, particularly where many indexes were in use. Similarly, you can cause metadata to be ignored during the restoration process by using the --disable-metadata option (short form: -M).
- **--epoch.** When the --epoch option (short form: -e) is used, epoch information is restored to the cluster replication status table (mysql.ndb_apply_status), which can be useful for MySQL Cluster replication slaves.
- --exclude-databases and --exclude-tables. Prevent one or more databases or tables from being restored using the options --exclude-databases and --exclude-tables. -exclude-databases takes a comma-delimited list of one or more databases which should not be restored. --exclude-tables takes a comma-delimited list of one or more tables (using the database.table format) which should not be restored. When --exclude-databases or -exclude-tables is used, only those databases or tables named by the option are excluded; all other databases and tables are restored.
- **--exclude-missing-columns.** When this option is used, restore cluster ignores any columns missing from tables being restored as compared to the versions of those tables found in the backup.
- **--exclude-missing-tables.** When this option is used, restore cluster ignores any tables from the backup that are not found in the target database.
- --exclude-intermediate-sql-tables[=TRUE|FALSE]. When performing ALTER TABLE operations, mysqld creates intermediate tables (whose names are prefixed with #sql-). When TRUE, the --exclude-intermediate-sql-tables option keeps restore cluster from restoring such tables that may have been left over from such operations. This option is TRUE by default.
- --include-databases and --include-tables. Use the --include-databases option or the --include-tables option for restoring only specific databases or tables, respectively. --include-databases takes a comma-delimited list of databases to be restored. --include-tables takes a comma-delimited list of tables (in the database.table format) to be restored. When --include-databases or --include-tables is used, only those databases or tables named by the

option are restored; all other databases and tables are excluded by restore cluster, and are not restored.

- --lossy-conversions. Using --lossy-conversions allows lossy conversions of column values (type demotions or changes in sign) when restoring data from backup. With some exceptions, the rules governing demotion are the same as for MySQL replication; see Replication of Columns Having Different Data Types, for information about specific type conversions currently supported by attribute demotion. restore cluster reports any truncation of data that it performs during lossy conversions once per attribute and column.
- **--no-binlog.** The --no-binlog option (short form: -1) stops any SQL nodes (mysqld processes) in the cluster from writing data from the restore into their binary logs.
- --no-restore-disk-objects. This option stops restore cluster from restoring any MySQL Cluster Disk Data objects, such as tablespaces and log file groups; see MySQL Cluster Disk Data Tables, for more information about these objects.
- --parallelism=#. The --parallelism option (short form: -p) sets the maximum number of parallel transactions that the restore cluster command attempts to use. The default value is 128; the maximum is 1024, and the minimum is 1.
- **--privilege-tables.** The --privilege-tables option (short form: -P) causes restoration of tables required for distributed grants (see Distributed MySQL Privileges for MySQL Cluster).
- **--progress-frequency=N.** Print a status report each N seconds to a temporary stdout dump file mcm creates at mcm_data/clusters/cluster_name/nodeid/tmp while the backup is in progress. 0 (the default) causes no status reports to be printed. The maximum is 65535.
- --rewrite-database=old_dbname,new_dbname. This option causes a database with the name old dbname in the backup to be restored under the name new dbname.
- **--skip-nodeid.** The **--skip-nodeid** option (short form: -s) takes a comma-separated list of node IDs. The nodes whose IDs are listed may include of data nodes, SQL nodes, or both. Nodes having these IDs are skipped by the restoration process.
- **--skip-broken-objects.** This option causes restore cluster to ignore corrupt tables while reading a backup, and to continue restoring any remaining tables (that are not also corrupted). Currently, the --skip-broken-objects option works only in the case of missing blob parts tables.
- **--skip-table-check.** It is possible to restore data without restoring table metadata. The default behavior when doing this is for restore cluster to fail with an error if table data do not match the table schema; this can be overridden using the **--skip-table-check** option.
- **--skip-unknown-objects.** This option causes restore cluster to ignore any schema objects it does not recognize while reading a backup. This can be used for restoring, for example, a backup made from a newer version of MySQL Cluster to an older version.

4.7.5 The backup agents Command

```
backup agents [--hosts=host_list] [site_name]
host_list:
   host[, host[, ...]]
```

This command backs up the configuration data for the mcmd agents on the hosts specified in <code>host_list</code> for the site named <code>site_name</code>. If no host names are specified, all agents of the site are backed up. If no <code>site_name</code> is given, only the agent that the mcm client is connected to is backed up.

The backup for each agent is created in a subfolder named rep_backup/timestamp under the agent repository (the mcm_data folder), with timestamp reflecting the time the backup began. If you want

the backup to be at another place, create a soft link from mcm_data/rep_backup to your desired storage location.

Notice that the backup agents command works differently from the backup cluster command, which backs up cluster data; the backup agents command, on the other hand, backs up agent configuration data. Using together the backups created by both commands, you can restore not just the cluster, but the complete cluster-plus-manager setup. See Section 3.7, "Backing Up and Restoring MySQL Cluster Manager Agents" for more details about backing up and restoring mcmd agents.

4.8 MySQL Cluster Manager Cluster Importation Commands

This section contains descriptions of MySQL Cluster Manager commands used to perform operations connected with importing clusters into MySQL Cluster Manager. These operations include migration of cluster processes and (in MySQL Cluster Manager 1.3.1 and later) copying of configuration data.

4.8.1 The import cluster Command

```
import cluster [--dryrun|-y] cluster_name
```

This command imports a MySQL Cluster created independently of MySQL Cluster Manager into a cluster named <code>cluster_name</code> that has been created in MySQL Cluster Manager. You are strongly advised to create <code>cluster_name</code> using the <code>create cluster</code> command's <code>--import</code> option; see that command's description for more information about the <code>--import</code> option and its effects.

import cluster requires a single argument, the name of the cluster created using MySQL Cluster Manager (cluster_name) into which you wish to import a MySQL Cluster created externally into MySQL Cluster Manager and bring it under MySQL Cluster Manager control. The cluster named in the command must already exist in MySQL Cluster Manager.

import cluster also supports a --dryrun option. When this option is used, only the checks required for importation are performed against the existing cluster. This makes it possible to test a given configuration without actually placing any cluster processes under MCM control. -y is supported as a short form of this option beginning with MySQL Cluster Manager 1.3.1.

For more information about importing clusters into MySQL Cluster Manager, including examples, see Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager".

4.8.2 The import config Command

```
import config [--dryrun|-y] cluster_name
```

This command imports the configuration of an autonomous or "wild" cluster into the cluster named cluster name.

import config requires a single argument, the name of the cluster created using MySQL Cluster Manager—that is, <code>cluster_name</code>—into which you wish to import the configuration of a MySQL Cluster created externally into one created using MySQL Cluster Manager. The cluster named in the command must already exist in MySQL Cluster Manager; you are also strongly advised to use <code>createcluster_-import</code> when creating <code>cluster_name</code>.

import config also supports a --dryrun option (short form: -y). When this option is used, only the checks required for importing the configuration data are performed. This makes it possible to perform tests without actually copying any of this data into a cluster under MCM control.

import config is available in MySQL Cluster Manager 1.3.1 and later.

For more information about importing clusters into MySQL Cluster Manager, including examples, see Section 3.5, "Importing MySQL Clusters into MySQL Cluster Manager".

	138	

Chapter 5 MySQL Cluster Manager Limitations and Known Issues

Table of Contents

5.1 MySQL Cluster Manager Usage and Design Limitations	139
5.2 MySQL Cluster Manager 1.3.6 Limitations Relating to the MySQL Server	139
5.3 MySQL Cluster Manager Limitations Relating to MySQL Cluster	140
5.4 Syntax and Related Issues in MySQL Cluster Manager	141

In this chapter we discuss limitations of and known issues in MySQL Cluster Manager version 1.3.6.

5.1 MySQL Cluster Manager Usage and Design Limitations

The limitations discussed in this section occur by intention or design in MySQL Cluster Manager 1.3.6. Some of these items may become obsolete in future versions; we will update this section accordingly if and as those changes come about.

change process command. Currently, the change process command can be used only to exchange an ndbd process for an ndbmtd process, or the reverse. That is, in effect, it can be used only to switch a data node between a single-threaded process and a multi-threaded process. It cannot be used for changing a cluster node's type (for example, you cannot change a data node to an SQL node, management node, or NDB API application node).

Because of this restriction, and due to the fact that multi-threaded data nodes are not supported in MySQL Cluster NDB 6.3 and earlier, the change process command is useful only with clusters running MySQL Cluster NDB 7.0 or newer.

License keys and operating platforms. License keys are not required to use MySQL Cluster Manager 1.3.6.

Concurrent client sessions unsupported. Currently there is no negotation or arbitration between multiple mcm clients. While it is possible to use the client from multiple locations, we do not support *concurrent* client sessions. You should be careful always to allow a command issued in one mcm client session to finish executing before issuing a new command in a different client session. This is true especially when using the -B or --background option with mcm client commands; see Backgrounded commands and error handling.

IPv6 and host names (Windows). When IPv6 support is enabled on Windows systems, host names other than localhost are resolved using IPv6. When an IPv6-enabled Windows system is used as a MySQL Cluster host under MySQL Cluster Manager, you must reference it using its IPv4 address. Otherwise, mcm will be unable to connect to the agent process on that host.

This applies to host names used with the MySQL Cluster Manager client commands create cluster, create site, add hosts, add package, delete package, stop agents, and add process.

No removal of hosts. Once a host is added to a management site using the add hosts command, it cannot be removed with MySQL Cluster Manager.

5.2 MySQL Cluster Manager 1.3.6 Limitations Relating to the MySQL Server

The limitations described in this section relate to functionality in the MySQL Server that is unsupported or reduced, or otherwise differs when using it with MySQL Cluster Manager.

Replication. Replication is currently not directly supported by MySQL Cluster Manager. See Section 5.3, "MySQL Cluster Manager Limitations Relating to MySQL Cluster", for more information.

Limited mysqld option modifier support. MySQL Cluster Manager does not recognize the --loose, --maximum, --enable, and --disable prefixes for mysqld options used as MySQL Cluster Manager configuration attributes (for a description of these modifiers, see Program Option Modifiers). For example, the command set loose-skip-innodb:mysqld=true mycluster; fails with the error No such config variable loose-skip-innodb for process mysqld.

The --skip option modifier is supported in some but not all cases, so that commands such as set skip-innodb:mysqld=true mycluster; and set skip-grant-tables:mysqld=true mycluster; can be used with MySQL Cluster Manager, while set skip-column-names:mysqld=true mycluster; cannot. (Bug #48559, Bug #47779)

Visibility of MySQL Cluster Manager mysqld attributes and MySQL server variables. Due in part to issues with mappings between my.cnf option names, mysqld command-line option names, and names of MySQL server variables, some MySQL server variables are not visible to MySQL Cluster Manager, or have different names. For example, the storage_engine server variable shown in the output of SHOW VARIABLES in the mysql client maps to the default-storage-engine configuration attribute used in the MySQL Cluster Manager get and set commands.

Dashes and underscores in MySQL option and variable names. When using the mysql client or other MySQL client applications, many MySQL system options and variables can be named using either dashes or underscores in their names. For example, you can use either ndb_batch_size or ndb-batch-size with the MySQL Server, and the variable is set correctly. This is not the case in MySQL Cluster Manager, where only the forms using underscores are accepted as attribute names. For example, assuming that mycluster is a viable cluster, the command set ndb_batch_size:mysqld=65536 mycluster; works to set the size of ndb_batch_size on all mysqld processes in the cluster, but set ndb-batch-size:mysqld=65536 mycluster; fails.

Dependencies between MySQL Cluster Manager mysqld attributes and MySQL server variables. MySQL Cluster Manager does not track dependencies between mysqld attributes (MySQL server options and variables). For example, MySQL Server 5.1 and earlier require, when the binlog_format attribute is set, that the log_bin attribute be used as well; if binlog_format is used without log_bin, mysqld fails to start (MySQL Server Bug #42928, fixed in MySQL 5.5 and MySQL Cluster NDB 7.2). If you do this using MySQL Cluster Manager, however, the MySQL Cluster Manager agent reports that the operation was started successfully, and from MySQL Cluster Manager's point of view, this is correct—MySQL Cluster Manager started the mysqld process with the indicated attribute settings, and it is up to the operator to verify that the result was the one expected. In such cases, it is a good idea to check the status of the mysqld process, perhaps using show status -- operation, before continuing.

MySQL Cluster Manager mysqld attributes and MySQL user variables. MySQL user variables are not accessible as MySQL Cluster Manager configuration attributes.

Default MySQL data directory. Formerly, the default tmpdir for MySQL servers installed under MySQL Cluster Manager was datadir/tmp, which caused issues with the mysql client. This issue was resolved in MySQL Cluster Manager 1.2. MySQL Cluster Manager 1.3 (and later) uses tmp in the MySQL installation directory for this purpose.

5.3 MySQL Cluster Manager Limitations Relating to MySQL Cluster

This section describes limitations relating to MySQL Cluster functionality that is unsupported or curtailed by MySQL Cluster Manager 1.3.6.

MySQL Cluster Manager and replication. MySQL Cluster Manager currently does not provide any explicit support for MySQL Cluster Replication. However, you should still be able to perform manual setup of replication of a MySQL Cluster that is managed by MySQL Cluster Manager.

Backup and restore operations. MySQL Cluster Manager provides integrated backup and restore functionality. You can back up NDB databases and tables using the mcm client backup cluster command, and restore them using the restore cluster client command. MySQL Cluster Manager also supports restoration of distributed privileges.

You can also back up NDB databases and tables using the ndb_mgm client START BACKUP command, and restore them using the ndb_restore program (see ndb_restore — Restore a MySQL Cluster Backup); however MySQL Cluster Manager is not aware of backups that it was not employed to create. Both of the programs just mentioned are supplied with the MySQL Cluster distribution; for more information, see Online Backup of MySQL Cluster, and ndb_restore — Restore a MySQL Cluster Backup.



Note

Backups of tables using storage engines other than NDB, as well as of all other database objects which are not tables, cannot be made using MySQL Cluster Manager, and must be made using some other method, such as mysqldump. (See mysqldump — A Database Backup Program.)

Rolling restarts. Currently, all cluster nodes must be running in order to perform a rolling restart using MySQL Cluster Manager. However, MySQL Cluster itself requires only that at least one management server and all data nodes are running (in other words, any mysqld processes and any additional ndb_mgmd processes can be stopped). In such cases, you can perform the rolling restart manually, after stopping the MySQL Cluster Manager agent.

When making changes in configuration attributes only those nodes requiring a restart to make the change take effect are actually restarted. ndbapi nodes are never restarted by MySQL Cluster Manager.

Cluster Imports.

MySQL Cluster Manager will reject an import if it cannot access the process information of the cluster being imported. Therefore, the MySQL Cluster Manager agents must be run by a sufficiently privileged user—normally the same user that runs the cluster.

5.4 Syntax and Related Issues in MySQL Cluster Manager

This section covers MySQL Cluster Manager issues relating to limitations in SQL and other syntax.

Backgrounded commands and error handling.

MySQL Cluster Manager client commands which are run in the background (that is, when they are invoked with the --background or -B option) do not issue any error messages in the client. If you run a command in the background, you must check the agent log or use the show status command to verify whether the backgrounded command was successful.



Appendix A Changes in MySQL Cluster Manager

MySQL Cluster Manager release notes are no longer published in the MySQL Cluster Manager User Manual.

Release notes for the changes in each release of MySQL Cluster Manager are located at MySQL Cluster Manager 1.3 Release Notes.



Appendix B Licenses for Third-Party Components Used in MySQL Cluster Manager 1.3.6

Table of Contents

B.1 GLib License (for MySQL Cluster Manager)	145
B.2 GNU Lesser General Public License Version 2.1, February 1999	146
B.3 libevent License	153
B.4 libintl License	155
B.5 LPeg Library License	156
B.6 Lua (liblua) License	156
B.7 LuaFileSystem Library License	156
B.8 PCRE License	157
B.9 SHA-1 in C License	158

Oracle acknowledges that certain third-party and Open Source software has been used to develop or is incorporated in the MySQL Cluster Manager product. This appendix includes required third-party license information.

MySQL Cluster Manager 1.3

- Section B.1, "GLib License (for MySQL Cluster Manager)"
- Section B.2, "GNU Lesser General Public License Version 2.1, February 1999"
- Section B.3, "libevent License"
- Section B.4, "libintl License"
- · Section B.5, "LPeg Library License"
- · Section B.6, "Lua (liblua) License"
- Section B.7, "LuaFileSystem Library License"
- Section B.8, "PCRE License"
- Section B.9, "SHA-1 in C License"

B.1 GLib License (for MySQL Cluster Manager)

The following software may be included in this product:

```
GLib
You are receiving a copy of the GLib library in both source
and object code in the following [mcm install dir]/lib/ and
[mcm install dir]/licenses/lgpl folders. The terms of the
Oracle license do NOT apply to the GLib library; it is licensed
under the following license, separately from the Oracle programs
you receive. If you do not wish to install this library, you
may create an "exclude" file and run tar with the X option, as
in the following example, but the Oracle program might not
operate properly or at all without the library:
  tar -xvfX <package-tar-file> <exclude-file>
where the exclude-file contains, e.g.:
  <package-name>/lib/libglib-2.0.so.0.1600.6
  <package-name>/lib/libglib-2.0.so.0
  <package-name>/lib/libglib-2.0.so
Example:
```

```
tar -xvfX mysql-cluster-manager-1.2.1-solaris10-x86-32bit.tar Exclude

Exclude File:
mysql-cluster-manager-1.2.1-solaris10-x86-32bit/lib/libglib-2.0.so.0.1600.6
mysql-cluster-manager-1.2.1-solaris10-x86-32bit/lib/libglib-2.0.so.0
mysql-cluster-manager-1.2.1-solaris10-x86-32bit/lib/libglib-2.0.so
```

This component is licensed under Section B.2, "GNU Lesser General Public License Version 2.1, February 1999".

B.2 GNU Lesser General Public License Version 2.1, February 1999

The following applies to all products licensed under the GNU Lesser General Public License, Version 2.1: You may not use the identified files except in compliance with the GNU Lesser General Public License, Version 2.1 (the "License"). You may obtain a copy of the License at http://www.gnu.org/licenses/lgpl-2.1.html. A copy of the license is also reproduced below. Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

GNU LESSER GENERAL PUBLIC LICENSE Version 2.1, February 1999

Copyright (C) 1991, 1999 Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301 USA Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

[This is the first released version of the Lesser GPL. It also counts as the successor of the GNU Library Public License, version 2, hence the version number 2.1.]

Preamble

The licenses for most software are designed to take away your freedom to share and change it. By contrast, the GNU General Public Licenses are intended to guarantee your freedom to share and change free software--to make sure the software is free for all its users.

This license, the Lesser General Public License, applies to some specially designated software packages--typically libraries--of the Free Software Foundation and other authors who decide to use it. You can use it too, but we suggest you first think carefully about whether this license or the ordinary General Public License is the better strategy to use in any particular case, based on the explanations below.

When we speak of free software, we are referring to freedom of use, not price. Our General Public Licenses are designed to make sure that you have the freedom to distribute copies of free software (and charge for this service if you wish); that you receive source code or can get it if you want it; that you can change the software and use pieces of it in new free programs; and that you are informed that you can do these things.

To protect your rights, we need to make restrictions that forbid distributors to deny you these rights or to ask you to surrender these rights. These restrictions translate to certain responsibilities for you if you distribute copies of the library or if you modify it.

For example, if you distribute copies of the library, whether gratis or for a fee, you must give the recipients all the rights that we gave you. You must make sure that they, too, receive or can get the source

code. If you link other code with the library, you must provide complete object files to the recipients, so that they can relink them with the library after making changes to the library and recompiling it. And you must show them these terms so they know their rights.

We protect your rights with a two-step method: (1) we copyright the library, and (2) we offer you this license, which gives you legal permission to copy, distribute and/or modify the library.

To protect each distributor, we want to make it very clear that there is no warranty for the free library. Also, if the library is modified by someone else and passed on, the recipients should know that what they have is not the original version, so that the original author's reputation will not be affected by problems that might be introduced by others.

Finally, software patents pose a constant threat to the existence of any free program. We wish to make sure that a company cannot effectively restrict the users of a free program by obtaining a restrictive license from a patent holder. Therefore, we insist that any patent license obtained for a version of the library must be consistent with the full freedom of use specified in this license.

Most GNU software, including some libraries, is covered by the ordinary GNU General Public License. This license, the GNU Lesser General Public License, applies to certain designated libraries, and is quite different from the ordinary General Public License. We use this license for certain libraries in order to permit linking those libraries into non-free programs.

When a program is linked with a library, whether statically or using a shared library, the combination of the two is legally speaking a combined work, a derivative of the original library. The ordinary General Public License therefore permits such linking only if the entire combination fits its criteria of freedom. The Lesser General Public License permits more lax criteria for linking other code with the library.

We call this license the "Lesser" General Public License because it does Less to protect the user's freedom than the ordinary General Public License. It also provides other free software developers Less of an advantage over competing non-free programs. These disadvantages are the reason we use the ordinary General Public License for many libraries. However, the Lesser license provides advantages in certain special circumstances.

For example, on rare occasions, there may be a special need to encourage the widest possible use of a certain library, so that it becomes a de-facto standard. To achieve this, non-free programs must be allowed to use the library. A more frequent case is that a free library does the same job as widely used non-free libraries. In this case, there is little to gain by limiting the free library to free software only, so we use the Lesser General Public License.

In other cases, permission to use a particular library in non-free programs enables a greater number of people to use a large body of free software. For example, permission to use the GNU C Library in non-free programs enables many more people to use the whole GNU operating system, as well as its variant, the GNU/Linux operating system.

Although the Lesser General Public License is Less protective of the users' freedom, it does ensure that the user of a program that is linked with the Library has the freedom and the wherewithal to run that program using a modified version of the Library.

The precise terms and conditions for copying, distribution and modification follow. Pay close attention to the difference between a "work based on the library" and a "work that uses the library". The former contains code derived from the library, whereas the latter must be combined with the library in order to run.

GNU LESSER GENERAL PUBLIC LICENSE
TERMS AND CONDITIONS FOR COPYING, DISTRIBUTION AND MODIFICATION

- O. This License Agreement applies to any software library or other program which contains a notice placed by the copyright holder or other authorized party saying it may be distributed under the terms of this Lesser General Public License (also called "this License"). Each licensee is addressed as "you".
- A "library" means a collection of software functions and/or data prepared so as to be conveniently linked with application programs (which use some of those functions and data) to form executables.

The "Library", below, refers to any such software library or work which has been distributed under these terms. A "work based on the Library" means either the Library or any derivative work under copyright law: that is to say, a work containing the Library or a portion of it, either verbatim or with modifications and/or translated straightforwardly into another language. (Hereinafter, translation is included without limitation in the term "modification".)

"Source code" for a work means the preferred form of the work for making modifications to it. For a library, complete source code means all the source code for all modules it contains, plus any associated interface definition files, plus the scripts used to control compilation and installation of the library.

Activities other than copying, distribution and modification are not covered by this License; they are outside its scope. The act of running a program using the Library is not restricted, and output from such a program is covered only if its contents constitute a work based on the Library (independent of the use of the Library in a tool for writing it). Whether that is true depends on what the Library does and what the program that uses the Library does.

1. You may copy and distribute verbatim copies of the Library's complete source code as you receive it, in any medium, provided that you conspicuously and appropriately publish on each copy an appropriate copyright notice and disclaimer of warranty; keep intact all the notices that refer to this License and to the absence of any warranty; and distribute a copy of this License along with the Library.

You may charge a fee for the physical act of transferring a copy, and you may at your option offer warranty protection in exchange for a fee.

- 2. You may modify your copy or copies of the Library or any portion of it, thus forming a work based on the Library, and copy and distribute such modifications or work under the terms of Section 1 above, provided that you also meet all of these conditions:
 - a) The modified work must itself be a software library.
 - b) You must cause the files modified to carry prominent notices stating that you changed the files and the date of any change.
 - c) You must cause the whole of the work to be licensed at no charge to all third parties under the terms of this License.
 - d) If a facility in the modified Library refers to a function or a table of data to be supplied by an application program that uses the facility, other than as an argument passed when the facility is invoked, then you must make a good faith effort to ensure that, in the event an application does not supply such function or table, the facility still operates, and performs whatever part of its purpose remains meaningful.

(For example, a function in a library to compute square roots has a purpose that is entirely well-defined independent of the application. Therefore, Subsection 2d requires that any application-supplied function or table used by this function must

be optional: if the application does not supply it, the square root function must still compute square roots.)

These requirements apply to the modified work as a whole. If identifiable sections of that work are not derived from the Library, and can be reasonably considered independent and separate works in themselves, then this License, and its terms, do not apply to those sections when you distribute them as separate works. But when you distribute the same sections as part of a whole which is a work based on the Library, the distribution of the whole must be on the terms of this License, whose permissions for other licensees extend to the entire whole, and thus to each and every part regardless of who wrote it.

Thus, it is not the intent of this section to claim rights or contest your rights to work written entirely by you; rather, the intent is to exercise the right to control the distribution of derivative or collective works based on the Library.

In addition, mere aggregation of another work not based on the Library with the Library (or with a work based on the Library) on a volume of a storage or distribution medium does not bring the other work under the scope of this License.

3. You may opt to apply the terms of the ordinary GNU General Public License instead of this License to a given copy of the Library. To do this, you must alter all the notices that refer to this License, so that they refer to the ordinary GNU General Public License, version 2, instead of to this License. (If a newer version than version 2 of the ordinary GNU General Public License has appeared, then you can specify that version instead if you wish.) Do not make any other change in these notices.

Once this change is made in a given copy, it is irreversible for that copy, so the ordinary GNU General Public License applies to all subsequent copies and derivative works made from that copy.

This option is useful when you wish to copy part of the code of the Library into a program that is not a library.

- 4. You may copy and distribute the Library (or a portion or derivative of it, under Section 2) in object code or executable form under the terms of Sections 1 and 2 above provided that you accompany it with the complete corresponding machine-readable source code, which must be distributed under the terms of Sections 1 and 2 above on a medium customarily used for software interchange.
- If distribution of object code is made by offering access to copy from a designated place, then offering equivalent access to copy the source code from the same place satisfies the requirement to distribute the source code, even though third parties are not compelled to copy the source along with the object code.
- 5. A program that contains no derivative of any portion of the Library, but is designed to work with the Library by being compiled or linked with it, is called a "work that uses the Library". Such a work, in isolation, is not a derivative work of the Library, and therefore falls outside the scope of this License.

However, linking a "work that uses the Library" with the Library creates an executable that is a derivative of the Library (because it contains portions of the Library), rather than a "work that uses the library". The executable is therefore covered by this License. Section 6 states terms for distribution of such executables.

When a "work that uses the Library" uses material from a header file that is part of the Library, the object code for the work may be a derivative work of the Library even though the source code is not. Whether this is true is especially significant if the work can be linked without the Library, or if the work is itself a library. The threshold for this to be true is not precisely defined by law.

If such an object file uses only numerical parameters, data structure layouts and accessors, and small macros and small inline functions (ten lines or less in length), then the use of the object file is unrestricted, regardless of whether it is legally a derivative work. (Executables containing this object code plus portions of the Library will still fall under Section 6.)

Otherwise, if the work is a derivative of the Library, you may distribute the object code for the work under the terms of Section 6. Any executables containing that work also fall under Section 6, whether or not they are linked directly with the Library itself.

6. As an exception to the Sections above, you may also combine or link a "work that uses the Library" with the Library to produce a work containing portions of the Library, and distribute that work under terms of your choice, provided that the terms permit modification of the work for the customer's own use and reverse engineering for debugging such modifications.

You must give prominent notice with each copy of the work that the Library is used in it and that the Library and its use are covered by this License. You must supply a copy of this License. If the work during execution displays copyright notices, you must include the copyright notice for the Library among them, as well as a reference directing the user to the copy of this License. Also, you must do one of these things:

- a) Accompany the work with the complete corresponding machine-readable source code for the Library including whatever changes were used in the work (which must be distributed under Sections 1 and 2 above); and, if the work is an executable linked with the Library, with the complete machine-readable "work that uses the Library", as object code and/or source code, so that the user can modify the Library and then relink to produce a modified executable containing the modified Library. (It is understood that the user who changes the contents of definitions files in the Library will not necessarily be able to recompile the application to use the modified definitions.)
- b) Use a suitable shared library mechanism for linking with the Library. A suitable mechanism is one that (1) uses at run time a copy of the library already present on the user's computer system, rather than copying library functions into the executable, and (2) will operate properly with a modified version of the library, if the user installs one, as long as the modified version is interface-compatible with the version that the work was made with.
- c) Accompany the work with a written offer, valid for at least three years, to give the same user the materials specified in Subsection 6a, above, for a charge no more than the cost of performing this distribution.
- d) If distribution of the work is made by offering access to copy from a designated place, offer equivalent access to copy the above specified materials from the same place.
- e) Verify that the user has already received a copy of these materials or that you have already sent this user a copy.

For an executable, the required form of the "work that uses the Library" must include any data and utility programs needed for reproducing the executable from it. However, as a special exception, the materials to be distributed need not include anything that is normally distributed (in either source or binary form) with the major components (compiler, kernel, and so on) of the operating system on which the executable runs, unless that component itself accompanies the executable.

It may happen that this requirement contradicts the license restrictions of other proprietary libraries that do not normally accompany the operating system. Such a contradiction means you cannot use both them and the Library together in an executable that you

distribute.

- 7. You may place library facilities that are a work based on the Library side-by-side in a single library together with other library facilities not covered by this License, and distribute such a combined library, provided that the separate distribution of the work based on the Library and of the other library facilities is otherwise permitted, and provided that you do these two things:
 - a) Accompany the combined library with a copy of the same work based on the Library, uncombined with any other library facilities. This must be distributed under the terms of the Sections above.
 - b) Give prominent notice with the combined library of the fact that part of it is a work based on the Library, and explaining where to find the accompanying uncombined form of the same work.
- 8. You may not copy, modify, sublicense, link with, or distribute the Library except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, link with, or distribute the Library is void, and will automatically terminate your rights under this License. However, parties who have received copies, or rights, from you under this License will not have their licenses terminated so long as such parties remain in full compliance.
- 9. You are not required to accept this License, since you have not signed it. However, nothing else grants you permission to modify or distribute the Library or its derivative works. These actions are prohibited by law if you do not accept this License. Therefore, by modifying or distributing the Library (or any work based on the Library), you indicate your acceptance of this License to do so, and all its terms and conditions for copying, distributing or modifying the Library or works based on it.
- 10. Each time you redistribute the Library (or any work based on the Library), the recipient automatically receives a license from the original licensor to copy, distribute, link with or modify the Library subject to these terms and conditions. You may not impose any further restrictions on the recipients' exercise of the rights granted herein. You are not responsible for enforcing compliance by third parties with this License.
- 11. If, as a consequence of a court judgment or allegation of patent infringement or for any other reason (not limited to patent issues), conditions are imposed on you (whether by court order, agreement or otherwise) that contradict the conditions of this License, they do not excuse you from the conditions of this License. If you cannot distribute so as to satisfy simultaneously your obligations under this License and any other pertinent obligations, then as a consequence you may not distribute the Library at all. For example, if a patent license would not permit royalty-free redistribution of the Library by all those who receive copies directly or indirectly through you, then the only way you could satisfy both it and this License would be to refrain entirely from distribution of the Library.

If any portion of this section is held invalid or unenforceable under any particular circumstance, the balance of the section is intended to apply, and the section as a whole is intended to apply in other circumstances.

It is not the purpose of this section to induce you to infringe any patents or other property right claims or to contest validity of any such claims; this section has the sole purpose of protecting the integrity of the free software distribution system which is implemented by public license practices. Many people have made generous contributions to the wide range of software distributed through that system in reliance on consistent application of that system; it is up to the author/donor to decide if he or she is willing to distribute software through any other system and a licensee cannot impose that choice.

This section is intended to make thoroughly clear what is believed to be a consequence of the rest of this License.

- 12. If the distribution and/or use of the Library is restricted in certain countries either by patents or by copyrighted interfaces, the original copyright holder who places the Library under this License may add an explicit geographical distribution limitation excluding those countries, so that distribution is permitted only in or among countries not thus excluded. In such case, this License incorporates the limitation as if written in the body of this License.
- 13. The Free Software Foundation may publish revised and/or new versions of the Lesser General Public License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns.

Each version is given a distinguishing version number. If the Library specifies a version number of this License which applies to it and "any later version", you have the option of following the terms and conditions either of that version or of any later version published by the Free Software Foundation. If the Library does not specify a license version number, you may choose any version ever published by the Free Software Foundation.

14. If you wish to incorporate parts of the Library into other free programs whose distribution conditions are incompatible with these, write to the author to ask for permission. For software which is copyrighted by the Free Software Foundation, write to the Free Software Foundation; we sometimes make exceptions for this. Our decision will be guided by the two goals of preserving the free status of all derivatives of our free software and of promoting the sharing and reuse of software generally.

NO WARRANTY

- 15. BECAUSE THE LIBRARY IS LICENSED FREE OF CHARGE, THERE IS NO WARRANTY FOR THE LIBRARY, TO THE EXTENT PERMITTED BY APPLICABLE LAW. EXCEPT WHEN OTHERWISE STATED IN WRITING THE COPYRIGHT HOLDERS AND/OR OTHER PARTIES PROVIDE THE LIBRARY "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE. THE ENTIRE RISK AS TO THE QUALITY AND PERFORMANCE OF THE LIBRARY IS WITH YOU. SHOULD THE LIBRARY PROVE DEFECTIVE, YOU ASSUME THE COST OF ALL NECESSARY SERVICING, REPAIR OR CORRECTION.
- 16. IN NO EVENT UNLESS REQUIRED BY APPLICABLE LAW OR AGREED TO IN WRITING WILL ANY COPYRIGHT HOLDER, OR ANY OTHER PARTY WHO MAY MODIFY AND/OR REDISTRIBUTE THE LIBRARY AS PERMITTED ABOVE, BE LIABLE TO YOU FOR DAMAGES, INCLUDING ANY GENERAL, SPECIAL, INCIDENTAL OR CONSEQUENTIAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE THE LIBRARY (INCLUDING BUT NOT LIMITED TO LOSS OF DATA OR DATA BEING RENDERED INACCURATE OR LOSSES SUSTAINED BY YOU OR THIRD PARTIES OR A FAILURE OF THE LIBRARY TO OPERATE WITH ANY OTHER SOFTWARE), EVEN IF SUCH HOLDER OR OTHER PARTY HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

END OF TERMS AND CONDITIONS

How to Apply These Terms to Your New Libraries

If you develop a new library, and you want it to be of the greatest possible use to the public, we recommend making it free software that everyone can redistribute and change. You can do so by permitting redistribution under these terms (or, alternatively, under the terms of the ordinary General Public License).

To apply these terms, attach the following notices to the library. It is safest to attach them to the start of each source file to most effectively convey the exclusion of warranty; and each file should have at least the "copyright" line and a pointer to where the full notice is found.

```
<one line to give the library's name and a brief idea of what it does.>
   Copyright (C) <year> <name of author>
   This library is free software; you can redistribute it and/or
   modify it under the terms of the GNU Lesser General Public
   License as published by the Free Software Foundation; either
    version 2.1 of the License, or (at your option) any later version.
   This library is distributed in the hope that it will be useful,
    but WITHOUT ANY WARRANTY; without even the implied warranty of
   MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU
   Lesser General Public License for more details.
   You should have received a copy of the GNU Lesser General Public
   License along with this library; if not, write to the Free Software
   Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA
    02110-1301
               USA
Also add information on how to contact you by electronic and paper mail.
You should also get your employer (if you work as a programmer) or your
school, if any, to sign a "copyright disclaimer" for the library, if
necessary. Here is a sample; alter the names:
  Yoyodyne, Inc., hereby disclaims all copyright interest in the
  library `Frob' (a library for tweaking knobs) written by James
 Random Hacker.
  <signature of Ty Coon>, 1 April 1990
 Ty Coon, President of Vice
That's all there is to it!
```

B.3 libevent License

The following software may be included in this product:

```
libevent
All rights reserved.
Redistribution and use in source and binary forms, with or without
modification, are permitted provided that the following conditions
are met:
1. Redistributions of source code must retain the above copyright
   notice, this list of conditions and the following disclaimer.
2. Redistributions in binary form must reproduce the above copyright
  notice, this list of conditions and the following disclaimer in the
  documentation and/or other materials provided with the distribution.
3. The name of the author may not be used to endorse or promote products
  derived from this software without specific prior written permission.
THIS SOFTWARE IS PROVIDED BY THE AUTHOR ``AS IS'' AND ANY EXPRESS OR
IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES
OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED.
IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT,
INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT
NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE,
DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY
THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT
(INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF
THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE
Parts developed by Adam Langley
log.c
```

Based on err.c, which was adapted from OpenBSD libc *err*warncode.

Copyright (c) 2005 Nick Mathewson Copyright (c) 2000 Dug Song

Copyright (c) 1993 The Regents of the University of California. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- Neither the name of the University nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

==

==

min_heap.h

Copyright (c) 2006 Maxim Yegorushkin All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

==

== win32.c

Copyright 2000-2002 Niels Provos Copyright 2003 Michael A. Davis All rights reserved. Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- The name of the author may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

B.4 libintl License

The following software may be included in this product:

libintl

Copyright (C) 1994 X Consortium

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE X CONSORTIUM BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

Except as contained in this notice, the name of the X Consortium shall not be used in advertising or otherwise to promote the sale, use or other dealings in this Software without prior written authorization from the X Consortium.

FSF changes to this file are in the public domain.

Copyright 1996-2007 Free Software Foundation, Inc. Taken from GNU libtool, 2001

Originally by Gordon Matzigkeit <gord@gnu.ai.mit.edu>, 1996

This file is free software; the Free Software Foundation gives unlimited permission to copy and/or distribute it, with or without modifications, as long as this notice is preserved.

You are receiving a copy of the libintl library. The terms of the Oracle license do NOT apply to the libintl library; it is licensed under the following license, separately from the Oracle programs you receive. If you do not wish to install this program, you may create an "exclude" file and run tar with the X option.

This component is licensed under Section B.2, "GNU Lesser General Public License Version 2.1, February 1999".

B.5 LPeg Library License

The following software may be included in this product:

LPeg

Use of any of this software is governed by the terms of the license below:

Copyright © 2008 Lua.org, PUC-Rio.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

B.6 Lua (liblua) License

The following software may be included in this product:

Lua (liblua)

Copyright © 1994-2008 Lua.org, PUC-Rio.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

B.7 LuaFileSystem Library License

The following software may be included in this product:

LuaFileSystem

Copyright © 2003 Kepler Project.

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

B.8 PCRE License

The following software may be included in this product:

PCRE (Perl Compatible Regular Expressions) Library

```
PCRE LICENCE
PCRE is a library of functions to support regular expressions
whose syntax and semantics are as close as possible to those
of the Perl 5 language.
Release 7 of PCRE is distributed under the terms of the "BSD"
licence, as specified below. The documentation for PCRE,
supplied in the "doc" directory, is distributed under the same
terms as the software itself.
The basic library functions are written in C and are
freestanding. Also included in the distribution is a set
of C++ wrapper functions.
THE BASIC LIBRARY FUNCTIONS
               Philip Hazel
Written by:
Email local part: ph10
Email domain:
                 cam.ac.uk
University of Cambridge Computing Service,
Cambridge, England. Phone: +44 1223 334714.
Copyright (c) 1997-2006 University of Cambridge
All rights reserved.
THE C++ WRAPPER FUNCTIONS
Contributed by: Google Inc.
Copyright (c) 2006, Google Inc.
All rights reserved.
THE "BSD" LICENCE
Redistribution and use in source and binary forms,
with or without modification, are permitted provided
that the following conditions are met:
* Redistributions of source code must retain the above
 copyright notice, this list of conditions and the
 following disclaimer.
```

- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- * Neither the name of the University of Cambridge nor the name of Google Inc. nor the names of their contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

End

B.9 SHA-1 in C License

The following software may be included in this product:

SHA-1 in C

SHA-1 in C By Steve Reid <steve@edmweb.com> 100% Public Domain

Appendix C Attribute Summary Tables

Table of Contents

C.1	Management Node Configuration Parameters	159
C.2	Data Node Configuration Parameters	161
C.3	API Node Configuration Parameters	176
	Other Node Configuration Parameters	
C.5	MySQL Server Option and Variable Reference for MySQL Cluster	182

This appendix provides tables of configuration attributes, grouped according to their process type or by the section of the MySQL Cluster configuration file in which they appear. This information is current for MySQL Cluster NDB 7.3. For information regarding MySQL Cluster NDB 7.2 and earlier versions of MySQL Cluster, see Configuration of MySQL Cluster, and Configuration of MySQL Cluster NDB 6.1-7.1.

Each table provides the following information:

- *Name*: The name of the attribute. The name of the attribute is linked to the attribute's full description in the online MySQL Cluster documentation.
- *Type/Units*: The data type or unit by which the attribute is measured.
- Range: The default value of the attribute if not set by the user, and the minimum and maximum values which can be set for the attribute.
- Restart Type: The type of restart required for a change in value in this attribute to be applied in a running MySQL Cluster. The restart type is indicated in this column by an N for a node restart, or an S for a system restart. Data node attributes: The presence of an I in this column indicates that a data node must be restarted using the --initial option for a change to take effect.

Attributes having restart type **N** can be changed using a rolling restart of the cluster, and thus can be changed at any time, even if the cluster is running. Changing an attribute whose restart type is **S** requires a complete shutdown of all cluster nodes, followed by a restart of the nodes once all of them have been stopped. Currently, such attributes can be set only before starting a cluster for the first time.

C.1 Management Node Configuration Parameters

Table C.1 Management Node Configuration Parameters

	Type or Units		
	Default Value		ln l
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	milliseconds		
	0	N	
ArbitrationDelay	0 / 4294967039 (0xFFFFEFF)		NDB 7.3.0
	0-2		
ArbitrationRank	1	N	NDB 7.3.0
	0/2		

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	path		
DataDir		N	NDB 7.3.0
	name		
ExecuteOnComputer	[none]	S	NDB 7.3.0
	milliseconds		
	1500		
HeartbeatIntervalMgmdMgmd	100 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.3
	string		
 HeartbeatThreadPriority	[none]	S	NDB 7.3.0
-			
	name or IP address	N	NIDD 7.0.0
HostName	[none]		NDB 7.3.0
	unsigned	IS	
Id	[none]		NDB 7.3.0
	1 / 255		
I ambantian	{CONSOLE SYSLOG FILE}	N	NDB 7.3.0
LogDestination	[see text]	IN	NDB 7.3.0
	unsigned		
	100		
MaxNoOfSavedEvents	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	unsigned		
NodeId	[none]	IS	NDB 7.3.0
	1 / 255		
	unsigned		
PortNumber	1186	S	NDB 7.3.0
	0 / 64K		
	unsigned	N	
PortNumberStats	[none]		NDB 7.3.0

	Type or Units		
	Default Value	Restart Type	In
Parameter Name	Minimum/ Maximum or Permitted Values		Version (and later)
	0 / 64K		
	bytes	N	
	0		
TotalSendBufferMemory	256K / 4294967039 (0xFFFFEFF)		NDB 7.3.0
	boolean		
wan	false	N	NDB 7.3.0
	true, false		

C.2 Data Node Configuration Parameters

Table C.2 Data Node Configuration Parameters

	Type or Units		
	Default Value		In
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	enumeration		
	Default		
Arbitration	Default, Disabled, WaitExternal	N	NDB 7.3.0
	milliseconds		NDB 7.3.0
	7500		
ArbitrationTimeout	10 / 4294967039 (0xFFFFEFF)	N	
	bytes	N	NDB 7.3.0
	16M		
BackupDataBufferSize	0 / 4294967039 (0xFFFFEFF)		
	path		
BackupDataDir	FileSystemPath	IN	NDB 7.3.0
	percent		
BackupDiskWriteSpeedPct	50	N	NDB 7.4.8
	0 / 90		
BackupLogBufferSize	bytes	N	NDB 7.3.0

Parameter Name	Type or Units		
	Default Value		
	Minimum/	Restart	In Version
	Maximum or Permitted Values	Туре	(and later)
	16M		
	0 / 4294967039 (0xFFFFEFF)		
	bytes		
	1M		
BackupMaxWriteSize	2K / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	bytes		
	32M		
BackupMemory	0 /	N	NDB 7.3.0
	4294967039 (0xFFFFFEFF)		
	seconds		NDB 7.3.0
	0		
BackupReportFrequency	0 / 4294967039 (0xFFFFEFF)	N	
	bytes		
	256K		
BackupWriteSize	2K / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	integer		
BatchSizePerLocalScan	256	N	NDB 7.3.0
	1 / 992		
	numeric		
BuildIndexThreads	0	S	NDB 7.3.0
	0 / 128		
	boolean		
CompressedBackup	false	N	NDB 7.3.0
	true, false		
	boolean		
CompressedLCP	false	N	NDB 7.3.0
	true, false		
Garage and the plants to the second and the second	milliseconds	N1	NDD 700
ConnectCheckIntervalDelay	0	N	NDB 7.3.0

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	0 / 4294967039 (0xFFFFEFF)		
	boolean		
CrashOnCorruptedTuple	true	S	NDB 7.3.0
	true, false		
	path		
DataDir		IN	NDB 7.3.0
	bytes		
DataMemory	80M	N	NDB 7.3.0
	1M / 1024G	.,	1122 11010
	LDM threads		
 DefaultHashMapSize	3840	N	NDB 7.3.0
20144101421114F0110	0 / 3840		
	bytes		
DictTrace	undefined	N	NDB 7.3.0
	0 / 100		
	bytes		
	10M		
DiskCheckpointSpeed	1M / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	bytes		
	100M		
DiskCheckpointSpeedInRestart	1M / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	threads		
	2		
DiskIOThreadPool	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	true false (1 0)		
Diskless	false	IS	NDB 7.3.0
	true, false		
	32K pages		
DiskPageBufferEntries	10	N	NDB 7.4.3
	1 / 1000	l	

	Type or Units		
Parameter Name	Default Value		l.
	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	bytes		
DiskPageBufferMemory	64M	N	NDB 7.3.0
	4M / 1T		
	bytes		
	4M		
DiskSyncSize	32K / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	name		
ExecuteOnComputer	[none]	S	NDB 7.3.0
	bytes		
ExtraSendBufferMemory	0	N	NDB 7.3.0
	0 / 32G		
	path		
FileSystemPath	DataDir	IN	NDB 7.3.0
	filename		
FileSystemPathDataFiles	[see text]	IN	NDB 7.3.0
	filename		
FileSystemPathDD	FileSystemPath	IN	NDB 7.3.0
	filename		
FileSystemPathUndoFiles	[see text]	IN	NDB 7.3.0
	bytes		
FragmentLogFileSize	16M	IN	NDB 7.3.0
	4M / 1G		
	milliseconds		
	1500	N	NDD TO
HeartbeatIntervalDbApi	100 / 4294967039 (0xFFFFFEFF)		NDB 7.3.0
HeartbeatIntervalDbDb	milliseconds	N	NDB 7.3.0
HeartbeatIntervalDDDD	5000		1,100 7.0.0

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	10 / 4294967039 (0xFFFFEFF)		
	numeric		
HeartbeatOrder	0	S	NDB 7.3.0
	0 / 65535		
	name or IP address		
HostName	localhost	N	NDB 7.3.0
	unsigned		
Id	[none]	IS	NDB 7.3.0
	1 / 48		
	bytes		
IndexMemory	18M	N	NDB 7.3.0
	1M / 1T		
	boolean	S	
IndexStatAutoCreate	false		NDB 7.3.0
	false, true		
	boolean		
IndexStatAutoUpdate	false	S	NDB 7.3.0
	false, true		
	percentage		
	100		
IndexStatSaveScale	0 / 4294967039 (0xFFFFEFF)	IN	NDB 7.3.0
	bytes		
	32768		
IndexStatSaveSize	exStatSaveSize 0 / IN 4294967039 (0xFFFFEFF)	IN	NDB 7.3.0
	percentage		
	100		
IndexStatTriggerPct	0 / 4294967039 (0xFFFFEFF)	NDB 7.3.0	
IndexStatTriggerScale	percentage 100	IN	NDB 7.3.0

	Type or Units															
Parameter Name	Default Value		In													
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)													
	0 / 4294967039 (0xFFFFEFF)															
	seconds															
	60															
IndexStatUpdateDelay	0 / 4294967039 (0xFFFFFEFF)	IN	NDB 7.3.0													
	[see values]															
To de Transcontent and the second	SPARSE	INI	NDB 7.3.0													
InitFragmentLogFiles	SPARSE, FULL	IN	NDB 7.3.0													
	string															
InitialLogFileGroup	[see text]	S	NDB 7.3.0													
	files															
	27	N														
InitialNoOfOpenFiles	20 / 4294967039 (0xFFFFFEFF)		NDB 7.3.0													
	string															
InitialTablespace	[see text]	S	NDB 7.3.0													
	numeric															
LateAlloc	1	N	NDB 7.3.0													
	0 / 1															
	second															
	60															
LcpScanProgressTimeout	0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.3													
	CPU ID															
LockExecuteThreadToCPU	64K	N	NDB 7.3.0													
	0 / 64K															
	CPU ID															
LockMaintThreadsToCPU	[none]	N	NDB 7.3.0													
	0 / 64K															
- 15	numeric	N	NDD 700													
LockPagesInMainMemory	0		NDB 7.3.0													

Parameter Name	Type or Units		
	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	0/2		
	log level		
LogLevelCheckpoint	0	N	NDB 7.3.0
	0 / 15		
	levelr		NDB 7.3.0
LogLevelCongestion	0	N	
	0 / 15		
	integer		
LogLevelConnection	0	N	NDB 7.3.0
	0 / 15		
	integer		
LogLevelError	0	N	NDB 7.3.0
	0 / 15		
	integer	N	NDB 7.3.0
LogLevelInfo	0		
	0 / 15		
	integer		
LogLevelNodeRestart	0	N	NDB 7.3.0
	0 / 15		
	integer	N	NDB 7.3.0
LogLevelShutdown	0		
	0 / 15		
	integer		
LogLevelStartup	1	N	NDB 7.3.0
	0 / 15		
	integer		
LogLevelStatistic	0	N	NDB 7.3.0
	0 / 15		
	bytes		
	64M	N	
LongMessageBuffer	512K / 4294967039 (0xFFFFEFF)		NDB 7.3.5
	unsigned		
MaxAllocate	32M	N	NDB 7.3.0
	1M / 1G		
MaxBufferedEpochs	epochs	N	NDB 7.3.0

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	100		
	0 / 100000		
	bytes		
	26214400		
MaxBufferedEpochBytes	26214400 (0x01900000) / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	numeric		
MaxDiskWriteSpeed	20M	S	NDB 7.4.1
	1M / 1024G		
	numeric		
MaxDiskWriteSpeedOtherNodeRestart	50M	S	NDB 7.4.1
	1M / 1024G		
	numeric		
MaxDiskWriteSpeedOwnRestart	200M	S	NDB 7.4.1
	1M / 1024G		
	operations (DML)		NDB 7.3.0
MaxDMLOperationsPerTransaction	4294967295	N	
	32 / 4294967295		
	seconds		
MaxLCPStartDelay	0	N	NDB 7.3.0
	0 / 600		
	integer		
	1000	N	NDB 7.3.0
MaxNoOfAttributes	32 / 4294967039 (0xFFFFFEFF)		
	integer		
	8K		
MaxNoOfConcurrentIndexOperations	0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
	integer		
	32K		
MaxNoOfConcurrentOperations	32 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0

	Type or Units		
Parameter Name	Default Value		ln.
	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	integer		
MaxNoOfConcurrentScans	256	N	NDB 7.3.0
	2 / 500		
	unsigned		
	256		
MaxNoOfConcurrentSubOperations	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	integer		
	4096		
MaxNoOfConcurrentTransactions	32 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	integer		NDB 7.3.0
	4000		
MaxNoOfFiredTriggers	0 / 4294967039 (0xFFFFEFF)	N	
	integer	N	NDB 7.3.0
	UNDEFINED		
MaxNoOfLocalOperations	32 / 4294967039 (0xFFFFEFF)		
	integer	N	NDB 7.3.0
	[see text]		
MaxNoOfLocalScans	NoOfLocalScans 32 / 4294967039 (0xFFFFEFF)		
	unsigned	N	NDB 7.3.0
	0		
MaxNoOfOpenFiles	20 / 4294967039 (0xFFFFEFF)		
	integer	N	NDB 7.3.0
	128		
MaxNoOfOrderedIndexes	0 / 4294967039 (0xFFFFEFF)		
MaxNoOfSavedMessages	integer 25	N	NDB 7.3.0

Parameter Name	Type or Units	Restart Type	In Version (and later)
	Default Value		
	Minimum/ Maximum or Permitted Values		
	0 / 4294967039 (0xFFFFEFF)		
MaxNoOfSubscribers	unsigned 0 0 / 4294967039	N	NDB 7.3.0
MaxNoOfSubscriptions	(0xFFFFEFF) unsigned 0 0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
MaxNoOfTables	integer 128 8 / 20320	N	NDB 7.3.0
MaxNoOfTriggers	integer 768 0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
MaxNoOfUniqueHashIndexes	integer 64 0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
MaxParallelCopyInstances	integer 0 0 / 64	S	NDB 7.4.3
MaxParallelScansPerFragment	bytes 256 1 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
MaxStartFailRetries	unsigned 3 0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
MemReportFrequency	unsigned	N	NDB 7.3.0

Parameter Name	Type or Units		
	Default Value		lm.
	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	0		
	0 / 4294967039 (0xFFFFEFF)		
	numeric		
MinDiskWriteSpeed	10M 1M / 1024G	S	NDB 7.4.1
	unsigned		
MinFreePct	5	N	NDB 7.3.0
MINITERPOL	0 / 100	IN	1100 7.3.0
NodeGroup	[none]	IS	NDB 7.3.0
	0 / 65536		
	unsigned		
NodeId	[none]	IS	NDB 7.3.0
	1 / 48		
	integer		
	16		
NoOfFragmentLogFiles	3 / 4294967039 (0xFFFFEFF)	IN	NDB 7.3.0
	integer		
NoOfReplicas	2	IS	NDB 7.3.0
	1 / 4		
	boolean		
Numa	1	N	NDB 7.3.0
	boolean		
ODirect	false	N	NDB 7.3.0
	true, false		
	boolean		
RealtimeScheduler	neduler false N	N	NDB 7.3.0
	true, false		
	bytes		
	32M		
RedoBuffer	1M / 4294967039	N	NDB 7.3.0
	(0xFFFFEFF)		

Parameter Name	Type or Units		
	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	numeric		
	3		
RedoOverCommitCounter	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	seconds		
	20		
RedoOverCommitLimit	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	bytes		
	256K		
ReservedSendBufferMemory	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	error code		NDB 7.3.0
RestartOnErrorInsert	2	N	
	0 / 4		
	µsec		
SchedulerExecutionTimer	50	N	NDB 7.3.0
	0 / 11000		
	µsec		NDB 7.3.0
SchedulerSpinTimer	0	N	
	0 / 500		
	unsigned		
ServerPort	[none]	S	NDB 7.3.0
	1 / 64K		
	bytes		
SharedGlobalMemory	edGlobalMemory 128M	N	NDB 7.3.0
	0 / 64T		
	unsigned	N	
	0		
StartFailRetryDelay	0 / 4294967039 (0xFFFFEFF)		NDB 7.3.0
StartFailureTimeout	milliseconds 0	N	NDB 7.3.0

Parameter Name	Type or Units		
	Default Value		
	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	0 / 4294967039 (0xFFFFFEFF)		
	milliseconds		
	15000		NDB 7.3.0
StartNoNodeGroupTimeout	0 / 4294967039 (0xFFFFFEFF)	N	
	milliseconds		
	30000		
StartPartialTimeout	0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
	milliseconds		NDB 7.3.0
	60000		
StartPartitionedTimeout	0 / 4294967039 (0xFFFFFEFF)	N	
	seconds		NDB 7.3.0
	0		
StartupStatusReportFrequency		N	
	boolean		
StopOnError	1	N	NDB 7.3.0
	0, 1		
	% or bytes		
	25	S	NDB 7.3.0
StringMemory	0 / 4294967039 (0xFFFFEFF)		
	boolean		
TcpBind_INADDR_ANY	DDR_ANY false N	N	NDB 7.3.0
	true, false		
	milliseconds	N	
TimeBetweenEpochs	100		NDB 7.3.0
	0 / 32000		
	milliseconds		
TimeBetweenEpochsTimeout	0	N	NDB 7.3.0
	0 / 256000		

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	milliseconds		
TimeBetweenGlobalCheckpoints	2000	N	NDB 7.3.0
	20 / 32000		
	milliseconds	N	NDB 7.3.9
	120000		
TimeBetweenGlobalCheckpointsTimeout	10 / 4294967039 (0xFFFFEFF)		
	milliseconds		
	1000		
TimeBetweenInactiveTransactionAbortCheck	1000 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
TimeBetweenLocalCheckpoints	number of 4- byte words, as a base-2 logarithm	N	NDB 7.3.0
	0 / 31		
	milliseconds		NDB 7.3.0
TimeBetweenWatchDogCheck	6000 70 / 4294967039 (0xFFFFFEFF)	N	
	milliseconds		
	6000		NDB 7.3.0
TimeBetweenWatchDogCheckInitial	enWatchDogCheckInitial 70 / 4294967039 (0xFFFFFEFF)	N	
	bytes		
	0		NDB 7.3.0
TotalSendBufferMemory	256K / 4294967039 (0xFFFFEFF)	N	
	bytes	N	
	1M		
TransactionBufferMemory	1K / 4294967039 (0xFFFFFEFF)		NDB 7.3.0
TransactionDeadlockDetectionTimeout	milliseconds 1200	N	NDB 7.3.0

	Type or Units		
	Default Value	Restart Type	In Version (and later)
Parameter Name	Minimum/ Maximum or Permitted Values		
	50 / 4294967039 (0xFFFFEFF)		
	milliseconds		
	[see text]		NDB 7.3.0
TransactionInactiveTimeout	0 / 4294967039 (0xFFFFEFF)	N	
	boolean		
TwoPassInitialNodeRestartCopy	false	N	NDB 7.3.0
	true, false		
	unsigned		
	16M		
UndoDataBuffer	1M / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	unsigned		
	2M		NDB 7.3.0
UndoIndexBuffer	1M / 4294967039 (0xFFFFEFF)	N	

Table C.3 Multi-Threaded Data Node Configuration Parameters

	Type or Units		
	Default Value	Restart Type	In Version (and later)
Parameter Name	Minimum/ Maximum or Permitted Values		
	integer		NDB 7.3.3 NDB 7.3.3
MaxNoOfExecutionThreads	2	IS IN	
	2 / 72		
	numeric		
 NoOfFragmentLogParts	4		
	4, 8, 12, 16, 24, 32		
	string		
ThreadConfig	"	IS	NDB 7.3.0

C.3 API Node Configuration Parameters

Table C.4 SQL Node / API Node Configuration Parameters

	Type or Units		
	Default Value		
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	milliseconds		
	0		
ArbitrationDelay	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	0-2		
ArbitrationRank	0	N	NDB 7.3.0
	0/2		
	boolean		
AutoReconnect	false	N	NDB 7.3.0
	true, false		
	bytes		
BatchByteSize	16K	N	NDB 7.3.0
	1024 / 1M		
	records	N	
BatchSize	256		NDB 7.3.0
	1 / 992		
	integer		
	0		
ConnectBackoffMaxTime	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.4.2
	string		
ConnectionMap	[none]	N	NDB 7.3.0
	buckets		
DefaultHashMapSize	3840	N	NDB 7.3.0
	0 / 3840		
	enumeration		
DefaultOperationRedoProblemAction	QUEUE	S	NDB 7.3.0
Delauroperacion Medori Obiem Accion	ABORT, QUEUE	J	7.0.0
	bytes		
EventLogBufferSize	8192	S	NDB 7.3.0
	0 / 64K		
ExecuteOnComputer	name	S	NDB 7.3.0

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	In Version (and later)
	[none]		
	bytes		
	0		
ExtraSendBufferMemory	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	string		
HeartbeatThreadPriority	[none]	S	NDB 7.3.0
HostName	name or IP address	N	NDB 7.3.0
	[none]	N	
	unsigned	IS	NDB 7.3.0
Id	[none]		
	1 / 255		
	bytes		NDB 7.3.0
MaxScanBatchSize	256K	N	
	32K / 16M		
	unsigned		
NodeId	[none]	IS	NDB 7.3.0
	1 / 255		
	integer		
	0		
StartConnectBackoffMaxTime	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.4.2
	bytes		
TotalSendBufferMemory	0		
	256K / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
	boolean	N	
wan	false		NDB 7.3.0
	true, false		

C.4 Other Node Configuration Parameters

Table C.5 Computer Configuration Parameters

	Type or Units	Restart Type	In Version (and later)
	Default Value		
Parameter Name	Minimum/ Maximum or Permitted Values		
	name or IP address		
HostName	[none]	N N	NDB 7.3.0
	string		
Id	[none]	IS	NDB 7.3.0

Table C.6 TCP Configuration Parameters

Parameter Name	Type or Units	Restart Type	In Version (and later)
	Default Value		
	Minimum/ Maximum or Permitted Values		
	boolean		
Checksum	false	N	NDB 7.3.0
	true, false		
	unsigned		
Group	55	N	NDB 7.3.0
	0 / 200		
	numeric		NDB 7.3.0
NodeId1	[none]	N	
	numeric	N	NDB 7.3.0
NodeId2	[none]		
	numeric	N	NDB 7.3.0
NodeIdServer	[none]		
	bytes		
OverloadLimit	0		
	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	unsigned	0	NDD 7.0.0
PortNumber	[none]	S	NDB 7.3.0

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	0 / 64K		
	string		
Proxy	[none]	N	NDB 7.3.0
	bytes		
	2M		
ReceiveBufferMemory	16K / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	unsigned		NDB 7.3.0
SendBufferMemory	2M	N	
	256K / 4294967039 (0xFFFFFEFF)		
	boolean		NDB 7.3.0
SendSignalId	[see text]	N	
	true, false		
	unsigned		
TCP_MAXSEG_SIZE	0	N	NDB 7.3.0
	0 / 2G		
	unsigned		
TCP_RCV_BUF_SIZE	0	N	NDB 7.3.1
	0 / 2G		
	unsigned		
TCP_SND_BUF_SIZE	0	N	NDB 7.3.1
	0 / 2G		
	boolean		
TcpBind_INADDR_ANY	false	N	NDB 7.3.0
	true, false		

Table C.7 Shared Memory Configuration Parameters

	Type or Units		
	Default Value		ln l
Parameter Name	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
Checksum	boolean true	N	NDB 7.3.0

	Type or Units		
Parameter Name	Default Value		In
	Minimum/ Maximum or Permitted Values	Restart Type	Version (and later)
	true, false		
	unsigned		
Group	35	N	NDB 7.3.0
	0 / 200		
	numeric		
NodeId1	[none]	N	NDB 7.3.0
	numeric		
NodeId2	[none]	N	NDB 7.3.0
	numeric		
NodeIdServer	[none]	N	NDB 7.3.0
	bytes		NDB 7.3.0
	0		
OverloadLimit	0 / 4294967039 (0xFFFFEFF)	N	
	unsigned		NDB 7.3.0
PortNumber	[none]	S	
	0 / 64K		
	boolean		
SendSignalId	false	N	NDB 7.3.0
	true, false		
	unsigned		
	[none]		
ShmKey	0 / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	bytes		
ShmSize	1M		
	64K / 4294967039 (0xFFFFEFF)	N	NDB 7.3.0
	unsigned		
	[none]		
Signum	0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0

Table C.8 SCI Configuration Parameters

Parameter Name Checksum	Type or Units Default Value Minimum/ Maximum or Permitted Values boolean false true, false	Restart Type	In Version (and later)
Group	unsigned 15 0 / 200	N	NDB 7.3.0
Host1SciId0	unsigned [none] 0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
HostlSciId1	unsigned 0 0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
Host2SciId0	unsigned [none] 0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
Host2SciId1	unsigned 0 0 / 4294967039 (0xFFFFFEFF)	N	NDB 7.3.0
NodeId1	numeric [none]	N	NDB 7.3.0
Nodeld2	numeric [none]	N	NDB 7.3.0
NodeldServer	numeric [none]	N	NDB 7.3.0
OverloadLimit	bytes 0	N	NDB 7.3.0

Parameter Name	Type or Units	Restart Type	In Version (and later)
	Default Value Minimum/ Maximum or Permitted Values		
	unsigned		
PortNumber	[none]	S	NDB 7.3.0
	0 / 64K		
	unsigned		
SendLimit	8K	N	NDB 7.3.0
	128 / 32K		
	boolean		
SendSignalId	true	N	NDB 7.3.0
	true, false		
SharedBufferSize	unsigned	N	NDB 7.3.0
	10M		
	64K / 4294967039 (0xFFFFEFF)		

C.5 MySQL Server Option and Variable Reference for MySQL Cluster

Table C.9 MySQL Server Options and Variables for MySQL Cluster: MySQL Cluster NDB 7.3-7.4

	Option or Variable N	Name
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		<u>'</u>
	Com_show_ndb_sta	atus
No	No	Yes
No	Both	No
DESCRIPTION: Count	of SHOW NDB STATUS statement	s
	create_old_tempo	rals
Yes	Yes	No
Yes	Global	No
•	e-5.6.4 storage format for temporal pgrades/downgrades between NDE	types when creating tables. Intended for 37.2 and NDB 7.3/7.4.
	Handler_discov	rer
No	No	Yes
No	Both	No

	Option or Variable N	lame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	have_ndbcluste	er
No	Yes	No
No	Global	No
DESCRIPTION: Whether	mysqld supports NDB Cluster tab ndb-batch-siz	• • •
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Size (in b	oytes) to use for NDB transaction	batches
	ndb-blob-read-batch	n-bytes
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Specifies	size in bytes that large BLOB rea	ads should be batched into. 0 = no limit.
	ndb-blob-write-batc	h-bytes
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Specifies	size in bytes that large BLOB wri	ites should be batched into. 0 = no limit.
Yes	Yes	Yes
Yes	Global	No
DESCRIPTION: Number of	of connections to the cluster used	by MySQL
	ndb-connectstri	ing
Yes	No	No
Yes		No
DESCRIPTION: Point to t	he management server that distributed in the management server that dist	•
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Specifies	that constraint checks on unique	indexes (where these are supported) or used; for testing purposes only.
Yes	Yes	No
Yes	Global	Yes
		CLUSTER (KEYHASH or LINHASH,
Yes	Yes	No
Yes	Global	No

	Option or Variable Name	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	server acting as a slave to log my er in its own binary log, using its or ster option. ndb-log-empty-epochs	
Yes	Yes	No
Yes	Global	Yes
	causes epochs in which there were g_index tables, even whenlog-slandb-log-exclusive-reads	
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Log primary key conflicts.	reads with exclusive locks; allow o	conflict resolution based on read
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Log originating s	erver id and epoch in mysql.ndb_b	pinlog_index table.
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Write NDB trans	action IDs in the binary log. Requir	eslog-bin-v1-events=OFF.
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: Toggles logging	of updates on the master between ndb-mgmd-host	updates (OFF) and writes (ON)
Yes	No	No
Yes		No
DESCRIPTION: Set the host (and	d port, if desired) for connecting to ndb-nodeid	management server
Yes	No	Yes
Yes	Global	No
DESCRIPTION: MySQL Cluster r	node ID for this MySQL server ecv-thread-activation-thre	eshold
Yes	No	No
Yes		No
DESCRIPTION: Activation thresh connection (measured in concurre	old when receive thread takes over ently active threads) ndb-recv-thread-cpu-mask	er the polling of the cluster

Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes	СССРС	
Yes	No	No
Yes	140	No
		pecific CPUs; specified as hexadecimal
Yes	No	No
No	110	No
DESCRIPTION: Enable of	or disable the ndb_transid_mysql_c DN_SCHEMA table having that nan ndb-wait-connect	connection_map plugin; that is, enable c ne.
Yes	Yes	No
Yes	Global	No
•	seconds) for the MySQL server to odes before accepting MySQL clier ndb-wait-setur	nt connections.
Yes	Yes	No
Yes	Global	No
No	No No No server to Ndb_api_bytes_receive	wait for NDB engine setup to complete. ed_count Yes
No	Global	No
DESCRIPTION: Amount node).	of data (in bytes) received from the	e data nodes by this MySQL Server (SQ
No	No	Yes
No	Session	No
DESCRIPTION: Amount	of data (in bytes) received from the Ndb_api_bytes_received_c	
No	No	Yes
No	Global	No
DESCRIPTION: Amount	of data (in bytes) received from the Ndb_api_bytes_sent_	·
No	No	Yes
No	Global	No
DESCRIPTION: Amount	of data (in bytes) sent to the data r	nodes by this MySQL Server (SQL node
No	No	Yes
No	Session	No

	Option or Variable N	ame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	Ndb_api_bytes_sent_co	unt_slave
No	No	Yes
No	Global	No
DESCRIPTION: Amour	nt of data (in bytes) sent to the data	nodes by this slave.
	Ndb_api_event_bytes	_count
No	No	Yes
No	Global	No
DESCRIPTION: Number	er of bytes of events received by this	s MySQL Server (SQL node).
	Ndb_api_event_bytes_cou	nt_injector
No	No	Yes
No	Global	No
DESCRIPTION: Number	er of bytes of events received by the	NDB binary log injector thread.
	Ndb_api_event_data	_count
No	No	Yes
No	Global	No
DESCRIPTION: Number	er of row change events received by	this MySQL Server (SQL node).
	Ndb_api_event_data_coun	nt_injector
No	No	Yes
No	Global	No
DESCRIPTION: Number	er of row change events received by	the NDB binary log injector thread.
	Ndb_api_event_nondat	a_count
No	No	Yes
No	Global	No
	er of events received, other than row	change events, by this MySQL Server
(SQL node).	Ndb oni cront nondoto go	unt indostor
No	Ndb_api_event_nondata_co	Yes
No	Global	No
injector thread.	er of events received, other than row	change events, by the NDB binary log
•	Ndb_api_pk_op_co	punt
No	No	Yes
No	Global	No
		rimary keys by this MySQL Server (SQL
	Ndb_api_pk_op_count_	session
No	No	Yes
No	Session	No
DESCRIPTION: Number	er of operations based on or using p	rimary keys in this client session.

	Option or Variable Name	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
	Ndb_api_pk_op_count_slave	
No	No	Yes
No	Global	No
DESCRIPTION: Number of opera	ations based on or using primary ke	eys by this slave.
	Ndb_api_pruned_scan_count	
No	No	Yes
No	Global	No
(SQL node).	s that have been pruned to a single _api_pruned_scan_count_ses	
No	No	Yes
No	Session	No
	s that have been pruned to a single	
	o_api_pruned_scan_count_sl	•
No	No	Yes
No	Global	No
	s that have been pruned to a single	
Description of search	Ndb_api_range_scan_count	paradon by and diaver
No	No	Yes
No	Global	No
DESCRIPTION: Number of range	e scans that have been started by t	this MySQL Server (SQL node).
Ndb	_api_range_scan_count_ses	sion
No	No	Yes
No	Session	No
DESCRIPTION: Number of range	e scans that have been started in the	nis client session.
Nd	b_api_range_scan_count_sla	ave
No	No	Yes
No	Global	No
DESCRIPTION: Number of range	e scans that have been started by t	his slave.
	Ndb_api_read_row_count	
No	No	Yes
No	Global	No
	rows that have been read by this Nb_api_read_row_count_sess:	
No	No	Yes
No	Session	No
	rows that have been read in this cl	

	Option or Variable Name	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		1
No	No	Yes
No	Global	No
DESCRIPTION: Total number of	rows that have been read by this s	slave.
	Ndb_api_scan_batch_count	
No	No	Yes
No	Global	No
DESCRIPTION: Number of batch	nes of rows received by this MySQI	L Server (SQL node).
Ndb	_api_scan_batch_count_ses	sion
No	No	Yes
No	Session	No
DESCRIPTION: Number of batch	nes of rows received in this client s	ession.
Nd	b_api_scan_batch_count_sla	ave
No	No	Yes
No	Global	No
DESCRIPTION: Number of batch	nes of rows received by this slave.	
	Ndb_api_table_scan_count	
No	No	Yes
No	Global	No
DESCRIPTION: Number of table	scans that have been started, incl	uding scans of internal tables, by
this MySQL Server (SQL node).		
Ndb	_api_table_scan_count_ses	sion
No	No	Yes
No	Session	No
	scans that have been started, incl	uding scans of internal tables, in
this client session.		
	b_api_table_scan_count_sla	
No	No	Yes
No	Global	No
DESCRIPTION: Number of table this slave.	scans that have been started, incl	uding scans of internal tables, by
triis slave.	Nidh and thong about count	
No	Ndb_api_trans_abort_count No	Yes
No	Global	No
	actions aborted by this MySQL Se	,
	_api_trans_abort_count_ses	1
No No		Yes
No	Session	No
	actions aborted in this client session	
Ndk	o_api_trans_abort_count_sl 	ave

	Option or Variable N	ame
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	No	Yes
No	Global	No
DESCRIPTION: Number	of transactions aborted by this slav	ve.
	Ndb_api_trans_close	_count
No	No	Yes
No	Global	No
	of transactions aborted (may be gi ransAbortCount) by this MySQL S Ndb_api_trans_close_cou	Server (SQL node).
No	No	Yes
No	Session	No
	of transactions aborted (may be gransAbortCount) in this client sess	sion.
No	No	Yes
No	Global	No
No	Ndb_api_trans_commit	Yes Yes
No	Global	No
DESCRIPTION: Number (of transactions committed by this Ndb_api_trans_commit_cou	, , ,
No	No	Yes
No	Session	No
DESCRIPTION: Number	of transactions committed in this c	lient session.
	Ndb_api_trans_commit_co	ount_slave
No	No	Yes
No	Global	No
	and the second s	ala a
DESCRIPTION: Number	of transactions committed by this s Ndb_api_trans_local_read	
DESCRIPTION: Number of	•	
	Ndb_api_trans_local_read	l_row_count
No No	Ndb_api_trans_local_read No Global	d_row_count Yes
No No DESCRIPTION: Total nur	Ndb_api_trans_local_read No Global	d_row_count Yes No by this MySQL Server (SQL node)
No No DESCRIPTION: Total nur	Ndb_api_trans_local_read No Global mber of rows that have been read	d_row_count Yes No by this MySQL Server (SQL node)

	Option or Variable Name	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	No	Yes
No	Global	No
DESCRIPTION: Total number of	rows that have been read by this s	slave.
	Ndb_api_trans_start_count	
No	No	Yes
No	Global	No
DESCRIPTION: Number of trans	actions started by this MySQL Ser	ver (SQL node).
Ndb_	_api_trans_start_count_ses	sion
No	No	Yes
No	Session	No
DESCRIPTION: Number of trans	actions started in this client session	n.
Ndk	_api_trans_start_count_sl	ave
No	No	Yes
No	Global	No
DESCRIPTION: Number of trans	actions started by this slave. Ndb_api_uk_op_count	
No	No	Yes
No	Global	No
node).	ations based on or using unique ke	
No	No	Yes
No	Session	No
	ations based on or using unique ke	
DEGOTAL FIGURE Number of opera	Ndb_api_uk_op_count_slave	
No	No	Yes
No	Global	No
·	ations based on or using unique ke _api_wait_exec_complete_co	•
No	No	Yes
No	Global	No
DESCRIPTION: Number of times operation to complete by this My	s thread has been blocked while was	aiting for execution of an
Ndb_api	_wait_exec_complete_count	_session
No	No	Yes
No	Session	No
operation to complete in this clier	thread has been blocked while want session. i_wait_exec_complete_count	-

Command Line		ame
	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	No	Yes
No	Global	No
DESCRIPTION: Number operation to complete by		-
No	Ndb_api_wait_meta_requ	
No	No	Yes
No	Global	No
this MySQL Server (SQL		waiting for a metadata-based signal by
No	No	Yes
	Session	
No		No
DESCRIPTION: Number this client session.	r of times thread has been blocked Ndb_api_wait_meta_request	waiting for a metadata-based signal in count slave
No	No	Yes
No	Global	No
this slave.	Ndb_api_wait_nanos	waiting for a metadata-based signal by _count
No	No	Yes
	No Global	
No DESCRIPTION: Total tir	Global me (in nanoseconds) spent waiting erver (SQL node).	Yes No for some type of signal from the data
No DESCRIPTION: Total tir nodes by this MySQL Se	Global me (in nanoseconds) spent waiting server (SQL node). Ndb_api_wait_nanos_cour	Yes No for some type of signal from the data nt_session
No DESCRIPTION: Total tir nodes by this MySQL Se	Global me (in nanoseconds) spent waiting server (SQL node). Ndb_api_wait_nanos_cour	Yes No for some type of signal from the data
No DESCRIPTION: Total tir nodes by this MySQL Se No No	Global me (in nanoseconds) spent waiting server (SQL node). Ndb_api_wait_nanos_cour No Session	Yes No for some type of signal from the data nt_session Yes No
No DESCRIPTION: Total tir nodes by this MySQL Se No No DESCRIPTION: Total tir	Global me (in nanoseconds) spent waiting a erver (SQL node). Ndb_api_wait_nanos_cour No Session me (in nanoseconds) spent waiting a ion.	Yes No for some type of signal from the data nt_session Yes No for some type of signal from the data
No DESCRIPTION: Total tir nodes by this MySQL Se No No DESCRIPTION: Total tir nodes in this client sessi	Global me (in nanoseconds) spent waiting forcer (SQL node). Ndb_api_wait_nanos_count No Session me (in nanoseconds) spent waiting forcer. Ndb_api_wait_nanos_count Ndb_api	Yes No for some type of signal from the data nt_session Yes No for some type of signal from the data
No DESCRIPTION: Total tir nodes by this MySQL Se No No DESCRIPTION: Total tir nodes in this client sessi	Global me (in nanoseconds) spent waiting ferver (SQL node). Ndb_api_wait_nanos_cour No Session me (in nanoseconds) spent waiting fion. Ndb_api_wait_nanos_cour No No	Yes No for some type of signal from the data nt_session Yes No for some type of signal from the data nt_slave Yes Yes
No DESCRIPTION: Total tir nodes by this MySQL Se No No DESCRIPTION: Total tir nodes in this client sessi No No DESCRIPTION: Total tir	Global me (in nanoseconds) spent waiting server (SQL node). Ndb_api_wait_nanos_cour No Session me (in nanoseconds) spent waiting sion. Ndb_api_wait_nanos_cour No Global	Yes No for some type of signal from the data nt_session Yes No for some type of signal from the data
No DESCRIPTION: Total tir nodes by this MySQL Se No No DESCRIPTION: Total tir nodes in this client sessi No No DESCRIPTION: Total tir	Global me (in nanoseconds) spent waiting server (SQL node). Ndb_api_wait_nanos_cour No Session me (in nanoseconds) spent waiting sion. Ndb_api_wait_nanos_cour No Global	Yes No for some type of signal from the data nt_session Yes No for some type of signal from the data unt_slave Yes No for some type of signal from the data
No DESCRIPTION: Total tir nodes by this MySQL Se No No DESCRIPTION: Total tir nodes in this client sessi No No DESCRIPTION: Total tir nodes by this slave.	Global me (in nanoseconds) spent waiting ferver (SQL node). Ndb_api_wait_nanos_counds No Session me (in nanoseconds) spent waiting from the spent waiting from	Yes No for some type of signal from the data nt_session Yes No for some type of signal from the data unt_slave Yes No for some type of signal from the data
No No DESCRIPTION: Total tir nodes in this client sessi No No	Global me (in nanoseconds) spent waiting rever (SQL node). Ndb_api_wait_nanos_cour No Session me (in nanoseconds) spent waiting reion. Ndb_api_wait_nanos_cour No Global me (in nanoseconds) spent waiting reion.	Yes No for some type of signal from the data nt_session Yes No for some type of signal from the data ant_slave Yes No for some type of signal from the data ant_slave Yes No for some type of signal from the data

	Option or Variable Name	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	No	Yes
No	Session	No
this client session.	s thread has been blocked while wa	-
	pi_wait_scan_result_count	1
No	No	Yes
No	Global	No
this slave.	sthread has been blocked while was db_autoincrement_prefetch_	
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: NDB auto-increi		
DECORM FIGURE 1800	ndb_cache_check_time	
Yes	Yes	No
Yes	Global	Yes
Yes No	ndb_clear_apply_status Yes Global	No Yes
	SLAVE to clear all rows from the r	
No	No	Yes
No	Both	No
DESCRIPTION: If the server is a node ID in the cluster	cting as a MySQL Cluster node, th Ndb_config_from_host	en the value of this variable its
No	No	Yes
No	Both	No
DESCRIPTION: The host name Ndb_connected_host	or IP address of the Cluster manag	gement server. Formerly
No	No	Yes
No	Both	No
DESCRIPTION: The port for con Ndb_connected_port	necting to Cluster management se	rver. Formerly
	Ndb_conflict_fn_epoch	1,,
No	No	Yes

	Option or Variable Name	
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	Global	No
DESCRIPTION: Number of rows detection function	that have been found in conflict by	the NDB\$EPOCH() conflict
	Ndb_conflict_fn_epoch2	\ <u>\</u>
No	No	Yes
detection function	Global that have been found in conflict by	"
	db_conflict_fn_epoch2_tran	T
No	No	Yes
No	Global	No TRANSO
conflict detection function	that have been found in conflict by Idb_conflict_fn_epoch_tran	ů.
No	No	Yes
No	Global	No
DESCRIPTION: Number of rows conflict detection function	that have been found in conflict by Ndb_conflict_fn_max	the NDB\$EPOCH_TRANS()
No	No	Yes
No	Global	No
this variable indicates the number has been applied	art of a MySQL Cluster involved in of times that conflict resolution ba	ased on "greater timestamp wins"
No	No	Yes
No	Global	No
DESCRIPTION: Number of times \$MAX_DELETE_WIN() has been	that conflict resolution based on o applied. Ndb_conflict_fn_old	utcome of NDB
No	No	Yes
No	Global	No
this variable indicates the number applied	art of a MySQL Cluster involved in of times that "same timestamp wi	ns" conflict resolution has been
No	Yes	No
No	Global	No
	Bepoch on this slave in which a co	nflict was detected.
Nd.	b_conflict_last_stable_epo	och

	Option or Variable	Name
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	No	Yes
No	Global	No
DESCRIPTION: Numb	per of rows found to be in conflict by	a transactional conflict function
	Ndb_conflict_reflected_op	_discard_count
No	No	Yes
No	Global	No
DESCRIPTION: Numb	per of reflected operations that were	not applied due an error during execution.
	Ndb_conflict_reflected_op	_prepare_count
No	No	Yes
No	Global	No
DESCRIPTION: Numb	per of reflected operations received	that have been prepared for execution.
	Ndb_conflict_refresh	_op_count
No	No	Yes
No	Global	No
DESCRIPTION: Numb	per of refresh operations that have b	een prepared.
	Ndb_conflict_trans_conflict	ct_commit_count
No	No	Yes
No	Global	No
DESCRIPTION: Numb	per of epoch transactions committed	after requiring transactional conflict
handling.		
	Ndb_conflict_trans_detection	
NI.	No	Yes
No	INU	168
No	Global	No
No DESCRIPTION: Numb	Global per of internal iterations required to o	No commit an epoch transaction. Should be
No DESCRIPTION: Numb	Global per of internal iterations required to coor equal to Ndb_conflict_trans_confl	No commit an epoch transaction. Should be lict_commit_count.
No DESCRIPTION: Numb (slightly) greater than o	Global per of internal iterations required to coor equal to Ndb_conflict_trans_confl Ndb_conflict_trans_re	No commit an epoch transaction. Should be lict_commit_count.
No DESCRIPTION: Numb (slightly) greater than o	Global per of internal iterations required to coor equal to Ndb_conflict_trans_confl Ndb_conflict_trans_re No	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes
No DESCRIPTION: Numb (slightly) greater than o	Global per of internal iterations required to control of conflict_trans_conflict_trans_re No	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No
No DESCRIPTION: Numb (slightly) greater than o	Global per of internal iterations required to control of conflict_trans_conflict_trans_re No	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes
No DESCRIPTION: Numb (slightly) greater than of No No DESCRIPTION: Numb	Global per of internal iterations required to contend to Ndb_conflict_trans_conflict_trans_re No	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No ng found in conflict by a transactional
No DESCRIPTION: Numb (slightly) greater than of No No DESCRIPTION: Numb	Global per of internal iterations required to control of conflict_trans_conflict_trans_re No	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No ng found in conflict by a transactional
No DESCRIPTION: Numb (slightly) greater than of No No DESCRIPTION: Numb conflict function.	Global oer of internal iterations required to cor equal to Ndb_conflict_trans_confl Ndb_conflict_trans_re No Global oer of transactions rejected after being the state of the state of trans_row_conflict_trans_row_confl	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No ng found in conflict by a transactional
No DESCRIPTION: Numb (slightly) greater than of No No DESCRIPTION: Numb conflict function. No No	Global per of internal iterations required to core equal to Ndb_conflict_trans_confl Ndb_conflict_trans_re No Global per of transactions rejected after being the second sec	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No ng found in conflict by a transactional conflict_count Yes No
No DESCRIPTION: Numb (slightly) greater than of No No DESCRIPTION: Numb conflict function. No No DESCRIPTION: Numb	Global per of internal iterations required to core equal to Ndb_conflict_trans_confl Ndb_conflict_trans_re No Global per of transactions rejected after being the second sec	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No ng found in conflict by a transactional conflict_count Yes
No DESCRIPTION: Numb (slightly) greater than of No No DESCRIPTION: Numb conflict function. No No DESCRIPTION: Numb	Global per of internal iterations required to cor equal to Ndb_conflict_trans_confl Ndb_conflict_trans_re No Global per of transactions rejected after being the second seco	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No ng found in conflict by a transactional conflict_count Yes No nsactional conflict function. Includes any
No DESCRIPTION: Numb (slightly) greater than of No No DESCRIPTION: Numb conflict function. No No DESCRIPTION: Numb	Global per of internal iterations required to cor equal to Ndb_conflict_trans_confl Ndb_conflict_trans_re No Global per of transactions rejected after being transactions. No Global per of rows found in conflict by a transpendent on conflicting transactions.	No commit an epoch transaction. Should be lict_commit_count. eject_count Yes No ng found in conflict by a transactional conflict_count Yes No nsactional conflict function. Includes any

Option or Variable Name			
Command Line	System Variable	Status Variable	
Option File	Scope	Dynamic	
Notes			
conflict function. Includes Ndb_co	DESCRIPTION: Total number of rows realigned after being found in conflict by a transactional conflict function. Includes Ndb_conflict_trans_row_conflict_count and any rows included in or dependent on conflicting transactions.		
Yes	ndb_deferred_constraints Yes	No	
Yes	Both	Yes	
DESCRIPTION: Specifies that co Not normally needed or used; for	Instraint checks should be deferred testing purposes only. ndb_distribution	d (where these are supported).	
Yes	Yes	No	
Yes	Global	Yes	
		1	
default is KEYHASH)	on for new tables in NDBCLUSTER _conflict_delete_delete_co	•	
No	No	Yes	
No	Global	No	
DESCRIPTION: Number of deletinot exist)	e-delete conflicts detected (delete	operation is applied, but row does	
Yes	Yes	No	
Yes	Global	Yes	
	ee memory that should be available ching limit set by ndb_eventbuffer_ndb_eventbuffer_max_alloce	_max_alloc.	
Yes	Yes	No	
Yes	Global	Yes	
DESCRIPTION: Maximum memory that can be allocated for buffering events by the NDB API. Defaults to 0 (no limit). Ndb_execute_count			
No	No	Yes	
No	Global	No	
DESCRIPTION: Provides the number of round trips to the NDB kernel made by operations ndb_extra_logging			
Yes	Yes	No	
Yes	Global	Yes	
DESCRIPTION: Controls logging of MySQL Cluster schema, connection, and data distribution events in the MySQL error log			
ndb_force_send			
Yes	Yes	No	
Yes	Both	Yes	

Option or Variable Name		
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		,
DESCRIPTION: Forces	sending of buffers to NDB immedia	tely, without waiting for other threads
	ndb_index_stat_cache	_entries
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Sets the ending keys	granularity of the statistics by dete	ermining the number of starting and
orialing Koyo	ndb_index_stat_en	nable
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Use ND	B index statistics in query optimiza	tion
	ndb_index_stat_op	otion
Yes	Yes	No
Yes	Both	Yes
contain no spaces	ndb_index_stat_updat	
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: How ofto	en to query data nodes instead of t	the statistics cache
	ndb_join_pushdo	own
No	Yes	No
No	Both	Yes
DESCRIPTION: Enables	pushing down of joins to data nod	les
	ndb_log_apply_sta	atus
Yes	Yes	No
Yes	Global	No
		a slave logs mysql.ndb_apply_status
updates received from its	s immediate master in its own binar ndb_log_bin	ry log, using its own server iD.
Yes	Yes	No
No	Both	Yes
		log. Effective only if binary logging is
onabled with log bill.	ndb_log_binlog_i	ndex
Yes	Yes	No
No	Global	Yes
	papping between epochs and binary fective only if binary logging is enal	y log positions into the ndb_binlog_index

Option or Variable Name		
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		,
Yes	Yes	No
Yes	Global	Yes
	nabled, epochs in which there were b_binlog_index tables, even when	log_slave_updates is enabled.
Vaa	ndb_log_exclusive_	
Yes	Yes	No
Yes	Both	Yes
conflicts.	nary key reads with exclusive locks ndb_log_orig	; allow conflict resolution based on read
Yes	Yes	No
Yes	Global	No
	the id and epoch of the originating table. Set using thendb-log-original ndb_log_transaction	option when starting mysqld.
No	Yes	No
No	Global	No
DESCRIPTION: Whether	NDB transaction IDs are written in	nto the binary log. (Read-only.)
	ndb_log_updated_o	only
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: Log com	plete rows (ON) or updates only (Ndb_number_of_data	•
No	No	Yes
No	Global	No
DESCRIPTION: If the ser data nodes in the cluster	rver is part of a MySQL Cluster, the ndb_optimization_c	e value of this variable is the number of delay
No	Yes	No
No	Global	Yes
DESCRIPTION: Sets the number of milliseconds to wait between processing sets of rows by OPTIMIZE TABLE on NDB tables.		
	ndb_optimized_node_se	
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Determines how an SQL node chooses a cluster data node to use as transaction coordinator		
No	Ndb_pruned_scan_c	
No	No	Yes
No	Global	No

Option File Notes DESCRIPTION: Number of scans executed by NDB since the cluster was last started where partition pruning could be used Notes Not	Option or Variable Name		
DESCRIPTION: Number of scans executed by NDB since the cluster was last started where partition pruning could be used Ndb_pushed_queries_defined No No Yes No Global No DESCRIPTION: Number of joins that API nodes have attempted to push down to the data nodes Ndb_pushed_queries_dropped No No Global No DESCRIPTION: Number of joins that API nodes have attempted to push down to the data nodes Ndb_pushed_queries_dropped No No Global No DESCRIPTION: Number of joins that API nodes have tried to push down, but failed Ndb_pushed_queries_executed No No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No Global Yes No No Global Yes No No No No No DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	Command Line	System Variable	Status Variable
DESCRIPTION: Number of scans executed by NDB since the cluster was last started where partition pruning could be used Ndb_pushed_queries_defined No No Yes No Global No DESCRIPTION: Number of joins that API nodes have attempted to push down to the data nodes Ndb_pushed_queries_dropped No No Global No DESCRIPTION: Number of joins that API nodes have tried to push down, but failed Ndb_pushed_queries_executed No No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No Yes No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	Option File	Scope	Dynamic
Pruning could be used No No Yes No Global No DESCRIPTION: Number of joins that API nodes have attempted to push down to the data nodes No No Global No DESCRIPTION: Number of joins that API nodes have attempted to push down to the data nodes No No Global No DESCRIPTION: Number of joins that API nodes have tried to push down, but failed No No Yes No No Yes No No Yes No No Yes No No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No Yes No Yes No Sidbal No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status	Notes		
No No Global No Yes No No No No Yes No No No No Yes No No No No Yes No Global No No No No No No No No No No No No No	pruning could be used	·	·
No Global No DESCRIPTION: Number of joins that API nodes have attempted to push down to the data nodes Ndb_pushed_queries_dropped No No Global No DESCRIPTION: Number of joins that API nodes have tried to push down, but failed Ndb_pushed_queries_executed No No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No No Yes No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) No Yes No Global Yes No Yes No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status			
DESCRIPTION: Number of joins that API nodes have attempted to push down to the data nodes Ndb_pushed_queries_dropped No No Yes No Global No DESCRIPTION: Number of joins that API nodes have tried to push down, but failed Ndb_pushed_queries_executed No No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No No Yes No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status			
No No Science No No No No No No No No No No No No No			
No Global No DESCRIPTION: Number of joins that API nodes have tried to push down, but failed Ndb_pushed_queries_executed No No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No No Global No Yes No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No No No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No No No No No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No No No No No No No Second No No No No No No No No No No No No Yes No No No No No No No No No No No No No	•	·	•
DESCRIPTION: Number of joins that API nodes have tried to push down, but failed Nob_pushed_queries_executed No No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Nob_pushed_reads No No Yes No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No Global Yes No DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No	No	Yes
No No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes No No Yes No Global No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No No Yes No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No	Global	No
No No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes No No Yes No Global No Yes No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No No Yes No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	DESCRIPTION: Number of joins	that API nodes have tried to push	down, but failed
No Global No DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Ndb_pushed_reads No No Global No Yes No Global No No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No No No No No No No No No No N	•	·	
DESCRIPTION: Number of joins successfully pushed down and executed on the data nodes Nob_pushed_reads No No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No	No	Yes
No No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No	Global	No
No No Global No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	DESCRIPTION: Number of joins	successfully pushed down and exe	ecuted on the data nodes
No No Silvation No Yes No DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins	,	• •	
DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No		Yes
DESCRIPTION: Number of reads executed on the data nodes by pushed-down joins ndb_recv_thread_activation_threshold No No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No	Global	No
No No No No No No No No No No No No No N	DESCRIPTION: Number of reads	s executed on the data nodes by p	⊥ ushed-down ioins
No No No No No No No No No No DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) **ndb_recv_thread_cpu_mask** No Yes No No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. **ndb_report_thresh_binlog_epoch_slip** Yes No No No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status **ndb_report_thresh_binlog_mem_usage** Yes No No No No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status			•
DESCRIPTION: Activation threshold when receive thread takes over the polling of the cluster connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No		1
connection (measured in concurrently active threads) ndb_recv_thread_cpu_mask No Yes No No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No Pes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No Pes No No Pes No No Pes No No Pes No No No Pes No No No No No Security (Percentage of free memory remaining before reporting binary log status)	No		No
No Yes No Global Yes DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No No Pes No No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No No Pes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status			er the polling of the cluster
DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip		ndb_recv_thread_cpu_mask	
DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details. ndb_report_thresh_binlog_epoch_slip	No	Yes	No
See documentation for details. ndb_report_thresh_binlog_epoch_slip Yes No No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No Yes No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	No	Global	Yes
Yes No No Yes No DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No Yes No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	DESCRIPTION: CPU mask for locking receiver threads to specific CPUs; specified as hexadecimal. See documentation for details.		
Yes DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No Yes DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status			
DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status ndb_report_thresh_binlog_mem_usage Yes No No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	Yes	No	No
status ndb_report_thresh_binlog_mem_usage Yes No No Yes No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	Yes		
Yes No No Yes No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status	DESCRIPTION: This is a threshold on the number of epochs to be behind before reporting binary log status		
Yes No DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status			1
DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status		No	
binary log status	Yes		
Ndb_scan_count	DESCRIPTION: This is a threshold on the percentage of free memory remaining before reporting binary log status		
	Ndb_scan_count		

Option or Variable Name		
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		,
No	No	Yes
No	Global	No
DESCRIPTION: The total numbe	r of scans executed by NDB since	the cluster was last started
ndb	_show_foreign_key_mock_tal	oles
Yes	Yes	No
Yes	Global	Yes
DESCRIPTION: Show the mock to	ables used to support foreign_key	_checks=0.
	ndb_slave_conflict_role	
Yes	Yes	No
Yes	Global	Yes
SECONDARY, PASS, or NONE (See documentation for further info	play in conflict detection and resolutefault). Can be changed only who crmation. b_slave_max_replicated_epo	en slave SQL thread is stopped.
No	Yes	No
No	Global	No
I .	ly committed NDB epoch on this slt_conflict_epoch, no conflicts have ndb_table_no_logging	_
No	Yes	No
No	Session	Yes
	ted when this setting is enabled ar created). The setting in effect when sists for the lifetime of the table. <pre>ndb_table_temporary</pre>	
No	Yes	No
No	Session	Yes
DESCRIPTION: NDB tables are not persistent on disk: no schema files are created and the tables are not logged ndb_use_exact_count		
No	Yes	No
No	Both	Yes
DESCRIPTION: Use exact row co	ount when planning queries	,
ndb_use_transactions		
Yes	Yes	No
Yes	Both	Yes
DESCRIPTION: Forces NDB to use a count of records during SELECT COUNT(*) query planning to speed up this type of query		
NI.	ndb_version	NI.
No	Yes	No

Option or Variable Name		
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	Global	No
DESCRIPTION: Shows build a	nd NDB engine version as an i	nteger.
	ndb_version_strin	g
No	Yes	No
No	Global	No
DESCRIPTION: Shows build in	formation including NDB engir	ne version in ndb-x.y.z format.
	ndbcluster	
Yes	No	No
Yes		No
DESCRIPTION: Enable NDB (Cluster (if this version of MySQI	L supports it)
Disabled byskip-ndbclus	rt or	
Disabled byskip-nabcius	ndbinfo_database	
No	Yes	No
No	Global	No
DESCRIPTION: The name use		
DESCRIPTION. THE hame use	ndbinfo_max_bytes	·
Yes	Yes	No
No	Both	Yes
DESCRIPTION: Used for debu		
Yes	ndbinfo_max_rows Yes	No
No	Both	Yes
DESCRIPTION: Used for debu		
NI .	ndbinfo_offline	1
No	Yes	No
No	Global	Yes
DESCRIPTION: Put the ndbint tables or views.	o database into offline mode, ir	n which no rows are returned from
tables of views.	ndbinfo_show_hidde	an an
Yes	Yes	No
No	Both	Yes
		s in the mysql client. The default is OFF.
DESCRIPTION. WHETHER to SH	ndbinfo_table_pref	
Yes	Yes	No
No		
	Both	Yes
DESCRIPTION: The prefix to u	<u> </u>	Dase ladies
No	ndbinfo_version	No
No	Yes	No

Option or Variable Name		
Command Line	System Variable	Status Variable
Option File	Scope	Dynamic
Notes		
No	Global	No
DESCRIPTION: The version of the	ne ndbinfo engine; read only.	
	server-id-bits	
Yes	Yes	No
Yes	Global	No
DESCRIPTION: Sets the number of least significant bits in the server_id actually used for identifying the server, permitting NDB API applications to store application data in the most significant bits. server_id must be less than 2 to the power of this value.		
Yes	Yes	No
Yes	Global	No
DESCRIPTION: The effective value of server_id if the server was started with theserver-id-bits option set to a nondefault value.		
Yes	slave_allow_batching Yes	No
	. 55	
Yes Global Yes DESCRIPTION: Turns update batching on and off for a replication slave		
transaction_allow_batching		
No	Yes	No
No	Session	Yes
DESCRIPTION: Allows batching of statements within a transaction. Disable AUTOCOMMIT to use.		

202

Index	limitations, 139
maex	changing data node processes, 127
Λ.	client
Α	commands in, 63
abort backup command, 132	defined, 2, 3
backupid option, 133	executing scripts with, 71
add hosts command, 76	importing, 39
add package command, 83, 86	mysql client commands in, 71
basedir option, 84	starting, 34
add process command, 125	client commands, 63
agent	abort backup, 132
backing up and restoring, 58, 136	add hosts, 76
configuration, 18	add nosts, 70 add package, 83, 86
defined, 2, 2	. •
	add process, 124
distribution, 5, 6	backup, 132
distribution layout, 6	backup agents, 136
installing, 5	backup cluster, 133
starting, 31	case-sensitivity in, 65
starting (Linux), 31	change log-level, 77
starting (Windows), 32	change process, 127
stopping (Linux), 32	cluster, 87
stopping (Windows), 34	collect logs, 78
agent-uuid option	command-specific, 70
mcmd, 24	configuration, 100
architecture, 1, 2	create cluster, 88
attributes	create site, 79
case-sensitivity, 65	delete cluster, 91
summary table, 159	delete package, 85
_	delete site, 80
В	get, 102
background option	help, 75
limitations, 141	identifiers in, 65
backgrounding of commands, 141	import cluster, 137
backup	import config, 137
commands, 132	importing clusters, 137
backup agents command, 136	information, 69
backup cluster command, 133	list backups, 134
snapshotend option, 133	list clusters, 92
snapshotstart option, 133	list hosts, 81
waitcompleted option, 133	list nextnodeids, 92
waitstarted option, 133	list processes, 130
backup images, 133	list sites, 80
backup option (show status command), 95	online help, 69
backup status, 95	options, 64, 67, 68
backupid option (abort backup), 133	package, 83
backupid option (restore cluster), 134	process, 124
backups	remove hosts, 76
creating, 58, 133, 136	remove process, 131
removing, 133	reset, 111
9.	
basedir option	restart cluster, 93 restore, 132
mcmd, 25	
basedir option (add package command), 84	restore cluster, 134
bootstrap option	results returned by, 67
mcmd, 25	rotate log, 78
С	set, 118
	show settings, 81
change log-level command, 77	show status, 93
change process command, 127	show warning, 82

site, 75	import option, 89
start cluster, 96	assignment of node IDs in, 89
start process, 130	create site command, 79
status, 94	hosts option, 79
stop agents, 82	
stop cluster, 98	D
stop process, 131	daemon option
syntax, 63	mcmd, 25
upgrade cluster, 98	defaults-file option
version, 82	mcmd, 25
cluster	delete cluster command, 91
defined, 1	delete package command, 85
cluster backups	delete site command, 80
aborting, 132	deployment (example), 3
creating, 54	disable-indexes option (restore cluster), 135
listing, 134	disable-metadata option (restore cluster), 135
restoring, 54	1 (//
restoring from, 134	E
cluster option (show status command), 94	epoch option (restore cluster), 135
cluster processes	event-threads option
adding, 125	mcmd, 25
cluster status, 94	exclude-databases option (restore cluster), 135
clusters	exclude-intermediate-sql-tables option (restore cluster)
creating, 37, 37, 88	135
creating for import, 89	exclude-missing-columns option (restore cluster), 135
importing, 137, 137	exclude-missing-tables option (restore cluster), 135
listing, 92	exclude-tables option (restore cluster), 135
removing, 91	excitate tables option (rectors diagter), rec
restarting, 93	G
starting, 96	_
stopping, 98	get command, 102
upgrading, 98	filtering output, 107
collect logs command, 78	include-defaults option, 105
command status, 94	with multiple attributes, 108
common terms, 1	Н
concurrent client sessions unsupported, 139	
configuration	help command, 75
derivation of attributes, 100	help for commands, 70
configuration attributes, 100	help option, 70
defined, 2	mcmd, 26
for TCP connections, 122	help-all option
getting, 102	mcmd, 26
how determined by MySQL Cluster Manager, 101	help-manager option
levels applying, 101	mcmd, 27
mandatory, 102	hosts
read-only, 102	defined, 1
resetting, 111	hosts option (create site), 79
setting, 118	1
configuration commands, 100	1
configuration data	identifiers, 65
importing, 137	case-sensitivity, 65
configuration file, 18	spaces in, 66
configuration parameters (see configuration attributes)	import cluster command, 137
configuration variables (see configuration attributes)	import config command, 137
connecting to agent	importing clusters
with more client, 35	creating for import, 89
with mysql client, 35	example, 40
create cluster command, 88	limitations, 141

include-databases option (restore cluster), 135	defined, 1
include-defaults option (get command), 105	management sites
include-tables option (restore cluster), 135	adding hosts, 76
initial option (start cluster), 97	creating, 79
installation, 5	deleting, 80
IPv6	listing, 80
and hostnames (Windows), 139	listing hosts, 81
	removing hosts, 76
K	manager-directory option
keepalive option	mcmd, 28
mcmd, 27	manager-password option
	mcmd, 29
L	manager-port option
license keys	mcmd, 29
and operating platform, 139	manager-username option
license keys (obsolete), 6	mcmd, 29
limitations, 139	max-open-files option
background option, 141	mcmd, 29
backup, 141, 141	mcm client
change process command, 139	and mysql client, 34
client, 140, 140, 140	mcmd, 31
cluster imports, 141	agent-uuid option, 24
concurrent usage, 139	basedir option, 25
IPv6, 139	bootstrap option, 25
license keys, 139	daemon option, 25
MySQL server variables, 140, 140	defaults-file option, 25
MySQL user variables, 140	event-threads option, 25
operating systems, 139	help option, 26
relating to MySQL Server, 139	help-all option, 26
replication, 140	help-manager option, 27
restarts, 141	keepalive option, 27 log-backtrace-on-crash option, 27
syntax, 141	log-file option, 27
Windows, 139	log-level option, 28
list backups command, 134	log-use-syslog option, 28
list clusters command, 92	manager-directory option, 28
list commands command, 69	manager-password option, 29
list hosts command, 81	manager-port option, 29
list nextnodeids command, 92	manager-username option, 29
list processes command, 130	max-open-files option, 29
list sites command, 80	pid-file option, 30
log-backtrace-on-crash option	plugin-dir option, 30
mcmd, 27	plugins option, 30
log-file option	verbose-shutdown option, 30
mcmd, 27	version option, 30
log-level option	xcom-port option, 31
mcmd, 28	mcmd.exe, 32
log-use-syslog option	multiple client sessions, 139
mcmd, 28	mysql client commands, 71
logging	mysql-cluster-manager (OBSOLETE, see mcmd), 31
configuring, 77	mysqld options, 140
logs	,
obtaining, 78	N
rotating, 78	ndb_mgm (MySQL Cluster command-line client)
lossy-conversions option (restore cluster), 136	using with MySQL Cluster Manager, 124
	no-binlog option (restore cluster), 136
M	no-restore-disk-objects option (restore cluster), 136
management site	node IDs

and create cluster command, 89 listing, 92	exclude-missing-tables option, 135 exclude-tables option, 135 include-databases option, 135
0	include-tables option, 135
obtaining MySQL Cluster Manager, 5	lossy-conversions option, 136
operation option (show status command), 94	no-binlog option, 136
operation option (show status command), 94	no-restore-disk-objects option, 136
P	parallelism option, 136
	privilege-tables option, 136
packages	progress-frequency option, 136
defined, 1	rewrite-database option, 136
listing, 83, 86	skip-broken-objects option, 136
registering, 83 removing, 85	skip-nodeid option, 136
parallelism option (restore cluster), 136	skip-table-check option, 136
pid-file option	skip-unknown-objects option, 136
mcmd, 30	rewrite-database option (restore cluster), 136
plugin-dir option	rolling restarts, 141
mcmd, 30	rotate log command, 78
plugins option	0
mcmd, 30	S
privilege-tables option (restore cluster), 136	scripts (MySQL Cluster Manager client), 71
process option (show status command), 95	SendBufferMemory, 117, 122
process status, 95	set command, 118
processes	and TCP connection attributes, 122
changing, 127	instance level, 119
commands, 124	paths used with (Windows), 121
defined, 1	scope, 118, 119
listing, 130	undoing effects of, 113
removing, 131	verifying effects, 119
starting, 130	with multiple attributes, 121
status, 95	with multiple processes, 120
stopping, 131	show settings command, 81 show status command, 93
progress-frequency option (restore cluster), 136	backup option, 95
D	cluster option, 94
R	operation option, 94
ReceiveBufferMemory, 117, 122	process option, 95
remove hosts command, 76	skip-broken-objects option (restore cluster), 136
remove process command, 131	skip-nodeid option (restore cluster), 136
replication, 140	skip-table-check option (restore cluster), 136
setup, 60	skip-unknown-objects option (restore cluster), 136
reset command, 111	snapshotend option (backup cluster), 133
and attribute name, 112	snapshotstart option (backup cluster), 133
and TCP connections, 117	start cluster command, 96
order of operands, 115	initial option, 97
process level, 113	start process command, 130
scope, 112	starting and stopping nodes
restart cluster command, 93	and ndb_mgm (MySQL Cluster command-line
restore (from backup) commands, 132	client), 124
restore cluster command, 134	stop agents command, 82
backupid option, 134	stop cluster command, 98
disable-indexes option, 135	stop process command, 131
disable-metadata option, 135	syntax issues, 141
epoch option, 135	-
exclude-databases option, 135	Т
exclude-intermediate-sql-tables option, 135	terminology, 1
exclude-missing-columns option, 135	

U

upgrade cluster command, 98 upgrades MySQL Cluster, 141

٧

verbose-shutdown option mcmd, 30 version command, 82 version option mcmd, 30

W

waitcompleted option (backup cluster), 133 waitstarted option (backup cluster), 133

X

xcom-port option mcmd, 31

208