

# Music Studio 1.4 User Manual

Music Studio is available on the App Store  
for all iPhone, iPod Touch and iPad models

# Table of Contents

<b>Quick Start Guide</b>	<b>1</b>
Reboot after the installation	1
Playing on the keyboard	1
Recording a song	2
<b>FAQ (Frequently Asked Questions)</b>	<b>3</b>
Performance and trouble shooting	3
Instruments tab	4
Tracks tab	4
Projects tab	4
Instrument shop	4
Which feature will be included in future updates?	4
<b>Keyboard Tab</b>	<b>5</b>
Introduction	5
Scrolling and resizing	5
Keyboard menu	5
Play button	5
Pause button (iPad only)	5
Loop button	5
Record button	6
Undo button	6
Display	6
Metronome button	6
Tempo Button (iPad only)	6
Keyboard layout button	6
Rows button (iPad only)	7
Key label button (iPad only)	7
Accelerometer button	7
<b>Velocity (volume)</b>	<b>7</b>
<b>Keyboard layout mode</b>	<b>8</b>
Octave buttons	8
Fullscreen button (iPhone only)	8
Keyboard map	8

Rows button (iPhone only)	8
Key label button (iPhone only)	8
<b>Keyboard playhead mode</b>	9
Rewind button	9
Bar reel buttons	9
Navigation map	9
Marker buttons	9
<b>Instruments Tab</b>	10
<b>Introduction</b>	10
<b>Sliders</b>	10
Volume	10
Attack time	10
Release time	10
<b>Buttons</b>	10
Category buttons (iPhone only)	10
Defaults button	11
Preview button	11
Keep attack/release times checkbox (iPad only)	11
Sync keyboard rows checkbox (iPad only)	11
<b>Row indicator</b>	11
<b>Tracks Tab</b>	12
<b>Introduction</b>	12
Scrolling	12
What is a track?	12
Track management	12
What is an event	12
<b>Common controls</b>	13
Play button	13
Loop button	13
Pause button	13
Undo button	13
Display	13
Tempo Button	13
Zoom button	14
Horizontal zoom buttons (iPad only)	14
Track view switch	14
Tempo indicator	14
Song ruler	14
Song markers	14
Track zoom mode	15

<i>Horizontal zoom buttons (iPhone only)</i>	15
<i>Vertical zoom buttons</i>	15
<i>Navigation map</i>	15
Track playhead mode	16
<i>Rewind button</i>	16
<i>Bar reel buttons</i>	16
<i>Navigation map</i>	16
<i>Marker buttons</i>	16
<b>Mixer</b>	17
Track list	17
<i>Instrument icon</i>	17
<i>Gain bars</i>	17
<i>Warning triangle</i>	17
<i>Keyboard row icon</i>	18
<i>Filter track</i>	18
Add track button	18
Mute button	18
Solo button	18
FX button	18
Edit button	18
Duplicate button	18
Delete button	18
Pan knob and volume slider	19
<b>Sequencer</b>	20
Track list	20
New selection button	20
Change selection button	20
Move button	20
Duplicate button	20
Repeat button	21
Transpose button	21
Quantize button	21
Edit button	21
Delete button	21
Song bar edit button	21
<b>Piano roll editor</b>	22
Piano roll view	22
Vertical scrolling	22
New selection button	22
Change selection button	22
Draw button	23
Draw mode	23

<i>Draw mode note buttons</i>	23
<i>Draw mode dotted button</i>	23
<i>Quantized drawing button</i>	23
Move button	24
Duplicate button	24
Length button	24
Volume button	24
Quantize button	24
Delete button	24
<b>Quantization popup</b>	25
Note buttons	25
Dotted button	25
Triplet button	25
Note length checkbox	25
Soft (humanize) checkbox	25
<b>Tempo popup</b>	26
Tempo	26
Signature	26
<b>Effects Tab</b>	27
<b>Bus structure</b>	27
<b>Common Controls</b>	28
Power button	28
Limit to FX tracks checkbox	28
Preview button	28
Default button	28
<b>Effects</b>	29
Volume	29
<i>Master gain</i>	29
<i>Device volume</i>	29
<i>Decibel meters</i>	29
Reverb	30
<i>Reverb size</i>	30
<i>Reverb brightness</i>	30
<i>Reverb stereo spread</i>	30
<i>Reverb mix (wet/dry)</i>	30
<i>Reverb style</i>	30
<i>Reverb quality</i>	30
<i>Remember settings for each style (iPad only)</i>	30
Delay	31
<i>Timing buttons</i>	31
<i>Timing switch</i>	31

<i>Feedback</i>	31
<i>Delay mix (wet/dry)</i>	31
Equalizer	32
Amplifier	32
<i>Overdrive</i>	32
<i>Style</i>	32
Filter	33
<i>Resonance/Frequency display</i>	33
<i>Filter type switch</i>	33
<i>Filter accelerometer axis</i>	33
<i>Accelerometer sensitivity</i>	33
<i>Snap back checkbox</i>	33
Pitch	34
<i>Semitone slider</i>	34
<i>Sensitivity slider</i>	34
<i>Pitch bend accelerometer axis</i>	34
<i>Pitch bend invert axis checkbox</i>	34
<i>Pitch bend record mode</i>	34

## Projects Tab 35

### Introduction 35

### Filename textfield 35

### File list 36

### Buttons 36

New 36

Load 36

Save 36

Delete 36

Export 36

Server 37

## Setup Tab 38

### Differences on the iPad 38

### General settings 38

Latency 38

Polyphony 38

Continuous playhead movement 39

Lock interface orientation (iPhone only) 39

Restore defaults button 39

### Keyboard settings 39

Velocity control 39

Snap to white keys 39

Allow touches between black keys	40
Allow touches on key borders	40
German key labeling	40
<b>Accelerometer settings</b>	40
Threshold slider	40
Reactivity slider	40
Calibration	40
<b>Interface settings</b>	41
Instruments tab	41
<i>Keep attack/release times on instrument change (iPhone only)</i>	41
Tracks tab	41
<i>Scroll on the margins when moving notes</i>	41
<i>Centered zooming</i>	41
Effects tab	41
<i>Remember reverb settings for each type (iPhone only)</i>	41
<b>Metronome settings</b>	42
Volume	42
Style	42
Precount	42
Precount only at song start	42
<b>Best practices</b>	43
<b>Version history</b>	44
<b>Version 1.4</b>	44
<b>Version 1.3</b>	45
<b>Version 1.2.1</b>	46
<b>Version 1.2</b>	46
<b>Version 1.1</b>	47
<b>Version 1.0.3</b>	48
<b>Version 1.0.2</b>	49
<b>Version 1.0.1</b>	50
<b>Version 1.0</b>	52

# Quick Start Guide

## Reboot after the installation

After installing or updating the app, reboot your device by holding the Home and the Sleep/Wake button for about 10 seconds until the Apple logo appears (don't slide to power off). This ensures optimum performance.

## Playing on the keyboard

You can adjust the size and position of the keyboard by making a slide or pinch gesture anywhere on the menu bar.





- To change the labels on the keys, press the keys button and switch between the 4 key label modes with the key label button.
- If you just want to play around with the instruments, switch to the instrument tab, select your instrument of choice (the list is scrollable), maybe preview it, and switch back to the keyboard tab to play.
- Tap the accelerometer button to enable pitch bend, then tilt your device to bend the played note's pitch.
- Adjust the attack/release sliders in the instruments tab to change the fade in/out times.
- The sound is greatly influenced by the reverb. Adjust the reverb type and size in the effects tab to simulate a specific room. High quality reverb sounds better but may introduce playback stuttering on older devices.
- You might want to get fancy with the effects: switch to the effects tab, choose an effect, switch it on, and play around with the settings.





## Recording a song

Follow these steps to create a simple song from scratch:

- Open the projects tab and tap the New button to create a new project.
- Open the tracks tab and tap the tempo button to set the tempo and signature of your new song.
- Open the instruments tab and select your instrument of choice.
- Open the keyboard tab and press the record button, wait for the counter to hit 1.1 (precount can be disabled in the metronome section of the setup screen), play your piece, then tap the stop button.
- If you made a mistake and want to re-record, simply tap the undo button to erase the notes you just recorded.
- Switch to the tracks tab to review what you just recorded. The track can be edited bar-wise (sequencer) and note-wise (piano roll editor), more on this topic in the tracks tab section.
- Tap the plus icon  to create a new track.  
The keyboard and instruments tabs always apply to the active track, so make sure that track 2 is selected.
- Repeat the previous steps to record something on the second track.
- Let's assume that your song has a duration of 20 bars and you want to start recording at bar 10. In the tracks tab, move the left marker  on the ruler to the 10th bar and recording will always start from there.
- Tune the reverb in the effects tab, maybe set the equalizer and play around with the other effects.
- To save your song, open the projects tab, enter a song name in the text field and tap the save button.



# FAQ (Frequently Asked Questions)

For more support-related discussions, please refer to the Forum on the Music Studio website.

## Performance and trouble shooting

### The application reacts slowly and crackling occurs

Rebooting your device will most likely resolve this issue. Press and hold the Home and the Sleep/Wake button for about 10 seconds until the Apple logo appears (don't slide to power off, hold longer). If playback stuttering remains, decrease the reverb quality, increase the [latency](#), or decrease the [polyphony](#).

### Key presses have a very high latency

- Deactivate the Zoom feature in the Accessibility section of the iPhone's Settings. Launch the Settings app, tap General, Accessibility, Zoom and turn it off.
- Switch to a lower [latency](#) in the general section of the setup tab.
- If you still experience latency problems try to [properly reboot your device](#).

### The audio output sounds noisy

Use earphones or external speakers because the device's internal speaker cannot cope with the broad frequency spectrum of Music Studio's instruments. Additionally, decrease the master gain (in the volume section of the effects tab) to prevent clipping. This might be necessary if many instruments play simultaneously, because their gains add up.

### The instruments sound unreal

To get the most out of the high quality studio-recorded instruments, use earphones or external speakers and set the reverb to high quality. Most instruments are designed for a specific tonal range, an E-Bass sounds as unreal in the 4th octave as a flute in the lowest octave. Some instruments also benefit from a higher or lower release time.

- Wind instruments in general sound best with a low release time and the reverb set to hall or canyon.
- A great effect for synths is to set the delay to 1/8th and dotted.
- String instruments sound best with a medium attack time (around 0.5s) and maybe a high release time.
- Keyboard instruments and guitars get a sustain feeling with a high release time.

### Do I loose my songs if I remove Music Studio from my device?

Yes, if you tap and hold the app icon and tap X to remove Music Studio, all files and settings are deleted too. Even if you sync Music Studio back from iTunes onto your device, it will be a fresh install and your files won't be restored. In order to save your songs, transfer them to your Mac/PC with the [Server](#) button. If you restore your iDevice by pressing the restore button in iTunes, your songs will be restored automatically (along with a reinstallation of iOS and all other apps).

### Why are the drum kit's sounds arranged in such a strange way?

This "strange way" is called the "General MIDI Level 1 Percussion Key Map". It is commonly used on nearly every hardware keyboard/synthesizer to retain full MIDI compatibility.

### During playback, some notes end too early

Increase the [polyphony](#) in the setup tab, but keep in mind that this may lead to stuttering with complex songs on older devices.

## Instruments tab

### Why is the default instrument volume 80% and not 100%?

This way you don't have to change all the other track's volumes if you want one track to be louder.

### Why doesn't the preview button play a nice melody?

Because it would be distracting for a musician who has a melody in mind while composing music.

## Tracks tab

### If I select and edit bars in the sequencer, why are some notes ignored?

Selected notes are colored dark blue. If you select a bar but a note starts a few ticks earlier than this bar, it will not be selected. If possible, quantize the track, thereby aligning the notes to simplify further editing.

## Projects tab

### The server does not work

Make sure that your device is connected to the same WiFi network as your Mac/PC. If your browser does not load the Music Studio webpage, enter the IP address (numbers) instead of the Bonjour address (device name) in the browser's address bar, followed by a colon and the number 8080. If the problem persists, try a different browser, try disabling your PC's firewall or try bypassing your router by setting up an ad-hoc network on your Mac/PC. Step by step instructions:

- Connect to a WiFi network with your iPhone
- Connect to the same WiFi network with your Mac/PC
- Tap the [Server](#) button in Music Studio
- Enter the IP address (without www) followed by the port in your Mac/PC's browser, e.g. 192.168.1.3:8080
- Right click a file and select Download (or "Save target" or something similar depending on your browser) to save it on your hard drive.

## Instrument shop

### How do I restore my purchased instruments or get them on my second device?

Simply enter the shop, tap the restore button in the upper right corner, enter your iTunes username and password, and wait for the instruments (which you already purchased) to appear in the instrument list. This process can take up to a few minutes depending on your connection speed (preferably WiFi).

### Why is the price \$0.99 for a single instrument?

This is the lowest possible price on the app store. The package's prices are much lower compared to buying the instruments individually.

## Which feature will be included in future updates?

Please refer to the Forum on the Music Studio website for more feature-related discussions.

# Keyboard Tab

## Introduction

Music Studio features a 85-key clavier capable of handling up to 5 simultaneous touches (10 on the iPad). Not every instrument has the full tonal range, hence the number of playable octaves varies from instrument to instrument.

If you are uneasy with the way the keys react to your input, the [setup tab](#) offers some handy keyboard preferences.

## Scrolling and resizing

The keyboard position and width can be adjusted via the scroll and pinch gestures. Either tap the keyboard layout button or simply do the gesture on the top menu bar: move one finger left or right to slide the keyboard, pinch with two fingers to adjust the key width.



## Keyboard menu



### Play button

Starts and stops playback of the song. Stop rewinds to the left marker.



### Pause button (iPad only)

Simply pauses playback, like stop but without rewinding.



### Loop button

Toggles looping, i.e. during playback and recording the song (or the section between the markers) will be repeated indefinitely.



### Record button

Start or stop a new recording. More on this topic in the [tracks tab](#).



### Undo button

Tap to undo the last recording, hold for 2 seconds to display a popup with the possible undo/redo actions.



### Display



The LCD displays the current instrument and the position of the playhead in the format measure-dot-beat, e.g. 7.2 means that the playhead is in the 2nd beat of the 7th bar (measure). Tap it to enter the [playhead mode](#). A small white dot in the upper left corner indicates that the current track is not empty.



### Metronome button

Toggles the metronome. Its state is remembered separately for playback and recording. Per default, the metronome is enabled only at recording. Beat and signature can be configured in the [tempo popup](#) in the tracks tab. Metronome volume and style settings are found in the [setup tab](#).

iPhone/iPod touch only: tap and hold the metronome button to bring up the tempo popup.



### Tempo Button (iPad only)

Toggles the [tempo popup](#).



### Keyboard layout button

Toggles the [keyboard layout mode](#).



### Rows button (iPad only)

Switches between one and two keyboard rows. More on this topic [here](#). On the iPhone, this button can be found in the [keyboard layout mode](#).



### Key label button (iPad only)

Switches between the 4 key label modes: off, C only, all keys labeled, and colored key labels. On the iPhone, this button can be found in the [keyboard layout mode](#).



### Accelerometer button

Toggles the accelerometer input. By default, it enables the [pitch bend effect](#). Tilt your device to bend the pitch of the currently played notes. The [filter effect](#) can also be configured to react to the accelerometer.

If this button is enabled while recording, the device tilt is also recorded (which could affect the pitch bend and/or the filter effect). In this case, the filter track will be overwritten unless you disable the accelerometer button or the accelerometer checkbox of the [filter effect](#).

## Velocity (volume)

In the setup tab, enable [Velocity](#) to control the note volume. If set to Touch-Y, the volume depends on where you touch a key (upper end quiet, lower end forte). The Accel setting allows you to control the note volume with the accelerometer by tilting the device.

## Keyboard layout mode

In this mode, the keyboard rows can be scrolled and resized anywhere on the screen.



### Octave buttons

The left and right octave buttons quickly scroll the keyboard one octave (12 semitones) down or up.



### Fullscreen button (iPhone only)

Switches to the full screen keyboard.

## Keyboard map



The map illustrates which part of the keyboard is currently visible. Slide or tap it to quickly scroll the keyboard.



### Rows button (iPhone only)

Switches between one and two keyboard rows. More on this topic [here](#).



### Key label button (iPhone only)

Switches between the 4 key label modes: off, C only, all keys labeled, and colored key labels.

## Keyboard playhead mode

Tap the LCD in the menu bar to enter the playhead mode. It allows you to adjust the position of the playhead and to set the markers. Use the controls in the bottom menu or simply slide your finger anywhere on the screen to adjust the position of the playhead.



### Rewind button


Rewinds the playhead to the left song marker. Tap it a second time to rewind to the beginning of the song.



### Bar reel buttons

Rewind and forward the playhead position by exactly 1 bar (measure).

## Navigation map



Tap or slide it to quickly position the playhead anywhere in the song. Areas outside the markers are darkened. The map also displays the current track's notes as white lines.



### Marker buttons

Set the left or right song marker to the current playhead position. The markers must be at least 1 bar apart.

Why markers? Recording always starts at the left marker. The loop button loops the section between the markers.

When exporting to a wav file, you can choose to only export the range between the markers.



# Instruments Tab

## Introduction

Change the selected track's instrument by tapping an instrument from the scrollable list.



## Sliders

### Volume

Sets the current track's gain, like the volume slider in the [mixer](#) does.

### Attack time

Controls the fade-in time, i.e. how long it takes for the instrument to reach its volume. Use longer attack times for soft sounds like strings and synth pads.

### Release time

Controls the fade-out time, i.e. how long the sound fades out after a key is released. Use longer release times for simulating legato or one-shot for drum kits and percussive instruments.

## Buttons

### Category buttons (iPhone only)




The category buttons filter the instrument list to show all instruments or just one category.



### Defaults button

Resets the three sliders to the instrument's default preset. If "Keep attack/release" is disabled in the setup tab, this button is automatically pressed each time you select an instrument.



### Preview button

Plays one or more notes (alternating) with the current instrument.

### Keep attack/release times checkbox (iPad only)

If this checkbox is disabled, each time you select an instrument its default attack and release time will be set. If enabled, the current track's attack/release durations are kept when you select another instrument. On the iPhone, this setting can be found in the [setup tab](#).

### Sync keyboard rows checkbox (iPad only)

Enable this checkbox to synchronize the settings (instrument, volume, attack and release time) of both keyboard rows. Every change you make will affect both rows and thus two tracks.



### Row indicator

Tap the lower row to switch to 2 keyboard rows. This control then allows you to switch between them to select different instruments for the upper and lower keyboard row. More on this topic [here](#).

# Tracks Tab

## Introduction



## Scrolling

Analogous to the keyboard tab, sliding and pinching on the menu bar scrolls and zooms the visible range of the song.

## What is a track?

Think of a track as one instrumentalist in a band or an orchestra. It holds recorded notes (events), one instrument and some parameters. There can be multiple tracks with the same instrument but different parameters (e.g. volume, pan, attack/release time).

## Track management

Only one track can be selected at a time. The keyboard will play this track's instrument, the record button will record on this track, and all the changes you make in the instrument tab will apply to it. You cannot delete the first track, the maximum number of tracks is 128. If you switch to [two keyboard rows](#), a separate track for the lower row is created (more on this topic [here](#))

## What is an event

A recorded note places 2 events on a track: key-down and key-up (also called note-on and note-off). The position of an event is stored with a resolution of 48 ticks per beat, which equals to 192 ticks per bar with a signature of 4/4, meaning that the shortest note can be a 1/192th.

## Common controls



### Play button

Starts and stops playback of the song. Stop rewinds to the left marker.



### Loop button

If looping is active and the playhead reaches the right song marker (by default the song end), it will jump to the left marker and continue playback from there. This allows you to loop any part of the song, the markers can be moved in the song ruler.



### Pause button

Simply pauses playback, like stop but without rewinding.



### Undo button

Tap to undo the previous action. Hold for 2 seconds to display a popup with the possible undo/redo actions. If the result would not be obvious, the popup appears anyway (e.g. if you would undo a recording but switched to the tracks tab, or if only redo is possible). Selection does not count as an action.



## Display



The LCD displays the position of the playhead in the format measure-dot-beat, e.g. 7.2 means that the playhead is in the 2nd beat of the 7th bar (measure). Tap it to enter the [playhead mode](#). The display also shows parameter values (pan, volume, transposition) while you are changing them, and the currently selected note range in the piano roll editor.



### Tempo Button

Toggles the [tempo popup](#).



### Zoom button

Toggles the [zoom mode](#).




### Horizontal zoom buttons (iPad only)

Zoom the ruler in or out. Tap the zoom-out button a few times to view the whole song. On the iPhone, these two buttons can be found in the [zoom mode](#).



### Track view switch

Switches between the [mixer](#) and the [sequencer](#).



### Tempo indicator

Displays the song tempo, bpm stands for beats per minute. Double tap it to enter the [tempo popup](#).

## Song ruler



The numbers and the vertical lines indicate the measures (bars), the short vertical lines are beats. The ruler also holds the playhead (white vertical line) and the markers (triangles). Slide anywhere on the ruler to position the playhead.

## Song markers



The left and right song makers are located on the ruler and can be moved to a certain song position. An alternative method for positioning the markers is via the [playhead mode](#).

Why markers? Recording always starts at the left marker. The loop button loops the section between the markers. When exporting to a wav file, you can choose to only export the range between the markers.

## Track zoom mode

In this mode, the view (i.e. the ruler) can be scrolled and resized anywhere on the screen.



### Horizontal zoom buttons (iPhone only)


Zoom the ruler in or out. Tap the zoom-out button a few times to view the whole song.



### Vertical zoom buttons

Only visible in the [piano roll editor](#) for zooming the mini keyboard.

## Navigation map



Tap or slide it to quickly position the viewed range. Areas outside the visible range are darkened. The map also displays the current track's notes as white lines.

## Track playhead mode

Tap the LCD in the menu bar to enter the playhead mode. It allows you to adjust the position of the playhead and to set the markers. Use the controls in the bottom menu or simply slide your finger anywhere on the screen to adjust the position of the playhead.



### Rewind button

Rewinds the playhead to the left song marker. Tap it a second time to rewind to the beginning of the song.



### Bar reel buttons

Rewind and forward the playhead position by exactly 1 bar (measure).

## Navigation map



Tap or slide it to quickly position the playhead anywhere in the song. Areas outside the markers are darkened. The map also displays the current track's notes as white lines.



### Marker buttons

Set the left or right song marker to the current playhead position. The markers must be at least 1 bar apart.

Why markers? Recording always starts at the left marker. The loop button loops the section between the markers.


When exporting to a wav file, you can choose to only export the range between the markers.

## Mixer

The mixer is designed to edit whole tracks and set their volume and pan.



## Track list



The track list allows you to select a track and scroll the list of tracks. Each track row holds its number, instrument icon, mute/solo/FX icons (see below), the keyboard row icon (if 2 rows), and the recorded notes as lines. Move your finger across the note area to scroll the playhead and get an audio preview. Double tap any region of a track to enter the piano roll editor.

Congruent (identical) and overlapping notes are marked orange. Congruent notes result in higher note volume, while overlapping notes may not play as intended. Delete congruent notes and move overlapping notes to an additional track.

## Instrument icon

Double tap it to change the track's color to a random color. Double tap and slide your finger to select a color (move horizontally to change the hue, vertically to set the saturation).

## Gain bars

These 2 green bars show the track's output gain for the left and right stereo channel, allowing you to see the volume and pan for each track at one glance. If the pan is centered, both bars have the same height.

## Warning triangle

Indicates that some notes on the track are outside the instrument's note range. Tap it to see more information. Notes outside the range will be played back but may sound atypical for this instrument, since every real instrument has a limited range of playable notes.



### Keyboard row icon

Only visible if 2 keyboard rows are enabled, indicating which keyboard row the track is assigned to. If you switch to [two keyboard rows](#), a separate track for the new row will be created. Selecting a track will always assign it to the upper row. However, the track assignment of the lower row cannot be changed. If you switch back to one row, the lower row's track will be deleted if nothing has been recorded on it.

### Filter track

The filter track appears only if the [filter effect](#) is enabled. The 2 lines represent the cutoff frequency and the resonance, like in the filter's panel. With the filter track selected, only the mute and the delete buttons are enabled. Muting the filter track prohibits it from being played back, allowing you to experiment with new filter settings.



### Add track button

The add track button is located at the end of the track list. It adds a new track with the current instrument to the bottom of the list.



### Mute button

Mutes the selected track, excluding it from playback. Muted tracks are darkened and are indicated by the mute icon.



### Solo button

If one or more tracks are switched to solo, all non-solo tracks will be excluded from playback.



### FX button

Sets the effects bus of the selected track. Per default, all standard effects apply to the track. Tap the FX button once to mark the track as an FX track, meaning that also the FX effects apply, in addition to the default effects. Tap the button again to exclude the track from all effects (useful for raw drum and base sounds). The blue FX icon next to the track icon indicates each track's FX state.



### Edit button

Switches to the [piano roll editor](#) for the selected track.



### Duplicate button

Duplicates the selected track, thereby copying its parameters and recorded notes.



### Delete button

Brings up a popup with the options to delete or clear a track. Clear will delete its notes but leave the track in the list. Delete will remove the track from the list. If the track holds pitch bend events, a checkbox for clearing only the pitch bend data appears.

## Pan knob and volume slider



The pan knob controls the track's stereo pan. Touch it and move your finger left or right to change the selected track's stereo pan. Double tap it to reset the pan to 0 (center). The [LCD](#) displays the current value (left is -127, center is 0, right is +127).

The volume slider displays and sets the track's volume. Its function is identical to the instrument tab's volume slider. The [LCD](#) displays the current value from 0 to 100%.

## Sequencer

The sequencer is designed for quick, bar-wise editing of the song. Select a range of bars (measures) and delete, repeat, move, or transpose them.



### Track list

The sequencer's track list is almost identical to the mixer's track list. Since the sequencer edits bars, track selection is not possible and the current track is not highlighted. Tapping a track's instrument icon will select all bars on the track.



#### New selection button

Clears the current selection and starts a new one. Tap it, then draw a rectangle on the note area in order to select bars. Selected bars are highlighted white and their notes are colored dark blue. Tap a track's instrument icon to select the whole track.



#### Change selection button

Adds or subtracts bars from an existing selection. Tap the button, then tap an unselected bar to add it to the selection, or a selected bar to deselect it. Tap a track's instrument icon to (de)select the whole track.



#### Move button

Activates the move mode where the selected bars can be dragged around. The song length can be increased by moving bars past the song end.



#### Duplicate button

Duplicates the selected bars and selects the new ones which can be moved around immediately. The copied notes will appear orange until they are moved, because they are congruent (identical) with the originals.

Important: Not moving the new notes will cause them to be identical (colored orange) to the originals, resulting in increased volume at playback.



### Repeat button

Duplicates the selected bars and moves them to the right so that they start where the selection ended. The song length is automatically increased if the new bars reach past the song end.



### Transpose button

Brings up the transpose menu which allows you to change the tone pitch of the selected bars. The semitone buttons de/increase it by one semitone, the octave buttons by 12 semitones. The [LCD](#) displays the number of semitones currently transposed.



### Quantize button

Tap the quantize button to bring up the quantization popup for quantizing the selected bars.



### Edit button

Switches to the [piano roll editor](#) for the selected track. This button is disabled if the selection encompasses more than one track.



### Delete button

Deletes the notes in the selected bars.




### Song bar edit button

Toggles the song bar edit mode where whole bars can be inserted and cut from the song. Tap anywhere to select a bar of the song (not just of individual tracks), which gets highlighted in red. The cut button deletes all notes in the selected bar and cuts it, i.e. shifts all later notes one bar to left and decreases the song length by 1 bar. The insert button inserts an empty bar at the position of the vertical line left to the red area. This means that the song length is increased by 1 bar and all notes to the right of the line are shifted one bar to the right.



## Piano roll editor



### Piano roll view

In contrast to the mixer and the sequencer screen, the piano roll editor displays only one track. The horizontal song ruler is still the same, but the vertical axis now represents keys. The mini keyboard on the left serves as a ruler for the note pitch. The background has the track's color scheme, where the dark stripes represent black notes. White horizontal lines between B and C keys mark the octaves. Notes are displayed as blocks, the color indicates the volume (or velocity) from dark blue (silent) to cyan (loudest).

Congruent (identical) and overlapping notes are marked orange. Congruent notes result in higher note volume, while overlapping notes may not play as intended. Delete congruent notes and move overlapping notes to an additional track.

Notes with [pitch bend data](#) have a different texture (a vertical color gradient).

### Vertical scrolling

Slide vertically on the mini keyboard to scroll and do the pinch gesture to zoom vertically. At low zoom factors, selecting individual notes is nearly impossible, but of course greater note ranges can be selected at once.



#### New selection button

Clears the current selection and starts a new one. Tap it, then draw a rectangle in order to select notes. Selected notes are highlighted and the note range of the whole selection is displayed in the [LCD](#).



#### Change selection button

Adds or subtracts notes from an existing selection. Tap the button, then select a range to toggle it.



### Draw button

Tap it to enable the draw mode.

## Draw mode



In the draw mode, notes can be created without recording on the keyboard. A crosshair, an OK button and a new menu will appear. Underneath the crosshair, the translucent note is the one which will be created if you press the OK or the Done button. Move the crosshair to the desired note location and tap OK to create the note - immediately, a new translucent note awaits creation. The song length can be increased by dragging the crosshair past the song end. Press the done button to exit the draw mode.



### Draw mode note buttons

The selected note button defines the length of the note to be drawn.



### Draw mode dotted button

Increases the note length by 50%.



### Quantized drawing button

Quantizes the new note even before it is drawn. If this button is enabled, the crosshair snaps to a raster defined by the selected note button.



### Move button

Activates the move mode where the selected notes can be dragged around.

The buttons in the menu (notes, dotted, done) have the same function as in draw mode. The OFF button disables quantization and allows for (almost continuous) movement with 1/192th precision. Tap one of the the lock buttons to lock horizontal or vertical movement, which is very handy if you intend to move or transpose only.



### Duplicate button

Duplicates the selected notes and selects the new ones which can be moved around immediately. The copied notes will appear orange until they are moved, because they are congruent (identical) with the originals.

Important: Not moving the new notes will cause them to be identical (colored orange) to the originals. They will be played back with increased volume.



### Length button

Tap it to enable the length edit mode which brings up a new menu. The buttons in this menu (notes, dotted, quantize, done) have the same function as in draw mode. Either tap a note button to set the length of all selected notes to an absolute value, or move your finger horizontally to de/increase the relative length.



### Volume button

Toggles the volume mode where the volume (also called key velocity) of the selected notes can be modified by moving your finger vertically. The LCD displays the current volume of the first selected note, ranging from 0 to 127 (default is 100). The note color indicates the volume from dark blue (silent) to cyan (loudest).



### Quantize button


Brings up the quantization popup for quantizing the selected notes.



### Delete button

Deletes the selected notes.

## Quantization popup



Quantization is the most important step after recording because it corrects the timing. If the quantization raster (resolution) is one quarter note, every selected note is moved to the nearest raster point in a 1/4 note raster. The selection of the right raster is crucial, therefore you might want to try out different settings for each recording. For example, if you played a rather fast melody and quantized it to 1/4, the timing will be ruined - in this case, just tap the undo button and try again with a higher resolution like 1/16. On the other hand, quantizing notes with a high resolution might not correct all timing errors you made when recording them.



### Note buttons

Set the quantization raster (or resolution) by selecting a note. In practice, low resolutions like 1/4 are the right choice for slow notes like the background cello in the demo "Canon in D (Pachelbel)". 1/16 fits to most melodies, while at 1/32 you will only notice the difference if you recorded fast notes (like a fast drum pattern) or at a low tempo setting.



### Dotted button

Increases the quantization raster by 50%. For example if you selected 1/8 dotted, the quantization resolution is 1/6 of a bar.



### Triplet button

Treats the notes as triplets, meaning that the raster interval is multiplied by 2/3. This allows for more swing and quantization of Jazz style melodies. Naturally, dotted and triplet cannot be enabled at the same time.



### Note length checkbox

If checked, note lengths will also be quantized, meaning that every note length will be an integer multiple of the selected quantization. This is especially handy if you want to enforce legato.



### Soft (humanize) checkbox

If you want to keep a human touch to the recording, soft quantization will shift every note by just 50%, keeping it slightly off the perfect timing.



## Tempo popup



### Tempo

Tap or hold the +/- buttons to change the tempo in the range of 40 to 240 bpm (beats per minute). A faster way to set the tempo is to tap and slide the value on the LCD. An alternative tempo input method is to tap the Tap Tempo button with the desired tempo for at least two times. Hold the Preview button to hear a metronome preview of the current tempo and signature.


### Signature

The song signature can be set to a value between 2/4 and 7/4. Most songs have a signature of 4/4, meaning that 1 bar has 4 beats (i.e. the length of 4 quarter notes). Hold the Preview button to hear a metronome preview of the current tempo and signature.

# Effects Tab


## Bus structure

The following diagram illustrates the audio signal flow:



- Tracks are treated separately depending on the [FX bus setting](#).
- Effects are always applied in the following order: pitch bend, amplifier, delay, equalizer, filter, reverb.
- If the amplifier effect (overdrive) is enabled, it's applied to the tracks like a pre-fader effect in order to have a high overdrive even on quiet tracks.
- All effects with the [FX checkbox](#) enabled are applied to the mix of all tracks with FX bus setting.
- This is added together with the rest of the tracks (those without [FX bus setting](#))
- The rest of the effects are applied to the mix (those effects with the [FX checkbox](#) disabled)
- The tracks with a [no-FX setting](#) are now added to the mix.
- The limiter is applied, according to the [master gain](#).

## Common Controls



### Power button

Simply switches the effect on or off.

### Limit to FX tracks checkbox

Puts the effect into the FX bus, meaning that it will be applied only to those tracks which have FX enabled (blue FX icon in the track list). All the other effects are still applied to all tracks after the FX effects are processed.

### Preview button

Identically to the instrument tab's preview button, it plays one or more notes (alternating) with the current instrument.

### Default button

Resets the current effect's settings to the preset values.

## Effects

### Volume



#### Master gain

This is not the device gain, instead it controls the gain of the internal limiter. High values may lead to unwanted volume compression or distortion, low values may not produce the desired volume. Different volumes may be required depending on your output route (the device's internal speaker, or earphones, or loudspeakers).

In technical terms, this setting is required because if all playing instruments are mixed (added up), the resulting values will in most cases be much higher than 65535 (the 16 bit border) and clipping would occur. The limiter uses a smooth mathematical function (a curve) to compress larger numbers into the 16 bit range. The master gain slider controls the slope of this curve.

#### Device volume

Brings up a popup with a slider which has the same function as the iPhone's hardware volume buttons. If the iPhone's internal speaker is used (not recommended), be sure not to turn it all the way up. If you connected external speakers, set this slider to maximum and control the volume via the speaker's volume controls for the best audio quality.

#### Decibel meters

These gauges indicate the current output level of each of the stereo channels.

## Reverb

Reverb simulates a room of a certain type (Hall/Canyon/Room) and size. If stuttering occurs during playback, decrease the reverb quality.



### Reverb size

Controls the size of the sound space. In larger spaces, the reverb is audible for a longer period of time. The size also depends on the selected reverb style, e.g. the largest room reverb is smaller than the largest canyon reverb.

### Reverb brightness

Low brightness gives the impression of a darker room (using a low pass filter), while maximum brightness leaves the reverb unfiltered.

### Reverb stereo spread

Controls the perception of stereo wideness of the reverb space. In technical terms, this slider sets the delay between the reverb reaching the left and the right channel.

### Reverb mix (wet/dry)

The mix slider controls the relation of the dry sound (the original, without the effect applied) and the wet sound (the effect's result).

### Reverb style

Selects the type of reverb (room, hall, canyon). Each style uses a different algorithm, thus the size slider has a different effect for each style.

### Reverb quality

Reverb requires a lot of processing power. In order to prevent playback stuttering on older devices or with complex songs, decrease the reverb quality. In technical terms, the reverb algorithm stays the same but the number of filters used in the reverbation filter chain is decreased.

### Remember settings for each style (iPad only)

As you change the reverb type, the previous settings you made for this type are recalled. If this checkbox is disabled, the reverb sliders remain unchanged if you change the reverb type.

## Delay

A delay repeats the original sound in a certain time interval set by the timing buttons/switch and the song tempo. The result is then fed back into the delay, resulting in many repetitions.



### Timing buttons

The selected note length will define the time interval of the delay, together with the song tempo.

### Timing switch

Dotted timing is 50% longer, triplet timing is 33% shorter.

### Feedback

Controls the gain of the feedback. Low values will limit the effect to just one audible repetition, high values will make the total delay duration very long.

### Delay mix (wet/dry)

The mix slider controls the relation of the dry sound (the original, without the effect applied) and the wet sound (the effect's result).

## Equalizer

The 3-band equalizer has fixed frequencies at 800Hz and 5kHz. Tap or move anywhere in the 3 areas to set the gain of bass, middle and treble tones. The range is -10dB to +10dB, the volume is automatically adapted to avoid clipping.



## Amplifier

The amplifier simulates overdrive by clipping the sound. It is a pre-fader effect, thus allowing high overdrive even if a track's volume is quiet.



### Overdrive

Controls the amount of distortion, i.e. the input gain for the amplifier.

### Style

Changes the mathematical function, resulting in a different timbre.

## Filter



The filter effect is a resonant low-, high-, or band-pass filter. The cutoff frequency and the resonance can be set by moving the crosshair, or by tilting the device if the accelerometer is enabled. The [filter track](#) in the mixer holds the recorded events (which can be deleted there).

For synth sounds and drum kits, this is a very useful effect. Enable the accelerometer control, switch to the keyboard tab and play or record something while gently tilting the device from one side to the center. A commonly used effect is, with the filter type set to low pass, changing the cutoff frequency from low to high, while keeping the resonance low.

### Resonance/Frequency display

The crosshair indicates the current values of the cutoff frequency (x axis) and the resonance (y axis). Move the crosshair to change the values. This can also be performed while recording.

Beware: high resonance values may lead to unpleasantly loud and high tones.

### Filter type switch

The filter type defines how the cutoff frequency influences the sound.

- Lowpass: All frequencies above the selected cutoff frequency are dampened (attenuated). The sound remains unchanged if the crosshair is in the lower right corner.
- Highpass: The effect behaves inverse to the lowpass. All frequencies below the selected cutoff frequency are dampened. The sound remains unchanged if the crosshair is in the lower left corner.
- Bandpass: Frequencies above and below the selected cutoff frequency are dampened. The sound remains unchanged if the crosshair is at the bottom center.

### Filter accelerometer axis

If the accelerometer is enabled, tilting it in any direction changes the cutoff and the resonance. The sound remains unchanged if the device lies flat on a surface.

- X+Y: Tilting along the x axis changes the cutoff frequency, while the y axis changes the resonance. Starting from the centered position, all 4 quadrants are symmetrical, i.e. tilting the device to the far left has the same effect as the far right.
- X: Filter and cutoff frequency are both changed if the device is tilted in the x axis.
- Y: Filter and cutoff frequency are both changed if the device is tilted in the y axis.

### Accelerometer sensitivity

With the sensitivity set to low, the device needs to be tilted almost 90 degrees to achieve the maximum effect. At high sensitivity, small movements are sufficient to set the filter values to maximum.

### Snap back checkbox

If snap back is enabled and the crosshair is moved, it snaps back to its original location after you release it.



## Pitch



If the pitch bend effect and the [accelerometer button](#) in the keyboard tab are enabled, the pitch of the currently played notes can be influenced by tilting the device.

Unlike most MIDI sequencers, Music Studio stores pitch bend data per note, not just per track. This means that two simultaneous notes on the same track can have different pitch bend data (events). The big advantage of this method is that editing a note automatically affects the pitch bend data for this note, but does not affect any other notes on the track (other software sequencers commonly ask if you want to move the pitch bend data too, this is obsolete with this method).

In the [piano roll editor](#), notes with pitch bend data have a different texture (a vertical color gradient).

### Semitone slider

Set the pitch bend range with the semitone slider from +/-1 to +/-24 semitones.

### Sensitivity slider

The tilt angle required to bend the maximum semitone range is controlled with the sensitivity slider. The text to the right of the sliders clarifies the behavior of the current setting (e.g. the device needs to be tilted 45 degrees to achieve a pitch bend of 8 semitones).

### Pitch bend accelerometer axis

This pulldown menu selects if the pitch bend reacts to tilt in the x or the y direction.

### Pitch bend invert axis checkbox

Enable it to invert the behavior of the current accelerometer axis, e.g. moving down (instead of up) will increase the pitch.

### Pitch bend record mode

The recording mode controls how existing pitch bend data is treated at recording.

- In overwrite mode, existing pitch bend events on the recorded track are overwritten by the new ones.
- Overdub mode preserves existing pitch bend data and stores the new pitch bend events only for newly recorded notes.

# Projects Tab

## Introduction



The projects tab can be used to create new projects, load, save and delete existing songs, or to export songs into WAV or MIDI files which can be transferred to your Mac/PC.

Projects (songs) are stored in the .xms file format, a custom and small format for Music Studio. It contains:


- Tracks, their recorded notes and parameters
- Song tempo, signature, markers
- Effects settings
- Keyboard layout (number of rows, positions, size)
- Metronome settings (volume, type, precount)
- Some user-interface settings (selected track, state of the loop-button etc.)
- Setup tab preferences are not contained in an .xms file, i.e. they remain unchanged if a project is loaded.

## Filename textfield



If a project is selected, its name is displayed in the textfield. To save the current song, tap the textfield to bring up the keyboard (be patient, this may take a few seconds on older devices) and enter the filename, then tap save. Tap the X icon on the right of the textfield to clear it.

## File list



SONG	Demo - Amazing Grace	1:52
SONG	Demo - Blue Danube (Strauss)	8:33
SONG	Demo - Blues	3:23
SONG	Demo - Canon Dance	2:10

The list displays the type, name and length (or size) of every .xms, .mid and .wav file. Select a file to view its details (date, size) in the area below the list. Double tap a file to load it.

## Buttons




### New

Creates a new project, deleting all tracks and resetting all effect parameters in the process.



### Load

Loads the selected .xms or .mid file. You can also double tap a song to load it. If the song requires instruments which are not present in your instrument list (i.e. not yet purchased), they are substituted by the closest matches from the available instruments and a popup informs you about that.



### Save

Saves the current song with the filename in the textfield. If the textfield is empty, the keyboard opens and the file is saved when you tap done.



### Delete

Deletes the selected file.




### Export

The export button does not export the current song, but the selected file. Songs can be exported into MIDI and WAV format. Choose the desired format and tap ok. The selected file will be loaded, exported and your current project will be loaded again.

The format of an exported wav file is 44kHz 16bit stereo. If the "apply markers" checkbox is enabled, only the range between the left and the right song marker of the selected song is exported. For the export process, the polyphony is automatically set to 128.

Exported MIDI files are format 1 files, i.e. each track is written into a MIDI track on a separate MIDI channel. Instruments are translated to closely match the GM (General MIDI) standard voices. Pitch bend is always compressed to the default MIDI range of +/- 2 semitones.

Tip: Before exporting to WAV, save the song with reverb quality set to high.



## Server


If your device is in the same WiFi (WLAN) network as your Mac or PC, files can be exchanged by tapping the server button and entering the displayed URL into the Mac or PC's browser.

In order for the Bonjour URL (e.g. <http://My-iPhones-Name.local:8080>) to work, PCs need to have Bonjour installed (comes with iTunes). Otherwise, use the IP (e.g. <http://192.168.1.3:8080>) to access the files.

In the browser, right click a file and select Download (or "Save target" or something similar depending on your browser) to save it on your hard disk drive.

Choose a file from your hard drive and click the import button to copy an .xms, .mid, .midi or .zip file onto your iDevice. Zip files are decompressed automatically on upload.

Read [this section in the FAQ](#) if you experience problems with the WiFi server.




# Setup Tab

## Differences on the iPad

On the iPad, all settings are organized on one screen, while on the iPhone/iPod touch they are split up into sub screens.

## General settings



## Latency

The time interval between your finger touching a key in the keyboard tab and the sound being audible is called latency. Low latency is required for a musician to feel connected with the virtual instrument and to play fast pieces. However, on slower devices, high CPU load can lead to stuttering/crackling in the audio output. This can happen if a complex song with many tracks is played back or if the device is busy with background tasks like mobile phone network processes. To avoid these performance dropouts, the latency can be increased, however the keyboard's responsiveness will suffer.

You might want to choose the lowest possible latency for recording and a higher latency to ensure stutter-free editing and playback.

## Polyphony

Polyphony defines the maximum number of notes that can be played simultaneously. High polyphony requires more CPU and can lead to stuttering/crackling in the audio output, but low polyphony can result in notes fading out too soon.

If it is set to 16 and at one point during playback, the song would require 17 notes to be played simultaneously, the oldest note will quickly be faded out to allow the new one to play. The required polyphony of a song depends on the number of simultaneous notes on all tracks, and heavily on the release times. When exporting a song to a wav file, a polyphony of 128 is applied.

## Continuous playhead movement

This checkbox appears only on the iPhone 3GS, iPod Touch 2nd generation, iPad and newer devices. In order to save CPU power, this setting is off by default and the playhead in the tracks tab moves only from beat to beat. Enable it to trade a lot of CPU power for more precise playhead movement (may introduce playback stuttering).

## Lock interface orientation (iPhone only)


Per default, the interface is adapted to the current device orientation, i.e. if the home button is left or right in landscape orientation. If this checkbox is enabled, the current interface orientation is locked.

On the iPad, use the hardware switch beside the volume buttons to lock the interface orientation.

## Restore defaults button

Brings up a popup asking you if the factory defaults should be restored. This means resetting all preferences in the setup tab and creating a new song. Saved songs (i.e. all files in the projects tab file list) will remain unchanged.

## Keyboard settings



### Velocity control

Enable velocity to control the note volume while playing on the keyboard. If set to Touch-Y, the volume depends on where you touch a key (upper end = quiet, lower end = forte). The accel setting allows you to control the note volume with the accelerometer by tilting the device in the selected axis.

### Snap to white keys

If enabled, scrolling in the keyboard tab will snap to the nearest white key.

## Allow touches between black keys

If enabled, white keys can be touched in the area between the black keys. Otherwise, white keys can only be touched on the area below the black keys.

## Allow touches on key borders

Allow touches on key borders If disabled, an invisible 5% border is between the white keys in order to minimize accidental touches.

## German key labeling

The German key naming system uses the letter B instead of H and A# instead of B. If checked, key labels on the keyboard tab and the piano roll editor's display use this naming convention.

## Accelerometer settings

[Pitch bend](#), the [filter effect](#) and the keyboard note velocity can be controlled via the accelerometer. The global settings in this screen might come in handy if you use the accelerometer a lot. The crosshair in the accelerometer panel indicates the current device tilt as perceived by the app (after processing the calibration, threshold and reactivity settings).



### Threshold slider

Device tilt is ignored up to the angle set the threshold slider. At a high threshold, the device can be tilted by about 15° until accelerometer values are recorded.


### Reactivity slider

High reactivity increases the effect of accelerometer noise while low reactivity leads to sluggish behavior (which may be a desired effect in some cases).

### Calibration

Tap the calibrate button to set the current device tilt as the centered position. The Reset Calibration button restores it.

## Interface settings



### Instruments tab

#### Keep attack/release times on instrument change (iPhone only)

If this is disabled, each time you select an instrument its default attack and release time will be set. If enabled, the current track's attack/release durations are kept when you select another instrument.

On the iPad, this setting is included right in the instruments tab.

### Tracks tab

#### Scroll on the margins when moving notes

If enabled, the sequencer and the piano roll editor automatically scroll if you move a selection to the edge.

#### Centered zooming

If checked, the pinch gesture in the tracks tab zooms into the center of the song ruler. Otherwise, the left song ruler position stays fixed and the right border changes when zooming.

### Effects tab

#### Remember reverb settings for each type (iPhone only)

As you change the reverb type, the previous settings you made for this type are recalled. If this checkbox is disabled, the reverb sliders remain unchanged if you change the reverb type.

On the iPad, this setting is included right on the reverb screen in the effects tab.



## Metronome settings



### Volume

The volume slider controls the gain of the metronome tick sound.

### Style

Choose between five metronome sounds. The higher pitched (first) sound indicates the beginning of a bar, the other sound marks the other beats.

### Precount

Set how many bars a recording will be precount. This is handy if you want to record the first note at the very beginning of the song (beat 1.1). Without precount, there wouldn't be enough time to tap the record button and immediately play the first note. Additionally, precount helps to get in line with the rhythm before you start playing (recording).

For example if precount is set to 2 bars, the playhead position is at the beginning of the song (1.1) and you tap the record button, the playhead will count 2 bars from -2.1, -1.1 until the recording starts at 1.1.

### Precount only at song start

If checked, precount is only applied if the left song marker is positioned at the beginning of the song. If it is not checked and the left song marker is for example at position 7.1, a 1-bar precount will begin at 6.1.

# Best practices

## Use higher latency for editing

Change the [latency](#) setting in the setup tab to achieve the best performance: low latency is best for recording and playing on the keyboard, while high latency minimizes stuttering when editing a complex song.

## Avoid overlapping (orange) notes

Congruent (identical) and overlapping notes are marked orange in the tracks tab. Congruent notes result in higher note volume, if the effect is unwanted just delete the top note.

## Make use of the undo button

If you misplaced a note while recording, don't even hit the stop button but instead tap the undo button , tap undo and restart recording.



## Try different quantization parameters

Every recording requires its own set of [quantization](#) parameters. Better results are obtained if you don't just stick with quantizing everything with 1/16. Try different settings and hit the undo button in between.

## Release times can simulate legato

If a recorded melody should flow but it sounds more like staccato, the notes are simply too short. The perfect correction would be to manually increase the note lengths in the [piano roll editor](#), but there is a quicker way: increase the track's release time until it sounds like legato.

## Adjust the reverb quality

Reverb requires a lot of CPU power. If stuttering occurs during playback, decrease the reverb quality. Set it to high quality before you export your final song to wav.

# Version history

## Version 1.4

Released July, 2010

### Major new features

- iPad optimization: Music Studio is now a universal binary
- New free instrument: a gorgeous grand piano
- iOS 4 multitasking enabled

### Keyboard tab

- Tap and hold the metronome button to bring up the tempo popup
- Fix: accelerometer pitch bend did not conform to the desired pitch range in some cases

### Instruments tab

- iPad: checkbox to synchronize the keyboard rows

### Projects tab

- Fix: File with the .midi extension were not recognized (only .mid was)
- Fix: signatures 2/4 and 7/4 were not loaded correctly
- New demo added: "Club on fire" by TecWeed

### Misc

- A tempo or signature change is now an undo step
- Fix: undo unloaded used samples in rare cases
- Fix: orientation changes were not handled correctly by the loading screen
- Various memory optimizations and stability improvements

## Version 1.3

Released June 29, 2010

### Major new features

- Pitch bend effect (accelerometer controlled)
- Filter effect (with accelerometer control)
- Improved help (internet connection no longer required)
- Reduced instrument shop prices
- New shop layout
- Note editing in the tracks tab is now possible during playback
- File loading times greatly reduced

### Major bug fixes

- Fix: crash on iPad if more than 5 fingers touched the screen
- Fix: audio route changes (connecting earphones) resulted in distorted audio
- Fix: MIDI import prioritized channels instead of tracks

### Keyboard tab

- Accelerometer button (to enable accelerometer effects)
- Interface orientation is locked while keys are touched
- Fullscreen button moved to layout mode
- Gestures tutorial is displayed at the first launch
- Fix: key label mode was not remembered

### Tracks tab

- New tempo and signature popup
- Tempo +/- buttons auto-in/decrease on hold
- Additional signatures available (2/4, 7/4)
- New metronome style
- New special track to display recorded filter effect data (visible if the filter effect is on)
- Fix: undo reset recent track and keyboard row changes
- Fix: rare crash at manual playhead scrolling

### Effects tab

- Filter and pitch bend effect

### Projects tab

- MIDI import/export includes pitch bend events
- File format improved

### Setup tab

- New layout
- Accelerometer and metronome settings
- New setting: continuous playhead movement
- New setting: reverb configuration is remembered per type
- New setting: track editing tips

## Version 1.2.1

Released May 6, 2010

### Major bug fixes

- Fix: Critical crash which occurred if a song with reverb set to room and low quality was loaded
- Fix: Rare crash in the keyboard tab

## Version 1.2

Released April 28, 2010

### Major new features

- New high-quality reverb algorithms with stereo spread
- 3 reverb qualities (higher quality requires more CPU and can lead to stuttering on older devices)
- Key velocity (volume) can be controlled via touch on the keyboard or the accelerometer (enable this in the setup tab)
- Piano-roll: 'selection change mode' toggles the selected range (instead of just single notes)

### Major bug fixes

- Fix: crash if a low memory warning occurred twice
- Fix: crash on iPad at launch
- Lots of stability and performance improvements

### Keyboard tab

- When recording, playback continues if a tab or the record button is tapped.

### Instruments tab

- Fix: lower row instrument selection
- Fix: lower row instrument was not fully loaded in low-memory situations
- Fix: instrument previews did not play all notes as intended
- Fix: instrument demo songs were copied at every app launch

### Tracks tab

- MIX: double tap a track's icon and slide your finger to select a color
- SEQ: song is cleared if the last (one and only) bar is cut
- Piano-roll: when exiting the draw mode, the done button draws the note if ok was not tapped
- Piano-roll: vertical lock button added to move mode
- Piano-roll: 1/64th note button added
- Piano-roll: quantization button added to length mode
- Fix: move and draw did not reload samples in low-memory situations
- Fix: when drawing notes, the position was shifted after tapping ok
- Fix: autoscrolling when moving notes in piano-roll view

### Effects tab

- Equalizer performance improved (requires less CPU)
- Fix: volume gauges were not reset to zero

### Projects tab

- File list performance greatly improved

- The last session's song name is displayed at the bottom
- Export wave popup: checkbox added to apply the song markers
- Fix: loading a song did not switch the tracks tab to the mix screen
- Fix: crashed if files with special chars in the filename were uploaded via the server

### **Undo**

- Fix: undo/redo remembers selected track and loop/metronome settings
- Fix: undo/redo popup displayed '? notes' after loop recording

## **Version 1.1**

Released April 7, 2010

### **Major new features**

- 4 new free instruments: trombone, rock bass, synth brass, marimba
- In-app shop with 48 studio-quality instruments
- 24 hour trial period to test all instruments
- Instruments arranged in 4 groups: classic, band, electronic, world
- Texture memory usage reduced by 50%, offering much more memory for loading instruments
- Huge performance and stability improvements
- Pause button in the tracks tab
- Playhead mode (tap the LCD) for quick playhead positioning in the keyboard and tracks tabs
- Horizontal lock button added to the piano-roll editor move menu
- Undo improved: redo added, popup (press the button for 2 sec.), undo files are kept throughout switching tabs
- Loading screen displays tips (touchable)

### **Audio**

- Existing instruments improved: clarinet, flute, grand piano
- Sustain looping improved
- Pan now preserves the volume
- New demo songs

### **Keyboard tab**

- Loop recording fixed
- Fixed some small touch input issues

### **Instruments tab**

- Instrument list scrollbar is touchable
- Tonal range warning popup substituted by touchable warning triangles in the tracks tab

### **Tracks tab**

- MIX: double tapping the pan knob sets it to 0
- SEQ: view can now fully zoom out
- SEQ: transpose is no longer restricted to the playable range
- Fix: piano-roll view was restricted to the playable range, notes outside were not editable
- Track list icons rearranged in MIX and are now identical in SEQ mode
- Piano-roll: maximum zoom factor increased
- Piano-roll: note coloring changed, from dark blue (silent) to cyan (loudest)
- Piano-roll: vertical zoom is now unrestricted (zoom out to all keys is possible)

- Piano-roll: vertical zoom buttons added (tap the magnifier button)
- Piano-roll: instrument icon moved to the bottom right corner
- Fix: piano-roll preview did not consider the note's velocity
- Fix: piano-roll move only worked if all selected notes were on-screen
- Fix: touches are now ignored during lengthy editing operations

### **Projects tab**

- When loading a song with unpurchased instruments, they are substituted and a popup lists the required instruments
- Song loading time decreased (especially if it shares instruments with the previous song)
- File list drawing speed improved
- Fix: protection against file corruption (e.g. in case of incoming call)
- Fix: exported wav file ended too soon in rare occasions if the delay effect was on

### **Setup tab**

- Added: Keep attack/release at instrument change
- Removed: LCD playhead scrolling (is now obsolete with the new playhead mode)
- Removed: Remember last state at exit

## **Version 1.0.3**

Released December 12, 2009

### **Major new features**

- Browser interface (WiFi server) now offers search, selection and delete functionality
- Piano-roll editor offers snap-to-grid when moving notes
- Zoom buttons and minimap added to the tracks tab (access via the magnifying glass button)
- Volume bars for L/R beside each track's instrument icon

### **Major bug fixes**

- Fix: exported wave files had the wrong tempo
- Fix: note selection did not work with signature 6/4
- Improvements and bug fixes
- Audio engine optimizations (decreased CPU load)
- Amplifier is now a pre-fader effect (this enables heavy distortion even for low-gain tracks)

### **Keyboard tab**

- Separate zoom factors for each keyboard row
- Fix: precount did not work at loop recording
- Fix: "Loading samples" popup was not shown when entering the keyboard tab
- Fix: stuttering when playing on 2 rows is fixed (as a trade-off the instrument icon always shows the upper row's instrument)

### **Instruments tab**

- Attack and release times are set to default when selecting an instrument

### **Tracks tab**

- Appearance of muted tracks improved
- Piano-roll: maximum zoom factor increased
- Fix: draw mode auto-scrolling in the piano-roll editor
- Fix: selection in the piano-roll editor was cleared at vertical scrolling

- Fix: entering the piano-roll editor in an empty track showed the highest octave
- Fix: SEQ selection was moved down if the empty area below the tracks was touched
- Fix: SEQ delete did not clear the selection
- Fix: some instruments were not audible at playhead scrubbing

### **Projects tab**

- Special characters are automatically removed from filenames
- File list automatically scrolls to the recently saved file
- Fix: export button could be tapped even it was disabled
- Fix: files with long filenames (abbreviated in the list) were not loaded
- Fix: remaining disk space calculation sometimes returned wrong results
- Fix: rare crash when loading a file
- Fix: rare crash when creating a new project
- Fix: dates of decompressed zip file contents were wrong

### **Misc.**

- Shadow added to the fonts in the popup window
- Loading screen adapts to the device orientation
- Animation of popup dialogs is skipped if playback is running
- Fix: font was blurry in the help tab
- Fix: "Loading textures" popup was shown only partially
- Fix: restore defaults while playback caused a crash
- Fix: the previous instrument was still selected under the loading instrument popup

## **Version 1.0.2**

Released November 4, 2009

### **Major new features**

- MIDI import
- ZIP files can be uploaded via WiFi (and are automatically decompressed)
- Increased and configurable polyphony (up to 64)
- Decreased latency
- Tracks are scanned for errors and repaired when loading an xms or midi file
- Double tap on a track in the MIX to switch to the piano roll editor at this position Projects tab: File list scroll bar is touchable for quick scrolling

### **Keyboard tab**

- Fix: pressed keys were released at song stop or loop end
- Fix: loop recording fixed
- Fix: undo button is active as soon as a note was recorded

### **Tracks tab**

- Tempo can be adjusted without pausing playback
- Tracks tab performance greatly increased
- Tracks tab scrolling speed increased, zoom speed adapts to the current zoom factor
- Double tapping on the tempo (above the track list) switches to the tempo screen
- Fix: space between bar number labels on the ruler is now adapted to their width
- Fix: stuck notes if solo was disabled but other tracks were still solo



- Fix: SEQ repeat now updates the right song marker
- Fix: SEQ zoomed to song end when tapping the SEQ button
- Fix: SEQ selection was cleared if only one bar was tapped
- Fix: crash if more than 32767 notes were drawn
- Fix: strange behavior of undo after duplication fixed
- Fix: quantize popup text was mispositioned

### **Projects tab**

- Fix: crashes could occur if more than 256 files were in the list
- Fix: long file names are trimmed in the file list
- Fix: file extensions were case sensitive
- Fix: an autosave is now generated immediately after a new project is created
- Fix: file list scrolled to top after deleting a file
- Fix: files are now sorted case insensitive
- Fix: when loading a future file format, a warning popup is displayed
- Fix: possible crash after a song was saved under heavy CPU load

### **MIDI and WAV export**

- Wave export switches polyphony to 128
- Fix: exported MIDI files had the sequence name TempoTrack instead of the song's name
- Fix: MIDI export track properties were wrong in some cases (pan, volume, attack, release)
- Fix: exported wave file memory estimation was off
- Fix: wave export cut the song before all effects were faded out in rare cases
- Fix: calculation of available space at wave export gave wrong results
- Fix: timeouts while exporting wave files in rare cases

### **Misc**

- Stability improvements
- Audio engine performance improvements
- Pulldown menus added for latency and polyphony settings
- New and improved demo songs
- Fix: popups with a loading bar were not rendered correctly
- Fix: possible crash at undo
- Fix: rare crash at instrument change while playback
- Fix: rare crash at the loading screen
- Fix: device orientation change sometimes did not rotate the screen
- Fix: effects screen required too much rendering performance

## **Version 1.0.1**

Released October 3, 2009

### **Major new features**

- MIDI export
- Resolution increased to 1/192 note (48 ticks per beat)
- Overlapping notes are colored orange
- New and improved demo songs

### **Major bug fixes**

- Dotted and triplet quantization produced wrong results
- Texture manager improved (effects textures were not loaded in low memory situations)
- Server had to be enabled multiple times until it worked in an ad-hoc network
- Wave export added too much silence after the song end

### **Keyboard**

- Fix: Undo did not work properly after loop recording
- Fix: Some key's up/down state was wrong after track switching or song stop
- Fix: When recording in loop mode, keys pressed during the loop end are now cut
- Fix: When recording is stopped, pressed keys are now recorded as note-off events

### **Tracks tab**

- Notes covering other notes are colored orange, congruent notes are selected separately
- MIX: double tapping a track brings up the piano roll editor
- SEQ: accidental song length increases while moving are prevented
- SEQ: the edit button can now be tapped even if only empty bars are selected from one track
- Playhead cursor line precision improved
- Fix: Sequencer repeat left empty bars in place
- Fix: Ruler sometimes did not draw the first or the last bar line
- Fix: SEQ ruler scrolling was possible on the track icons
- Fix: SEQ move gestures worked on tracks only
- Fix: Piano roll editor auto zoom improved
- Fix: SEQ was not updated if touched outside a track in new selection mode
- Fix: Undo in piano roll editor draw mode improved
- SEQ: In bar edit mode, it is now easier to select the last bar in order to add new bars at the song end
- Maximum zoom factor, scrolling and sliding speed increased

### **Effects tab**

- Equalizer and amp are now updated in real-time (while you are moving the controls)
- Fix: Volume needles were not updated at song stop
- Fix: Crackling noise occurred when reverb/delay/equalizer were changed

### **Projects tab**

- Status info improved (last action with time stamp)
- Fix: Tapping the projects tab textfield clear button crashed the app
- Fix: New/load project confirmation popup sometimes was not shown even if the project was changed
- Fix: Export button was tap-able even if no song was selected
- Fix: Wave export sometimes showed the not-enough-memory popup without reason
- Fix: Audio engine was not restarted after export
- Fix: Entering Japanese or special characters in the project name could lead to a crash
- Fix: File list scrolling was possible everywhere
- Fix: Undos were not purged at load or new project
- Export popup displays the filename

### **Misc**

- Preview buttons now always plays the first preview type (one note) first
- Fix: Settings were lost if the app was quit while it was still loading
- Fix: Crackling noise and crash in rare circumstances

## Version 1.0

Initial version. Released September 4, 2009