

DBS Tailoring System

- a reference manual of the software

(version 1.0)

Kean Foster
Swedish Meteorological and Hydrological Institute

Contents

| CONT | TENTS | 3 | | | | | |
|---|---|----|--|--|--|--|--|
| THE C | DISTRIBUTED BASED SCALING METHOD | 4 | | | | | |
| 1 | INTRODUCTION | | | | | | |
| 2 | THEORY | 4 | | | | | |
| 2.1 | The DBS Tailoring system | 4 | | | | | |
| 2.2 | Precipitation | 5 | | | | | |
| 2.3 | Temperature | 5 | | | | | |
| 3 | REQUIREMENTS | 7 | | | | | |
| 3.1 | System requirements | 7 | | | | | |
| 3.2 | Program files | 7 | | | | | |
| 3.3 | Data requirements | 8 | | | | | |
| 4 | THE USER INTERFACE | 9 | | | | | |
| 4.1 | Save | 10 | | | | | |
| 4.2 | Save to | 10 | | | | | |
| 4.3 | Load | 10 | | | | | |
| 4.4 | Clear | 10 | | | | | |
| 4.5 | Add | 10 | | | | | |
| 4.5.1 4.5.2 4.5.3 4.5.4 4.5.5 | LOAD 11 PLOT 14 EXPORT 16 DBS 18 FLIPPER 22 | | | | | | |
| 5 | EXAMPLES | 23 | | | | | |
| 5.1 | Typical DBS job process diagrams | 23 | | | | | |
| 5.2 | Sample xml files | 25 | | | | | |

Acknowledgements

The development of the DBS tailoring system was co-funded by the national research programs CLEO (CLimate change and Environmental Objectives) of the Swedish Environmental Protection Agency and HYDROIMPACTS2.0 (Hydrological climate change impact scenarios: developing the tools for a new generation) by the Swedish Research Council Formas.

The Distributed based scaling method

1 Introduction

Today there is a huge demand for knowledge on climate change and the impact on our environment. One source of information on possible outcomes of climate change is the numerical global circulation models (GCMs). The GCMs model the climate for the entire globe, from the past into the future. Different assumptions on how the greenhouse gas emotions will evolve can thus be tested within this framework. However, the scale of the information obtained from those models are often to coarse for any impact study on a regional scale. To downscale the information from the GCMs either statistical methods or regional climate models (RCM) are used. Both methods have their advantages and disadvantages. The RCMs hold more physics and might give a better representation of the geographical variation. The statistical methods on the other hand are more straightforward and don't require the same amount of computational time as the RCMs. To make the regional information useful in hydrological impact studies the information has to be even further downscaled and bias corrected. The DBS Tailoring System presented in this reference manual is an interface to a statistical method to do this downscaling and bias correction of two variables important for hydrological modelling, namely precipitation and temperature. DBS is an acronym for Distribution Based Scaling; the method was developed at the Swedish Meteorological and Hydrological Institute.

2 Theory

2.1 The DBS Tailoring system

The DBS tailoring system is a tool used primarily for facilitating bias correction/downscaling using the DBS approach (see the theory sections *Precipitation* and *Temperature* below). The DBS tailoring system is used both to prepare the different data and control files needed to perform a DBS bias correction/downscaling and run the DBS motor.

A typical DBS job can be broken down into six general steps:

- 1) Calculate the statistical parameters related to the reference precipitation. This step requires an ASCII file containing observed precipitation (or the desired analogous substitute) for a chosen reference period.
- 2) Calculate the statistical parameters related to the simulated precipitation. This step requires an ASCII file containing modelled precipitation for a chosen reference period, and the parameters from step 1.
- 3) The scaling of the simulated precipitation. This step requires an ASCII file containing modelled precipitation for the entire period of interest and the parameters from steps 1 and 2.
- 4) Calculate the statistical parameters related to the reference temperature. This step requires an ASCII file containing observed temperature (or the desired analogous substitute) for a chosen reference period and the reference precipitation data again.
- 5) Calculate the statistical parameters related to the simulated temperature. This step requires an ASCII file containing simulated temperature for a chosen reference period and the results from the scaling of the precipitation data.
- 6) The scaling of the simulated precipitation. This step requires an ASCII file containing modelled temperature for the entire period of interest and the following files; the parameters from steps 2, 4 and 5, and the results from the scaling of the precipitation data.

The DBS tailoring system helps to create the required files for the different steps described above and controls the DBS motor in each step. The DBS tailoring system uses XML files to define how to perform these tasks. These XML files are constructed with the help of the user-interface (see sections 4 and 5 for more details).

2.2 Precipitation

In the case of precipitation, the DBS approach uses two steps: (1) spurious drizzle generated by the climate model is removed to obtain the correct percentage of wet days and (2) the remaining precipitation is transformed to match the observed frequency distribution. To obtain the percentage of wet days correctly, a threshold is identified for each sub-basin and season. Days with precipitation amount larger than the threshold value were considered as wet days and all other days as dry days.

There are various theoretical distributions available to describe the probability distribution function (PDF) of precipitation intensities. A commonly used distribution is the gamma distribution, because of its ability to represent the typically asymmetrical and positively skewed distribution of daily precipitation intensities (Wilks 1995; Haylock et al. 2006; Yang et al. 2008). A single gamma distribution was therefore considered as the first choice in the DBS method, but then expanded as discussed below. The gamma distribution is a two-parameter distribution whose density distribution is expressed as:

$$f(x) = \frac{(x/\beta)^{\alpha - 1} \exp(-1/\beta)}{\beta \Gamma(x)} \qquad x, \alpha > 0$$

where α is the shape parameter, β is the scale parameter and Γ is the gamma function. The distribution parameters were estimated using maximum likelihood estimation (MLE). Daily precipitation distributions are typically heavily skewed towards low-intensity values. As a result, the distribution parameters will be dominated by the most frequently occurring values, but may not be able to accurately describe the properties of extreme values. To capture the main properties of normal precipitation as well as extremes, the precipitation distribution was divided into two partitions separated by the 95th percentile. The resulting distribution is hereafter referred to as the double gamma distribution. Two sets of parameters $-\alpha$, β and α_{95} , β_{95} , - were estimated from observations and the RCA3 output in the control period (1961–1990). These parameter sets were in turn used to correct the RCA3 outputs for the entire projection period up to 2100 using the equation:

$$\begin{cases} P_{DBS} = F^{-1} \big(\alpha_{Obs}, \beta_{Obs}, F(P, \alpha_{CTL}, \beta_{CTL}) \big) & \text{if } P < 95th \ percentile \ value} \\ P_{DBS} = F^{-1} \big(\alpha_{Obs,95}, \beta_{Obs,95}, F^{-1} \big(P, \alpha_{CTL,95}, \beta_{CTL,95} \big)) & \text{if } P < 95th \ percentile \ value} \end{cases}$$

where Obs denotes parameters estimated from observations and CTL denotes parameters estimated from the RCA3 output in the control period. F represents the gamma probability distribution. The DBS parameters for daily precipitation were optimized separately for each sub-basin to preserve spatial variability of the RCA3 outputs. To take seasonal dependencies into account, they were also optimized for each season: DJF (Dec–Feb), MAM (Mar–May), JJA (Jun–Aug) and SON (Sep–Nov).

2.3 Temperature

Compared to precipitation, temperature is more symmetrically distributed. It can be accurately described by a normal distribution with mean m and standard deviation s:

$$f(x) = \frac{1}{\sigma\sqrt{2\pi}}e^{-\left(\frac{x-\mu}{\sqrt{2}\sigma}\right)^2}$$

The mean and standard deviation of daily temperature on a Julian day were smoothed over the control period using a 15-day moving window. Considering dependence between precipitation and temperature, temperature time series were described with distribution parameters conditioned by the wet or dry state of the day. Fourier series were used to smooth the seasonal mean and standard deviation of temperature for wet and dry days:

$$\mu(t^*_{Dry/Wet}) = \frac{a_{0,Dry/Wet}}{2} + \sum_{k=1}^{K} [a_{k,Dry/Wet} \cos(k\omega t^*) + b_{k,Dry/Wet} \sin(k\omega t^*)]$$

$$\sigma(t^*_{Dry/Wet}) = \frac{c_{0,Dry/Wet}}{2} + \sum_{k=1}^{K} [c_{k,Dry/Wet} \cos(k\omega t^*) + d_{k,Dry/Wet} \sin(k\omega t^*)]$$

where a_0 , a_k , b_k , c_0 , c_k and d_k are the Fourier coefficients, t^* is the day of the year; we quals 2p/n, where n is the time units per cycle and k stands for the nth harmonic used for describing the annual cycle of adjusted daily temperature, TDBS. Theoretically, $t^*/2 + 1$ harmonics are able to represent a complete cycle. Five harmonics were used and found to be sufficient.

The DBS parameters for temperature were calculated for both observations and RCM-simulated data series. They are denoted μ_{Obs} , σ_{Obs} , μ_{CTL} and σ_{CTL} and are used to scale the daily temperature:

$$T_{DBS} = F^{-1} \left(\sigma_{Obs}, \mu_{Obs}, F(T_{RCA}, \sigma_{CTL}, \mu_{CTL}) \right)$$

3 Requirements

3.1 System requirements

To run the DBS tailoring system you need to have Java 7 installed on your system. The necessary files can be downloaded from:

http://www.oracle.com/technetwork/java/javase/downloads/index.html

3.2 Program files

| Name | Date modified | Туре | |
|-------------------|------------------|---------------------|--|
|] lib | 2012-03-26 09:13 | File folder | |
| ■ DBS.jar | 2012-02-10 17:16 | Executable Jar File | |
| DBS_generator.exe | 2012-02-14 14:13 | Application | |
| Run_DBS.bat | 2012-01-18 14:07 | Windows Batch File | |

figure 1. Image of the work folder showing the required program files. The contents of the lib folder are shown in figure 2 below.

| Name | Date modified | Туре |
|------------------------|------------------|---------------------|
| appframework-1.0.3.jar | 2012-02-10 17:16 | Executable Jar File |
| beansbinding-1.2.1.jar | 2012-02-10 17:16 | Executable Jar File |
| ihlabs.jar | 2012-02-10 17:16 | Executable Jar File |
| library_basic.jar | 2012-02-10 17:16 | Executable Jar File |
| Library_dataform.jar | 2012-02-10 17:16 | Executable Jar File |
| 🔟 netcdfAll-4.2.jar | 2012-02-10 17:16 | Executable Jar File |
| swing-worker-1.1.jar | 2012-02-10 17:16 | Executable Jar File |

figure 2. Image of the contents of the lib folder.

The system can be opened by double clicking on DBS.jar; however it is advised to use the batch file (Run_DBS.bat) to open the system as it increases the available computing resources to the system and relative information regarding the scaling job can be read in the command window.

If you do not have access to the batch file you can make your own using a text editor and typing in the following command:

java -Xss2048k -Xms512m -Xmx1024m -jar DBS.jar tasklist.xml

The yellow highlighted text above is the name of the xml file you would like the system to load automatically on start up. This is not necessary and can be left blank. You can also add the term

"nogui" to the end of the command; this will automatically load and run the xml file entered without opening the user interface:

java -Xss2048k -Xms512m -Xmx1024m -jar DBS.jar tasklist.xml nogui

3.3 Data requirements

This version of the DBS Tailoring system works with precipitation and temperature data. *An important note:* it is important to choose the correct temperature variables from the scenario to scale. Some models have variables that represent non-grid-averaged data, which is a better representation of observations than grid-averaged data. So if you are using observation data as a reference it is encouraged that you try to use a non-grid averaged variable such as 'tasol' (temperature near surface over open land) from the RCA model. On the other hand, if you are using modelled data as a reference e.g. EraInterim data, then it is encouraged that you use a grid-averaged variable e.g. t2m (2m temperature) and tas (temperature near surface).

The DBS stage of the system requires ASCII files to be 'time' oriented, that is to say with time on the x-axis and id on the y-axis (fig).

| %ID\TIME | 19810101 | 19810102 | 19810103 | 19810104 | %ID\TIME | 21619 | 21620 | 22099 | 22100 |
|----------|----------|----------|----------|----------|----------|-------|-------|-------|-------|
| 21619 | 10.49 | 9.51 | 8.26 | 6.69 | 19810101 | 10.49 | 12.87 | 10.14 | 12.38 |
| 21620 | 12.87 | 12.58 | 11.11 | 9.69 | 19810102 | 9.51 | 12.58 | 9.14 | 11.89 |
| 22099 | 10.14 | 9.14 | 7.49 | 6.47 | 19810103 | 8.26 | 11.11 | 7.49 | 10.42 |
| 22100 | 12.38 | 11.89 | 10.42 | 9.14 | 19810104 | 6.69 | 9.69 | 6.47 | 9.14 |

figure 3. A sample of typical 'time' orientated data (left) and the same sample data in 'id' orientation. The files are tab delaminated ASCII files and can be created using any suitable software e.g. Excel if you need to create them manually from data sources not supported by this system.

4 The User Interface

The user interface allows users to create DBS jobs by building and editing XML files that run the system. When you first open the DBS tailoring system interface you will see a blank workspace (figure 4), if you have not loaded an existing xml file).




figure 4. The blank user interface (left). The action wheel can be opened by right clicking in the work space (right).

Here you can build and edit tailoring jobs with the help of the action wheel, to access the action wheel right-click anywhere on the empty workspace. The action wheel has five alternatives:

Save: saves the xml file you are working on to you work folder. If you have not previously

saved the xml file before it will open the 'Save To' option instead.

Save To: opens a standard window for saving files where you can enter/change the name of

the xml file and the location.

Load: for loading existing xml files into the system.

Clear: clears the workspace.

Add: opens the new task window.

By right clicking on the tasks (not on the empty work space) you will see the following drop down menu (*figure 5*). With this drop down menu you can delete or edit the task you clicked on, insert a new task before the task you clicked on, delete the entire list, or delete large parts of the task list i.e. all tasks before excluding this task or all tasks after including this task, with the last two options.

Another helpful feature are the arrows that appear if you move the cursor over the left margin of the task boxes. These allow you to move that task up or down the list.




figure 5. By right clicking on the tasks you will get this menu. Here you can delete or edit the task you clicked on, insert a new task before the task you clicked on, delete the entire list, or delete large parts of the task list with the last two options.

4.1 Save

This option saves the xml file you are working on. If you have not saved it for the first time a standard windows 'save' popup window will appear where you can enter the file name and location.

4.2 Save to

This option allows you to save the xml file you are working on to a different location or under a different name. It is the same as the 'save as' option in many other programs.

4.3 Load

This option allows you to open existing xml files saved on your system. If you already have an xml file open in the interface you will be asked if you want to add the xml file to the end of open group. If you choose 'yes' the tasks in the xml file that you are loading will be added to those already in the user interface to create one long group. If you choose 'no' the tasks in the xml file that you are loading will be added as a new group after those already in the user interface to create two groups of tasks.

The difference between one or more groups is that the tasks in each group are independent of those in the other groups. This means that if a job crashes in a critical task in one group the system will skip to the next group and continue running. If you only have one long group the entire job will crash if a critical task crashes.

4.4 Clear

This option on the action wheel allows you to clear the user interface of all tasks, instead of having to delete the individual tasks one at a time.

4.5 Add

This option on the action wheel allows you to add the different individual tasks and in that way build up an xml file. The individual tasks used to build an xml file are; 'load', 'plot', 'export' 'DBS', and 'flipper' (figure 6).



figure 6. New task window, for adding one of the five base tasks to the workspace.

4.5.1 LOAD

This base task allows you to load file information for different file types into the system. Left clicking on the task in the workspace will open a tab where you can choose which file you want to use in the system. At the moment the system can only work with three types of files (*figure 7*); shapefiles (see *Loading shapefiles*), netCDF files (see *Loading netCDF files*) and three types of ASCII data (see *Loading ASCII files*). The other file types are unavailable in this version but will be activated in future versions.

This step creates a 'posmap' file; a file that contains information regarding the data contained in the file i.e. number of data points, data ranges etc. These POSMAP files, with their information regarding how the data is stored in each file, allows the system to identify where in the ASCII files the is stored which allows for faster reading of the data.

If you have prior tasks that have created data files, clicking on the source box will give you the option to load a 'system file' or a 'task output'. By choosing 'system file' you will enter the menu as seen in *figure 7* below, while choosing 'task output' will open a drop down menu with all the task outputs that can be loaded at that stage. Click on the green light to save settings and close the tab. By clicking on the red light will cancel any changes made and close the tab.




figure 7. Left clicking on the task opens the task tab. Here you can choose the data you want to load into the system by right clicking in the source box, the currently supported file types are shapefiles, netCDF files and ASCII files (discrete data, time series with time as the X axis header,

or time series with ID number as the X axis header). The other options are not available in this version but will be available in the next version of the system.

4.5.1.1 Loading shapefiles

To load information for a shapefile, click on the source box and choose SHAPEFILE. This will open a normal windows load window where you can choose the shapefile you want to load. Click on the green light to save settings and close the tab.

NOTE: shapefiles should have a latitude/longitude projection, preferably WGS84.

4.5.1.2 Loading netCDF files

To load information for a netCDF file, click on the source box and choose SHAPEFILE. A secondary drop down menu will open but only one option is selectable at this stage. Choose single, this will open a normal windows load window where you can choose the netCDF file you want to load information for. NOTE: netCDF files should have a latitude and longitude as field variables.

After selecting the netCDF file the following window will appear (*figure 8*) where you need to identify the netCDF variables that are needed. Right click on the relevant variables and select from the menu to set the field. To use a netCDF file you need to set four fields i.e. longitude, latitude, the data field, and time.




figure 8. After selecting a netCDF file you need to set the required fields longitude, latitude, the data field, and time. This is done by right clicking on the variable and setting it to the appropriate field. Selecting 'Show attributes' or 'Show data' options displays the netCDF variable attributes and a sample of the data respectively (figure 9).

Selecting either 'Show attributes' or 'Show data' options from the menu, as seen in *figure 8*, opens a window with the attributes of the netCDF variable and a sample of the variable data respectively (figure 9). This can be very useful for determining the calendar type and variable units which are important in later steps.

When you right click on 'time' another window will appear, here you will be asked to input optional 'time' related information. Here it is possible to set the start date for the netCDF data and change the calendar type used in the netCDF (*figure 10*). The default calendar setting is 'NORMAL'. The option ONLY360 refers to a calendar that uses a 360 day year while NOLEAPS refers to calendar that uses a 365 day year but does not have leap years.




figure 9. Right clicking on a variable and choosing 'Show attributes' opens a window with a summary of the netCDF variable's attributes (left). Similarly, by choosing 'Show data' opens a window that shows a sample of the variable data (right).

Information about the start date for the data and the calendar type can be seen in the 'Variable attributes' window (*figure 10*) and calculated from information found using the and 'Show data' function described above (*figure 8* and *figure 9*). Although this information is optional it is advisable to enter it, otherwise all data will have relative time step labels starting at 1 i.e. 1, 2, 3 etc. as opposed to dates e.g. 19610101, 19610102, 19610103 etc.

<u>NOTE:</u> it is important to check that the calendar setting corresponds to the calendar used in the netCDF to avoid temporal shifts.

You can only proceed when all the relevant fields are set i.e. the 'ok' button will only become active when this step is complete. Click on the green light to save settings and close the tab.




figure 10. Information about the start date and calendar type for the data contained in the netCDF can be entered here. The NORMAL calendar is the default setting with two other options, ONLY360 and NOLEAPS. If no date is entered for the data in the netCDF file then relative time steps will be used starting at 1.

4.5.1.3 Loading ASCII files

To load information for an ASCII file, click on the source box and choose ASCIIDATA. A secondary drop down menu will open with three choices (*figure 11*):

Discrete – non continuous data such as parameter files.

Timeserie – 'time' orientated time series i.e. they have time on the x-axis.

Idserie – 'id' orientated time series i.e. they have id on the x-axis.




figure 11. The secondary drop down menu for ASCIIDATA contains three selectable options: Discrete, Timeserie, and Idserie. Select the option that is relevant to the data you are loading information from.

Choose the option that is relevant to the file you want to load information for, this will open a normal windows load window where you can choose the ASCII file you want to load information for. When you have done this another window will open (*figure 12*). Here you need to confirm the type of ASCII information the file contains, data series or discrete values, and the orientation of the file, whether it is 'Id' oriented or 'time' oriented (choose 'Id' for discrete data). Further down there are two fields where you enter information regarding headings in the file. 'Header at row:' refers to which row the header is on (normally this is row 1) and the second 'Skip first rows:' refers to how many rows need to be skipped to reach the data (again this is usually 1).

At this point there is no need to make any changes to the last three options. These are used to import information about geographical data that may be saved in an ASCII file. Here you would enter which columns contain the id information, latitude information and longitude information.



figure 12. After selecting the ASCII file for which to load information about, this window appears in which you need to select the type of data the file contains (data series or discrete values), indicate the orientation (select 'Id' for discrete data), which row the header is on and how many rows to skip to reach the data.

4.5.2 PLOT

This task allows you to create images of shapefiles. Load in the information for the shapefile you want to plot, as described in *Loading shapefiles* above. Once you have added the plot task, left click on the task to open the task tab (*figure 13*). Source refers to the shapefile to be plotted, click

in the source box, select task output and choose the shapefile from the dropdown menu as shown in figure 13.




figure 13. The "Plot" task tab, to choose the shapefile you wish to plot from navigate the dropdown lists and click on the desired shapefile.

A popup menu will appear listing the different variables in the shapefile (*figure 14*), here you can choose "<all items>" to create plots for all variables or choose a specific variable from the dropdown menu to create a plot for just that variable.



figure 14. A popup with a dropdown menu with the different variables that can be chosen. Here you can choose <all items> if you wish to plot all of them, otherwise chose the one you are interested in.

Clicking on OK will automatically fill the "Data source" box with your choice. Next, click on the "Target" box; here you enter the location and name of the images that will be created. It is advised to save the images as PNG files; this is done by adding ".png" as the file extension when entering the file name. When this is done a popup window will appear figure 15asking you to enter the image width. The larger the number the larger the image so you are free to choose the image size; a width of 800 is suggested for a standard sized image.




figure 15. Popup box to eneter in the image width, a width of "800" can be used as standard.

4.5.3 EXPORT

This task allows you to export data from a file. The task can be divided into two main types of export i.e. using geographic information to select the relevant data, and using unique ids to select the relevant data.

The former type is mostly used to extract data from netCDF files to be in the scaling process. The export task uses the geographic data in the shapefile to select the nearest corresponding point in space from the netCDF file and assigns the id number from the shapefile to the data at that point.

The latter type is more versatile and can be used for a number of different tasks e.g. export statistics for the data to a shapefile for analysis purposes, or extract a subset from an existing dataset.



figure 16. The 'Export' task tab. Here you can enter the shapefile and data source files being used into the 'source' and 'extra data source' respectively. After clicking on the target box you need to choose what type of file you are exporting the data to, at present only shapefiles and ASCII files are supported.

The "Export" task requires two files, 1) a shapefile captaining information on the data to export, and 2) the source data which can be either a netCDF file or an ASCII file (both time and id orientated files work). In this version of the program it is possible to export data to two different file types, namely shapefiles and ASCII files. The ASCII files can be further divided into three subgroups; 'time-orientated' ASCII files, 'ID-orientated' ASCII files and 'discrete' ASCII files.

Click on the task to open the task tab (*figure 16*). The source data is the shapefile that will be used in the export job, click in the box and navigate the dropdown list to select the shapefile that you intend to use (you need to have loaded the information into the system prior using a load task). The extra data source is the file from which the data will be exported (again you need to have loaded the information into the system prior using a load task).

A window will appear after you have selected the "source" file and the "extra data source" respectively asking you to define the data ranges (*figure 17*). Here you can limit/select the ranges of the data being used in the export task either selecting the ranges directly or, as in the case for time related data; you can set the start and end dates using these buttons in the ranges section. You can also perform simple data manipulations, i.e. unit conversions, with the help of the "data multiple" or "data add".

Additionally there is a box, "convert to normal calendar", that you can select when exporting data from netCDF files that do not use a normal calendar. If you do not select this box and the data you are exporting has a non-normal calendar the exported data will retain the non-normal calendar attributes.




figure 17. After selecting each of the files for the "source" and the "extra data source" you will be asked to define the data item. Here you can limit/select the ranges of the data being used in the export task. You can also perform simple data manipulations, i.e. unit conversions, with the help of the "data multiple" or "data add". There is also a box, "convert to normal calendar", which you can select if you are exporting data from a netcdf file that has a non-normal calendar and wish to have the data converted to a normal calendar.

4.5.4 DBS

This task prepares the 'info_DBS_generator.txt' file which controls the DBS engine - 'DBS_generator.exe', which performs the scaling. To perform a scaling job you will need to set up six different DBS tasks, three for each variable. The first two tasks prepare parameter files for the observed and simulated datasets respectively and the third uses these parameter files to perform the scaling.

4.5.4.1 DBS tasks 1 and 2

The first two DBS tasks calculate the parameters for the reference and simulated precipitation dataset to be used in the scaling of the scenario data later. The DBS engine must be saved in a work folder where all the necessary files for the scaling tasks are/will be saved. In *figure 18*, below, you have the first two of the DBS tasks where the parameters for the reference precipitation and the simulated datasets are calculated. You need to enter where the DBS engine and the work folder are located (as mentioned above, these should be in the same folder).



figure 18. The first two DBS tasks, perparing the parameter files for the reference (observed) and the simulated data sets. Here you need to enter where the DBS engine and work folder are located and define the reference period. You can also change how the seasons are defined here.

The seasons are each three months as default, you can change the number and length of the seasons by selecting the season number and then clicking on the month you want in that season.

You need to enter the period for this task. That is the date when the DBS engine needs to start calculating and the end date. These dates are entered in a popup window with the following format

YYYY-MM-DD. As the first task is calculating the parameters for the reference precipitation dataset the time period you need to enter is the reference period being used (period of the reference data).

The relevant datasets are entered into the corresponding boxes by navigating the dropdown menus to the relevant files (you have to have loaded this file info into the system before you can select it). In DBS task 1 you need to enter the reference precipitation dataset, in DBS task 2 you need to enter the simulated precipitation dataset (for the reference period) and the parameters for the reference precipitation dataset (calculated in DBS task 1).

The name and location of the parameter files are entered in the save boxes furthest down the task

Note that every time you add a new DBS task you need to re-enter all the search paths, dates and seasons etc.

4.5.4.2 DBS task 3

The third DBS task uses the two parameter files created in the first two DBS tasks to scale the simulated precipitation dataset (*figure 19*). If you are using DBS engines versions 1, 2 or 3 it is recommended to perform this task twice, once to scale the simulated precipitation for the reference period and a second time for the entire simulated dataset. This is because scaled precipitation data for the reference period is needed in DBS step 5 and it is not yet clear if the DBS engine selects the correct period from the full data set.




figure 19. The third DBS task, scaling of the simulated precipitation dataset using the parameters calculated in DBS tasks 1 and 2. Here you need to reenter where the DBS engine and work folder are located, the reference period and redefine the seasons, if needed done in previous BDS tasks.

As with DBS tasks 1 and 2, all the information needs to be re-entered for the DBS engine, directory, seasons etc. only this time you need to enter the start and end date for the scaling i.e. the reference period for the first run and the entire simulation period for the second run.

You then need to select the necessary files for the scaling process; the simulated precipitation dataset (first a file for only the reference period and then the file for the entire period), the parameters for the reference precipitation dataset, and the parameters for the simulated precipitation dataset.

You can choose to save the scaling strengths, a measure of how much the DBS scaling has affected each data point, which can be useful for analysing the scaling results. To save the scaling strengths you must click on the box for saving the scaling strengths and select a path and file name.

Lastly select the path and file name for the scaled precipitation data.

4.5.4.3 DBS tasks 4 and 5

DBS tasks 4 and 5 are similar to DBS tasks 1 and 2 in that they prepare the parameter files for the reference and simulated temperature datasets. They differ, though, in that they use files related to precipitation in the process (*figure 20*).



figure 20. DBS tasks 4 and 5 are similar to DBS tasks 1 and 2 only that they need files related to precipitation in the process. Again, all the initial information needs to be re-entered as per DBS tasks 1,2 and 3, then the relevant files for calculating the paramete files are entered as well as the path and names of the parameter files being calculated.

The initial data (the path to the DBS engine and work folder, seasons, dates etc.) needs to be reentered. Then you need to enter in the reference temperature and precipitation datasets into DBS task 4 so that the parameters for the reference temperature dataset can be calculated.

For DBS task 5 you need to enter the simulated temperature dataset and the results from the scaling of the simulated precipitation dataset for the reference period (as discussed above in *DBS task 3*).

And again enter in the path and filenames for the parameter files to be calculated.

4.5.4.4 DBS task 6

DBS task 6 is the last of the DBS tasks (*figure 21*), scaling the temperature dataset. Once again the initial data in the header needs to be entered as per the previous tasks, except that the period is now just the period of the simulated data. There are more files to enter as the temperature scaling is dependant information from the precipitation files.




figure 21. DBS task 6, scaling the temperature dataset. The initial information needs to be reentered in the header, the period is the entire simulation period. Then all the required files need to entered. It is not possible to save the scaling strengths for the temperature scaling in this version.

You need to enter in the required files for the scaling; the simulated temperature data set, parameter files for the simulated and the reference temperature datasets, the parameters for the simulated precipitation dataset, and the scaled simulated precipitation data. Lastly you need to enter the path and filename for the scaled simulated temperature.

This version of the DBS tailoring system does not support saving the scaling strengths for temperature scaling.

4.5.5 FLIPPER

This task allows you to change the orientation of the ASCII files. The DBS engine requires that all ASCII files are 'time-orientated', that is to say they need to have the dates on the x-axis and the IDs on the y-axis. HYPE, on the other hand, requires that the files are 'ID-orientated'.

There are two ways to transpose the ASCII files:

- You can use an export task and export the ASCII file as another ASCII file but with the required orientation.
- You can use the flipper task to transpose the data in the ASCII file being flipped.

Using the flipper task is much simpler, all you need to do is enter the file to be flipped and set the path and name of the flipped or transposed file (*figure 22*).





figure 22. The flipper task transposes ASCII files from ID-orientated to time-orientated and viceversa. Enter the input file, the file to fllip/transpose, and the output file.


5 Examples


5.1 Typical DBS job process diagrams



Scaling process using modelled reference data (E-Hype)

Scaling process using observed reference data (S-Hype)





5.2 Sample xml files

As mentioned earlier (*The DBS Tailoring system*) the XML files are used to run the DBS tailoring system. Here are two examples of xml files. The first file is for when you already have the

reference data in ASCII form and the second is for when you have to extract reference data from a netCDF file i.e. when using EraInterim data.

Please note that these are examples and are not generic for every situation, you will need to at least need to input your own data, filenames, dates etc.



tasklist_a.xml



tasklist b.xm