Virtual Disk Programming Guide

Virtual Disk Development Kit (VDDK) 5.1 vSphere Storage APIs – Data Protection (VADP) 5.1

This document supports the version of each product listed and supports all subsequent versions until the document is replaced by a new edition. To check for more recent editions of this document, see http://www.vmware.com/support/pubs.

EN-000851-01



You can find the most up-to-date technical documentation on the VMware Web site at:

http://www.vmware.com/support/

The VMware Web site also provides the latest product updates.

If you have comments about this documentation, submit your feedback to:

docfeedback@vmware.com

Copyright © 2008–2012 VMware, Inc. All rights reserved. This product is protected by U.S. and international copyright and intellectual property laws. VMware products are covered by one or more patents listed at http://www.vmware.com/go/patents.

VMware is a registered trademark or trademark of VMware, Inc. in the United States and/or other jurisdictions. All other marks and names mentioned herein may be trademarks of their respective companies.

VMware, Inc. 3401 Hillview Ave. Palo Alto, CA 94304 www.vmware.com

Contents

About This Book 9

1 Introduction to the Virtual Disk API 11

	About the Virtual Disk API 11	
	VDDK Components 11	
	Virtual Disk Library 12	
	Disk Mount Library 12	
	Virtual Disk Utilities 12	
	Backup and Restore on vSphere 12	
	Backup Design for vCloud Director 12	
	Use Cases for the Virtual Disk Library 12	
	Developing for VMware Platform Products 13	
	Managed Disk and Hosted Disk 13	
	Advanced Transports 14	
	VDDK and VADP Compared 14	
	Platform Product Compatibility 14	
	Redistributing VDDK Components 14	
2	Installing the Development Kit 15	
	Prerequisites 15	
	Development Systems 15	
	Programming Environments 15	
	Visual Studio on Windows 15	
	C++ and C on Linux 15	
	Java Development for VADP 15	
	VMware Platform Products 15	
	Storage Device Support 16	
	Installing the VDDK Package 16	
	Repackaging VDDK Libraries 16	
	How to Find VADP Components 17	
3	Virtual Disk Interfaces 19	
	VMDK File Location 19	
	Virtual Disk Types 19	
	Persistence Disk Modes 20	
	VMDK File Naming 20	
	Thin Provisioned Disk 21	
	Internationalization and Localization 21	
	Virtual Disk Internal Format 21	
	Grain Directories and Grain Tables 21	
	Data Structures in Virtual Disk API 21	
	Credentials and Privileges for VMDK Access	22
	Adapter Types 23	
	Virtual Disk Transport Methods 23	
	Local File Access 23	
	SAN Transport 23	
	HotAdd Transport 24	

About the HotAdd Proxy 24 NBD and NBDSSL Transport 25 SSL Certificates and Security 25 NFC Session Limits 26 Virtual Disk API Functions 27 Virtual Disk Library Functions 27 Alphabetic Table of Functions 28 Start Up 28 Initialize the Library 29 Connect to a Workstation or Server 29 VMX Specification 29 Disk Operations 30 Create a New Hosted Disk 30 Open a Local or Remote Disk 30 Read Sectors From a Disk 30 Write Sectors To a Disk 30 Close a Local or Remote Disk 30 Get Information About a Disk 30 Free Memory from Get Information 31 Error Handling 31 Return Error Description Text 31 Free Error Description Text 31 Metadata Handling 31 Read Metadata Key from Disk 31 Get Metadata Table from Disk 31 Write Metadata Table to Disk 31 Cloning a Virtual Disk 31 Compute Space Needed for Clone 31 Clone a Disk by Copying Data 32 Disk Chaining and Redo Logs 32 Create Child from Parent Disk 32 Attach Child to Parent Disk 33 Opening in a Chain 33 Administrative Disk Operations 33 Rename an Existing Disk 34 Grow an Existing Local Disk 34 Defragment an Existing Disk 34 Shrink an Existing Local Disk 34 Unlink Extents to Remove Disk 34 Combine Links for a Disk 34 Change the Parent for a Disk 35 Shut Down 35 Disconnect from Server 35 Clean Up and Exit 35 Advanced Transport APIs 35 Initialize Virtual Disk API 35 Location of Log Files 37 List Available Transport Methods 37 SAN Mode on Linux Uses Direct Mode 37 Connect to VMware vSphere 37 Get Selected Transport Method 38

Prepare For Access and End Access 38

Updating Applications for Advanced Transport 39

Clean Up After Disconnect 39

	Algorithm for vSphere Backup 39 Best Practices for Backup 40 Backup and Recovery Example 40 Licensing of Advanced Transports 41 Multithreading Considerations 41 Multiple Threads and VixDiskLib 41 Capabilities of Library Calls 41 Support for Managed Disk 41 Support for Hosted Disk 42
5	Virtual Disk API Sample Code 43
	Compiling the Sample Program 43
	Visual C++ on Windows 43
	SLN and VCPROJ Files 43
	C++ on Linux Systems 44
	Makefile 44
	Library Files Required 44
	Usage Message 44
	Walk-Through of Sample Program 45
	Include Files 45
	Definitions and Structures 45 Dynamic Loading 46
	Wrapper Classes 46
	Command Functions 46
	DoInfo() 46
	DoCreate() 47
	DoRedo() 47
	Write by DoFill() 47
	DoReadMetadata() 47
	DoWriteMetadata() 47
	DoDumpMetadata() 47
	DoDump() 48
	DoTestMultiThread() 48
	DoClone() 48
	SSL Certificate Thumbprint 48
6	Practical Programming Tasks 49
	Scan VMDK for Virus Signatures 49
	Creating Virtual Disks 50
	Creating Local Disk 50
	Creating Remote Disk 51
	Special Consideration for ESX/ESXi Hosts 51
	Working with Virtual Disk Data 51
	Reading and Writing Local Disk 51
	Reading and Writing Remote Disk 52 Deleting a Disk (Unlink) 52
	Effects of Deleting a Virtual Disk 52
	Renaming a Disk 52
	Effects of Renaming a Virtual Disk 52
	Working with Disk Metadata 52
	Managing Child Disks 52
	Creating Redo Logs 52
	Virtual Disk in Snapshots 53
	Windows 2000 Read-Only File System 53

```
RDM Disks and Virtual BIOS 53
       Restoring RDM Disks 53
       Restoring the Virtual BIOS or UEFI 54
   Interfacing With VMware vSphere 54
       The VIX API 54
       Virus Scan all Hosted Disk 54
       The vSphere Web Services API 55
       Virus Scan All Managed Disk 55
       Read and Write VMDK with vSphere WS API 56
Designing vSphere Backup Solutions
   Design and Implementation Overview 57
       The Backup Process 57
       Communicating With the Server 58
       Information Containers as Managed Objects 58
          More About Managed Objects 58
          Managed Object References 59
          Unique ID for a Different vCenter 59
       Gathering Status and Configuration Information 59
          PropertyCollector Data 59
          Useful Property Information 60
       Doing a Backup Operation 60
          Prerequisites 60
          Create a Temporary Snapshot on the Target Virtual Machine 60
          Changed Block Tracking 61
          Extract Backup Data from the Target Virtual Machine 61
          Delete the Temporary Snapshot 61
       The Restore Process 61
       Doing a Restore Operation 62
          Prerequisites 62
          Restoring an Existing Virtual Machine to a Previous State 62
          Creating a New Virtual Machine 62
       Accessing Files on Virtual Disks 63
       Summary 63
   Low Level Backup Procedures 64
       Communicating with the Server 64
       The PropertyCollector 64
          PropertyCollector Arguments 64
          Getting the Data from the PropertyCollector 67
          Identifying Virtual Disks for Backup and Restore 68
       Creating a Snapshot 68
       Backing Up a Virtual Disk 69
       Deleting a Snapshot 69
       Changed Block Tracking on Virtual Disks 70
          Enabling Changed Block Tracking 70
          Gathering Changed Block Information 71
          Troubleshooting 72
          Limitations on Changed Block Tracking 72
          Checking for Namespace 73
   Low Level Restore Procedures 73
       Restoring a Virtual Machine and Disk 73
          Creating a Virtual Machine 73
          Using the VirtualMachineConfigInfo 79
          Editing or Deleting a Device 80
```

	Raw Device Mapping (RDM) Disks 80	
	Restore of Incremental Backup Data 80	
		81
	Tips and Best Practices 81	
	Best Practices for SAN Transport 81	
	Best Practices for HotAdd Transport 81	
	Best Practices for NBDSSL Transport 82	
	General Backup and Restore 82	
	Backup and Restore of Thin-Provisioned Disk 82	
	Virtual Machine Configuration 83	
	About Changed Block Tracking 83	
	Windows and Linux Implementations 83	
	The VMware VSS Implementation 83	
	Working with Microsoft Shadow Copy 84	
	Linux HotAdd and SCSI Controller ID 85	
A	Virtual Disk Mount API 87	
	The VixMntapi Library 87	
	Types and Structures 87	
	Operating System Information 87	
	Disk Volume Information 88	
	Function Calls 88	
	VixMntapi_Init() 88	
	VixMntapi_Exit() 88	
	VixMntapi_OpenDiskSet() 89	
	VixMntapi_OpenDisks() 89	
	VixMntapi_GetDiskSetInfo() 89	
	VixMntapi_FreeDiskSetInfo() 90	
	VixMntapi_CloseDiskSet() 90	
	VixMntapi_GetVolumeHandles() 90	
	VixMntapi_GetVolumeHandles() 90	
	VixMntapi_freeVolumer landles() 50 VixMntapi_GetOsInfo() 90	
	¥ = "	
	VixMntapi_FreeOsInfo() 91	
	VixMntapi_MountVolume() 91	
	VixMntapi_DismountVolume() 91	
	VixMntapi_GetVolumeInfo() 91	
	VixMntapi_FreeVolumeInfo() 91	
	Programming with VixMntapi 92	
	File System Support 92	
	Read-Only Mount on Linux 92	
	VMware Product Platforms 92	
	Sample VixMntapi Code 93	
	Restrictions on Virtual Disk Mount 93	
В	Errors Codes and Open Source 95	
	Finding Error Code Documentation 95	
	Association With VIX API Errors 95	
	Interpreting Errors Codes 95	
	Interpreting Errors Codes 95 Troubleshooting Dynamic Libraries 95 Open Source Components 96	

Restoring Virtual Disk Data 80

Glossary 97

Index 99

About This Book

The VMware[®] Virtual Disk Programming Guide introduces the Virtual Disk Development Kit (VDDK) and the vSphere Storage APIs – Data Protection (VADP). For VDDK it describes how to develop software using a virtual disk library that provides a set of system-call style interfaces for managing virtual disks. For VADP it describes how to write backup and restore software for vSphere.

To view this version or previous versions of this book and other public VMware API and SDK documentation, go to http://www.vmware.com/support/pubs/sdk_pubs.html.

Revision History

Table 1 summarizes the significant changes in each version of this guide.

Table 1. Revision History

Revision	Description
2012-12-21	Bug fix version of the vSphere 5.1 manual: numeric change ID policy, mount restrictions.
2012-10-05	Final version of this manual for the vSphere 5.1 release.
2011-11-18	Bug fix version for 4Q 2011 refresh of the VMware vSphere Documentation Center.
2011-08-22	Final version for the VDDK 5.0 release, subsuming <i>Designing Backup Solutions</i> technical note.
2010-10-12	Bug fix revision for the VDDK 1.2.1 release
2010-08-05	Version for vSphere 4.1 and the VDDK 1.2 public release.
2009-05-29	Final version for the VDDK 1.1 public release.
2008-04-11	Updated version for release 1.0 of the Virtual Disk Development Kit.
2008-01-31	Initial version of the Virtual Disk Development Kit for partner release.

Intended Audience

This guide is intended for developers who are creating applications that manage virtual storage. It assumes knowledge of C and C++ programming. For VADP development, it assumes knowledge of Java.

Supported Platform Products

You can develop VDDK programs using either Linux or Windows, and test them using VMware Workstation. To develop and test VADP programs, you need an ESXi host, preferably with shared SAN storage.

Document Feedback

VMware welcomes your suggestions for improving our developer documentation. Send your feedback to docfeedback@vmware.com.

VMware Technical Publications

VMware Technical Publications provides a glossary of terms that might be unfamiliar to you. For definitions of terms as they are used in VMware technical documentation go to http://www.vmware.com/support/pubs.

To access the current versions of VMware manuals, go to http://pubs.vmware.com/vsphere-50/index.jsp.

Technical Support and Education Resources

The following sections describe the technical support resources available to you.

Online and Telephone Support

To use online support to submit technical support requests, view your product and contract information, and register your products, go to http://www.vmware.com/support.

Support Offerings

To find out how VMware support offerings can help meet your business needs, go to http://www.vmware.com/support/services.

VMware Professional Services

VMware Education Services courses offer extensive hands-on labs, case study examples, and course materials designed to be used as on-the-job reference tools. Courses are available onsite, in the classroom, and live online. For onsite pilot programs and implementation best practices, VMware Consulting Services provides offerings to help you assess, plan, build, and manage your virtual environment. To access information about education classes, certification programs, and consulting services, go to http://www.vmware.com/services.

Introduction to the Virtual Disk API

1

This chapter presents the following topics:

- "About the Virtual Disk API" on page 11
- "VDDK Components" on page 11
- "Use Cases for the Virtual Disk Library" on page 12
- "Developing for VMware Platform Products" on page 13

The virtual disk development kit (VDDK) is an SDK to help developers create applications that access storage on virtual machines. The VDDK package is based on the virtual disk API, introduced in this chapter.

The VMware Storage APIs – Data Protection (VADP) use the virtual disk API and a subset of vSphere APIs to take snapshots of virtual machines running on ESXi, enabling full or incremental backup and restore. VADP replaces VMware Consolidated Backup (VCB).

About the Virtual Disk API

The virtual disk API, or VixDiskLib, is a set of function calls to manipulate virtual disk files in VMDK format (virtual machine disk). Function call semantics are patterned after C system calls for file I/O. Using the virtual disk API, you can write programs to manage VMDK files directly from your software applications.

These library functions can manipulate virtual disks on VMware Workstation or similar products (hosted disk) or virtual disks residing on VMFS volumes of an ESX/ESXi host (managed disk). Hosted is a term indicating that the virtualization platform is hosted by a guest operating system such as Windows or Linux.

The VDDK package installs on either Windows or Linux, so you can write VDDK and VADP applications using either system. Applications can manipulate the virtual disks of any operating system that runs on a supported VMware platform product. You may repackage VDDK binaries into your software application after signing a redistribution agreement. See the *VDDK Release Notes* for a list of supported platform products and development systems.

The VDDK and VADP enable you to develop applications that work effectively across multiple virtual disks from a central location.

VDDK Components

The virtual disk development kit includes the following components:

- The virtual disk library, a set of C function calls to manipulate VMDK files
- The disk mount library, a set of C function calls to remote mount VMDK file systems
- C++ code samples that can be compiled with Visual Studio or the GNU C compiler
- VDDK utilities: disk mount and virtual disk manager
- PDF manuals and online HTML reference

Virtual Disk Library

VixDiskLib is a standalone wrapper library to help you develop solutions that integrate into VMware platform products. The virtual disk library has the following capabilities:

- It allows programs to create, convert, expand, defragment, shrink, and rename virtual disk files.
- It can create redo logs (parent-child disk chaining, or deltas) and can delete VMDK files.
- It permits random read/write access to data anywhere in a VMDK file, and reads metadata.
- It can connect to remote vSphere storage using advanced transports, SAN or HotAdd.

For Windows, the virtual disk kernel-mode driver is 32-bit or 64-bit depending on the underlying system. User-mode libraries are 32-bit because Windows On Windows 64 can run 32-bit programs without alteration. For Linux, both 32-bit and 64-bit user-mode libraries are provided.

Disk Mount Library

The virtual disk mount library, vixMntapi, allows programmatic access of virtual disks as if they were mounted disk partitions. For more information see Appendix A, "Virtual Disk Mount API," on page 87. The vixMntapi library is packaged in the VDDK with vixDiskLib.

Virtual Disk Utilities

The Virtual Disk Development Kit includes two command-line utilities for managing virtual disk: disk mount and virtual disk manager. The virtual disk manager has been included with VMware Server and Workstation. Disk mount is available in the Virtual Disk Development Kit.

VMware disk mount (vmware-mount) is a utility for Windows and Linux hosts. If a virtual disk is not in use, the utility mounts it as an independent disk volume, so it can be examined outside its original virtual machine. You can also mount specific volumes of a virtual disk if the virtual disk is partitioned.

VMware virtual disk manager (vmware-vdiskmanager) is a command-line utility for Windows and Linux hosts. It allows you to create, convert, expand, defragment, shrink, and rename virtual disk files. It does not have a facility to create redo logs or snapshots.

For more information see the Disk Mount and Virtual Disk Manager User's Guide, which is available on the Web.

Backup and Restore on vSphere

The VMware Storage APIs – Data Protection (VADP) is a collection of APIs that are useful for developing or extending backup software so it can protect virtual machines running on ESX/ESXi hosts in VMware based datacenters. For more information see Chapter 7, "Designing vSphere Backup Solutions," on page 57.

Backup Design for vCloud Director

With VMware vCloud[®], the self-service capabilities of vCloud Director provide three levels of data protection. Backup providers can offer vApp protection at the system level, the tenant level, or the end-user level. For information about vCloud data protection, see the technical note *Backup Design for vCloud Tenant vApps*.

Use Cases for the Virtual Disk Library

The VDDK provides easy access to virtual disk storage, enabling a wide range of use cases for application vendors including:

- Back up a particular volume, or all volumes, associated with a virtual machine.
- Connect a backup proxy to vSphere and back up all virtual machines on a storage cluster.
- Read virtual disk and run off-line centralized anti-virus scanning of virtual machines.
- Read virtual disk and run software package analysis of virtual machines.

- Write to virtual disk, enabling off-line centralized patching of virtual machines.
- Manipulate virtual disks to defragment, expand, rename, or shrink the file system image.
- Convert a virtual disk to another format, for example from thick to thin provisioned.
- Perform data recovery or virus cleaning on corrupt or infected off-line virtual machines.

Developing for VMware Platform Products

In a VMware based datacenter, commercial backup software is likely to access virtual disks remotely, perhaps from a backup proxy. The backup proxy can be a virtual machine with backup-restore software installed and knowledge of a tape autochanger or equivalent. At a given point in time, the backup software:

- 1 Snapshots the virtual machines in a cluster (one by one, or in parallel).
- 2 Copies the VMDK files, or (for incremental backup) only changed blocks, to backup media.
- 3 Records configuration of virtual machines.
- 4 Deletes the snapshot, which acted as a quiesced virtual machine.

In the above procedure, the virtual disk library is used in the second step only. The other steps use a portion of the vSphere API (called VADP) to snapshot and save configuration of virtual machines. The virtual disk in a cluster is "managed" by vSphere.

Managed Disk and Hosted Disk


Analogous to a hard disk drive, virtual disk files represent the storage volumes of a virtual machine. Each is named with .vmdk suffix. On a system running VMware Workstation, file systems of each guest OS are kept in VMDK files hosted on the system's physical disk. VMDK files can be accessed directly on the host.


With the virtual machine file system (VMFS) on ESX/ESXi hosts, VMDK files again represent storage volumes of virtual machines. They are on VMFS, which often resides on shared storage in a cluster. The vCenter Server manages the cluster storage so it can migrate (vMotion) virtual machines from one ESX/ESXi host to another without moving VMDK files. VMFS storage is therefore called managed disk.

VMFS disk can reside on a storage area network (SAN) attached to ESX/ESXi hosts by Fibre Channel, iSCSI, or SAS connectors. It can also reside on network attached storage (NAS), or on directly attached disk.

Figure 1-1 depicts the arrangement of managed disk (in this case VMDK on a SAN-hosted VMFS file system) and hosted disk (VMDK files on physical disk).

Figure 1-1. Managed Disk and Hosted Disk





The VDDK supports both managed disk and hosted disk, although some functions are not supported for managed disk, and other facilities are not supported for hosted disk. Exceptions are noted in documentation.

Advanced Transports

With managed disk, VDDK applications can make use of advanced transports to perform many I/O operations directly on the SAN, rather than over the LAN. This improves performance and saves network bandwidth.

VDDK and VADP Compared

The Virtual Disk Development Kit (VDDK) includes a set of C library routines for manipulating virtual disk (VixDiskLib) and for mounting virtual disk partitions (VixMntapi). The VDDK focuses on efficient access and transfer of data on virtual disk storage.

The vSphere Storage APIs for Data Protection (VADP) is a marketing term for a subset of the vSphere API that enables backup and restore applications. The snapshot-based VADP framework allows efficient, off-host, centralized backup of virtual machine storage. After taking a snapshot to quiesce virtual disk, software can then back up storage using VDDK library routines.

The vSphere API is an XML-based Web service that provides the interfaces for vCenter Server management of virtual machines running on ESX/ESXi hosts.

Developers need both VDDK and VADP to write data protection software. VADP is presented in Chapter 7, "Designing vSphere Backup Solutions," on page 57.

Platform Product Compatibility

To support a new release of vSphere, in most cases you should update and recompile your software with a corresponding new release of VDDK. This is because VDDK is continually updated to support new features in vSphere. As of 5.0, the version number of VDDK matches the version number of vSphere.

Since its inception in 2008, VDDK has been backward compatible with VMware platform products such as Workstation, ESX/ESXi 3.5, and VirtualCenter 2.5 (now vCenter Server). VMware Fusion was never supported. VDDK is no longer tested with Workstation, but Workstation makes a good development platform.

Redistributing VDDK Components

After you use the VDDK to develop software applications that run on VMware platform products, you might need to repackage library components that are compiled into your software.

To qualify for VDDK redistribution, you must be in the VMware TAP program at Select level or above, and sign a redistribution agreement. Contact your VMware alliance manager to request the VDDK redistribution agreement. VMware would like to know how you use the VDDK, in what products you plan to redistribute it, your company name, and your contact information.

Installing the Development Kit

To develop virtual disk applications, install the VDDK as described in this chapter. For backup applications, VADP development requires the vSphere Web Services SDK.

- "Prerequisites" on page 15
- "Installing the VDDK Package" on page 16

Prerequisites

This section covers what you need to begin VDDK and VADP development.

Development Systems

The VDDK has been tested and is supported on the following systems:

- Windows, both 32-bit x86 and 64-bit x86-64
- Linux, separate packages for 32-bit x86 and 64-bit x86-64

See the VDDK Release Notes for specific versions, which change over time. Mac OS X is not supported.

Programming Environments

You can compile the sample program and develop vSphere applications in the following environments:

Visual Studio on Windows

On Windows systems, programmers can use the C++ compiler in Visual Studio 2003 (except with x86-64), Visual Studio 2005, Visual Studio 2008, and later.

C++ and C on Linux

On Linux systems, programmers can use the GNU C compiler, version 4 and higher. The sample program compiles with the C++ compiler g++, but VDDK also works with the C compiler gcc.

Java Development for VADP

When developing backup and restore software to run on vSphere, VMware recommends Eclipse with Java, on both Windows and Linux. The vSphere Web Services SDK now includes both Axis and JAX-WS bindings. You can call C or C++ code with wrapper classes, as in Java Native Interface (JNI).

VMware Platform Products

Software applications developed with the VDDK and VADP target the following platform products:

- vCenter Server managing ESX/ESXi hosts
- ESX/ESXi hosts directly connected

See the VDDK Release Notes for specific versions, which change over time.

Hosted products including VMware Workstation are neither tested nor supported.

Storage Device Support

VMware Consolidated Backup (VCB) had knowledge base article http://kb.vmware.com/kb/1007479 showing the support matrix for storage devices and multipathing. VMware does not provide a similar support matrix for VDDK and VADP. Customers must get this information from you, their backup software vendor.

Installing the VDDK Package

The VDDK is packaged as an executable installer for Windows, including 64-bit libraries, or a compressed archive for Linux, with separate 32-bit and 64-bit packages. It includes the following components:

- Header files vixDiskLib.h and vm_basic_types.h in the include directory.
- Function library vixDiskLib.lib (Windows) or libvixDiskLib.so (Linux) in the lib directory.
- HTML reference documentation and sample program in the doc directory.

To install the package on Windows

- 1 On the Download page, choose the binary .exe for Windows and download it to your desktop.
- 2 Run or double-click the downloaded .exe installer.
- 3 Follow the on-screen instructions.

To unpack Windows 64-bit Libraries

- 1 Install VDDK on Windows as above.
- Find vddk64.zip in the install directory, which by default is: C:\Program Files\VMware\VMware Virtual Disk Development Kit\bin
- 3 Unzip this into a location of your choice, taking care not to overwrite any existing files. Do not select the above bin directory as the extraction target!
- 4 You should see bin and lib directories. You can build your VixDiskLib and VixMntapi code against these. Be sure to add the bin directory to the Path when you run your binary.

To Install the package on Linux

- 1 On the Download page, choose the binary tar.gz for either 32-bit Linux or 64-bit Linux.
- 2 Unpack the archive, which creates the vmware-vix-disklib-distrib subdirectory.

```
tar xvzf VMware-vix-disklib.*.tar.gz
```

3 Change to that directory and run the installation script as the superuser:

```
cd vmware-vix-disklib-distrib
sudo ./vmware-install.pl
```

4 Read the license terms and type yes to accept them.

Software components install in /usr unless you specify otherwise.

You might need to edit your LD_LIBRARY_PATH environment to include the library installation path, /usr/lib/vmware-vix-disklib/lib32 (or lib64) for instance. Alternatively, you can add the library location to the list in /etc/ld.so.conf and run ldconfig as the superuser.

Repackaging VDDK Libraries

After you develop an application based on VDDK, you might need the VDDK binaries to run your application.

As described in "Redistributing VDDK Components" on page 14, partners can sign a license agreement to redistribute VDDK binaries that support VADP applications.

To enable VDDK binaries on Windows virtual machines without VDDK installed

- Install the Microsoft Visual C++ (MSVC) redistributable, possibly as a merge module. The latest MSVC runtime works as side-by-side component, so manually copying it might not work on Vista. See details on the Microsoft Web site for the redistributable package, x86 processors or x64 processors. Side-by-side is also explained on the Microsoft Web site.
- Install VMware executables and DLLs from the \bin and \lib folders of the installed VDDK, and the vstor2-mntapi10.sys driver into the Windows\system32\drivers folder or equivalent.
- 3 Create and install your application, compiled in a manner similar to the vixDiskLibSample.exe code, discussed in Chapter 5, "Virtual Disk API Sample Code," on page 43.

How to Find VADP Components

ESX/ESXi hosts and vCenter Server similarly implement managed objects that support inventory traversal and task requests. Before you write VADP software in Java, you need to download the vSphere Web Services SDK. You can find documentation and ZIP file for download on the VMware Web site.

Virtual Disk Programming Guide

Virtual Disk Interfaces

VMware offers many options for virtual disk layout, encapsulated in library data structures described here.

- "VMDK File Location" on page 19
- "Virtual Disk Types" on page 19
- "Data Structures in Virtual Disk API" on page 21
- "Virtual Disk Transport Methods" on page 23

VMDK File Location

On ESX/ESXi hosts, virtual machine disk (VMDK) files are located under one of the /vmfs/volumes, perhaps on shared storage. Storage volumes are visible from the vSphere Client, in the inventory for hosts and clusters. Typical names are datastore1 and datastore2. To see a VMDK file, click Summary > Resources > Datastore, right-click Browse Datastore, and select a virtual machine.

On Workstation, VMDK files are stored in the same directory with virtual machine configuration (VMX) files. On Linux this directory could be anywhere, and is usually documented as /path/to/disk. On Windows this directory is likely to be C:\My Documents\My Virtual Machines, under the virtual machine name.

VMDK files store data representing a virtual machine's hard disk drive. Almost the entire portion of a VMDK file is the virtual machine's data, with a small portion allotted to overhead.

Virtual Disk Types

The following disk types are defined in the virtual disk library:

- VIXDISKLIB_DISK_MONOLITHIC_SPARSE Growable virtual disk contained in a single virtual disk file. This is the default type for hosted disk, and the only setting in the Chapter 5 sample program.
- VIXDISKLIB_DISK_MONOLITHIC_FLAT Preallocated virtual disk contained in a single virtual disk file. This takes time to create and occupies a lot of space, but might perform the best.
- VIXDISKLIB_DISK_SPLIT_SPARSE Growable virtual disk split into 2GB extents (s sequence). These files start small but can grow to 2GB, which is the maximum allowed on old file systems. This type is highly manageable because split VMDK can be defragmented and works on all file systems.
- VIXDISKLIB_DISK_SPLIT_FLAT Preallocated virtual disk split into 2GB extents (f sequence). These files start at 2GB, so they take a while to create and consume disk, but available space can grow.
- VIXDISKLIB_DISK_VMFS_FLAT Preallocated virtual disk compatible with ESX 3 and later. This is a type of "managed disk" introduced in "Managed Disk and Hosted Disk" on page 13.
- VIXDISKLIB_DISK_VMFS_THIN Growable (sparse) virtual disk compatible with ESX 3 and later. As of VDDK 1.1, thin-provisioned is a supported type of managed disk that saves storage space.
- VIXDISKLIB_DISK_STREAM_OPTIMIZED Monolithic sparse format compressed for streaming. Stream optimized format does not support random reads or writes.

Sparse disks employ the copy-on-write (COW) mechanism, in which virtual disk contains no data in places, until copied there by a write. This optimization saves storage space.

Persistence Disk Modes

In **persistent** disk mode, changes are immediately and permanently written to the virtual disk, so that they survive even through to the next power on.

In **nonpersistent** mode, changes to the virtual disk are discarded when the virtual machine powers off. The VMDK files revert to their original state.

The virtual disk library does not encapsulate this distinction, which is a virtual machine setting.

VMDK File Naming

Table 3-1 explains the different types of virtual disk. The first column corresponds to "Virtual Disk Types" on page 19 but without the VIXDISKLIB_DISK prefix. The third column gives the possible names of VMDK files as implemented on Workstation and ESX/ESXi hosts.

NOTE When you open a VMDK file with the virtual disk library, always open the one that points to the others, not the split or flat sectors. The file to open is most likely the one with the shortest name.

For information about other virtual machine files, see section "Files that Make Up a Virtual Machine" in the *VMware Workstation User's Manual*. On ESX/ESXi hosts, VMDK files are type VMFS_FLAT or VMFS_THIN.

Table 3-1. VMDK Virtual Disk Files

Disk Type in API	Virtual Disk Creation on VMware Host	Filename on Host
MONOLITHIC_SPARSE	In Select A Disk Type , accepting the defaults by not checking any box produces one VMDK file that can grow larger if more space is needed. The <vmname> represents the name of a virtual machine. On VMFS partitions, this is name of the disk descriptor file.</vmname>	<vmname>.vmdk</vmname>
MONOLITHIC_FLAT or VMFS_FLAT or VMFS_THIN	If you select only the Allocate all disk space now check box, space is pre-allocated, so the virtual disk cannot grow. The first VMDK file is small and points to a much larger one, whose filename says flat without a sequence number. Similarly on VMFS partitions, this is the virtual disk file that points to virtual disk data files, either thick or thin provisioned.	<vnname>-flat.vmdk</vnname>
SPLIT_SPARSE	If you select only the Split disk into 2GB files check box, virtual disk can grow when more space is needed. The first VMDK file is small and points to a sequence of other VMDK files, all of which have an s before a sequence number, meaning sparse. The number of VMDK files depends on the disk size requested. As data grows, more VMDK files are added in sequence.	<vmname>-s<###>.vmdk</vmname>
SPLIT_FLAT	If you select the Allocate all disk space now and Split disk into 2GB files check boxes, space is pre-allocated, so the virtual disk cannot grow. The first VMDK file is small and points to a sequence of other files, all of which have an f before the sequence number, meaning flat. The number of files depends on the requested size.	<vnname>-f<###>.vmdk</vnname>
MONOLITHIC_SPARSE or SPLIT_SPARSE snapshot	A redo log (or child disk or delta link) is created when a snapshot is taken of a virtual machine, or with the virtual disk library. Snapshot file numbers are in sequence, without an s or f prefix. The numbered VMDK file stores changes made to the virtual disk <diskname> since the original parent disk, or previously numbered redo log (in other words the previous snapshot).</diskname>	<diskname>-<###>.vmdk</diskname>
SE_SPARSE	Space-efficient sparse format, used by VMware View for redo logs and snapshots. Available in vSphere 5.1 and later.	
n/a	Snapshot of a virtual machine, which includes pointers to all its .vmdk virtual disk files.	<vnname>Snapshot.vmsn</vnname>

Thin Provisioned Disk

With thin provisioned disk, the vSphere Client may report that provisioned size is greater than disk capacity.

Provisioned size for a thin disk is the maximum size the disk will occupy when fully allocated. Actual size is the current size of the thin disk. Overcommit means that if all thin disks were fully provisioned, there would not be enough space to accommodate all of the thin disks.

Internationalization and Localization

The path name to a virtual machine and its VMDK can be expressed with any character set supported by the host file system. As of vSphere 4 and Workstation 7, VMware supports Unicode UTF-8 path names, although for portability to various locales, ASCII-only path names are recommended.

Windows 2000 systems (and later) use UTF-16 for localized path names. For example, in locale FR (Français) the VDDK sample code might mount disk at C:\Windows\Temp\vmware-Système, where è is encoded as UTF-16 so the VixMntapi library cannot recognize it. In this case, a workaround is to set the tmpDirectory configuration key with an ASCII-only path before program start-up; see "Initialize the Library" on page 29.

For programs opening arbitrary path names, Unicode offers a GNU library with C functions iconv_open() to initialize codeset conversion, and iconv() to convert UTF-8 to UTF-16, or UTF-16 to UTF-8.

Virtual Disk Internal Format

A document detailing the VMware virtual disk format is available on request. To obtain the document, navigate to the Virtual Machine Disk Format page at this Web address:

http://www.vmware.com/technical-resources/interfaces/vmdk.html

Click the **Request...** specification link. Provide your name, organization, and email address. A link to the online PDF document should arrive shortly in your email inbox. The *Virtual Disk Format 5.0* technical note provides useful information about the VMDK format.

Grain Directories and Grain Tables

SPARSE type virtual disks use a hierarchical representation to organize sectors. See *Virtual Disk Format* 5.0 referenced in "Virtual Disk Internal Format" on page 21. In this context, grain means granular unit of data, larger than a sector. The hierarchy includes:

- Grain directory (and redundant grain directory) whose entries point to grain tables.
 - Grain tables (and redundant grain tables) whose entries point to grains.
 - Each grain is a block of sectors containing virtual disk data. Default size is 128 sectors or 64KB.

Data Structures in Virtual Disk API

Here are important data structure objects with brief descriptions:

VixError – Error code of type uint64.

VixDiskLibConnectParams – Public types designate the virtual machine credentials vmxSpec (possibly through vCenter Server), the name of its host, and the credential type for authentication. For details, see "VMX Specification" on page 29. The credType can be VIXDISKLIB_CRED_UID (user name / password, most common), VIXDISKLIB_CRED_SESSIONID (the HTTP session ID), VIXDISKLIB_CRED_TICKETID (vSphere ticket ID), or VIXDISKLIB_CRED_SSPI (Windows only, current thread credentials).

```
typedef char * vmxSpec
typedef char * serverName
typedef VixDiskLibCredType credType
```

■ VixDiskLibConnectParams::VixDiskLibCreds - Credentials for either user ID or session ID.

VixDiskLibConnectParams::VixDiskLibCreds::VixDiskLibUidPasswdCreds – String data fields represent user name and password for authentication.

VixDiskLibConnectParams::VixDiskLibCreds::VixDiskLibSessionIdCreds – String data fields represent the session cookie, user name, and encrypted session key.

VixDiskLibConnectParams::VixDiskLibCredsb::VixDiskLibSSPICreds – String data fields represent security support provider interface (SSPI) authentication. User name and password are null.

■ VixDiskLibCreateParams – Types represent the virtual disk (see "Virtual Disk Types" on page 19), the disk adapter (see "Adapter Types" on page 23), VMware version, and capacity of the disk sector.

```
typedef VixDiskLibDiskType diskType
typedef VixDiskLibAdapterType adapterType
typedef uint hwVersion
typedef VixDiskLibSectorType capacity
```

VixDiskLibDiskInfo – Types represent the geometry in the BIOS and physical disk, the capacity of the
disk sector, the disk adapter (see "Adapter Types" on page 23), the number of child-disk links (redo logs),
and a string to help locate the parent disk (state before redo logs).

```
VixDiskLibGeometry biosGeo
VixDiskLibGeometry physGeo
VixDiskLibSectorType capacity
VixDiskLibAdapterType adapterType
int numLinks
char * parentFileNameHint
```

■ VixDiskLibGeometry – Types specify virtual disk geometry, not necessarily the same as physical disk.

```
typedef uint32 cylinders
typedef uint32 heads
typedef uint32 sectors
```

Credentials and Privileges for VMDK Access

Local operations are supported by local VMDK. Access to ESX/ESXi hosts is authenticated by login credentials, so with proper credentials VixDiskLib can reach any VMDK on an ESX/ESXi host. VMware vSphere has its own set of privileges, so with the proper privileges (see below) and login credentials, VixDiskLib can reach any VMDK on an ESX/ESXi host managed by vCenter Server. VixDiskLib supports the following:

- Both read-only and read/write modes
- Read-only access to disk associated with any snapshot of online virtual machines
- Access to VMDK files of offline virtual machines (vCenter restricted to registered virtual machines)
- Reading of Microsoft Virtual Hard Disk (VHD) format

With vCenter Server, the Role of the backup appliance when saving data must have these privileges for all the virtual machines being backed up:

- VirtualMachine > Configuration > Disk change tracking
- VirtualMachine > Provisioning > Allow read-only disk access
- VirtualMachine > Provisioning > Allow VM download
- VirtualMachine > State > Create snapshot and Remove snapshot

On the backup appliance, the user must have the following privileges:

- Datastore > Allocate space
- VirtualMachine > Configuration > Add new disk and Remove disk
- VirtualMachine > Configuration > Change resource and Settings

The user must have these privileges for vCenter Server and all ESX/ESXi hosts involved in backup:

- Global > DisableMethods and EnableMethods
- Global > License

Adapter Types

The library can select the following adapters:

- VIXDISKLIB_ADAPTER_IDE Virtual disk acts like ATA, ATAPI, PATA, SATA, and so on. You might select this adapter type when it is specifically required by legacy software.
- VIXDISKLIB_ADAPTER_SCSI_BUSLOGIC Virtual SCSI disk with Buslogic adapter. This is the default on some platforms and is usually recommended over IDE due to higher performance.
- VIXDISKLIB_ADAPTER_SCSI_LSILOGIC Virtual SCSI disk with LSI Logic adapter. Windows Server 2003 and most Linux virtual machines use this type by default. Performance is about the same as Buslogic.

Virtual Disk Transport Methods

VMware supports file-based or image-level backups of virtual machines hosted on an ESX/ESXi host with SAN or NAS storage. Virtual machines read data directly from a shared VMFS LUN, so backups are efficient and do not put significant load on production ESX/ESXi hosts or the virtual network.

VMware offers interfaces for integration of storage-aware applications, including backup, with efficient access to storage clusters. Developers can use VDDK advanced transports, which provide efficient I/O methods to maximize backup performance. VMware supports five access methods: local file, NBD (network block device) over LAN, NBD with encryption (NBDSSL), SAN, and SCSI HotAdd.


Local File Access

The virtual disk library reads virtual disk data from /vmfs/volumes on ESX/ESXi hosts, or from the local filesystem on hosted products. This file access method is built into VixDiskLib, so it is always available on local storage. However it is not a network transport method.

SAN Transport

SAN mode requires applications to run on a backup server with access to SAN storage (Fibre Channel, iSCSI, or SAS connected) containing the virtual disks to be accessed. As shown in Figure 3-1, this is an efficient method because no data needs to be transferred through the production ESX/ESXi host. If the backup server is a physical machine with optical media or tape drive connected, backups can be made entirely LAN-free.

Figure 3-1. SAN Transport Mode for Virtual Disk



In SAN transport mode, the virtual disk library obtains information from an ESX/ESXi host about the layout of VMFS LUNs, and using this information, reads data directly from the storage LUN where a virtual disk resides. This is the fastest transport method for software deployed on SAN-connected ESX/ESXi hosts.

SAN storage devices can contain SATA drives, but currently there are no SATA connected SAN devices on the VMware hardware compatibility list.

HotAdd Transport

If your backup application runs in an appliance, it can create a linked-clone virtual machine starting from the backup snapshot and read the linked clone's virtual disks for backup. This involves a SCSI HotAdd on the host where the backup application is running – disks associated with the linked clone are HotAdded on the backup application's machine, also called the backup proxy.

HotAdd is a VMware feature where devices can be added "hot" while a virtual machine is running. Besides SCSI disk, virtual machines can add additional CPUs and memory capacity.

VixTransport handles the temporary linked clone and hot attachment of virtual disks. VixDiskLib opens and reads the HotAdded disks as a "whole disk" VMDK (virtual disk on the local host). This strategy works only on virtual machines with SCSI disks and is not supported for backing up virtual IDE disks.

SCSI HotAdd is a good way to get virtual disk data from a virtual machine to a backup virtual appliance (or backup proxy) for sending to the media server. The HotAdd disk is shown as local storage in Figure 3-2.




Figure 3-2. HotAdd Transport Mode for Virtual Disk

Running the backup proxy as a virtual machine has two advantages: it is easy to move a virtual machine to a new media server, and it can back up local storage without using the LAN, although this incurs more overhead on the physical ESX/ESXi host than when using SAN transport mode.

About the HotAdd Proxy

The HotAdd proxy can be a virtual machine or a physical machine, although virtual proxies are preferable. In typical implementations, a HotAdd proxy backs up either Windows or Linux virtual machines, but not both.

For parallel backup, sites can deploy multiple proxies.

If the HotAdd proxy is a virtual machine that resides on a VMFS-3 volume, choose a volume with block size appropriate for the maximum virtual disk size of virtual machines that customers want to back up, as shown in Table 3-2. This caveat does not apply to VMFS-5 volumes, which always have 1MB file block size.


Table 3-2. VMFS-3 Block Size for HotAdd Backup Proxy

VMFS Block Size	Maximum Target Disk Size
1MB	256GB
2MB	512GB
4MB	1024GB
8MB	2048GB

NBD and NBDSSL Transport

When no other transport is available, networked storage applications can use LAN transport for data access, either NBD (network block device) or NBDSSL (encrypted). NBD is a Linux-style kernel module that treats storage on a remote host as a block device. NBDSSL is similar but uses SSL to encrypt all data passed over the TCP connection. The NBD transport method is built into the virtual disk library, so it is always available, and is the fall-back when other transport methods are unavailable.

Figure 3-3. LAN (NBD) Transport Mode for Virtual Disk



In this mode, the ESX/ESXi host reads data from storage and sends it across a network to the backup server. With LAN transport, large virtual disks can take a long time to transmit. This transport mode adds traffic to the LAN, unlike SAN and HotAdd transport, but NBD transport offers the following advantages:

- The ESX/ESXi host can use any storage device, including local storage or remote-mounted NAS.
- The backup proxy can be a virtual machine, so customers can use vSphere resource pools to minimize the performance impact of backup. For example, the backup proxy can be in a lower-priority resource pool than the production ESX/ESXi hosts.
- If virtual machines and the backup proxy are on a private network, customers can choose unencrypted data transfer. NBD is faster and consumes fewer resources than NBDSSL. However VMware recommends encryption for sensitive information, even on a private network.

SSL Certificates and Security

The VDDK 5.1 release has been security hardened, and virtual machines can be set to verify SSL certificates.

On Windows, the three keys shown in Table 3-3 are required at one of the following Windows registry paths:

- For 32-bit Windows systems use

 HKEY_LOCAL_MACHINE\SOFTWARE\VMware, Inc.\VMware Virtual Disk Development Kit
- For 64-bit Windows systems use

 HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\VMware, Inc.\VMware Virtual Disk Development Kit

To support registry redirection, registry entries needed by VDDK on 64-bit Windows must be placed under registry path Wow6432Node. This is the correct location for both 32-bit and 64-bit binaries on 64-bit Windows.

Table 3-3. Windows Registry Keys for VDDK

Key Name	Туре	Possible Settings
InstallPath	REG_SZ	<pre><path directory="" install="" the="" to=""></path></pre>
PackageCode	REG_SZ	{27E8F1B5-07F3-41F3-A29E-4CFF3A6EECFA} This is the 5.1 package code (GUID). It will change with each new build number.
VerifySSLCertificates	REG_DWORD	Either 0 = off, 1 = on. Default is 0 (zero). If 0, SSL certificate validation will be ignored. If 1, the SSL certificate of the target virtual machine must be: ■ properly signed by a certificate authority, ■ self-signed, or ■ the thumbprint of the target machine's SSL certificate must match the thumbprint provided in the communication configuration structure.

On Linux, SSL certificate verification requires the use of thumbprints – there is no mechanism to validate an SSL certificate without a thumbprint. On vSphere the thumbprint is a hash obtained from a trusted source such as vCenter Server, and passed in the SSLVerifyParam structure from the NFC ticket. If you add the following line to the VixDiskLib_InitEx configuration file, Linux virtual machines will check the SSL thumbprint:

vixDiskLib.linuxSSL.verifyCertificates = 1

The following library functions enforce SSL thumbprint on Linux: InitEx, PrepareForAccess, EndAccess, GetNfcTicket, and the GetRpcConnection interface that is used by the advanced transports.

NFC Session Limits

NBD employs the VMware network file copy (NFC) protocol. Table 3-4 shows limits on the number of network connections for various host types. VixDiskLib_Open() uses one connection for every virtual disk that it accesses on an ESX/ESXi host. VixDiskLib_Clone() also requires a connection. It is not possible to share a connection across disks. These are host limits, not per process limits, and do not apply to SAN or HotAdd.

Table 3-4. NFC Session Connection Limits

Host Platform	When Connecting	Limits You To About
vSphere 4	to an ESX host	9 connections directly, 27 connections through vCenter Server
vSphere 4	to an ESXi host	11 connections directly, 23 connections through vCenter Server
vSphere 5	to an ESXi host	Limited by a transfer buffer for all NFC connections, enforced by the host; the sum of all NFC connection buffers to an ESXi host cannot exceed 32MB. 52 connections through vCenter Server, including the above per-host limit.

Virtual Disk API Functions

This chapter provides an overview of functions in the Virtual Disk API and includes the following sections:

- "Virtual Disk Library Functions" on page 27
- "Start Up" on page 28
- "Disk Operations" on page 30
- "Error Handling" on page 31
- "Metadata Handling" on page 31
- "Cloning a Virtual Disk" on page 31
- "Disk Chaining and Redo Logs" on page 32
- "Administrative Disk Operations" on page 33
- "Shut Down" on page 35
- "Advanced Transport APIs" on page 35
- "Updating Applications for Advanced Transport" on page 39
- "Multithreading Considerations" on page 41
- "Capabilities of Library Calls" on page 41

After a presentation of Virtual Disk API functions in alphabetic order, sections focus on what the functions do, in the normal order they would appear in a program, except advanced transport functions (SAN and HotAdd) appear after the shutdown functions.

Virtual Disk Library Functions

You can find the *VixDiskLib API Reference* by using a Web browser to open the doc/index.html file in the VDDK software distribution. As in most reference manuals, functions are organized alphabetically, whereas in this chapter, functions are ordered by how they might be called.

When the API reference says that a function supports "only hosted disks," it means virtual disk images hosted by VMware Workstation or similar products. Virtual disk stored on VMFS partitions managed by ESX/ESXi or vCenter Server is called "managed disk."

The functions described in this chapter are based on concepts and employ data structures documented in Chapter 3, "Virtual Disk Interfaces," on page 19.

If the library accesses virtual disk on VMFS, I/O by default goes through the ESX/ESXi host, which manages physical disk storage. To use function calls that provide direct access to SAN storage, start your program by calling the VixDiskLib_ConnectEx() function, as described in "Advanced Transport APIs" on page 35.

Alphabetic Table of Functions

Function calls in the Virtual Disk API are listed alphabetically in Table 4-1.

Table 4-1. Virtual Disk API Functions

Function	Description
VixDiskLib_Attach	Attaches the child disk chain to the parent disk chain.
VixDiskLib_Cleanup	Removes leftover transports. See "Clean Up After Disconnect" on page 39.
VixDiskLib_Clone	Copies virtual disk to some destination, converting formats as appropriate.
VixDiskLib_Close	Closes an open virtual disk. See "Close a Local or Remote Disk" on page 30.
VixDiskLib_Connect	Connects to the virtual disk library to obtain services. See also ConnectEx.
VixDiskLib_ConnectEx	Connects to optimum transport. See "Connect to VMware vSphere" on page 37
VixDiskLib_Create	Creates a virtual disk according to specified parameters.
VixDiskLib_CreateChild	Creates a child disk (redo log or delta link) for a hosted virtual disk.
VixDiskLib_Defragment	Defragments the sectors of a virtual disk.
VixDiskLib_Disconnect	Disconnects from the library. See "Disconnect from Server" on page 35.
VixDiskLib_EndAccess	Notifies a host that it may again relocate a virtual machine. See page 38.
VixDiskLib_Exit	Releases all resources held by the library. See "Clean Up and Exit" on page 35.
VixDiskLib_FreeErrorText	Frees the message buffer allocated by GetErrorText.
VixDiskLib_FreeInfo	Frees the memory allocated by GetInfo.
VixDiskLib_GetErrorText	Returns the text description of a library error code.
VixDiskLib_GetInfo	Retrieves information about a virtual disk.
VixDiskLib_GetMetadataKeys	Retrieves all keys in the metadata of a virtual disk.
VixDiskLib_GetTransportMode	Gets current transport mode. See "Get Selected Transport Method" on page 38.
VixDiskLib_Grow	Increases size of an existing virtual disk.
VixDiskLib_Init	Initializes the old virtual disk library. Replaced by InitEx function.
VixDiskLib_InitEx	Initializes new virtual disk library. See "Initialize Virtual Disk API" on page 35.
VixDiskLib_ListTransportModes	Available transport modes. See "List Available Transport Methods" on page 37.
VixDiskLib_Open	Opens a virtual disk. See "Open a Local or Remote Disk" on page 30.
VixDiskLib_PrepareForAccess	Notifies a host to refrain from relocating a virtual machine. See page 38.
VixDiskLib_Read	Reads from an open virtual disk. See "Read Sectors From a Disk" on page 30.
VixDiskLib_ReadMetadata	Retrieves the value of a given key from disk metadata.
VixDiskLib_Rename	Changes the name of a virtual disk.
VixDiskLib_Shrink	Reclaims blocks of zeroes from the virtual disk.
VixDiskLib_SpaceNeededForClone	Computes the space required to clone a virtual disk, in bytes.
VixDiskLib_Unlink	Deletes the specified virtual disk.
VixDiskLib_Write	Writes to an open virtual disk. See "Write Sectors To a Disk" on page 30.
VixDiskLib_WriteMetadata	Updates virtual disk metadata with the given key/value pair.

Start Up

The VixDiskLib_Init() and VixDiskLib_Connect() functions must appear in all virtual disk programs. VixDiskLib_Init() has been superseded by VixDiskLib_InitEx().

Initialize the Library

VixDiskLib_Init() initializes the old virtual disk library. The arguments majorVersion and minorVersion represent the VDDK library's release number and dot-release number. The third, fourth, and fifth arguments specify log, warning, and panic handlers. DLLs and shared objects are located in libDir.

VixError vixError = VixDiskLib_Init(majorVer, minorVer, &logFunc, &warnFunc, &panicFunc, libDir);

You should call VixDiskLib_Init() only once per process because of internationalization restrictions, at the beginning of your program. You should call VixDiskLib_Exit() at the end of your program for cleanup. For multithreaded programs you should write your own logFunc because the default function is not thread safe.

In most cases you should replace VixDiskLib_Init() with VixDiskLib_InitEx(), which allows you to specify a configuration file. For information about InitEx, see "Initialize Virtual Disk API" on page 35.

Connect to a Workstation or Server

VixDiskLib_Connect() connects the library to either a local VMware host or a remote server. For hosted disk on the local system, provide null values for most connection parameters. For managed disk on an ESX/ESXi host, specify virtual machine name, ESX/ESXi host name, user name, password, and possibly port.

vixError = VixDiskLib_Connect(&cnxParams, &srcConnection)

You can opt to use the VixDiskLibSSPICreds connection parameter to enable Security Support Provider Interface (SSPI) authentication. SSPI provides the advantage of not storing passwords in configuration files in plain text or in the registry. In order to be able to use SSPI, the following conditions must be met:

- Connections must be made directly to a vSphere Server or a VirtualCenter Server version 2.5 or later.
- Applications and their connections must employ one of two user account arrangements. The connection must be established either:
 - Using the same user context with the same user name and password credentials on both the proxy and the vSphere Server or
 - Using a domain user. Attempts by applications to establish connections using the Local System account context will fail.
- User contexts must have administrator privileges on the proxy and have the VCB Backup User role assigned in vSphere or VirtualCenter.

If your setup meets all these conditions, you can enable SSPI authentication by setting USERNAME to __sspi__. For SSPI, the password must be set, but it is ignored. It can be set to "" (null).

Always call VixDiskLib_Disconnect() before the end of your program.

VMX Specification

On VMware platform products, .vmx is a text file (usually located in the same directory as virtual disk files) specifying virtual machine configuration. The Virtual Machine eXecutable (VMX) process is the user-space component (or "world") of a virtual machine. The virtual disk library connects to virtual machine storage through the VMX process.

When specifying connection parameters (see "Data Structures in Virtual Disk API" on page 21) the preferred syntax for vmxSpec is as follows:

Managed object reference of the virtual machine, an opaque object that you obtain programmatically using the PropertyCollector managed object:

```
moRef=<moref-of-vm>
```

The moRef of a virtual machine or disk snapshot on an ESX/ESXi host is likely different than the moRef of the same virtual machine or disk snapshot as managed by vCenter Server. Here are two example moRef specifications, one for ESXi and one for vCenter Server, both referring to the same snapshot:

```
moref=153
moref=271
```

Disk Operations

These functions create, open, read, write, query, and close virtual disk.

Create a New Hosted Disk

VixDiskLib_Create() locally creates a new virtual disk, after being connected to the host. In createParams, you must specify the disk type, adapter, hardware version, and capacity as a number of sectors. This function supports hosted disk. For managed disk, first create a hosted type virtual disk, then use VixDiskLib_Clone() to convert the virtual disk to managed disk.

```
vixError =
VixDiskLib_Create(appGlobals.connection, appGlobals.diskPath, &createParams, NULL, NULL);
```

VixDiskLib_Create() enforces a 4GB limit for virtual disks on FAT32 and FAT file systems, a 16TB - 54KB (hex FFFFFFF0000) limit on NTFS file systems, and a 2^64 - 1 limit (more than an exabyte) on ReFS and exFAT file systems. POSIX based file systems including NFS no longer have a 2GB file size limit. Although various checks are done to avoid creating impossibly large files, it becomes the customer's responsibility to cope with 2GB limits on NFSv2 or Linux kernel 2.4 (EFS).

Open a Local or Remote Disk

After the library connects to a workstation or server, VixDiskLib_Open() opens a virtual disk. With SAN or HotAdd transport, opening a remote disk for writing requires a pre-existing snapshot.

```
vixError =
VixDiskLib_Open(appGlobals.connection, appGlobals.diskPath, appGlobals.openFlags, &srcHandle);
The following flags modify the open instruction:
```

- VIXDISKLIB_FLAG_OPEN_UNBUFFERED Disable host disk caching.
- VIXDISKLIB_FLAG_OPEN_SINGLE_LINK Open the current link, not the entire chain (hosted disk only).
- VIXDISKLIB_FLAG_OPEN_READ_ONLY Open the virtual disk read-only.

Read Sectors From a Disk

VixDiskLib_Read() reads a range of sectors from an open virtual disk. You specify the beginning sector and the number of sectors. Sector size could vary, but is defined in <vixDiskLib.h> as 512 bytes because VMDK files have that sector size.

```
vixError = VixDiskLib_Read(srcHandle, i, j, buf);
```

Write Sectors To a Disk

VixDiskLib_Write() writes one or more sectors to an open virtual disk. This function expects the fourth parameter buf to be VIXDISKLIB_SECTOR_SIZE bytes long.

```
vixError = VixDiskLib_Write(newDisk.Handle(), i, j, buf);
```

Close a Local or Remote Disk

```
VixDiskLib_Close() closes an open virtual disk.
VixDiskLib_Close(srcHandle);
```

Get Information About a Disk

```
vixError = VixDiskLib_GetInfo(srcHandle, diskInfo);
```

VixDiskLib_GetInfo() gets data about an open virtual disk, allocating a filled-in VixDiskLibDiskInfo structure. Some of this information overlaps with metadata (see "Metadata Handling" on page 31).

Free Memory from Get Information

This function deallocates memory allocated by VixDiskLib_GetInfo(). Call it to avoid a memory leak. vixError = VixDiskLib_FreeInfo(diskInfo);

Error Handling

These functions enhance the usefulness of error messages.

Return Error Description Text

```
VixDiskLib_GetErrorText() returns the textual description of a numeric error code.
char* msg = VixDiskLib_GetErrorText(errCode, NULL);
```

Free Error Description Text

```
VixDiskLib_FreeErrorText() deallocates space associated with the error description text.
VixDiskLib_FreeErrorText(msq);
```

Metadata Handling

VMware provides a mechanism for virtual disk metadata, but it is seldom used.

Read Metadata Key from Disk

```
vixError = VixDiskLib_ReadMetadata(disk.Handle(), appGlobals.metaKey, &val[0], requiredLen, NULL); Retrieves the value of a given key from disk metadata. The metadata for a hosted VMDK is not as extensive as for managed disk on an ESX/ESXi host. Held in a mapping file, VMFS metadata might also contain information such as disk label, LUN or partition layout, number of links, file attributes, locks, and so forth. Metadata also describes encapsulation of raw disk mapping (RDM) storage, if applicable.
```

Get Metadata Table from Disk

VixDiskLib_GetMetadataKeys() retrieves all existing keys from the metadata of a virtual disk, but not the key values. Use this in conjunction with VixDiskLib_ReadMetadata().

```
vixError = VixDiskLib_GetMetadataKeys(disk.Handle(), &buf[0], requiredLen, NULL);
```

Here is an example of a simple metadata table. Uuid is the universally unique identifier for the virtual disk.

```
adapterType = buslogic
geometry.sectors = 32
geometry.heads = 64
geometry.cylinders = 100
uuid = 60 00 C2 93 7b a0 3a 03-9f 22 56 c5 29 93 b7 27
```

Write Metadata Table to Disk

VixDiskLib_WriteMetadata() updates virtual disk metadata with the given key-value pair. If the key-value pair is new, it gets added. If the key already exists, its value is updated. A key can be zeroed but not deleted.

```
vixError = VixDiskLib_WriteMetadata(disk.Handle(), appGlobals.metaKey, appGlobals.metaVal);
```

Cloning a Virtual Disk

Compute Space Needed for Clone

```
This function computes the space required (in bytes) to clone a virtual disk, after possible format conversion.

vixError = VixDiskLib_SpaceNeededForClone(child.Handle(), VIXDISKLIB_DISK_VMFS_FLAT, &spaceReq);
```



VixDiskLib_SpaceNeededForClone() might not give accurate results, or could return VIX_E_INVALID_ARG, when used with thin provisioned disk type VIXDISKLIB_DISK_VMFS_THIN.

Clone a Disk by Copying Data

This function copies data from one virtual disk to another, converting (disk type, size, hardware) as specified.

Disk Chaining and Redo Logs

In VMDK terminology, all the following are synonyms: child disk, redo log, and delta link. From the original parent disk, each child constitutes a redo log pointing back from the present state of the virtual disk, one step at a time, to the original. This pseudo equation represents the relative complexity of backups and snapshots:

backup image < child disk = redo log = delta link < snapshot

A backup image (such as on magnetic tape) is less than a child disk because the backup image is merely a data stream. A snapshot is more than a child disk because it also contains the virtual machine state, with pointers to associated file system states on VMDK.

Create Child from Parent Disk

Generally, you create the first child from the parent and create successive children from the latest one in the chain. The child VMDK tracks, in SPARSE type format, any disk sectors changed since inception, as illustrated in Figure 4-1.

Child3 vm.vmdk vm-001.vmdk

Changed Sectors Only

Child2 vm.vmdk vm-002.vmdk

Child1 vm.vmdk vm-001.vmdk

Parent vm.vmdk vm-flat.vmdk

Figure 4-1. Child Disks Created from Parent

VixDiskLib_CreateChild() creates a child disk (or redo log) for a hosted virtual disk:

After you create a child, it is an error to open the parent, or earlier children in the disk chain. In VMware products, the children's vm.vmdk files point to redo logs, rather than to the parent disk, vm-flat.vmdk in this example. If you must access the original parent, or earlier children in the chain, use VixDiskLib_Attach().

Attach Child to Parent Disk

VixDiskLib_Attach() attaches the child disk into its parent disk chain. Afterwards, the parent handle is invalid and the child handle represents the combined disk chain of redo logs.

vixError = VixDiskLib_Attach(parent.Handle(), child.Handle());

For example, suppose you want to access the older disk image recorded by Child1. Attach the handle of new Child1a to Child1, which provides Child1a's parent handle, as shown in Figure 4-2. It is now permissible to open, read, and write the Child1a virtual disk.

The parent-child disk chain is efficient in terms of storage space, because the child VMDK records only the sectors that changed since the last VixDiskLib_CreateChild(). The parent-child disk chain also provides a redo mechanism, permitting programmatic access to any generation with VixDiskLib_Attach().

Virtual Machine Writes Here vm-001.vmdk Child3 vm.vmdk vm.vmdk Child2 vm-002.vmdk Attach Child1a.vmdk Child1 vm.vmdk vm-001.vmdk vm-flat.vmdk Parent vm.vmdk Physical Disk

Figure 4-2. Child Disks Created from Parent

Opening in a Chain

With (parent) base disk B and children C0, C1, and C2, opening C2 gives you the contents of B + C0 + C1 + C2 (not really addition linked data sectors), while opening C1 gives you the contents of B + C0 + C1.

A better solution than recording base disks and which children are descended from which is changed block tracking, QueryChangedDiskAreas in the vSphere API. See "Algorithm for vSphere Backup" on page 39.

Administrative Disk Operations

These functions rename, grow, defragment, shrink, and remove virtual disk.

Rename an Existing Disk

VixDiskLib_Rename() changes the name of a virtual disk. Use this function only when the virtual machine is powered off.

vixError = VixDiskLib_Rename(oldGlobals.diskPath, newGlobals.diskPath);

Grow an Existing Local Disk

VixDiskLib_Grow() extends an existing virtual disk by adding sectors. This function supports hosted disk, but not managed disk.

vixError =
VixDiskLib_Grow(appGlobals.connection, appGlobals.diskPath, size, FALSE, GrowProgressFunc, NULL);

Defragment an Existing Disk

VixDiskLib_Defragment() defragments an existing virtual disk. Defragmentation is effective with SPARSE type files, but might not do anything with FLAT type. In either case, the function returns VIX_OK. This function supports hosted disk, but not managed disk.

vixError = VixDiskLib_Defragment(disk.Handle(), DefragProgressFunc, NULL);

Defragment consolidates data in the 2GB extents, moving data to lower-numbered extents, and is independent of defragmentation tools in the guest OS, such as **Disk > Properties > Tools > Defragmentation** in Windows, or the **defrag** command for the Linux Ext2 file system.

VMware recommends defragmentation from the inside out: first within the virtual machine, then using this function or a VMware defragmentation tool, and finally within the host operating system.

Shrink an Existing Local Disk

VixDiskLib_Shrink() reclaims unused space in an existing virtual disk, unused space being recognized as blocks of zeroes. This is more effective (gains more space) with SPARSE type files than with pre-allocated FLAT type, although FLAT files might shrink by a small amount. In either case, the function returns VIX_OK. This function supports hosted disk, but not managed disk.

```
vixError = VixDiskLib_Shrink(disk.Handle(), ShrinkProgressFunc, NULL);
```

In VMware system utilities, "prepare" zeros out unused blocks in the VMDK so "shrink" can reclaim them. In the API, use VixDiskLib_Write() to zero out unused blocks, and VixDiskLib_Shrink() to reclaim space. Shrink does not change the virtual disk capacity, but it makes more space available.

Unlink Extents to Remove Disk

VixDiskLib_Unlink() deletes all extents of the specified virtual disk, which unlinks (removes) the disk data. This is similar to the remove or erase command in a command tool.

vixError = VixDiskLib_Unlink(appGlobals.connection, appGlobals.diskPath);

Combine Links for a Disk

VixDiskLib_Combine() combines links for the disk specified by diskHandle. The combining process begins with the last link in the chain specified by the linkOffsetFromBottom and continues for the number of links specified by numLinksToCombine. If the function succeeds, the function returns VIX_OK. Otherwise, the appropriate VIX error code is returned. This function supports hosted disk, but not managed disk.

vixError = VixDiskLib_Combine(VixDiskLibHandle diskHandle, uint32 linkOffsetFromBottom, uint32 numLinksToCombine, VixDiskLibProgressFunc progressFunc, void *progressCallbackData);

Change the Parent for a Disk

VixDiskLib_Reparent() changes the parent for the disk path to the given string value. The VMDK file name must be an absolute path. The parentHint could be the file name of the parent disk. If the function succeeds, the function returns VIX_OK. Otherwise, the appropriate VIX error code is returned. This function is available only for hosted disk in new releases.

```
vixError =
VixDiskLib_Reparent(VixDiskLibConnection connection, const char *path, const char *parentHint);
```

Shut Down

All Virtual Disk API applications should call these functions at end of program.

Disconnect from Server

```
VixDiskLib_Disconnect() breaks an existing connection.
```

VixDiskLib_Disconnect(srcConnection);

Clean Up and Exit

VixDiskLib_Exit() cleans up the library before exit.

VixDiskLib_Exit();

Advanced Transport APIs

For managed disk, the first release of VDDK required network access ESX/ESXi host (LAN or NBD transport). With VDDK 1.1 programs can access virtual disks directly on a storage device, LAN-free. Direct SAN access increases I/O performance. To select the most efficient transport method, a set of APIs is available, including:

- VixDiskLib_InitEx() Initializes the advanced transport library. You must specify the library location.
 Replaces VixDiskLib_Init() in your application.
- VixDiskLib_ListTransportModes() Lists transport modes that the virtual disk library supports.
- VixDiskLib_ConnectEx() Establishes a connection using the best transport mode available, or one you select, to access a given machine's virtual disk. Currently it does not check validity of transport type. Replaces VixDiskLib_Connect() in your application.

Initialize Virtual Disk API

Replacing VixDiskLib_Init(), VixDiskLib_InitEx() initializes new releases of the library, Parameters are similar, except you should specify an actual libDir, and the new configFile parameter. For multithreaded programming, you should write your own logFunc, because the default logging function is not thread-safe. On Windows, *libDir could be C:\Program Files\VMware\VMware Virtual Disk Development Kit. On Linux, *libDir is probably /usr/lib/vmware-vix-disklib.

Logged messages appear by default in a temporary folder or log directory, for VDDK and for many other VMware products. See "Location of Log Files" on page 37.

The currently supported entries in the configFile are listed below. The correct way to specify a configuration is name=value. See Example 4-1 for a sample configuration file.

- tmpDirectory = "<TempDirectoryForLogging>"
- vixDiskLib.transport.LogLevel Overrides the default logging for vixDiskLib transport functions (not including NFC). The default value is 6. The range is 0 to 6, where 6 is most verbose and 0 is quiet.

The following NFC related options override the default numbers provided to the various NFC functions. Timeout values are stored in a 32-bit field, so the maximum timeout you may specify is 2G (2,147,483,648).

- vixDiskLib.nfc.AcceptTimeoutMs Overrides the default value (default is no timeout, or 0) for accept operations. This timeout is specifed in milliseconds. Applies to NBD/NBDSSL ibkt not SAN or HotAdd
- vixDiskLib.nfc.RequestTimeoutMs Overrides the default value (default is no timeout, or 0) for NFC request operations. This timeout is specifed in milliseconds.
- vixDiskLib.nfc.ReadTimeoutMs Overrides the default value (default is no timeout, or 0) for NFC read operations. This timeout is specifed in milliseconds.
- vixDiskLib.nfc.WriteTimeoutMs Overrides the default value (default is no timeout, or 0) for NFC write operations. This timeout is specifed in milliseconds.
- vixDiskLib.nfcFssrvr.TimeoutMs Overrides the default value (default is 0, indefinite waiting) for NFC file system operations. This timeout is specifed in milliseconds. If you specify a value, then a timeout occurs if the file system is idle for the indicated period of time. The hazard of using the default value is that in a rare case of catastrophic communications failure, the file system will remain locked.
- vixDiskLib.nfcFssrvrWrite.TimeoutMs Overrides the default value (default is no timeout) for NFC file system write operations. The timeout is specifed in milliseconds. If you specify a value, it will time out when a write operation fails to complete in the specified time interval.
- vixDiskLib.nfc.LogLevel Overrides the default logging level for NFC operations. The default value is 1, indicating error messages only. The meaning of values is listed below. Each level includes all of the messages generated by (lower numbered) levels above. This is the final NFC setting.
 - 0 = None
 - 1 = Error
 - 2 = Warning
 - 3 = Info
 - 4 = Debug

LogLevel and the six NFC timeout settings affect only NBD/NBDSSL. They do not affect SAN and HotAdd transport. The NFC timeouts are applied to each disk handle.

- vixDiskLib.disklib.EnableCache Caching by vixDiskLib is off (0) by default. Setting 1 turns it on. Caching increases performance when information is read repeatedly, or accessed randomly. In backup applications, information is usually accessed sequentially, and caching can actually reduce performance. Moreover with caching, backup applications risk getting stale information if a disk sector is rewritten (by another application) before the cache is refreshed.
- vixDiskLib.linuxSSL.verifyCertificates Whether to check for SSL thumbprint when connecting to a Linux virtual machine. Possible values are 0 for Off and 1 for On. Default is 0.

Example 4-1. Sample InitEx configuration file

```
tmpDirectory="/usr/local/vendorapp/var/vmware/temp"
# log level 0 to 6 for quiet ranging to verbose
vixDiskLib.transport.LogLevel=2
# disable caching to disk
vixDiskLib.disklib.EnableCache=0
# whether to check SSL thumbprint on Linux
vixDiskLib.linuxSSL.verifyCertificates=0
# network file copy options
vixDiskLib.nfc.AcceptTimeoutMs=180000
vixDiskLib.nfc.RequestTimeoutMs=180000
vixDiskLib.nfc.ReadTimeoutsMs=60000
vixDiskLib.nfc.WriteTimeoutsMs=600000
vixDiskLib.nfcFssrvr.TimeoutMs=0
vixDiskLib.nfcFssrvrWrite.TimeoutMs=0
# nfc.LogLevel (0 = none, 1 = Error, 2 = Warning, 3 = Info, 4 = Debug)
vixDiskLib.nfc.LoaLevel=2
```

The NFC timeouts shown in Example 4-1 are the default values on ESXi 5.0 and ESXi 5.1 hosts.

Location of Log Files

On Linux, log messages appear under /var/log by default. On Windows, they appear in a temporary folder, whose location can change from time to time. Early Windows systems used C:\Windows\Temp. Windows XP and Server 2003 use C:\Documents and Settings\cuser>\Local Settings\Temp\vmware-<user>. Vista, Windows 7, and Server 2008 use C:\Users\cuser>AppData\Local\Temp\vmware-<user>.

On all versions of Windows the user's TEMP environment setting overrides the default Temp folder location. Temporary is something of a misnomer because files are never deleted from the Temp folder, unless the user or an application deletes them. If the TEMP or Windows default Temp folder is not found, VDDK (and other VMware software) have a fallback to <localAppDir>\Temp.

Alternatively, your software can set a custom temporary directory, as shown in Example 4-1.

List Available Transport Methods

The VixDiskLib_ListTransportModes() function returns the currently supported transport methods as a colon-separated string value, currently "file:san:hotadd:nbd" where nbd indicates LAN transport. When available, SSL encrypted NBD transport is shown as nbdssl.

```
printf("Transport methods: %s\n", VixDiskLib_ListTransportModes());
```

The default transport priority over the network is san:hotadd:nbdssl:nbd assuming all are available.

SAN Mode on Linux Uses Direct Mode

With SAN transport on Linux, read and write operations are performed in "direct" mode (O_DIRECT), meaning that no read or write buffering is done. Direct mode prevents other processes from accessing the latest data, and avoids loss of information if the process dies before committing its write buffers. In direct mode, the most time efficient performance can be achieved if applications follow these guidelines when performing reads and writes:

- The offset into the SAN where the operation is performed should be an even multiple of page size, 4096.
- The buffer used for data transfer should be aligned on a page boundary.
- The transfer length should be an even multiple of the page size.

Connect to VMware vSphere

VixDiskLib_ConnectEx() connects the library to managed disk on a remote ESX/ESXi host or through VMware vCenter Server. For hosted disk on the local system, it works the same as VixDiskLib_Connect(). VixDiskLib_ConnectEx() takes three additional parameters:

- Boolean indicating TRUE for read-only access, often faster, or FALSE for read/write access. If connecting read-only, later calls to VixDiskLib_Open() are always read-only regardless of the openFlags setting.
- Managed object reference (MoRef) of the snapshot to access with this connection. This is required for most transport methods (SAN, HotAdd, NBDSSL) and to access a powered-on virtual machine. You must also specify the associated vmxSpec property in connectParams. When connecting directly to an ESX/ESXi host, provide the ESX/ESXi MoRef. When connecting through vCenter Server, pass the vSphere MoRef, which differs.
- Preferred transport method, or NULL to accept defaults. If you specify SAN as the only transport, and SAN is not available, VixDiskLib_ConnectEx() does not fail, but the first VixDiskLib_Open() call will fail.

```
VixDiskLibConnectParams cnxParams = {0};
if (appGlobals.isRemote) {
    cnxParams.vmName = vmxSpec;
    cnxParams.serverName = hostName;
    cnxParams.credType = VIXDISKLIB_CRED_UID;
    cnxParams.creds.uid.userName = userName;
    cnxParams.creds.uid.password = password;
    cnxParams.port = port;
}
```

Even when a program calls VixDiskLib_ConnectEx() with NULL parameter to accept the default transport mode, SAN is selected as the preferred mode, if SAN storage is available from the ESX/ESXi host. Then if the program opens a virtual disk on local storage, subsequent writes will fail. In this case, the program should explicitly pass nbd or nbdssl as the preferred transport mode.

In the connection parameters cnxParams, the vmxSpec managed object reference would be different on an ESX/ESXi host than on the vCenter Server:

```
vmxSpec = "moid=23498";
vmxSpec = "moid=898273";
```

The port should be the one on which vCenter Server listens for API queries. Specifying a null port allows the library to select the default communications port. It is likely to be 443 (HTTPS) or maybe 902 (VIX automation). This is the port for data copying, not the port for SOAP requests.

Get Selected Transport Method

The VixDiskLib_GetTransportMode() function returns the transport method selected for diskHandle.

```
printf("Selected transport method: %s\n", VixDiskLib_GetTransportMode(diskHandle));
```

Prepare For Access and End Access

The VixDiskLib_PrepareForAccess() function notifies a vCenter-managed host that a virtual machine's disks are being opened, probably for backup, so the host should postpone virtual machine operations that might interfere with virtual disk access. Call this function before creating a snapshot on a virtual machine. Internally, this function disables the vSphere API method RelocateVM_Task.

```
vixError = VixDiskLib_PrepareForAccess(&cnxParams, "vmName");
```

The connection parameters must indicate one virtual machine only. When opening a managed disk, provide valid credentials for the vCenter Server that manages the ESXi host with the disk. The second parameter is currently just for tracking purposes, and could be the virtual machine name or the name of your application. If you run VixDiskLib_PrepareForAccess() directly on an ESXi host, the system throws an error saying "VDDK: HostAgent is not a VirtualCenter, cannot disable sVmotion."

Every VixDiskLib_PrepareForAccess() call should have a matching VixDiskLib_EndAccess() call.

The VixDiskLib_EndAccess() function notifies the host that a virtual machine's disks have been closed, so operations that rely on the virtual disks to be closed, such as vMotion, can now be allowed. Call this function after closing all the virtual disks, and after deleting the virtual machine snapshot. Normally this function is called after previously calling VixDiskLib_PrepareForAccess, but you can call it to clean up after a crash. Internally, this function re-enables the vSphere API method RelocateVM_Task.

```
vixError = VixDiskLib_EndAccess(&cnxParams, "vmName");
```

Here is a code snippet showing use of PrepareForAccess in a backup program that waits up to 10 minutes for Storage vMotion to finish. Regular vMotion would finish much faster than that.

```
if (appGlobals.vmxSpec != NULL) {
   int i;
   retry:
    vixError = VixDiskLib_PrepareForAccess(&cnxParams, "VMname");
   for (i = 0; i < 10; i++) {
      if (vixError != VIX_OK) { // no specific error code for vMotion-in-progress sleep(60);
      goto retry;
    }
  }
}</pre>
```

Clean Up After Disconnect

If virtual machine state was not cleaned up correctly after connection shut down, VixDiskLib_Cleanup() removes extra state for each virtual machine. Its three parameters specify connection, and pass back the number of virtual machines cleaned up, and the number remaining to be cleaned up.

```
int numCleanedUp, numRemaining;
VixError vixError = VixDiskLib_Cleanup(&cnxParams, &numCleanedUp, &numRemaining);
```

Updating Applications for Advanced Transport

To update your applications for advanced transport with managed disk, follow these steps:

- 1 Find all instances of VixDiskLib_Connect() and change them to VixDiskLib_ConnectEx().
 The vixDiskLib sample program was extended to use VixDiskLib_ConnectEx() with the -mod option.
- 2 Likewise, change VixDiskLib_Init() to VixDiskLib_InitEx() and be sure to call it only once.
- 3 Disable virtual machine relocation with the VixDiskLib_PrepareForAccess() call.
- 4 Add parameters in the middle:
 - a TRUE for high performance read-only access, FALSE for read/write access.
 - b Snapshot moRef, if applicable.
 - c NULL to accept transport method defaults (recommended).
- 5 Re-enable virtual machine relocation with the VixDiskLib_EndAccess() call.
- 6 Find VixDiskLib_Disconnect() near the end of program, and for safety add a VixDiskLib_Cleanup() call immediately afterwards.
- 7 Compile with the new flexible-transport-enabled version of VixDiskLib.

The advanced transport functions are useful for backing up or restoring data on virtual disks managed by VMware vSphere. Backup is based on the snapshot mechanism, which provides a data view at a certain point in time, and allows access to quiescent data on the parent disk while the child disk continues changing.

Algorithm for vSphere Backup

A typical backup application follows this algorithm:

- Preferably through vCenter Server, contact the ESX/ESXi host and discover the target virtual machine.
- Ask the ESX/ESXi host to take a snapshot of the target virtual machine.
- Using the vSphere API (PropertyCollector), capture configuration (VirtualMachineConfigInfo) and changed block information (with queryChangedDiskAreas). Save these for later.
- Using advanced transport functions and VixDiskLib, access the snapshot and save the data in it.
 If Changed Block Tracking is enabled, the snapshot contains only incremental backup data.
- Ask the ESX/ESXi host to delete the backup snapshot.

A typical back-in-time disaster recovery or file-based restore follows this algorithm:

- Preferably through VMware vCenter, contact the ESX/ESXi host containing the target virtual machine.
- Ask the ESX/ESXi host to halt and power off the target virtual machine.
- Using advanced transport functions, restore a snapshot from saved backup data.
- For disaster recovery to a previous point in time, have the virtual machine revert to the restored snapshot. For file-based restore, mount the snapshot and restore requested files.

Chapter 7, "Designing vSphere Backup Solutions," on page 57 presents these algorithms in more detail and includes code samples.

Best Practices for Backup

See "Tips and Best Practices" on page 81.

Backup and Recovery Example

The VMware vSphere API method queryChangedDiskArea returns a list of disk sectors that changed between an existing snapshot, and some previous time identified by a change ID.

The queryChangedDiskAreas method takes four arguments, including a snapshot reference and a change ID. It returns a list of disk sectors that changed between the time indicated by the change ID and the time of the snapshot. If you specify change ID as * (star), queryChangedDiskAreas returns a list of allocated disk sectors so your backup can skip the unallocated sectors of sparse virtual disk.

Suppose that you create an initial backup at time *T1*. Later at time *T2* you take an incremental backup, and another incremental backup at time *T3*. (You could use differential backups instead of incremental backups, which would trade off greater backup time and bandwidth for shorter restore time.)

For the full backup at time T1:

- 1 Keep a record of the virtual machine configuration, VirtualMachineConfigInfo.
- 2 Create a snapshot of the virtual machine, naming it **snapshot_T1**.
- 3 Obtain the change ID for each virtual disk in the snapshot, **changeId_T1** (per VMDK).
- 4 Back up the sectors returned by queryChangedDiskAreas(..."*"), avoiding unallocated disk.
- 5 Delete **snapshot_T1**, keeping a record of **changeId_T1** along with lots of backed-up data.

For the incremental backup at time T2:

- 1 Create a snapshot of the virtual machine, naming it **snapshot_T2**.
- 2 Obtain the change ID for each virtual disk in the snapshot, **changeId_T2** (per VMDK).
- 3 Back up the sectors returned by queryChangedDiskAreas(snapshot_T2,... changeId_T1).
- 4 Delete **snapshot_T2**, keeping a record of **changeId_T2** along with backed-up data.

For the incremental backup at time T3:

- 1 Create a snapshot of the virtual machine, naming it snapshot_T3.
 At time T3 you can no longer obtain a list of changes between T1 and T2.
- 2 Obtain the change ID for each virtual disk in the snapshot, changeId_T3 (per VMDK).
- Back up the sectors returned by queryChangedDiskAreas(snapshot_T3,... changeId_T2).

 A differential backup could be done with queryChangedDiskAreas(snapshot_T3,... changeId_T1).
- 4 Delete **snapshot_T3**, keeping a record of **changeId_T3** along with backed-up data.

For a disaster recovery at time T4:

- 1 Create a new virtual machine with no guest operating system installed, using configuration parameters you previously saved from VirtualMachineConfigInfo. You do not need to format the virtual disks, because restored data includes formatting information.
- 2 Restore data from the backup at time T3. Keep track of which disk sectors you restore.
- 3 Restore data from the incremental backup at time T2, skipping any sectors already recovered. With differential backup, you can skip copying the T2 backup.
- 4 Restore data from the full backup at time T1, skipping any sectors already recovered. The reason for working backwards is to get the newest data while avoiding unnecessary data copying.
- 5 Power on the recovered virtual machine.

IMPORTANT When programs open remote disk with SAN transport mode, they can write to the base disk, but they cannot write to a snapshot (redo log). Opening and writing snapshots is supported only for hosted disk.

Licensing of Advanced Transports

The advanced transport license for VDDK includes all transport types.

Multithreading Considerations

In multithreaded programs, disk requests should be serialized by the client program. Disk handles are not bound to a thread and may be used across threads. You can open a disk in one thread and use its handle in another thread, provided you serialize disk access. Alternatively you can use a designated open-close thread, as shown in the workaround below.

Multiple Threads and VixDiskLib

VDDK supports concurrent I/O to multiple virtual disks, with certain limitations:

- VixDiskLib_InitEx() or VixDiskLib_Init() should be called only once per process. VMware recommends that you call them from the main thread.
- In the VixDiskLib_InitEx() or VixDiskLib_Init() function call, do not specify logging callbacks as NULL. This causes VixDiskLib to provide its default logging functions, which are not thread safe. If you are using VDDK in a multithreaded environment, you must provide your own thread-safe log functions.
- When you call VixDiskLib_Open() and VixDiskLib_Close(), VDDK initializes and uninitializes a number of libraries. Some of these libraries fail to work if called from multiple threads. For example, the following call sequence does not work:

The workaround is to use one designated thread to do all opens and closes, and to have other worker threads doing reads and writes. This diagram shows concurrent reads on two separate disk handles. Concurrent reads on the same disk handles are not allowed.

```
Open/Close Thread:

VixDiskLib_Open ..... VixDiskLib_Open ..... VixDiskLib_Close ..... VixDiskLib_Close ..... (handle1) (handle2) (handle1) (handle2)

I/O Thread 1:
(owns handle1) VixDiskLib_Read ... VixDiskLib_Read ...

I/O Thread 2:
(owns handle2) VixDiskLib_Read ... VixDiskLib_Read ... VixDiskLib_Read ...
```

Capabilities of Library Calls

This section describes limitations, if any.

Support for Managed Disk

Some operations are not supported:

- For VixDiskLib_Connect() to open a managed disk connection, you must provide valid vSphere access credentials. On ESX/ESXi hosts, VixDiskLib_Open() cannot open a single link in a disk chain.
- For VixDiskLib_Create() to create a managed disk on an ESX/ESXi host, first create a hosted type disk, then use VixDiskLib_Clone() to convert the hosted virtual disk to managed virtual disk.
- Until ESXi 5.1, the HotAdd transport was available only with vSphere Enterprise Edition and higher.
- VixDiskLib_Defragment() can defragment hosted disks only.
- VixDiskLib_Grow() can grow hosted disks only.

■ VixDiskLib_Unlink() can delete hosted disks only.

Support for Hosted Disk

Most everything (except advanced transport) is supported, except.

Prepare for access and end access.

Virtual Disk API Sample Code

5

This chapter discusses the VDDK sample program, in the following sections:

- "Compiling the Sample Program" on page 43
- "Usage Message" on page 44
- "Walk-Through of Sample Program" on page 45

Compiling the Sample Program

The sample program is written in C++, although the Virtual Disk API also supports C.

For compilation to succeed, the correct DLLs or shared objects must be loaded. You can ensure the success of dynamic loading in a variety of ways.

- Set the path inside the VDDK program.
- Set the path for the shell being used in Linux or in Visual Studio for Windows.

 For a default installation, the Linux path is /usr/share/doc/vmware-vix-disklib/sample.
- In Windows, set the Path element in the System Variables.

To do this in Windows XP, right-click **Computer > Properties > Advanced > Environment Variables**, select **Path** in the **System Variables** lower list, click **Edit**, and add the path of the VDDK bin directory.

In Windows 7, right-click **Computer > Properties > Advanced System Settings > Environment Variables**, select Path in the **System Variables** list, click **Edit**, and add the path of the VDDK bin directory.

Note that VDDK loads DLLs by relative path rather than absolute path, so conflicting versions of the DLLs could cause problems.

Visual C++ on Windows

To compile the program, find the sample source vixDiskLibSample.cpp at this location:

C:\Program Files\VMware\VMware Virtual Disk Development Kit\doc\sample\

Double-click the vcproj file, possibly convert format to a newer version, and choose **Build > Build Solution**.

To execute the compiled program, choose **Debug > Start Without Debugging**, or type this in a command prompt after changing to the doc\sample location given above:

Debug\vixdisklibsample.exe

SLN and VCPROJ Files

The Visual Studio solution file vixDiskLibSample.sln and project file vixDiskLibSample.vcproj are included in the sample directory.

C++ on Linux Systems

Find the sample source in this directory:

```
/usr/share/doc/vmware-vix-disklib/samples/diskLib
```

You can copy vixDiskLibSample.cpp and its Makefile to a directory where you have write permission, or switch user to root. On some Linux systems you need to add #include statements for <stdio.h> and <string.h> after the #else clause on line 15. Type the make command to compile. Run the application:

```
make
./vix-disklib-sample
```

NOTE If this fails, edit /etc/ld.so.conf and run ldconfig as root or change your LD_LIBRARY_PATH environment to include the library installation path, /usr/lib/vmware-vix-disklib/lib32 (or lib64).

Makefile

The Makefile fetches any packages that are required for compilation but are not installed.

Library Files Required

The virtual disk library comes with dynamic libraries, or shared objects on Linux, to simplify the delivery of third-party and open source components.

Windows requires the lib/vixDiskLib.lib file for linking, and the bin/*.dll files at runtime.

Linux uses .so files for both linking and running.

Usage Message

Running the sample application without arguments produces the following usage message:

```
Usage: vixdisklibsample command [options] diskPath
commands:
-create : creates a sparse virtual disk with capacity specified by -cap
-redo parentPath : creates a redo log 'diskPath' for base disk 'parentPath'
-info : displays information for specified virtual disk
-dump: dumps the contents of specified range of sectors in hexadecimal
-fill : fills specified range of sectors with byte value specified by -val
-wmeta key value : writes (key, value) entry into disk's metadata table
-rmeta key: displays the value of the specified metada entry
-meta : dumps all entries of the disk's metadata
-clone sourcePath : clone source vmdk possibly to a remote site
-readbench blocksize: do read benchmark on a disk using the specified I/O block size in sectors
-writebench blocksize: do write benchmark on disk using the specified I/O block size in sectors
options:
 -adapter [ide|scsi] : bus adapter type for 'create' option (default='scsi')
-start n : start sector for 'dump/fill' options (default=0)
-count n : number of sectors for 'dump/fill' options (default=1)
-val byte: byte value to fill with for 'write' option (default=255)
-cap megabytes : capacity in MB for -create option (default=100)
-single : open file as single disk link (default=open entire chain)
-multithread n: start n threads and copy the file to n new files
-host hostname: hostname / IP addresss (ESX 3.x or VC 2.x)
-user userid : user name on host (default = root)
-password password : password on host
 -port port : port to use to connect to host (default = 902)
-vm vmPath=/path/to/vm : inventory path to vm that owns the virtual disk
-libdir dir : Directory containing vixDiskLibPlugin library
-initex configfile : Use VixDiskLib_InitEx
-ssmoref moref : Managed object reference of VM snapshot
-mode mode : Mode string to pass into VixDiskLib_ConnectEx
-thumb string : Provides a SSL thumbprint string for validation
```

The -thumb option is a new security-related feature in the VDDK 5.1 release. See "SSL Certificate Thumbprint" on page 48.

The sample program's -single option, which opens a single link instead of the entire disk chain, is supported for (local) hosted disk, but not for (remote) managed disk.

To connect to an ESXi host with the sample program, you must specify the options -host, -user, -password, and provide a diskPath on the ESXi host's datastore. For example:

```
vix-diskLib-sample -info -host esx5 -user root -password secret "[datastore1] <VM>/<VM>.vmdk"
```

To connect to vCenter Server, you must also specify the options —libdir and —vm. Programs need libdir so the DiskLibPlugin can connect with vCenter Server, which must locate the VM. For example:

```
vix-diskLib-sample -info -host vc5 -user Administrator -password secret
    -libdir <pluginDir> -vm vmPath=<path/to/VM> "[<partition>] <VM>/<VM>.vmdk"
```

The vmPath is formulated in vSphere Client by starting at vCenter and inserting /vm/ before the VM name. The diskPath is ascertained by clicking Edit Settings > Hard Disk and copying the Disk File name.

To connect using an advanced transport, for example to virtual machine disk on SAN storage, you must also specify the options <code>-mode</code> and <code>-ssmoref</code>. The transport mode and managed object reference (of a snapshot) are required for <code>VixDiskLib_ConnectEx()</code>. To find the <code>ssmoref</code>, log in to the managed object browser for the vCenter Server, and click <code>content > rootFolder > Datacenter > datastore > vm > snapshot</code>. A snapshot must exist, because it is a bad idea to open the base disk of a powered-on VM.

On 64-bit Linux, <pluginDir> would end in /lib64 not /lib32. On Windows, the VDDK package installs diskLibPlugin.dll in the \bin folder, not the \lib folder, so change <pluginDir> accordingly.

Walk-Through of Sample Program

The sample program is the same for Windows as for Linux, with #ifdef blocks for Win32.

Include Files

Windows dynamic link library (DLL) declarations are in process.h, while Linux shared object (.so) declarations are in dlfcn.h. Windows offers the tchar.h extension for Unicode generic text mappings, not readily available in Linux.

Definitions and Structures

The sample program uses twelve bitwise shift operations (1 << 11) to track its available commands and the multithread option. The Virtual Disk API has about 30 library functions, some for initialization and cleanup. The following library functions are not demonstrated in the sample program:

- VixDiskLib_Rename()
- VixDiskLib_Defragment()
- VixDiskLib_Grow()
- VixDiskLib_Shrink()
- VixDiskLib_Unlink()
- VixDiskLib_Attach()

The sample program transmits state in the appGlobals structure.

Dynamic Loading

The #ifdef DYNAMIC_LOADING block is long, starting on line 97 and ending at line 339. This block contains function definitions for dynamic loading. It also contains the LoadOneFunc() procedure to obtain any requested function from the dynamic library and the DynLoadDiskLib() procedure to bind it. This demonstration feature could also be called "runtime loading" to distinguish it from dynamic linking.

To try the program with runtime loading enabled on Linux, add –DDYNAMIC_LOADING after g++ in the Makefile and recompile. On Windows, define DYNAMIC_LOADING in the project.

Wrapper Classes

Below the dynamic loading block are two wrapper classes, one for error codes and descriptive text, and the other for the connection handle to disk.

The error wrapper appears in catch and throw statements to simplify error handling across functions.

Wrapper class VixDisk is a clean way to open and close connections to disk. The only time that library functions VixDiskLib_Open() and VixDiskLib_Close() appear elsewhere, aside from dynamic loading, is in the CopyThread() function near the end of the sample program.

Command Functions

The print-usage message appears next, with output partially shown in "Usage Message" on page 44.

Next comes the main() function, which sets defaults and parses command-line arguments to determine the operation and possibly set options to change defaults. Dynamic loading occurs, if defined. Notice the all-zero initialization of the VixDiskLibConnectParams declared structure:

```
VixDiskLibConnectParams cnxParams = {0};
```

For connections to an ESX/ESXi host, credentials including user name and password must be correctly supplied in the <code>-user</code> and <code>-password</code> command-line arguments. Both the <code>-host</code> name of the ESX/ESXi host and its <code>-vm</code> inventory path (<code>vmxSpec</code>) must be supplied. When set, these values populate the <code>cnxParams</code> structure. Initialize all parameters, especially <code>vmxSpec</code>, or else the connection might behave unexpectedly.

A call to VixDiskLib_Init() initializes the library. In a production application, you can supply appropriate log, warn, and panic functions as parameters, in place of NULL.

A call to VixDiskLib_Connect() creates a connection to disk. If host cnxParams.serverName is null, as it is without the -host argument, a connection is made to hosted disk on the local host. Otherwise a connection is made to managed disk on the remote host. With -ssmoref argument, advanced transport is used.

Next, an appropriate function is called for the requested operation, followed by error information if applicable. Finally, the main() function closes the library connection to disk and exits.

DoInfo()

This procedure calls VixDiskLib_GetInfo() for information about the virtual disk, displays results, and calls VixDiskLib_FreeInfo() to reclaim memory. The parameter disk.Handle() comes from the VixDisk wrapper class discussed in "Wrapper Classes" on page 46.

In this example, the sample program connects to an ESX/ESXi host named esx5 and displays virtual disk information for a Red Hat Enterprise Linux client. For an ESX/ESXi host, path to disk is often something like [datastore1] followed by the virtual machine name and the VMDK filename.

```
vix-diskLib-sample -info -host esx5 -user root -password secret "[datastore1] RHEL6/RHEL6.vmdk"
Disk "[datastore1] RHEL6/RHEL6.vmdk" is open using transport mode "nbd".
capacity = 4194304 sectors
number of links = 1
adapter type = LsiLogic SCSI
BIOS geometry = 0/0/0
physical geometry = 261/255/63
Transport modes supported by vixDiskLib: file:nbdssl:nbd
```

If you multiply physical geometry numbers (261 cylinders * 255 heads per cylinder * 63 sectors per head) the result is a capacity of 4192965 sectors, although the first line says 4194304. A small discrepancy is possible due to rounding. In general, you get at least the capacity that you requested. The number of links specifies the separation of a child from its original parent in the disk chain (redo logs), starting at one. The parent has one link, its child has two links, the grandchild has three links, and so forth.

DoCreate()

This procedure calls VixDiskLib_Create() to allocate virtual disk. Adapter type is SCSI unless specified as IDE on the command line. Size is 100MB, unless set by -cap on the command line. Because the sector size is 512 bytes, the code multiplies appGlobals.mbsize by 2048 instead of 1024. Type is always monolithic sparse and Workstation 5. In a production application, progressFunc and callback data can be defined rather than NULL. Type these commands to create a sample VMDK file (the first line is for Linux only):

```
export LD_LIBRARY_PATH=/usr/lib/vmware-vix-disklib/lib32
vix-disklib-sample -create sample.vmdk
```

As a VMDK file, monolithic sparse (growable in a single file) virtual disk is initially 65536 bytes (2^16) in size, including overhead. The first time you write to this type of virtual disk, as with DoFill() below, the VMDK expands to 131075 bytes (2^17), where it remains until more space is needed. You can verify file contents with the –dump option.

DoRedo()

This procedure calls VixDiskLib_CreateChild() to establish a redo log. A child disk records disk sectors that changed since the parent disk or previous child. Children can be chained as a set of redo logs.

The sample program does not demonstrate use of VixDiskLib_Attach(), which you can use to access a link in the disk chain. VixDiskLib_CreateChild() establishes a redo log, with the child replacing the parent for read/write access. Given a pre-existing disk chain, VixDiskLib_Attach() creates a related child, or a cousin you might say, that is linked into some generation of the disk chain.

For a diagram of the attach operation, see Figure 4-2, "Child Disks Created from Parent," on page 33.

Write by DoFill()

This procedure calls VixDiskLib_Write() to fill a disk sector with ones (byte value FF) unless otherwise specified by -val on the command line. The default is to fill only the first sector, but this can be changed with options -start and -count on the command line.

DoReadMetadata()

This procedure calls VixDiskLib_ReadMetadata() to serve the -rmeta command-line option. For example, type this command to obtain the universally unique identifier:

vix-disklib-sample -rmeta uuid sample.vmdk

DoWriteMetadata()

This procedure calls VixDiskLib_WriteMetadata() to serve the -wmeta command-line option. For example, you can change the tools version from 1 to 2 as follows:

vix-disklib-sample -wmeta toolsVersion 2 sample.vmdk

DoDumpMetadata()

This procedure calls VixDiskLib_GetMetadataKeys() then VixDiskLib_ReadMetadata() to serve the -meta command-line option. Two read-metadata calls are needed for each key: one to determine length of the value string and another to fill in the value. See "Get Metadata Table from Disk" on page 31.

In the following example, the sample program connects to an ESX/ESXi host named esx3 and displays the metadata of the Red Hat Enterprise Linux client's virtual disk. For an ESX/ESXi host, path to disk might be [storage1] followed by the virtual machine name and the VMDK filename.

```
vix-diskLib-sample -meta -host esx3 -user admin -password secret "[storage1]RHEL5/RHEL5.vmdk"
geometry.sectors = 63
geometry.heads = 255
geometry.cylinders = 522
adapterType = buslogic
toolsVersion = 1
virtualHWVersion = 7
```

Tools version and virtual hardware version appear in the metadata, but not in the disk information retrieved by "DoInfo()" on page 46. Geometry information and adapter type are repeated, but in a different format. Other metadata items not listed above might exist.

DoDump()

This procedure calls VixDiskLib_Read() to retrieve sectors and displays sector contents on the output in hexadecimal. The default is to dump only the first sector numbered zero, but you can change this with the -start and -count options. Here is a sequence of commands to demonstrate:

```
vix-disklib-sample -create sample.vmdk
vix-disklib-sample -fill -val 1 sample.vmdk
vix-disklib-sample -fill -val 2 -start 1 -count 1 sample.vmdk
vix-disklib-sample -dump -start 0 -count 2 sample.vmdk
od -c sample.vmdk
```

On Linux (or Cygwin) you can run the od command to show overhead and metadata at the beginning of file, and the repeated ones and twos in the first two sectors. The –dump option of the sample program shows only data, not overhead.

DoTestMultiThread()

This procedure employs the Windows thread library to make multiple copies of a virtual disk file. Specify the number of copies with the <code>-multithread</code> command-line option. For each copy, the sample program calls the <code>CopyThread()</code> procedure, which in turn calls a sequence of six Virtual Disk API routines.

On Linux the multithread option is unimplemented.

DoClone()

This procedure calls VixDiskLib_Clone() to make a copy of the data on virtual disk. A callback function, supplied as the sixth parameter, displays the percent of cloning completed. For local hosted disk, the adapter type is SCSI unless specified as IDE on the command line, size is 200MB, unless set by -cap option, and type is monolithic sparse, for Workstation 5. For an ESX/ESXi host, adapter type is taken from managed disk itself, using the connection parameters established by VixDiskLib_Connect().

The final parameter TRUE means to overwrite if the destination VMDK exists.

The clone option is an excellent backup method. Often the cloned virtual disk is smaller, because it can be organized more efficiently. Moreover, a fully allocated flat file can be converted to a sparse representation.

SSL Certificate Thumbprint

The sample program in the VDDK 5.1 release added the -thumb option to allow an SSL Certificate thumbprint to be provided and used. The thumbprint is used for authentication through vCenter Server.

6

This chapter presents some practical programming challenges not covered in the sample program, including:

- "Scan VMDK for Virus Signatures" on page 49
- "Creating Virtual Disks" on page 50
- "Working with Virtual Disk Data" on page 51
- "Managing Child Disks" on page 52
- "RDM Disks and Virtual BIOS" on page 53
- "Interfacing With VMware vSphere" on page 54

Scan VMDK for Virus Signatures

One of the tasks listed in "Use Cases for the Virtual Disk Library" on page 12 is to scan a VMDK for virus signatures. Using the framework of our sample program, a function can implement the <code>-virus</code> command-line option. The function in <code>Example 6-1</code> relies on a pre-existing library routine called <code>SecureVirusScan()</code>, which typically is supplied by a vendor of antivirus software. As it does for email messages, the library routine scans a buffer of any size against the vendor's latest pattern library, and returns TRUE if it identifies a virus.

Example 6-1. Function to Scan VMDK for Viruses

```
extern int SecureVirusScan(const uint8 *buf, size_t n);
    DoVirusScan - Scan the content of a virtual disk for virus signatures.
*/
static void DoVirusScan(void)
    VixDisk disk(appGlobals.connection, appGlobals.diskPath, appGlobals.openFlags);
    VixDiskLibDiskInfo info;
    uint8 buf[VIXDISKLIB_SECTOR_SIZE];
    VixDiskLibSectorType sector;
    VixError vixError = VixDiskLib_GetInfo(disk.Handle(), &info);
    CHECK_AND_THROW(vixError);
    cout << "capacity = " << info.capacity << " sectors" << endl;</pre>
    // read all sectors even if not yet populated
    for (sector = 0; sector < info.capacity; sector++) {</pre>
        vixError = VixDiskLib_Read(disk.Handle(), sector, 1, buf);
        CHECK_AND_THROW(vixError);
        if (SecureVirusScan(buf, sizeof buf)) {
            printf("Virus detected in sector %d\n", sector);
    }
    cout << info.capacity << " sectors scanned" << endl;</pre>
}
```

This function calls VixDiskLib_GetInfo() to determine the number of sectors allocated in the virtual disk. The number of sectors is available in the VixDiskLibDiskInfo structure, but normally not in the metadata. With SPARSE type layout, data can occur in any sector, so this function reads all sectors, whether filled or not. VixDiskLib_Read() continues without error when it encounters an empty sector full of zeroes.

The following difference list shows the remaining code changes necessary for adding the -virus option to the vixDiskLibSample.cpp sample program:

Creating Virtual Disks

This section discusses the types of local VMDK files and how to create virtual disk for a remote ESX/ESXi host.

Creating Local Disk

The sample program presented in Chapter 5 creates virtual disk of type MONOLITHIC_SPARSE, in other words one big file, not pre-allocated. This is the default because modern file systems, in particular NTFS, support files larger than 2GB, and can hold more than 2GB of total data. This is not true of legacy file systems, such as FAT16 on MS-DOS and early Windows, or the ISO9660 file system for writing files on CD, or NFS version 2, or Linux kernel 2.4. All are limited to 2GB per volume. FAT and FAT32 were extended to 4GB in NT 3.51.

However, a SPLIT virtual disk might be safer than the MONOLITHIC variety, because if something goes wrong with the underlying host file system, some data might be recoverable from uncorrupted 2GB extents. VMware products do their best to repair a damaged VMDK, but having a split VMDK increases the chance of salvaging files during repair. On the downside, SPLIT virtual disk involves higher overhead (more file descriptors) and increases administrative complexity.

When required for a FAT16 or early Linux file system, you can create SPLIT_SPARSE virtual disk. The change is simple: the line highlighted in boldface. The sample program could be extended to have an option for this.

NOTE You can split VMDK files into smaller than 2GB extents, but created filenames still follow the patterns shown in Table 3-1, "VMDK Virtual Disk Files," on page 20.

This one-line change to DoCreate() causes creation of 200MB split VMDK files (200MB being the capacity set on the previous line) unless the –cap command-line argument specifies otherwise.

Creating Remote Disk

As stated in "Support for Managed Disk" on page 41, VixDiskLib_Create() does not support managed disk. To create a managed disk on the remote ESX/ESXi host, first create a hosted disk on the local Workstation, then convert the hosted disk into managed disk with VixDiskLib_Clone() over the network.

To create remote managed disk using the sample program, type the following commands:

```
./vix-disklib-sample -create -cap 1000000 virtdisk.vmdk
./vix-disklib-sample -clone virtdisk.vmdk -host esx3i -user root -password secret vmfsdisk.vmdk
```

You could write a virtual-machine provisioning application to perform the following steps:

- 1 Create a hosted disk VMDK with 2GB capacity, using VixDiskLib_Create().
- 2 Write image of the guest OS and application software into the VMDK, using VixDiskLib_Write().
- 3 Clone the hosted disk VMDK onto the VMFS file system of the ESX/ESXi host.

In this call, appGlobals.connection and appGolbals.diskPath represent the remote VMDK on the ESX/ESXi host, while srcConnection and appGlobals.srcPath represent the local hosted VMDK.

4 Power on the new guest OS to get a new virtual machine.

On Workstation, the VixVMPowerOn() function in the VIX API does this. For ESX/ESXi hosts, you must use the PowerOnVM_Task method. As easy way to use this method is in the VMware vSphere Perl Toolkit, which has the PowerOnVM_Task() call (non-blocking), and the PowerOnVM() call (synchronous).

5 Provision and deploy the new virtual machine on the ESX/ESXi host.

Special Consideration for ESX/ESXi Hosts

No matter what virtual file type you create in Step 1, it becomes type VIXDISKLIB_DISK_VMFS_FLAT in Step 3.

Working with Virtual Disk Data

The virtual disk library reads and writes sectors of data. It has no interface for character or byte-oriented I/O.

Reading and Writing Local Disk

Demonstrating random I/O, this function reads a sector at a time backwards through a VMDK. If it sees the string "VmWare" it substitutes the string "VMware" in its place and writes the sector back to VMDK.

```
#include <string>
static void DoEdit(void)/
   VixDisk disk(appGlobals.connection, appGlobals.diskPath, appGlobals.openFlags);
   uint8 buf[VIXDISKLIB_SECTOR_SIZE];
   VixDiskLibSectorType i;
    string str:
    for (i = appGlobals.numSectors; i >= 0; i--) {
        VixError vixError;
        vixError = VixDiskLib_Read(disk.Handle(), appGlobals.startSector + i, 1, buf);
       CHECK_AND_THROW(vixError);
        str = buf;
        if (pos = str.find("VmWare", 0)) {
            str.replace(pos, 5, "VMware");
            buf = str;
            vixError = VixDiskLib_Write(disk.Handle(), appGlobals.startSector + i, 1, buf);
            CHECK_AND_THROW(vixError);
    }
}
```

Reading and Writing Remote Disk

The DoEdit() function is similar for remote managed virtual disk on ESX/ESXi hosts, but beforehand you must call VixDiskLib_Connect() with authentication credentials instead of passing NULL parameters.

Deleting a Disk (Unlink)

The function to delete virtual disk files is VixDiskLib_Unlink(). It takes two arguments: a connection and a VMDK filename.

```
vixError = VixDiskLib_Unlink(appGlobals.connection, appGlobals.diskPath);
```

Effects of Deleting a Virtual Disk

When you delete a VMDK, you lose all the information it contained. In most cases, the host operating system prevents you from doing this when a virtual machine is running. However, if you delete a VMDK with its virtual machine powered off, that guest OS becomes unbootable.

Renaming a Disk

The function to rename virtual disk files is VixDiskLib_Rename(). It takes two arguments: the old and the new VMDK filenames.

```
vixError = VixDiskLib_Rename(oldGlobals.diskpath, newGlobals.diskpath);
```

Effects of Renaming a Virtual Disk

The server expects VMDK files of its guest OS virtual machines to be in a predictable location. Any file accesses that occur during renaming might cause I/O failure and possibly cause a guest OS to fail.

Working with Disk Metadata

With VMFS on ESX/ESXi hosts, disk metadata items could be important because they store information about the disk mapping and interactions with the containing file system.

Managing Child Disks

In the Virtual Disk API, redo logs are managed as a parent-child disk chain, each child being the redo log of disk changes made since its inception. Trying to write on the parent after creating a child results in an error. The library expects you to write on the child instead. See Figure 4-2, "Child Disks Created from Parent," on page 33 for a diagram.

Creating Redo Logs

A redo log is created by taking a virtual machine snapshot, which contains both disk data and virtual machine state. On hosted disk only, VixDiskLib_CreateChild() creates a redo log without virtual machine state.

You could write a simple application to create redo logs, or snapshots on managed disk, at 3:00 AM nightly. (although multiple snapshots have a performance impact). When you create a redo log while the virtual machine is running, the VMware host re-arranges file pointers so the primary VMDK, <vmname>.vmdk for example, keeps track of redo logs in the disk chain. Use the disk chain to re-create data for any given day.

To re-create data for any given day

- Locate the <vmname>-<NNN>.vmdk redo log for the day in question.<NNN> is a sequence number. You can identify this redo log or snapshot by its timestamp.
- 2 Initialize the virtual disk library and open the redo log to obtain its parent handle.
- 3 Create a child disk with the VixDiskLib_Create() function, and attach it to the parent: vixError = VixDiskLib_Attach(parent.Handle(), child.Handle());
- 4 Read and write the virtual disk of the attached child.

This is just an example. On managed disk, multiple snapshots are not recommended for performance reasons. Backup software on vSphere usually takes a snapshot, saves data to backup media, then deletes the snapshot.

Virtual Disk in Snapshots


The Virtual Disk API provides the following features to deal with the disk component of snapshots:

- Attaching an arbitrary child in a disk chain
- Opening read-only virtual disks
- Ability to open snapshot disk on ESX/ESXi hosts through VMware vCenter

Windows 2000 Read-Only File System

Another use of parent-child disk chaining is to create read-only access for Windows 2000, which has no option for mounting a read-only file system. In Figure 6-1, the gray circle represents a virtual disk that must remain read-only because it has children. In this example, you want the Windows 2000 virtual machine to use that virtual disk, rather than the newer ones C1 and C2. Create new child disk RO, attach to the gray virtual disk as parent, and mount RO as the (mostly empty) read-only virtual disk of the Windows 2000 guest OS.

Figure 6-1. Attaching Virtual Read/Write Disk for Windows 2000



RDM Disks and Virtual BIOS

This section outlines low-level procedures for restoring raw device mapping (RDM) disks and NVRAM.

Restoring RDM Disks

Backing up and restoring RDM disks presents unusual challenges. The original backed-up RDM configuration might not apply, and is probably not appropriate, if users restore:

- A virtual machine to a different host or datastore.
- A virtual machine that was deleted, when its originally mapped RDM was also deleted, or the containing LUN was repurposed and rewritten.
- The RDM to a different virtual machine, even if that virtual machine is on the same host and datastore. Users might do this to access files on the disk, or to test a restore.

When performing a proxy backup of an RDM disk, you must present the same LUN ID to both the ESXi host and the proxy server. (This restriction does not apply to VMFS disk because the virtual disk library reads the VMFS header and matching UUID. But for RDM the host and proxy require the same LUN ID.)

Restoring RDM disks is appropriate if the original virtual machine's VMX file and disk mapping is no longer available, but the LUN containing the RDM is still available. In this case, the RDM image on the LUN might still be valid, so it does not need to be restored. If this is true, do not make changes to the RDM configuration during your restore operations. Instead, complete the restore process in two phases:

- Restore the virtual machine configuration (VMX) and system disk. This restores the virtual machine, but does not restore the RDM.
- Add the RDM disk to the virtual machine. After doing so, you can complete normal restore operations on the RDM disk.

Alternatively, it is possible to create a virtual machine that can host the RDM disk and access its contents. After you create the virtual machine, restore its virtual machine configuration (VMX) from backup, and then restore any selected disks.

Restoring the Virtual BIOS or UEFI

The .nvram file stores the BIOS or UEFI customizations of a virtual machine. Usually the only important items in this file are the boot drive setting and the boot order (in the case of multiple virtual disks).

Newer releases of vSphere can change the boot order using extended attribute settings, so boot order no longer must be stored in the .nvram file. However some users want to preserve a virtual machine's serial port settings in the .nvram file, and possibly other items, so applications should back up and restore this information.

To back up and restore NVRAM

- 1 For each virtual machine, make a separate copy of the .nvram file.
- 2 Back up each virtual machine using standard methods.
- 3 If necessary, restore the virtual machine using standard methods.
- 4 Overwrite the virtual machine's .nvram file with the saved copy of the original .nvram file.

IMPORTANT VMware now recommends saving the .nvram file as part of virtual machine backup, a change in recommendation since vSphere 4.1.

Interfacing With VMware vSphere

This section provides pointers to other vSphere programming interfaces.

The VIX API

The VIX API is a popular, easy-to-use developer interface for VMware Workstation, other hosted products, and ESX/ESXi. See the VMware developer documentation for information about the VIX API:

http://www.vmware.com/support/developer/vix-api

The *VIX API Reference* guide includes function reference pages for C++, Perl, and COM (component object model) for Microsoft C#, VBScript, and Visual Basic. Most reference pages include helpful code examples. Additionally, the vix-api Web guide includes examples for power on and off, suspending a virtual machine, taking a snapshot, guest operations, virtual machine discovery, and asynchronous callbacks.

Virus Scan all Hosted Disk

Suppose you want to run the antivirus software presented in "Scan VMDK for Virus Signatures" on page 49 for all virtual machines hosted on a VMware Workstation. Here is the high-level algorithm for an VIX-based application that would scan hosted disk on all virtual machines.

To virus scan hosted virtual disk

- 1 Write an application including both the Virtual Disk API and the VIX API.
- 2 Initialize the virtual disk library with VixDiskLib_Init().
- 3 Connect VIX to the Workstation host with VixHost_Connect().
- 4 Call VixHost_FindItems() with item-type (second argument) VIX_FIND_RUNNING_VMS.
 - This provides to a callback routine (fifth argument) the name of each virtual machine, one at a time. To derive the name of each virtual machine's disk, append ".vmdk" to the virtual machine name.
- 5 Write a callback function to open the virtual machine's VMDK.
 - Your callback function must be similar to the VixDiscoveryProc() callback function shown as an example on the VixHost_FindItems() page in the VIX API Reference Guide.
- Instead of printing "Found virtual machine" in the callback function, call the DoVirusScan() function shown in "Scan VMDK for Virus Signatures" on page 49.
- 7 Decontaminate any infected sectors that the virus scanner located.

The vSphere Web Services API

The VMware vSphere Web Services (WS) API is a developer interface for ESX/ESXi hosts and vCenter Server. See the VMware developer documentation for information about the vSphere WS API:

http://www.vmware.com/support/developer/vc-sdk

The *Developer's Setup Guide* for the VMware vSphere WS SDK has a chapter describing how to set up your programming environment for Microsoft C# or Java. Some of the information applies to C++ also.

The *Programming Guide* for the vSphere SDK contains some sample code written in Microsoft C# but most examples are written in Java, and based on the JAX-WS development framework.

ESX/ESXi hosts and the VMware vSphere WS API use a programming model based on Web services, in which clients generate Web services description language (WSDL) requests that pass over the network as XML messages encapsulated in simple object access protocol (SOAP). On ESX/ESXi hosts or vCenter Server, the vSphere layer answers client requests, usually passing back SOAP responses. This is a different programming model than the object-oriented function-call interface of C++ and the VIX API.

Virus Scan All Managed Disk

Suppose you want to run the antivirus software presented in "Scan VMDK for Virus Signatures" on page 49 for all virtual machines hosted on an ESX/ESXi host. Here is the high-level algorithm for a VMware vSphere solution that can scan managed disk on all virtual machines.

To virus scan managed virtual disk

- 1 Using the VMware vSphere Perl Toolkit, write a Perl script that connects to a given ESX/ESXi host.
- 2 Call Vim::find_entity_views() to find the inventory of every VirtualMachine.
- 3 Call Vim::get_inventory_path() to get the virtual disk name in its appropriate resource.

 The VMDK filename is available as diskPath in the GuestDiskInfo data object.
- 4 Using Perl's system(@cmd) call, run the extended vixDiskLibSample.exe program with -virus option. For ESX/ESXi hosts you must specify -host, -user, and -password options.
- 5 Decontaminate any infected sectors that the virus scanner located.

Read and Write VMDK with vSphere WS API

Version 2.5 and later of the VMware vSphere WS API contain some useful methods to manage VMDK files. See the managed object type VirtualDiskManager, which contains about a dozen methods similar to those in the Virtual Disk API documented here.

If you are interested, navigate to VMware Infrastructure SDK on the Web and click VI API Reference Guide for the 2.5 version or VMware vSphere WS API Reference Guide for the 4.0 version. Click All Types, search for VirtualDiskManager, and follow its link.

Designing vSphere Backup Solutions

7

This chapter documents how to write backup and restore software for virtual machines running in vSphere, and contains the following sections about the vSphere Storage APIs – Data Protection (VADP):

- "Design and Implementation Overview" on page 57
- "Low Level Backup Procedures" on page 64
- "Low Level Restore Procedures" on page 73
- "Tips and Best Practices" on page 81
- "Windows and Linux Implementations" on page 83

For an overview of backup, and help designing your top-level program structure, read the first section below. For details about implementing low-level backup code, read the remaining sections. You should be familiar with virtual machines, snapshots, ESXi, vCenter, and Java.

Design and Implementation Overview

On vSphere, backups are usually done by taking a snapshot, to efficiency obtain a static image of the virtual machine. Snapshots are a view of a virtual machine at a certain point in time, and enable quick and clean backup operation. Snapshots also provide an incremental backup mechanism called changed block tracking.

To back up virtual machines on vSphere, VMware recommends a two-language solution. First use Java to code the backup program that contacts the host, takes a temporary snapshot, records virtual machine configuration, and (later) deletes the snapshot. Then use C++ or C to code the VDDK program that transfers virtual disk data from the snapshot to backup media.

For restore, VMware recommends a two-language solution. First use Java to code the program that instructs the virtual machine to halt, or re-creates the target virtual machine from recorded configuration. Then use C or C++ to code the VDDK program that transfers saved data from backup media to virtual disk.

The Backup Process

These are the high-level steps to back up a virtual machine running in vSphere:

- Connect to the ESXi host containing the virtual machine targeted for backup.
 A side-effect of this step is determining the arrangement and description of virtual machines on the host.
- 2 Tell the host to take a snapshot of the target virtual machine, using the vSphere API. The virtual machine continues to run while the snapshot view is static (quiesced).
- 3 Capture the virtual disk data and virtual machine configuration information (vim.vm.ConfigInfo).
- 4 On the ESXi host, use the VDDK (programming in C or C++) to open and read the virtual disk and snapshot files. Copy them to backup media, along with configuration information.
- 5 Tell the host to delete the backup snapshot, using the vSphere API.

Communicating With the Server

In a typical vSphere deployment with many ESXi hosts, an instance of vCenter Server manages the ESXi hosts, and can move virtual machines from host to host (vMotion) to balance load and possibly save electricity by powering off an ESXi host. VMware therefore recommends that backup applications communicate with the vCenter Server instead of with individual ESXi hosts.

The vCenter Server provides location transparency for vSphere Web Services developers. The vCenter Server tracks virtual machines as they move (through vMotion) from one ESXi host to another, and vCenter Server directs SDK operations to the ESXi host that currently runs a virtual machine. Using the vSphere Web Services API, it is possible to back up all the virtual disks associated with a virtual machine.

The handling of the vCenter or an individual ESXi host is essentially equivalent when using the vSphere SDK. With vCenter management, there is no need to contact individual ESXi hosts directly. The remainder of this chapter uses the term vSphere to indicate either a vCenter Server or an ESXi host.

To reduce the resources used by vSphere, VMware recommends that the number of connections (or Sessions) be minimized. It is in the best interests of any program that communicates with vSphere to create one Session and share it with all elements of the program that need to exchange information with vSphere. This means that if your program supports multiple threads, your program should multiplex the use of connection objects by use of access control locks (mutex and the like).

It is also important that all vSphere SDK operations proceed from one instance of the "Session" object that your application requests after logging into vSphere. Using the vSphere API your application can create objects that are "Session specific" and therefore would not be known to other portions of your application that might use a different Session.

Information Containers as Managed Objects

VMware documentation introduces you to the concept of the managed object and its handle, called a managed object reference (moRef). You might be tempted to get configuration and status information of managed objects using a piecemeal approach. This has the severe disadvantage of creating a lot of chatter over the server connection, so it is very slow. A mechanism has been created to provide status information efficiently: the PropertyCollector, discussed in "PropertyCollector Data" on page 59.

More About Managed Objects

The documentation for the vSphere API and object model introduces a large number of managed objects. There are five basic types of managed objects that describe the organization of a server. Other managed objects can be considered as details expanding on these five basic types:

- Folder
- Datacenter
- ComputeResource
- ResourcePool
- VirtualMachine

It is a characteristic of all managed objects that they have a moRef to the managed object that serves as the parent to the managed object. This parent moRef allows you to reconstruct the object hierarchy exposed by the vSphere SDK. In general the hierarchy is a tree-like structure along the lines of:

Root Folder > Datacenter > ComputeResource > ResourcePool > VirtualMachine

There are variations on this theme, depending on whether you connect to vCenter or directly to an ESXi host, but the overall organization is like the structure above. Each managed object also has a Name property.

The virtual machine that you want to back up, and the snapshot you take of it (the extensible managed object VirtualMachineSnapshot) are both designated by their moRef.

Managed Object References

A managed object reference (moRef) is actually a handle and not the managed object itself. While it is certain that a moRef always contains a unique value, the unique value is only relative to the instance of vSphere to which you are connected. For example, if vCenter Server manages a cluster of ESXi hosts, each ESXi host maintains its own managed object reference namespace and the vCenter must maintain a managed object reference namespace representing all of its servers. So when an ESXi host is represented by a vCenter, the vCenter must ensure that the managed object references are unique. The vCenter accomplishes this by creating unique managed object reference names inside its own namespace, which differ from the names that ESXi uses for the same managed objects.

A vSphere instance (vCenter or ESXi) tries to keep the moRef for a virtual machine consistent across sessions, however consistency is not guaranteed. For example, unregistering and reregistering a virtual machine could result in a change to the moRef for the virtual machine. Thus, it is a bad idea to store a moRef and expect it to work correctly in future sessions, or with a different vCenter Server.

Unique ID for a Different vCenter

On one vCenter Server, the moRef uniquely identifies a virtual machine. If you need to track and inventory virtual machine backups across multiple vCenter Servers, you can use moRef together with instanceUuid. You can see the instanceUuid at the following browser path:

https://<vcserver>/mob/?moid=ServiceInstance&doPath=content.about

For direct connections to ESXi, the host address and moRef uniquely identify a virtual machine. However this moRef could be different from the one that vCenter Server returns, hence the fallback to instanceUuid. The instanceUuid was new in VMware vSphere 4.0. In previous releases, the fallback was to Uuid.

Gathering Status and Configuration Information

To save configuration of a virtual machine so you can restore it later, you can use the PropertyCollector to get the virtual machine configuration.

The PropertyCollector is the most efficient mechanism to specify, at the top level, all of the managed objects that are of interest to your application. It has methods for providing updates that indicate only changes to the previous state of these objects. There are two mechanisms for acquiring these updates:

- Polling Check for changes. The result is either "no change" or an object containing the changes. One
 advantage of this mechanism is that it involves no network traffic except for a poll request and reporting.
- Wait for updates "Wait for updates" is basically a blocking call to the PropertyCollector. This is only useful if you dedicate a program thread waiting for the call to unblock. The advantage of this mechanism is that there is no traffic on the communications thread unless something must be reported.

The PropertyCollector is powerful but requires great attention to detail. Backup-related features of the PropertyCollector are covered in "Low Level Backup Procedures" on page 64 of this document. The next section provides some background about PropertyCollector.

PropertyCollector Data

This document assumes that you want to keep up with changes in the configuration of the vCenter Server, and therefore plan to use the update tracking capability of the PropertyCollector.

The PropertyCollector requires two fairly complex arguments: the PropertySpec and the ObjectSpec. The ObjectSpec contains instructions to the PropertyCollector describing where to look for the desired data. Because configuration information in vSphere is organized like a directory tree, the ObjectSpec must describe how to traverse the tree to obtain the desired information. The net result is a complex, nested, and recursive list of instructions. Fortunately, once you have determined the location of all the desired information, the ObjectSpec needed to determine the layout of a vSphere object hierarchy can be a static unvarying object. See the code example in section "Understanding an ObjectSpec" on page 64.

The PropertySpec is a list of desired property information. Formulating a list that includes all of the desired information can take some effort to compile, but once determined, this can be a static object also.

The data returned from the PropertyCollector is a container class called PropertyFilterUpdate, which contains an objectSet with an item-by-item list of changes to object properties. Every item in this container is identified with one of the following keys: enter (add), leave (delete), and modify. On the first data request, every data item is included, and "enter" is marked for every data item.

The PropertyCollector presents its results in what amounts to random order. Since all managed objects have a "parent" property, you can reconstruct the configuration hierarchy by building a tree in memory, using the parent identification to organize. The root folder is identified as the only folder without a parent.

Useful Property Information

In the data returned from PropertyCollector, you can find most of the information that is useful for backup in the Virtual Machine managed object, including the following:

- Virtual Disks names, types, and capacities.
- Virtual Machine Type and Configuration Whatever would be useful in (re)creating a virtual machine. This list might include such information as memory size and number of CPUs.
- Display Names These names appear in VMware products such as the vSphere Client. You should keep track of these names and correlate them for consistency between your product and VMware products.

VMware supports many virtual disk implementations. The disk implementation type is important because:

- On restore, you should re-create virtual disk with the same disk type as the original virtual machine used.
- A disk backed by a pass-through raw device mapping (RDM) mostly bypasses the ESXi storage stack. You cannot make a snapshot of this virtual disk type. Therefore, you cannot back up pass-through RDM disk using the snapshot method described in this document.

For more information about the Java APIs, read the first several chapters of the *VMware vSphere Web Services SDK Programming Guide*, and related pages of the Web-based *VMware vSphere API Reference Documentation*. Both are available at http://www.vmware.com/support/developer/vc-sdk. Examples in this chapter assume that you have set up the vSphere SDK as described in documentation.

Doing a Backup Operation

After your program obtains information about what is available to back up, it can perform a backup. The three steps to the backup process are:

- "Create a Temporary Snapshot on the Target Virtual Machine" on page 60
- "Extract Backup Data from the Target Virtual Machine" on page 61, and save configuration information.
- "Delete the Temporary Snapshot" on page 61

Prerequisites

To complete a backup, the calling program requires the permissions shown in Table 7-1.

Table 7-1. Required Permissions to Complete a Backup

Privilege Category	Privilege Subcategory	Privilege
Virtual Machine	Provisioning	Allow Virtual Machine Download
	State	Create Snapshot
		Remove Snapshot
	Configuration	Disk Lease

Create a Temporary Snapshot on the Target Virtual Machine

The low-level procedure for creating a snapshot of a virtual machine is documented in the section "Creating a Snapshot" on page 68. Set the quiesce flag True to make the file system quiescent, otherwise the snapshot might represent a transitional system state, with inconsistent data. Restoring such data might be destructive.

Another flag named memory allows you to include in the snapshot a dump of the powered on virtual machine's in-memory state. This is not needed for backup, so set this flag to False.

Changed Block Tracking

This feature, first available in vSphere 4, provides the foundation for incremental (or differential) backup of virtual disks. Your application can back up only changed data as indicated by the QueryChangedDiskAreas method. Virtual machines with virtual hardware version 7 and later support changed block tracking. These virtual machines contain changeTrackingSupported in the capability field of the VirtualMachine managed object. See "Changed Block Tracking on Virtual Disks" on page 70 for details.

Extract Backup Data from the Target Virtual Machine

Associated with the snapshot you just created are "versions" of the virtual disks. To identify these disks, you obtain a moRef to the snapshot you just created. From this snapshot moRef, you can extract the disk names and paths. How to do this is demonstrated in section "Backing Up a Virtual Disk" on page 69.

To read the data in a virtual disk, it is necessary to use the VixDiskLib. This library isolates the programmer from the details of extracting data from a virtual disk and its redo logs. For example, when doing backup you call functions VixDiskLib_Open() and VixDiskLib_Read(), among others. VixDiskLib allows access to disk data on sector boundaries only; the transfer size is some multiple of the disk sector size.

When accessing disks on ESXi hosts, VixDiskLib release 1.0 transferred virtual disk data over the network. Later VixDiskLib releases contain API enhancements so you can request more efficient data paths, such as direct SAN access or HotAdding disks to a virtual backup appliance. These efficient data paths requires minor code changes, such as calling VixDiskLib_ConnectEx() instead of plain connect.

Part of virtual disk information is metadata: a number of key/value pairs describing configuration of the virtual disk. Metadata information can be extracted from a virtual disk using the VixDiskLib functions VixDiskLib_GetMetadataKeys() and VixDiskLib_ReadMetadata(). You should save metadata keys along with the backup, in case you need to re-create the virtual disk.

The VixDiskLib API allows a backup application to perform a full backup of a virtual machine. The newer VixMntapi library can extract information about a guest operating system from its virtual disks, so your backup application can determine the type of operating system that is involved. This allows mounting the volumes to device nodes, so your application can perform file-oriented backups and restores.

Delete the Temporary Snapshot

As the last part of the backup process, you should delete the temporary snapshot. It is no longer needed, worsens virtual machine performance, and takes up storage space that could be put to better use.

The Restore Process

Your software can follow one of two restore scenarios: either revert to a saved state, or disaster recovery:

To bring an existing virtual machine to a previous state

- 1 Connect to the server and command it to halt and power off the target virtual machine.
- 2 Use the server to gain access to the virtual disks. With SAN transport mode, create a snapshot, because creating and deleting a snapshot is required for SAN mode restore.
- 3 Transfer the disk images from backup using VixDiskLib. Revert-to and delete the snapshot, if applicable.

To completely re-create a virtual machine (disaster recovery)

- 1 Connect to the server.
- 2 Command the server to create a new virtual machine and its virtual disks using the configuration information saved from vim.vm.ConfigInfo during backup.
- 3 Transfer virtual disk data to the newly created virtual disks using VixDiskLib. Virtual disk data includes disk formatting information, so you do not need to build any kind of file system on the virtual disks.

Doing a Restore Operation

The two scenarios of restore operation are described below.

- "Restoring an Existing Virtual Machine to a Previous State" on page 62
- "Creating a New Virtual Machine" on page 62

Prerequisites

To complete a restore, the calling process requires the permissions in Table 7-2.

Table 7-2. Required permissions to complete a restore

Privilege Category	Privilege Subcategory	Privilege
Virtual Machine	Inventory	Create
		Remove
	Configuration	Settings
		Change Resource
Resource		Assign Virtual Machine to Resource Pool

For security reasons, programs are not granted write access to the disks of a running virtual machine. Before you shut it down, you should determine the run-state of the virtual machine.

Run-state information is available from the PropertyCollector, and if you keep this information up-to-date, your application already knows the run-state of the virtual machine. To change the run-state you must have the moRef of the virtual machine. Use this moRef in a PowerOnVM_Task call through the server connection. For virtual machine shutdown, call the PowerOffVM_Task method.

Restoring an Existing Virtual Machine to a Previous State

The following steps restore a virtual machine to a certain saved state:

- 1 Shut down the virtual machine (if it is not already shut down).
- 2 With SAN transport only, a snapshot is required to restore a virtual machine, so create this snapshot.
- Restore contents of the virtual disk(s). If there were no pre-existing snapshots at backup time, just the snapshot created for backup, restore only the base disks.

Restoring disk data requires that you obtain the current names of virtual disks. This process is similar to the one described in "Extract Backup Data from the Target Virtual Machine" on page 61, except in this case you obtain this information directly from the virtual machine and not from a snapshot. The target for the saved disk data must be the actual disk name (including any sequence number) because the current incarnation of a virtual machine may be derived from one or more snapshots.

Restoring disk data requires use of the VixDiskLib interface. The VixDiskLib_Write() function allows you to open the virtual machine's virtual disks and write your restore data. VixDiskLib functions transfer data to even-sector boundaries only, and the transfer length must be an even multiple of the sector size. Because the virtual disk already exists, it is not necessary to restore the disk configuration information mentioned in "Extract Backup Data from the Target Virtual Machine" on page 61.

4 With SAN transport mode, revert-to and delete the snapshot that you created in Step 2. Failing to perform these steps with SAN could yield a virtual machine that cannot be powered on.

Creating a New Virtual Machine

The process of building a virtual machine from backup data involves the following steps:

1 Create the virtual machine.

To create a new virtual machine, you use the information about virtual machine configuration that you derived and saved during the backup process.

You might allow users of restore software an opportunity to rename the virtual machine during recovery in case they want to clone or move the virtual machine. Also you might consider offering them an opportunity to change virtual machine layout (for instance, storing virtual disks on a different datastore). Creating the virtual disks is also done at the time when you create the virtual machine. This process is fairly complicated. See the section "Low Level Backup Procedures" on page 64 for details.

2 Restore the virtual disk data.

This process is similar to restoring the contents of virtual disks (Step 3 under "Restoring an Existing Virtual Machine to a Previous State" on page 62) with the following exception: you must call the VixDiskLib_WriteMetadata() function to write all the disk configuration key/value data into the virtual disk before restoring any backed-up data to the virtual disk. Then call VixDiskLib_Write() to restore the virtual disk data, as described in Step 3 above.

3 Power on the virtual machine.

Accessing Files on Virtual Disks

It might be necessary for a backup application to access individual files or groups of files on the virtual disks. For example, data protection applications might need to restore individual files on demand.

You can find the interfaces to accomplish this in the VixMntapi library associated with VixDiskLib. The VixMntapi library allows disks or volumes of a virtual machine to be mounted and examined as needed. VixMntapi provides access at the file system level, whereas VixDiskLib provides access at the sector level.

To mount a virtual disk

- 1 Locate the path names of all the virtual disks associated with a snapshot.
- 2 Call VixDiskLib_Open() to open all of these virtual disks. This gives you a number of VixDiskLib handles, which you should store in an array.
- 3 Call VixMntapi_OpenDiskSet() to create a VixDiskSetHandle, passing in the array of VixDiskLib handles that you created in step 2.
- 4 Pass VixDiskSetHandle as a parameter to VixMntapi_GetVolumeHandles() to obtain an array of VixVolumeHandle pointers to all volumes in the disk set.
- 5 Call VixMntapi_GetOsInfo() to determine what kind of operating system is involved, and decide where important pieces of information are to be found.
- 6 For important volumes, call VixMntapi_MountVolume() then VixMntapi_GetVolumeInfo(), which reveals how the volume is set up. (Unimportant volumes include swap partitions.)
- 7 If you need information about how the guest operating system sees the data on this volume, you can look in the data structure VixVolumeInfo returned by VixMntapi_GetVolumeInfo(). For example, VixVolumeInfo::symbolicLink, obtained using VixMntapi_GetVolumeInfo(), is the path on the proxy where you can access the virtual disk's file system using ordinary open, read, and write calls.

Once you are done accessing files in a mounted volume, there are VixMntapi procedures for taking down the abstraction that you created. These calls are:

- VixMntapi_DismountVolume() for each volume handle
- VixMntapi_FreeOsInfo() and VixMntapi_FreeVolumeInfo()
- VixMntapi_CloseDiskSet()

This leaves the VixDiskLib handles that you obtained in the beginning; you must dispose of them properly.

Summary

The preceding sections explained how to contact vSphere and extract information from it, and how to back up or restore virtual disks. The following sections cover the same information at a lower level.

Low Level Backup Procedures

This section describes low level details that may be helpful in coding a backup application. It is not the intent of this material to impose a design, but only to serve as a guideline with examples and exposition. The code samples provided below are not complete. They generally lack error handling and ignore critical details.

Communicating with the Server

Connections to the server machine require credentials: user name, password, and host name (or IP address). The following code connects to the server and extracts information useful for manipulating a service:

1 Create the service instance moRef:

```
ManagedObjectReference svcRef = new ManagedObjectReference();
svcRef.setType("ServiceInstance");
svcRef.setValue("ServiceInstance");
Locate the service:

VimServiceLocator locator = new VimServiceLocator();
locator.setMaintainSession(true);
VimPortType serviceConnection = locator.getVimPort("https://your_server/sdk");
```

3 Log in to the session manager:

```
ServiceInstanceContent serviceContent = serviceConnection.retrieveContent(svcRef);
ManagedObjectReference sessionManager = serviceInstance.getSessionManager();
UserSession us = serviceConnection.login(sessionManager, username, password, null);
```

The PropertyCollector

The PropertyCollector is used in this section to apply the above details to the backup task.

PropertyCollector Arguments

The PropertyCollector uses two relatively complicated argument structures. As was mentioned in "PropertyCollector Data" on page 59, these arguments are PropertySpec and ObjectSpec. PropertySpec is a list of the information desired, and ObjectSpec is a list of instructions indicating where to find the information. In theory, you could directly address an object using its moRef. In that case an ObjectSpec can be very simple. However, getting the initial moRef can be a challenge when a complicated ObjectSpec is required. To formulate a complex ObjectSpec, you need to understand the structure of the available data. This is complicated by the fact that an ObjectSpec can contain recursive elements.

Understanding an ObjectSpec

An ObjectSpec is a list of ObjectSpec elements, each specifying an object type, and giving a "selection spec" for the object. "More About Managed Objects" on page 58 describes five types of managed objects: Folder, Datacenter, ComputeResource, ResourcePool, and VirtualMachine. VirtualApp (vApp) is a sixth type. You can "traverse" objects, because one managed object leads to another.

- Folder One of the items contained in the Folder is called childEntity, which is a list of moRefs that can contain one of the five managed object types. A Folder can be parent to any of these managed objects.
- Datacenter This managed object has two items that lead to other managed objects:
 - hostFolder A moRef to a Folder containing a list of ComputeResources comprising a Datacenter.
 - vmFolder A moRef to a Folder containing the VirtualMachines that are part of the Datacenter. If it is your objective to duplicate the display seen in a vSphere Client GUI, then this Folder is of limited use because it does not describe the ResourcePool that is the parent of a virtual machine.
- ComputeResource A ComputeResource is basically hardware. A ComputeResource can comprise multiple systems. The hardware represents resources that can be used to implement a VirtualMachine object. VirtualMachine is a child of ResourcePool, which controls the sharing of a physical machine's resources among VirtualMachine objects. A ComputeResource contains an item named resourcePool, which is a moRef to a ResourcePool.

- VirtualApp A VirtualApp (vApp) is a collection of VirtualMachines that make up a single application. This is a special form of ResourcePool (defined below). A VirtualApp may have three types of children:
 - VirtualMachine A folder named vm contains a list of moRefs to child VirtualMachines.
 - resourcePool A folder containing a list of moRefs pointing to child ResourcePools or VirtualApps.
 - VirtualApp A VirtualApp can be composed of other VirtualApps.
 - ResourcePool You can segment the resources of a VirtualApp using a ResourcePool.
- ResourcePool This managed object contains two child items:
 - resourcePool A folder containing a list of moRefs pointing to child ResourcePools or VirtualApps.
 - vm A list of moRefs to child VirtualMachines that employ the resources of the parent ResourcPool. A VirtualMachine always lists a ResourcePool as its parent.
- VirtualMachine The VirtualMachine is often considered an "end object" so you do not need to describe any traversal for this object.

The ObjectSpec does not have to lead you any farther than the moRef of a target object. You can gather information about the managed object itself using the moRef and the PropertySpec. This is described in detail in the section "Understanding a PropertySpec" on page 66.

A Traversal Spec extends Selection Spec, a property of Object Spec, and contains the following elements:

- Path The element contained in the object that is used to steer traversal.
- SelectSet An array containing either SelectionSpec or TraversalSpec elements.
- Skip Whether or not to filter the object in the Path element.
- Type The type of object being referenced.
- Name Optional name you can use to reference the TraversalSpec, inherited from SelectionSpec.

SelectionSpec is a direct target for traversal, as is TraversalSpec (a class extending SelectionSpec). It is in the SelectSet that recursion can occur.

If you wish to traverse the entire configuration tree for a server, then you need only the "root node" moRef, which is always a Folder. This root folder moRef is available in the property rootFolder of the ObjectSpec service instance content. All of the above goes into this Java code sample.

```
// Traversal objects can use a symbolic name.
// First we define the TraversalSpec objects used to fill in the ObjectSpec.
// This TraversalSpec traverses Datacenter to vmFolder
TraversalSpec dc2vmFolder = new TraversalSpec();
dc2vmFolder.setType("Datacenter"); // Type of object for this spec
dc2vmFolder.setPath("vmFolder"); // Property name defining the next object
dc2vmFolder.setSelectSet(new SelectionSpec[] {"folderTSpec"});
// This TraversalSpec traverses Datacenter to hostFolder
TraversalSpec dc2hostFolder = new TraversalSpec();
dc2hostFolder.setType("Datacenter");
dc2hostFolder.setPath("hostFolder");
// We use the symbolic name "folderTSpec" which will be defined when we create the folderTSpec.
dc2vmFolder.setSelectSet(new SelectionSpec[] {"folderTSpec"});
// This TraversalSpec traverses ComputeResource to resourcePool
TraversalSpec cr2resourcePool = new TraversalSpec();
cr2resourcePool.setType("ComputeResource");
cr2resourcePool.setPath("resourcePool");
// This TraversalSpec traverses ComputeResource to host
TraversalSpec cr2host = new TraversalSpec();
cr2host.setType("ComputeResource");
cr2host.setPath("host");
```

```
//
// This TraversalSpec traverses ResourcePool to resourcePool
TraversalSpec rp2rp = new TraversalSpec();
rp2rp.setType("ResourcePool");
rp2rp.setPath("resourcePool");
// Finally, we tie it all together with the Folder TraversalSpec
TraversalSpec folderTS = new TraversalSpec();
folderTS.setName{"folderTSpec"); // Used for symbolic reference
folderTS.setType("Folder");
folderTS.setPath("childEntity");
folderTS.setSelectSet(new SelectionSpec[]{ "folderTSpec",
                                            dc2vmFolder,
                                            dc2hostFolder,
                                            cr2resourcePool,
                                            rp2rp}):
ObjectSpec ospec = new ObjectSpec();
ospec.setObj(startingPoint); // This is where you supply the starting moRef (usually root folder)
ospec.setSkip(Boolean.FALSE);
ospec.setSelectSet(folderTS); // Attach the TraversalSpec we designed above
```

Understanding a PropertySpec

A PropertySpec is a list of individual properties that can be found at places identified by the ObjectSpec and its TraversalSpec. Once the PropertyCollector has a moRef, it can then return the properties associated with that moRef. This can include "nested" properties. Nested properties are properties that can be found inside of properties identified at the top level of the managed object. Nested properties are identified by a "dot" notation.

An example of nested properties can be drawn from the VirtualMachine managed object. A VirtualMachine has the property identified as summary, which identifies a VirtualMachineSummary data object. The VirtualMachineSummary contains property config, which identifies a VirtualMachineConfigSummary data object. The VirtualMachineConfigSummary has a property called name, which is a string containing the display name of the VirtualMachine. You can access this name property using the summary.config.name string value. To address all the properties of the VirtualMachineConfigSummary object, you would use the summary.config string value.

The PropertyCollector requires an array of PropertySpec elements. Each element includes:

- Type The type of object that contains the enclosed list of properties.
- PathSet An array of strings containing names of properties to be returned, including nested properties.

It is necessary to add an element for each type of object that you wish to query for properties. The following is a code sample of a PropertySpec:

```
// This code demonstrates how to specify a PropertySpec for several types of target objects:
PropertySpec folderSp = new PropertySpec();
folderSp.setType("Folder");
folderSp.setAll(Boolean.FALSE);
folderSp.setPathSet(new String [] {"parent", "name"});
PropertySpec dcSp = new PropertySpec();
dcSp.setType("Datacenter");
dcSp.setAll(Boolean.FALSE);
dcSp.setPathSet(new String [] {"parent","name"});
PropertySpec rpSp = new PropertySpec();
rpSp.setType("ResourcePool");
rpSp.setAll(Boolean.FALSE);
rpSp.setPathSet(new String [] {"parent","name","vm"});
PropertySpec crSp = new PropertySpec();
crSp.setType("ComputeResource");
crSp.setAll(Boolean.FALSE);
crSp.set:PathSet(new String [] {"parent","name"});
PropertySpec vmSp = new PropertySpec();
vmSp.setType("VirtualMachine");
vmSp.setAll(Boolean.FALSE);
vmSp.setPathSet(new String [] {"parent",
                               "name".
```

Getting the Data from the PropertyCollector

Now that we have defined ObjectSpec and PropertySpec (the where and what), we need to put them into a FilterSpec that combines the two. An array of FilterSpec elements is passed to the PropertyCollector (the minimum number of elements is one). Two mechanisms can retrieve data from PropertyCollector:

- RetrieveProperties A one-time request for all of the desired properties. This can involve a lot of data, and has no refresh option. RetrievePropertiesEx has an additional options parameter.
- Update requests PropertyCollector update requests take two forms: polling and waiting (see below).

Requesting Updates

The update method is the way to keep properties up to date. In either Polling or Waiting, it is first necessary to register your FilterSpec array object with the PropertyCollector. You do this using the CreateFilter method, which sends a copy of your FilterSpec to the server. Unlike the RetrieveProperties method, FilterSpec is retained after CreateFilter operation. The following code shows how to set FilterSpec:

```
// We already showed examples of creating pspec and ospec in the examples above.
// The PropertyCollector wants an array of FilterSpec objects, so:
PropertyFilterSpec fs = new PropertyFilterSpec();
fs.setPropSet(pspec);
fs.setObjectSet(ospec);
PropertyFilterSpec [] fsa = new PropertyFilterSpec [] {fs};
ManagedObjectReference pcRef = serviceContent.getPropertyCollector();
// This next statement sends the filter to the server for reference by the PropertyCollector
ManagedObjectReference pFilter = serviceConnection.CreateFilter(pcRef, fsa, Boolean.FALSE);
```

If you wish to begin polling, you may then call the function CheckForUpdates, which on the first try (when it must contain an empty string for the version number) returns a complete dump of all the requested properties from all the eligible objects, along with a version number. Subsequent calls to CheckForUpdates must contain this version number to indicate to the PropertyCollector that you seek any changes that deviate from this version. The result is either a partial list containing only the changes from the previous version (including a new version number), or a return code indicating no data has changed. The following code sample shows how to check for updates:

```
String updateVersion = ""; // Start with no version
UpdateSet changeData = serviceConnection.CheckForUpdates(pcRef, updateVersion);
if (changeData != nil) {
    updateVersion = changeData.getVersion(); // Extract the version of the data set
}
// ...
// Get changes since the last version was sent.
UpdateSet latestData = serviceConnection.CheckForUpdates(pcRef, updateVersion);
```

If instead you wish to wait for updates to occur, you must create a task thread that blocks on the call WaitForUpdates. This task thread would return changes only as they occur and not at any other time. However if the request times out, you must renew it.

NOTE The order of property retrieval is not guaranteed. Multiple update requests may be needed.

Extracting Information from the Change Data

The data returned from CheckForUpdates (or WaitForUpdates) is an array of PropertyFilterUpdate entries. Since a PropertyFilterUpdate entry is very generic, here is some code showing how to extract information from the PropertyFilterUpdate.

```
// Extract the PropertyFilterUpdate set from the changeData
PropertyFilterUpdate [] updateSet = changeData.getFilterSet();
// There is one entry in the updateSet for each filter you registered with the PropertyCollector.
// Since we currently have only one filter, the array length should be one.
PropertyFilterUpdate myUpdate = updateSet[0];
ObjectUpdate [] changes = myUpdate.getObjectSet();
for (a = 0; a < changes.length; a++) {
    ObjectUpdate theObject = changes[a];
    String objName = theObject.getObj().getMoType().getName();
    // Must decide how to handle the value based on the name returned.
    // The only names returned are names found in the PropertySpec lists.
    // Get propertyName and value ...
}</pre>
```

Getting Specific Data

From time to time, you might need to get data that is relevant to a single item. In that case you can create a simple ObjectSpec including the moRef for the item of interest. The PropertySpec can then be set to obtain the properties you want, and you can use RetrieveProperties to get the data. Hopefully you can deduce moRef from a general examination of the properties, by searching for information from the rootFolder.

Identifying Virtual Disks for Backup and Restore

To back up a virtual machine, you first need to create a snapshot. Once the snapshot is created, you then need to identify the virtual disks associated with this snapshot. A virtual machine might have multiple snapshots associated with it. Each snapshot has a virtual "copy" of the virtual disks for the virtual machine. These copies are named with the base name of the disk, and a unique decimal number appended to the name. The format of the number is a hyphen character followed by a 6-digit zero-filled number. An example a disk copy name might be mydisk-NNNNNN.vmdk where NNNNNN would be some number like: 000032.

The vSphere API identifies virtual disk files by prefixing the datastore name onto the file system pathname and the filename: [storageN] myvmname/mydisk-NNNNNN.vmdk. The name in square brackets corresponds to the short name of the datastore that contains this virtual disk, while the remainder of the path string represents the location relative to the root of this datastore.

To get the name and characteristics of a virtual disk file, you use the PropertyCollector to select the property: config.hardware.device from a VirtualMachine managed object. This returns an array of virtual devices associated with a VirtualMachine or Snapshot. You must scan this list of devices to extract the list of virtual disks. All that is necessary is to see if each VirtualDevice entry extends to VirtualDisk. When you find such an entry, examine the BackingInfo property. You must extend the type of the backing property to one of the following, or a VirtualMachineSnapshot managed object:

- VirtualDiskFlatVer1BackingInfo
- VirtualDiskFlatVer2BackingInfo
- VirtualDiskRawDiskMappingVer1BackingInfo
- VirtualDiskSparseVer1BackingInfo
- VirtualDiskSparseVer2BackingInfo

It is important to know which backing type is in use in order to be able to re-create the Virtual Disk.It is also important to know that you cannot snapshot a disk of type VirtualDiskRawDiskMappingVer1BackingInfo, and therefore you cannot back up this type of Virtual Disk.

The properties of interest are the backing fileName and the VirtualDisk capacityInKB. Additionally, when change tracking is in place, you should also save the changeID.

Creating a Snapshot

Before performing a backup operation, you must create a snapshot of the target virtual machine. Both full and incremental backup rely on the snapshot in vSphere.

With SAN transport on VMFS volumes, the virtual machine should not have any pre-existing snapshots, so that reporting of in-use disk sectors will work. For details see "About Changed Block Tracking" on page 83.

As a best practice, you should search for and delete any pre-existing snapshots with the same name that you selected for the temporary snapshot. These snapshots are possibly remnants from failed backup attempts.

Within a specific snapshot, the names of virtual disk files (with extension .vmdk) can be modified with a zero-filled 6-digit decimal sequence number to ensure that the .vmdk files are uniquely named. Depending on whether or not the current virtual machine had a pre-existing snapshot, the disk name for a snapshot could have this format: <diskname>-<NNNNN>.vmdk. This unique name is no longer valid after the snapshot is destroyed, so any data for a snapshot disk should be stored in the backup program under its base disk name.

The following code sample shows how to create a snapshot on a specific virtual machine:

You can use the taskRef return value as a moRef to track progress of the snapshot operation. After successful completion, taskRef.info.result contains the moRef of the snapshot.

Backing Up a Virtual Disk

This section describes how to get data from the Virtual Disk after you have identified it. In order to access a virtual disk, you must use the VixDiskLib. The following code shows how to initialize the VixDiskLib and use it for accessing a virtual disk. All operations require a VixDiskLib connection to access virtual disk data. At the present time VixDiskLib is not implemented for the Java language, so this code is C++ language:

```
VixDiskLibConnectParams connectParams;
VixDiskLibConnection srcConnection;
connectParams.serverName = strdup("TargetServer");
connectParams.creds.uid.userName = strdup("root");
connectParams.creds.uid.password = strdup("yourPasswd");
connectParams.port = 902;
VixError vixError = VixDiskLib_Init(1, 0, &logFunc, &warnFunc, &panicFunc, libDir);
vixError = VixDiskLib_Connect(&connectParams, &srcConnection);
This next section of code shows how to open and read a specific virtual disk:
VixDiskLibHandle diskHandle;
vixError = VixDiskLib_Open(srcConnection, diskPath, flags, &diskHandle);
uint8 mybuffer[some_multiple_of_512];
vixError = VixDiskLib_Read(diskHandle, startSector, numSectors, &mybuffer);
// Also getting the disk metadata:
size_t requiredLength = 1;
char *buf = new char [1];
// This next operation fails, but updates "requiredLength" with the proper buffer size
vixError = VixDiskLib_GetMetadataKeys(diskHandle, buf, requiredLength, &requiredLength);
delete [] buf;
buf = new char[requiredLength]; // Create a large enough buffer
vixError = VixDiskLib_GetMetadataKeys(diskHandle, buf, requiredLength, NULL);
// And finally, close the diskHandle:
vixError = VixDiskLib_Close(diskHandle);
// And if you are completely done with the VixDiskLib
VixDiskLib_Disconnect(srcConnection);
VixDiskLib_Exit();
```

Deleting a Snapshot

When you are done performing a backup, you need to delete the temporary snapshot. You can get the moRef for the snapshot from taskRef.info.result as describe above for the create snapshot operation. The following Java code demonstrates how to delete the snapshot:

```
ManagedObjectReference removeSnapshotTask;
ManagedObjectReference snapshot; // Already initialized.
removeSnapshotTask = serviceConnection.getservice().removeSnapshot_Task(snapshot, Boolean FALSE);
```

Changed Block Tracking on Virtual Disks

On hosts running ESX/ESXi 4.0 and later, virtual machines can keep track of disk sectors that have changed. This is called changed block tracking. Its method in the VMware vSphere API is QueryChangedDiskAreas, which takes the following parameters:

- _this Managed object reference to the virtual machine.
- snapshot Managed object reference to a Snapshot of the virtual machine.
- deviceKey Virtual disk for which to compute the changes.
- startOffset Byte offset where to start computing changes to virtual disk. The length of virtual disk sector(s) examined is returned in DiskChangeInfo.
- changeId An identifier for the state of a virtual disk at a specific point in time. A new ChangeId results every time someone creates a snapshot. You should retain this value with the version of change data that you extract (using QueryChangedDiskAreas) from the snapshot's virtual disk.

When you back up a snapshot for the first time, ChangeId should be unset, or unsaved, indicating that a baseline (full) backup is required. If you have a saved ChangeId, it identifies the last time a backup was taken, and tells the changed block tracking logic to identify changes that have occurred since the time indicated by the saved ChangeId.

There are two ways to get this baseline backup:

- 1 Directly save the entire contents of the virtual disk.
- 2 Provide the special ChangeId "*" (star). The star indicates that QueryChangedDiskAreas should return only active portions of the virtual disk. For both thin provisioned (sparse) virtual disks and for ordinary virtual disks, this causes a substantial reduction in the amount of data to save.

To summarize, changeID is an identifier for a time in the past. It can be star "*" to identify all allocated areas of virtual disk, ignoring unallocated areas (of sparse disk), or it could be a changeId string saved at the time when a pre-backup snapshot was taken. It only makes sense to use the special ChangeId = "*" when no previous ChangeId exists. If a previous ChangeId does exist, then QueryChangedDiskAreas returns the disk sectors that changed since the new ChangeId was collected. Table 7-3 shows the algorithm.

Table 7-3. Use of Change ID for Changed Block Tracking

New Change ID	Old Change ID	Used for Query	Result
change 0	none	*	All in-use sectors of the disk.
change 1	change 0	change 0	All sectors altered since change 0.

The following restrictions are imposed on the "*" query when determining allocated areas of a virtual disk:

- The disk must be located on a VMFS volume (backing does not matter).
- The virtual machine must have had **no** (zero) snapshots when changed block tracking was enabled.

Enabling Changed Block Tracking

This feature is disabled by default, because it reduces performance by a small but measurable amount. If you query the virtual machine configuration, you can determine if it is capable of changed block tracking. Use the property collector to retrieve the capability field from the VirtualMachineManagedObject. If the capability field contains the flag changeTrackingSupported, then you can proceed. The virtual machine version must be 7 or higher to support this. If the virtual machine version is lower than 7, upgrade the virtual hardware.

If supported, you enable changed block tracking using an abbreviated form of VirtualMachineConfigSpec, then use the ReconfigVM_Task method to reconfigure the virtual machine with changed block tracking:

```
VirtualMachineConfigSpec configSpec = new VirtualMachineConfigSpec();
configSpec.changeTrackingEnabled = new Boolean(true);
ManagedObjectReference taskMoRef =
    serviceConnection.getService().ReconfiqVm_Task(targetVM_MoRef, configSpec);
```

Powered-on virtual machines must go through a stun-unstun cycle (triggered either by power on, migrate, resume after suspend, or snapshot create/delete/revert) before the virtual machine reconfiguration takes effect.

To enable changed block tracking with the vSphere Client:

- 1 Select the virtual machine and ensure that **Summary > VM Version** says "7" or higher compatibility.
- 2 In the Summary tab, click **Edit Settings > Options > Advanced > General**.
- 3 In the right side of the dialog box, click **Configuration Parameters...**
- In the new dialog box, locate or create a row with name ctkEnabled, and set its value to true not false. See above concerning the stun-unstun cycle.

To enable changed block tracking and back up with the VMware vSphere API:

- 1 Query change tracking status of the virtual machine. If false, activate changed block tracking.
 configSpec.changeTrackingEnabled = new Boolean(true);
- Create a snapshot of the virtual machine. The snapshot operation causes a stun-unstun cycle.
 CreateSnapshot_Task(VMmoRef, SnapshotName, Description, memory_files, quiesce_filesystem);
- 3 Starting from the snapshot's ConfigInfo, work your way to the BackingInfo of all virtual disks in the snapshot. This gives you the change IDs for all the disks of the virtual machine.
- 4 Hold onto the change IDs and do a full backup of the snapshot, since this is the first time for backup. VixDiskLib_Read(snapshotDiskHandle, startSector, numSectors, &buffer); /* C not Java */
- 5 Delete the snapshot when your backup has completed. removeSnapshot_Task(SnapshotName, Boolean FALSE);
- 6 Next time you back up this virtual machine, create a snapshot and use QueryChangedDiskAreas with the change IDs from your previous backup to take advantage of changed block tracking.

```
changes = theVM.queryChangedDiskAreas(SnapshotMoRef, diskDeviceKey, startPosition, changeId);
```

Gathering Changed Block Information

Associated with changed block tracking is changeId, an identifier for versions of changed block data. Whenever a virtual machine snapshot is created, associated with that snapshot is a changeId that functions as a landmark to identify changes in virtual disk data. So it follows that when a snapshot is created for the purpose of creating an initial virtual disk backup, the changeId associated with that snapshot can be used to retrieve changes that have occurred since snapshot creation.

To obtain the changeId associated with any disk in a snapshot, you examine the "hardware" array from the snapshot. Any item in the devices table that is of type vim.vm.device.VirtualDevice.VirtualDisk encloses a class describing the "backing storage" (obtained using getBacking) that implements virtual disk. If backing storage is one of the following disk types, you can use the changeId property of the BackingInfo data object to obtain the changeId:

```
vim.vm.device.VirtualDevice.VirtualDiskFlatVer2BackingInfo
vim.vm.device.VirtualDevice.VirtualDiskSparseVer2BackingInfo
vim.vm.device.VirtualDevice.VirtualDiskRawDiskMappingVer1BackingInfo
vim.vm.device.VirtualDevice.VirtualDiskRawDiskVer2BackingInfo
```

Information returned by the QueryChangedDiskAreas method is a DiskChangeInfo data object containing an array of DiskChangeInfo.DiskChangeExtent items that enumerate the start offset and length of various disk areas that changed, and the length and start offset of the entire disk area covered by DiskChangeInfo.

When using QueryChangedDiskAreas to gather information about snapshots, enable change tracking before taking a snapshot. Attempts to collect information about changes that occurred before change tracking was enabled result in a FileFault error. Enabling change tracking provides the additional benefit of saving space because it enables backup of only information that has changed. If change tracking is not enabled, the entire virtual machine must be backed up each time, rather than incrementally.

Changed block tracking is supported whenever the I/O operations are processed by the ESXi storage stack:

- For a virtual disk stored on VMFS, no matter what backs the VMFS volume (SAN or local disk).
- For a virtual disk stored on NFS.
- For an RDM in virtual compatibility mode.

When I/O operations are not processed by the ESXi storage stack, changed block tracking is not usable:

- For an RDM in physical compatibility mode.
- A disk that is accessed directly from inside a VM. For example if you are running an iSCSI initiator within the virtual machine to access an iSCSI LUN from inside the VM, vSphere cannot track it.

If the guest actually wrote to each block of a virtual disk (long format or secure erase), or if the virtual disk is thick and eager zeroed, or cloned thick disk, then the "*" query reports the entire disk as being in use.

To find change information, you can use the managed object browser at <a href="http://<ESXhost>/mob">http://<ESXhost>/mob to follow path content > rootFolder > datacenter > datastore > vm > snapshot > config > hardware > virtualDisk > backing. Changed block tracking information (changeId) appears in the BackingInfo.

The following C++ code sample assumes that, in the past, you obtained a complete copy of the virtual disk, and at the time when the changeId associated with the snapshot was collected, you stored it for use at a later time, which is now. A new snapshot has been created, and the appropriate moRef is available:

```
// Already initialized: changeId, snapshotMoRef, theVM
String changeId;
ManagedObjectReference snapshotMoRef;
ManagedObjectReference theVM;
int diskDeviceKey; // Identifies the virtual disk.
VirtualMachine.DiskChangeInfo changes;
long startPosition = 0;
do {
   changes = the VM. query Changed Disk Areas (snapshot MoRef, disk Device Key, start Position, change Id); \\
   for (int i = 0; i < changes.changedArea.length; i++) {</pre>
      long length = changes.changedArea[i].length;
      long offset = changes.changedArea[i].startOffset;
      // Go get and save disk data here
   }
   startPosition = changes.startOffset + changes.length;
} while (startPosition < diskCapacity);</pre>
```

In the above code, QueryChangedDiskAreas is called repeatedly, as position moves through the virtual disk. This is because the number of entries in the ChangedDiskArea array could occupy a large amount of memory for describing changes to a large virtual disk. Some disk areas may have no changes for a given changeId.

The changeId (changed block ID) contains a sequence number in the form <UUID>/<nnn>. If <UUID> changes, it indicates that tracking information has become invalid, necessitating a full backup. Otherwise incremental backups can continue in the usual pattern.

Troubleshooting

If you reconfigure a virtual machine to set changeTrackingEnabled, but the property remains false, check that you have queried the virtual machine status with VirtualMachine->config() after reconfiguration with VirtualMachine->reconfigure() and not before. Also make sure that virtual machine compatibility is hardware version 7 or higher, and that it has undergone a stun-unstun cycle since reconfiguration.

Limitations on Changed Block Tracking

Changed block tracking does not work if the virtual hardware version is 6 or earlier, in physical compatibility RDM mode, or when the virtual disk is attached to a shared virtual SCSI bus. ESX/ESXi 3.5 supported only up to virtual hardware version 4.

Changed block tracking can be enabled on virtual machines that have disks like these, but when queried for their change ID, these disks always return an empty string. So if you have a virtual machine with a regular system disk and a pass-through RDM as a data disk, you can track changes only on the system disk.

Checking for Namespace

You can avoid using the queryChangedDiskAreas API on ESX/ESXi 3.5 based storage by parsing XML files for the namespace. For prepackaged methods that do this, see these SDK code samples:

Axis/java/com/vmware/samples/version/displaynewpropertieshost/DisplayNewPropertiesHostV25.java Axis/java/com/vmware/samples/version/getvirtualdiskfiles/GetVirtualDiskFilesV25.java DotNet/cs/DisplayNewProperties/DisplayNewPropertiesV25.cs DotNet/cs/GetVirtualDiskFiles/GetVirtualDiskFilesV25.cs

Low Level Restore Procedures

The following sections describe how to recover virtual machines and restore virtual disk data.

- "Restoring a Virtual Machine and Disk" on page 73
- "Restore of Incremental Backup Data" on page 80

Restoring a Virtual Machine and Disk

You cannot get write access to a virtual disk that is in active use. For a full restore, you first must ensure that the virtual disk is not in use by halting the parent virtual machine, then performing the "power off" sequence. The following code sample demonstrates how to "power off" a Virtual Machine:

```
// At this point we assume that you have a ManagedObjectReference to the VM - vmMoRef.
// Power on would need a ManagedObjectReference to the host running the VM - hostMoRef.
ManagedObjectReference taskRef = serviceConnection.powerOffVm(vmMoRef);
```

With SAN transport mode, before virtual disk restore, you must create a snapshot of the virtual machine. See "Creating a Snapshot" on page 68. Formerly the snapshot was required for other advanced transport modes (such as HotAdd) but as of VDDK 5.0 is required only for SAN mode. If at restore time the virtual machine had a pre-existing snapshot, you should remove it, otherwise the SAN mode restore will fail.

In this phase you use VixDiskLib to reload contents of the Virtual Disk, so the following code is C++ not Java:

```
// At this point we assume that you already have a VixDiskLib connection to the server machine.
uint8 mybuffer[some_multiple_of_512];
int mylocalfile = open("localfile", openflags); // Contains backup copy of virtual disk.
read(mylocalfile, mybuffer, sizeof mybuffer);
vixError = VixDiskLib_Open(srcConnection, path, flags, &diskHandle);
VixDiskLib_Write(diskHandle, startsector, (sizeof mybuffer) / 512, mybuffer);
```

With SAN transport mode, you must revert-to and delete the snapshot. If you forget the snapshot revert, snapshot delete will fail due to CID mismatch, so the virtual machine cannot be powered on. If you forget the snapshot delete, the extraneous snapshot will cause restore problems for subsequent backups.

Creating a Virtual Machine

This section shows how to create a VirtualMachine object, which is complicated but necessary so you can restore data into it. Before creating this object, you must create a VirtualMachineConfigSpec describing the virtual machine and all of its supporting virtual devices. Almost all the required information is available from the virtual machine property config.hardware.device, which is a table containing the device configuration information. The relationships between devices are described by the value key, which is a unique identifier for the device. In turn, each device has a controllerKey, which is the key identifier of the controller where the device is connected. Use negative integers as temporary key values in the VirtualMachineConfigSpec to guarantee that temporary key numbers do not conflict with real key numbers when they are assigned by the server. When associating virtual devices with default devices, the controllerKey property should be reset with the key property of the controller. Below are the settings for a sample VirtualMachineConfigSpec used to create a virtual machine.

```
// beginning of VirtualMachineConfigSpec, ends several pages later
{
   dynamicType = <unset>,
   changeVersion = <unset>,
//This is the display name of the VM
   name = "My New VM",
```

```
version = "vmx-04",
  uuid = <unset>,
   instanceUuid = <unset>,
  npivWorldWideNameType = <unset>,
  npivDesiredNodeWwns = <unset>,
  npivDesiredPortWwns = <unset>,
  npivTemporaryDisabled = <unset>,
  npivOnNonRdmDisks = <unset>,
  npivWorldWideNameOp = <unset>,
  locationId = <unset>,
// This is advisory, the disk determines the O/S
guestId = "winNetStandardGuest",
   alternateGuestName = "Microsoft Windows Server 2003, Standard Edition (32-bit)",
   annotation = <unset>,
   files = (vim.vm.FileInfo) {
      dynamicType = <unset>,
      vmPathName = "[plat004-local]",
      snapshotDirectory = "[plat004-local]",
      suspendDirectory = <unset>,
      logDirectory = <unset>,
  },
   tools = (vim.vm.ToolsConfigInfo) {
      dynamicType = <unset>,
      toolsVersion = <unset>,
      afterPowerOn = true,
      afterResume = true,
      beforeGuestStandby = true,
      beforeGuestShutdown = true,
      beforeGuestReboot = true,
      toolsUpgradePolicy = <unset>,
      pendingCustomization = <unset>,
      syncTimeWithHost = <unset>,
   flags = (vim.vm.FlagInfo) {
      dynamicType = <unset>,
      disableAcceleration = <unset>,
      enableLogging = <unset>,
      useToe = <unset>,
      runWithDebugInfo = <unset>,
      monitorType = <unset>,
      htSharing = <unset>,
      snapshotDisabled = <unset>,
      snapshotLocked = <unset>,
      diskUuidEnabled = <unset>,
      virtualMmuUsage = <unset>,
      snapshotPowerOffBehavior = "powerOff",
      recordReplayEnabled = <unset>,
  },
  consolePreferences = (vim.vm.ConsolePreferences) null,
   powerOpInfo = (vim.vm.DefaultPowerOpInfo) {
      dynamicType = <unset>,
      powerOffType = "preset"
      suspendType = "preset",
      resetType = "preset",
      defaultPowerOffType = <unset>,
      defaultSuspendType = <unset>,
      defaultResetType = <unset>,
      standbyAction = "powerOnSuspend",
  }.
// the number of CPUs
  numCPUs = 1,
// the number of memory megabytes
  memoryMB = 256,
  memoryHotAddEnabled = <unset>,
   cpuHotAddEnabled = <unset>,
   cpuHotRemoveEnabled = <unset>,
  deviceChange = (vim.vm.device.VirtualDeviceSpec) [
      (vim.vm.device.VirtualDeviceSpec) {
```

```
dynamicType = <unset>,
         operation = "add",
         fileOperation = <unset>,
// CDROM
         device = (vim.vm.device.VirtualCdrom) {
           dynamicType = <unset>,
// key number of CDROM
           key = -42,
            deviceInfo = (vim.Description) null,
           backing = (vim.vm.device.VirtualCdrom.RemotePassthroughBackingInfo) {
               dynamicType = <unset>,
               deviceName = "",
               useAutoDetect = <unset>,
               exclusive = false,
            },
            connectable = (vim.vm.device.VirtualDevice.ConnectInfo) {
               dynamicType = <unset>,
               startConnected = false,
               allowGuestControl = true,
               connected = false,
           },
// connects to this controller
            controllerKey = 200,
            unitNumber = 0,
         },
     },
      (vim.vm.device.VirtualDeviceSpec) {
         dynamicType = <unset>,
         operation = "add",
         fileOperation = <unset>,
// SCSI controller
         device = (vim.vm.device.VirtualLsiLogicController) {
            dynamicType = <unset>,
// key number of SCSI controller
            key = -44,
            deviceInfo = (vim.Description) null,
            backing = (vim.vm.device.VirtualDevice.BackingInfo) null,
            connectable = (vim.vm.device.VirtualDevice.ConnectInfo) null,
           controllerKey = <unset>,
           unitNumber = <unset>,
            busNumber = 0,
            hotAddRemove = <unset>,
            sharedBus = "noSharing",
            scsiCtlrUnitNumber = <unset>,
         },
     },
      (vim.vm.device.VirtualDeviceSpec) {
         dynamicType = <unset>,
         operation = "add",
         fileOperation = <unset>.
// Network controller
         device = (vim.vm.device.VirtualPCNet32) {
            dynamicType = <unset>,
// key number of Network controller
            key = -48,
            deviceInfo = (vim.Description) null,
            backing = (vim.vm.device.VirtualEthernetCard.NetworkBackingInfo) {
               dynamicType = <unset>,
               deviceName = "Virtual Machine Network",
               useAutoDetect = <unset>,
               network = <unset>,
               inPassthroughMode = <unset>,
            },
            connectable = (vim.vm.device.VirtualDevice.ConnectInfo) {
               dynamicType = <unset>,
               startConnected = true,
               allowGuestControl = true,
               connected = true,
```

```
controllerKey = <unset>,
            unitNumber = <unset>,
            addressType = "generated",
            macAddress = <unset>,
           wakeOnLanEnabled = true,
         },
     },
      (vim.vm.device.VirtualDeviceSpec) {
         dynamicType = <unset>,
         operation = "add",
         fileOperation = "create",
// SCSI disk one
         device = (vim.vm.device.VirtualDisk) {
            dynamicType = <unset>,
// key number for SCSI disk one
            key = -1000000,
            deviceInfo = (vim.Description) null,
            backing = (vim.vm.device.VirtualDisk.FlatVer2BackingInfo) {
               dynamicType = <unset>,
               fileName = "".
               datastore = <unset>,
               diskMode = "persistent",
               split = false,
               writeThrough = false,
               thinProvisioned = <unset>,
               eagerlyScrub = <unset>,
               uuid = <unset>,
               contentId = <unset>,
               changeId = <unset>,
               parent = (vim.vm.device.VirtualDisk.FlatVer2BackingInfo) null,
           },
            connectable = (vim.vm.device.VirtualDevice.ConnectInfo) {
               dynamicType = <unset>,
               startConnected = true,
               allowGuestControl = false,
               connected = true,
// controller for SCSI disk one
           controllerKey = -44,
           unitNumber = 0,
// size in MB SCSI disk one
           capacityInKB = 524288,
            committedSpace = <unset>,
            shares = (vim.SharesInfo) null,
         },
     },
      (vim.vm.device.VirtualDeviceSpec) {
         dynamicType = <unset>,
         operation = "add",
         fileOperation = "create",
// SCSI disk two
         device = (vim.vm.device.VirtualDisk) {
           dynamicType = <unset>,
// key number of SCSI disk two
            key = -100,
            deviceInfo = (vim.Description) null,
            backing = (vim.vm.device.VirtualDisk.FlatVer2BackingInfo) {
               dynamicType = <unset>,
               fileName = "".
               datastore = <unset>,
               diskMode = "persistent",
               split = false,
               writeThrough = false,
               thinProvisioned = <unset>,
               eagerlyScrub = <unset>,
               uuid = <unset>,
               contentId = <unset>,
```

```
changeId = <unset>,
               parent = (vim.vm.device.VirtualDisk.FlatVer2BackingInfo) null,
           },
            connectable = (vim.vm.device.VirtualDevice.ConnectInfo) {
               dynamicType = <unset>,
               startConnected = true.
               allowGuestControl = false,
               connected = true,
           },
// controller for SCSI disk two
           controllerKey = -44.
           unitNumber = 1,
// size in MB SCSI disk two
            capacityInKB = 131072,
            committedSpace = <unset>,
            shares = (vim.SharesInfo) null,
         },
     }
  },
  cpuAllocation = (vim.ResourceAllocationInfo) {
     dynamicType = <unset>,
      reservation = 0,
      expandableReservation = <unset>,
     limit = <unset>,
      shares = (vim.SharesInfo) {
         dynamicType = <unset>,
         shares = 100,
         level = "normal",
     },
     overheadLimit = <unset>,
  },
  memoryAllocation = (vim.ResourceAllocationInfo) {
     dynamicType = <unset>,
      reservation = 0,
      expandableReservation = <unset>,
      limit = <unset>,
      shares = (vim.SharesInfo) {
         dynamicType = <unset>,
         shares = 100.
         level = "normal",
     overheadLimit = <unset>,
  },
  cpuAffinity = (vim.vm.AffinityInfo) null,
  memoryAffinity = (vim.vm.AffinityInfo) null,
  networkShaper = (vim.vm.NetworkShaperInfo) null,
   swapPlacement = <unset>,
   swapDirectory = <unset>,
  preserveSwapOnPowerOff = <unset>,
   bootOptions = (vim.vm.BootOptions) null,
  appliance = (vim.vService.ConfigSpec) null,
   ftInfo = (vim.vm.FaultToleranceConfigInfo) null,
  applianceConfigRemoved = <unset>,
  vAssertsEnabled = <unset>,
   changeTrackingEnabled = <unset>,
// end of VirtualMachineConfigSpec
```

The information above is quite complex, but much of the input consists of defaulted values that are assigned by the system. The remainder of the supplied information can be extracted from the output of the config.hardware.device table returned from PropertyCollector. Borrowing heavily from an SDK code example, the following code sets up the configuration specification:

```
// Duplicate virtual machine configuration
VirtualMachineConfigSpec configSpec = new VirtualMachineConfigSpec();
// Set the VM values
configSpec.setName("My New VM");
configSpec.setVersion("vmx-04");
```

```
configSpec.setGuestId("winNetStandardGuest");
configSpec.setNumCPUs(1);
configSpec.setMemoryMB(256);
// Set up file storage info
VirtualMachineFileInfo vmfi = new VirtualMachineFileInfo();
vmfi.setVmPathName("[plat004-local]");
configSpec.setFiles(vmfi);
vmfi.setSnapshotDirectory("[plat004-local]");
// Set up tools config info
ToolsConfigInfo tools = new ToolsConfigInfo();
configSpec.setTools(tools);
tools.setAfterPowerOn(new Boolean(true));
tools.setAfterResume(new Boolean(true));
tools.setBeforeGuestStandby(new Boolean(true));
tools.setBeforeGuestShutdown(new Boolean(true));
tools.setBeforeGuestReboot(new Boolean(true));
// Set flags
VirtualMachineFlagInfo flags = new VirtualMachineFlagInfo();
configSpec.setFlags(flags);
flags.setSnapshotPowerOffBehavior("powerOff");
// Set power on info
VirtualMachineDefaultPowerOpInfo powerInfo = new VirtualMachineDefaultPowerOpInfo();
configSpec.setPowerOpInfo(powerInfo);
powerInfo.setPowerOffType("preset");
powerInfo.setSuspendType("preset");
powerInfo.setResetType("preset");
powerInfo.setStandbyAction("powerOnSuspend");
// Now add in the devices
VirtualDeviceConfigSpec[] deviceConfigSpec = new VirtualDeviceConfigSpec [5];
configSpec.setDeviceChange(deviceConfigSpec);
// Formulate the CDROM
deviceConfigSpec[0].setOperation(VirtualDeviceConfigSpecOperation.add);
VirtualCdrom cdrom = new VirtualCdrom();
VirtualCdromIsoBackingInfo cdDeviceBacking = new VirtualCdromRemotePassthroughBackingInfo();
cdDeviceBacking.setDatastore(datastoreRef);
cdrom.setBacking(cdDeviceBacking);
cdrom.setKey(-42);
cdrom.setControllerKey(new Integer(-200)); // Older Java required type for optional properties
cdrom.setUnitNumber(new Integer(0));
deviceConfigSpec[0].setDevice(cdrom);
// Formulate the SCSI controller
deviceConfigSpec[1].setOperation(VirtualDeviceConfigSpecOperation.add);
VirtualLsiLogicController scsiCtrl = new VirtualLsiLogicController();
scsiCtrl.setBusNumber(0);
deviceConfigSpec[1].setDevice(scsiCtrl);
scsiCtrl.setKey(-44);
scsiCtrl.setSharedBus(VirtualSCSISharing.noSharing);
// Formulate SCSI disk one
deviceConfiqSpec[2].setFileOperation(VirtualDeviceConfiqSpecFileOperation.create);
deviceConfigSpec[2].setOperation(VirtualDeviceConfigSpecOperation.add);
VirtualDisk disk = new VirtualDisk();
VirtualDiskFlatVer2BackingInfo diskfileBacking = new VirtualDiskFlatVer2BackingInfo();
diskfileBacking.setDatastore(datastoreRef);
diskfileBacking.setFileName(volumeName);
diskfileBacking.setDiskMode("persistent");
diskfileBacking.setSplit(new Boolean(false));
diskfileBacking.setWriteThrough(new Boolean(false));
disk.setKey(-1000000);
disk.setControllerKey(new Integer(-44));
disk.setUnitNumber(new Integer(0));
disk.setBacking(diskfileBacking);
disk.setCapacityInKB(524288);
deviceConfigSpec[2].setDevice(disk);
// Formulate SCSI disk two
deviceConfigSpec[3].setFileOperation(VirtualDeviceConfigSpecFileOperation.create);
deviceConfigSpec[3].setOperation(VirtualDeviceConfigSpecOperation.add);
VirtualDisk disk2 = new VirtualDisk();
VirtualDiskFlatVer2BackingInfo diskfileBacking2 = new VirtualDiskFlatVer2BackingInfo();
```

```
diskfileBacking2.setDatastore(datastoreRef);
diskfileBacking2.setFileName(volumeName);
diskfileBacking2.setDiskMode("persistent");
diskfileBacking2.setSplit(new Boolean(false));
diskfileBacking2.setWriteThrough(new Boolean(false));
disk2.setKey(-100);
disk2.setControllerKey(new Integer(-44));
disk2.setUnitNumber(new Integer(1));
disk2.setBacking(diskfileBacking2);
disk2.setCapacityInKB(131072);
deviceConfigSpec[3].setDevice(disk2);
// Finally, formulate the NIC
deviceConfigSpec[4].setOperation(VirtualDeviceConfigSpecOperation.add);
com.VMware.vim.VirtualEthernetCard nic = new VirtualPCNet32();
VirtualEthernetCardNetworkBackingInfo nicBacking = new VirtualEthernetCardNetworkBackingInfo();
nicBacking.setNetwork(networkRef);
nicBacking.setDeviceName(networkName);
nic.setAddressType("generated");
nic.setBacking(nicBacking);
nic.setKey(-48);
deviceConfigSpec[4].setDevice(nic);
// Now that it is all put together, create the virtual machine.
// Note that folderMo, resourcePool, and hostMo, are moRefs to the Folder, ResourcePool, and Host
// where the VM is to be created
ManagedObjectReference taskMoRef =
    serviceConnection.getService().createVM_Task(folderMo, configSpec, resourcePool, hostMo);
```

Using the VirtualMachineConfigInfo

A backup application can also use information contained in a VirtualMachineConfigInfo. If at backup time you preserve all the VirtualMachineConfigInfo details that describe the virtual machine, you can transfer much of this information into a VirtualMachineConfigSpec to create a virtual machine at restore time. However, some of the information in VirtualMachineConfigInfo is not needed, and if used in the Spec, virtual machine creation can fail. For example, a VirtualMachineConfigSpec that contains information about so called "Default Devices" usually fails. The list of default devices includes:

```
vim.vm.device.VirtualIDEController vim.vm.device.VirtualPS2Controller vim.vm.device.VirtualPCIController vim.vm.device.VirtualSIOController vim.vm.device.VirtualKeyboard vim.vm.device.VirtualVMCIDevice vim.vm.device.VirtualPointingDevice
```

However, other controllers and devices must be explicitly included in the VirtualMachineConfigSpec. Some information about devices is unneeded and can cause problems if supplied. Each controller device has its vim.vm.device.VirtualController.device field, which is an array of devices that report to the controller. The server rebuilds this list when a virtual machine is created, using the (negative) device key numbers supplied as a guide. The relationship between controller and device must be preserved using negative key numbers in the same relationship as in the hardware array of VirtualMachineConfigInfo.

The parent property for virtual disk backing information must be set to null. In the sample code for creating a virtual machine, find vim.vm.device.VirtualDisk.FlatVer2BackingInfo on page 76 and page 77. The null setting is required because the pre-backup snapshot causes the parent property to be populated with a reference to the base disk.

One other configuration needs substitution. VirtualMachineConfigInfo contains the cpuFeatureMask, field, which is an array of HostCpuIdInfo. The array entries must be converted to ArrayUpdateSpec entries containing the VirtualMachineCpuIdInfoSpec along with the "operation" field, which must contain the value ArrayUpdateOperation::add. The VirtualMachineCpuIdInfoSpec also contains a HostCpuIdInfo array that you can copy from the cpuFeatureMask array in VirtualMachineConfigInfo. These items are not reflected in the sample code.

Everything else can be copied intact from VirtualMachineConfigInfo data.

To summarize: when creating a virtual machine in which to restore virtual disk:

- Exclude default devices, and VirtualController.device, from the VirtualMachineConfigSpec.
- Set the parent virtual disk backing information (VirtualDisk.FlatVer2BackingInfo) to null.
- Convert HostCpuIdInfo array entries to ArrayUpdateSpec, insert ArrayUpdateOperation::add, and copy the HostCpuIdInfo array from cpuFeatureMask into VirtualMachineConfigInfo.

Editing or Deleting a Device

If backup clients want to edit or delete a device, they must use the server-provided key when referring to an existing device. For the definition of key, see "Creating a Virtual Machine" on page 73. For example, see the key and controllerKey for CDROM in the source code on page 75. The key uniquely identifies a device, while the controllerKey uniquely identifies the controller where it is connected.

Restoring Virtual Disk Data

As in the section "Low Level Restore Procedures" on page 73, VixDiskLib functions provide interfaces for writing the data to virtual disk, either locally or remotely.

Raw Device Mapping (RDM) Disks

To create an RDM disk using CreateVM_Task, use a LUN that is not occupied and thus is still available. Developers sometimes use the same LUN uuid that is available in the configInfo object, which can cause errors because the LUN uuid is datastore specific.

Call QueryConfigTarget to fetch the ConfigTarget.ScsiDisk.Disk.CanonicalName property, set in VirtualDiskRawDiskMappingVer1BackInfo.deviceName. Also call QueryConfigTarget to fetch ConfigTarget.ScsiDisk.Disk.uuid, set in VirtualDiskRawDiskMappingVer1BackInfo.lunUuid. When creating the virtual machine, avoid host-specific properties of configInfo, which should be set according to host configuration where the virtual machine is restored.

Restore of Incremental Backup Data

At some point you might need to restore a virtual disk from the backup data that you gathered as described in "Changed Block Tracking on Virtual Disks" on page 70. The essential procedure is as follows:

- 1 Power off the virtual machine, if powered on.
- 2 Using VirtualMachineConfigInfo that corresponds to the last known good state of the guest operating system, re-create the virtual machine as described in "Using the VirtualMachineConfigInfo" on page 79.
- 3 Completely reload the base virtual disk using the full backup that started the most recent series of incremental backups.
- 4 Create a snapshot. This is mandatory for SAN mode restore.
- 5 For SAN mode restore, disable changed block tracking. SAN writes are not possible with it enabled.
- 6 Sequentially restore the incremental backup data. You can do this either forwards or backwards. If you work forwards, the restore might write some sectors more than once. If you work backwards, you must keep track of which sectors were restored so as to avoid restoring them again from older data.
 - a From your backup records, get the change ID of the incremental backup to be restored. Your software must also store the changed-block information, so it knows which sectors of virtual disk to restore. Once you start restoring virtual disk, the change tracking mechanism will misreport.
 - b Restore only changed areas to the virtual disks referred to by the snapshot. This ensures that you do not write the data to the redo log created by the snapshot. When restoring a thin provisioned (sparse) disk, use the star "*" change ID to avoid writing zeroes to the unallocated blocks.
 - c Repeat Step a and Step b as necessary by applying incremental backup data sets in order.
- 7 If applicable, revert to the base virtual disk, thus eliminating the snapshot.

Restore Fails with Direct Connection to ESXi Host

Sometimes you must restore a virtual machine directly to an ESXi host, for example in disaster recovery when vCenter Server runs on ESXi as a virtual machine. A new vSphere 5 feature tries to prevent this if the ESXi host is managed by vCenter. To circumvent this and restore the virtual machine, you must first disassociate the host from vCenter. In earlier releases, vCenter management had less state but was revocable only from vCenter.

- 1 Using the vSphere Client, connect directly to the ESXi 5.0 or later host.
- 2 In the Inventory left-hand panel, select the host. In the right-hand panel, click Summary.
- 3 In the box titled Host Management, click **Disassociate host from vCenter Server**. You do not need to put the host in Maintenance Mode.
- 4 After the vCenter Server has been restored and is back in service, use it to reacquire the host.

Currently there is no API to disassociate a host from vCenter Server.

Tips and Best Practices

VDDK 5.0 contained two new VixDiskLib calls (PrepareForAccess and EndAccess) to disable and enable Storage vMotion during backup. This prevents stale disk images from being left behind if a virtual machine has its storage moved while a backup is taking place. VMware strongly recommends use of these calls.

When an ESX/ESXi host is managed by vCenter Server, vSphere API calls cannot contact the host directly: they must go through vCenter. If necessary, especially during disaster recovery, the administrator must disassociate the ESXi host from vCenter Server before the host can be contacted directly.

Advanced transports allow programs to transfer data in the most efficient manner. SAN transport is available only when the physical-machine host has SAN access. HotAdd works for the appliance model, where backup is done from inside virtual machines. HotAdd requires the virtual machine datastore to be accessible from the backup appliance. NBDSSL is a secure fallback when over-the-network backup is your only choice.

Best Practices for SAN Transport

For array-based storage, SAN transport is often the best performing choice for backups when running on a physical proxy. It is disabled inside virtual machines, so use SCSI HotAdd instead on a virtual proxy.

SAN transport is not always the best choice for restores. It offers the best performance on thick disks, but the worst performance on thin disks, because of round trips through the disk manager APIs, AllocateBlock and ClearLazyZero. For thin disk restore, NBDSSL is usually faster, and NBD is even faster. Changed Block Tracking (CBT) must be disabled for SAN restores. Also, SAN transport does not support writing to redo logs (snapshots or child disks), only to base disks.

When writing to SAN during restore, disk size should be a multiple of the underlying VMFS block size, otherwise write to the last fraction of a disk will fail. For example, if virtual disk has a 1MB block size and the datastore is 16.3MB large, the last 0.3MB will not get written. Add 0.7MB of zeroes to complete the block.

Programs that open a local virtual disk in SAN mode might be able to read (if the disk is empty) but writing will throw an error. Even if programs call VixDiskLib_ConnextEx() with NULL parameter to accept the default transport mode, SAN is selected as the preferred mode if SAN storage is connected to the ESXi host. VixDiskLib should, but does not, check SAN accessibility on open. With local disk, programs must explicitly request NBD or NBDSSL mode.

For a Windows Server 2008 proxy, set SAN policy to onlineAll. Set SAN disk to read-only except for restore. You can use the **diskpart** utility to clear the read-only flag. SAN policy varies by Windows Server 2008 edition. For Enterprise and Datacenter editions, the default Windows SAN policy is offline, which is unnecessary when vSphere mediates SAN storage.

Best Practices for HotAdd Transport

Deploy the proxy on VMFS-5 volumes, or on VMFS-3 volumes capable of large block size (see "About the HotAdd Proxy" on page 24) so that the proxy can back up very large virtual disks.

A redo log is created for HotAdded disks, on the same datastore as the base disks. Do not remove the target virtual machine (the one being backed up) while HotAdded disk is still attached. If removed, HotAdd fails to properly clean up redo logs so virtual disks must be removed manually from the backup appliance. Also, do not remove the snapshot until after cleanup. Removing it could result in an unconsolidated redo log.

HotAdd is a SCSI feature and does not work for IDE disks. The paravirtual SCSI controller (PVSCSI) is not supported for HotAdd; use the LSI controller instead.

Removing all disks on a controller with the vSphere Client also removes the controller. You might want to include some checks in your code to detect this in your appliance, and reconfigure to add controllers back in.

Virtual disk created on Windows by HotAdd backup or restore might have a different disk signature than the original virtual disk. The workaround is to reread or rewrite the first disk sector in NBD mode.

HotAdded disks should be released with VixDiskLib_Cleanup() before snapshot delete. Cleanup might cause improper removal of the change tracking (ctk) file. You can fix it by power cycling the virtual machine.

Customers running a Windows Server 2008 proxy on SAN storage should set SAN policy to onlineAll (see note about SAN policy in "Best Practices for SAN Transport" on page 81).

Best Practices for NBDSSL Transport

Various versions of ESX/ESXi have different defaults for NBD timeouts. Some have no timeouts. VMware recommends that you specify a default NBD timeout in the VixDiskLib configuration file. If you do not specify a timeout, some versions of ESX/ESXi will hold the corresponding disk open indefinitely, until vpxa or hostd is restarted. However, if you set a timeout, you might have to perform some "keepalive" operations to prevent the disk from being closed on the server side. Reading block 0 periodically is a good keepalive operation.

Before ESXi 5.0 there were no default network file copy (NFC) timeouts. Default NFC timeout values may change in future releases. VMware recommends that you specify default NFC timeouts in the VixDiskLib configuration file. If you do not specify a timeout, older versions of ESX/ESXi hold the corresponding disk open indefinitely, until vpxa or hostd is restarted. However with a timeout, you might need to perform some "keepalive" operation to prevent the disk from being closed on the server side. Reading block 0 periodically is a good keepalive operation.

As a starting point, recommended settings are 3 minutes for Accept and Request, 1 minute for Read, 10 minutes for Write, and no timeouts (0) for nfcFssrvr and nfcFssrvrWrite.

General Backup and Restore

For incremental backup of virtual disk, always enable changed block tracking (CBT) before the first snapshot. When doing full restores of virtual disk, disable CBT for the duration of the restore. File-based restores affect change tracking, but disabling CBT is optional for partial restores, except with SAN transport. CBT should be disabled for SAN transport writes because the file system must be able to account for thin-disk allocation and clear-lazy-zero operations.

Backup software should ignore independent disks (those not capable of snapshots). These virtual disks are unsuitable for backup. They throw an error if a snapshot is attempted on them.

To back up thick disk, the proxy's datastore must have at least as much free space as the maximum configured disk size for the backed-up virtual machine. Thin-provisioned disk is often faster to back up.

If you do a full backup of lazy-zeroed thick disk with CBT disabled, the software reads all sectors, converting data in empty (lazy-zero) sectors to actual zeros. Upon restore, this full backup data will produce eager-zeroed thick disk. This is one reason why VMware recommends enabling CBT before the first snapshot.

Backup and Restore of Thin-Provisioned Disk

Thin-provisioned virtual disk is created on first write. So the first-time write to thin-provisioned disk involves extra overhead compared to thick disk, whether using NBD, NBDSSL, or HotAdd. This is due to block allocation overhead, not VDDK advanced transports. However once thin disk has been created, performance is similar to thick disk, as discussed in the *Performance Study of VMware vStorage Thin Provisioning*.

When applications perform random I/O or write to previously unallocated areas of thin-provisioned disk, subsequent backups can be larger than expected, even with CBT enabled. In some cases, disk defragmentation might help reduce the size of backups.

Virtual Machine Configuration

Do not make verbatim copies of configuration files, which can change. For example, entries in the .vmx file point to the snapshot, not the base disk. The .vmx file contains virtual-machine specific information about current disks, and attempting to restore this information could fail. Instead use PropertyCollector and keep a record of the ConfigInfo structure.

About Changed Block Tracking

QueryChangedDiskAreas("*") returns information about areas of a virtual disk that are in use (allocated). The current implementation depends on VMFS properties, similar to propertues that SAN transport mode uses to locate data on a SCSI LUN. Both rely on unallocated areas (file holes) in virtual disk, and the LazyZero designation for VMFS blocks. Thus, changed block tracking yields meaningful results only on VMFS. On other storage types, it either fails, or returns a single extent covering the entire disk.

You should enable changed block tracking in the order recommended by "Enabling Changed Block Tracking" on page 70. The first time you call QueryChangedDiskAreas ("*"), it should return allocated areas of virtual disk. Subsequent calls return changed areas, instead of allocated areas. If you call QueryChangedDiskAreas after a snapshot but before you enable changed block tracking, it also returns unallocated areas of virtual disk. With thin-provisioned virtual disk this could be a large amount of zero data.

The guest operating system has no visibility of changed block tracking. Once a virtual machine has written to a block on virtual disk, the block is considered in use. The information required for the "*" query is computed when changed block tracking is enabled, and the .ctk file is pre-filled with allocated blocks. The mechanism cannot report changes made to virtual disk before changed block tracking was enabled.

Windows and Linux Implementations

The following sections discuss issues that depend on whether a virtual machine is running Windows or Linux.

The VMware VSS Implementation

On Windows Server 2008, disk UUIDs must be enabled for VSS quiesced snapshots. Disk UUIDs might not be enabled if a virtual machine was upgraded from virtual hardware version 4.

VMware VSS does not support virtual machines with IDE disks, nor does it support virtual machines with an insufficient number of free SCSI slots.

Before vSphere 5.1, reverting to a writable snapshot sometimes left orphaned virtual disks that the system never removed. In the vSphere 5.1 release, writable snapshots are correctly accounted for as sibling snapshots. This permits cleaner management, because the disk chain matches the snapshot hierarchy, and it avoids orphaned disks. Most backup software takes a read-only snapshot so is not affected. VSS backup software may create two snapshots, one made writable by calling CreateSnapshot_task with the quiesce flag set true.

To add support for granular application control, specify:

- whether pre-freeze and post-thaw scripts get invoked
- whether quiescing gets invoked
- VSS snapshot context (application, file system quiescing, and so forth)
- VSS backup context (full, differential, incremental)
- writers/components to be involved during quiescing
- whether to fail quiescing or continue if one of the writers fails to quiesce
- retry count

A VSS quiesced snapshot reports as VSS_BT_COPY to VSS, hence no log truncation. The VSS manifest can be downloaded with HTTP. By default, all VSS writers are involved, but a mechanism for excluding writers exists; see the VMware KB article 1031200. For help troubleshooting, see KB article 1007696.

Working with Microsoft Shadow Copy

Microsoft Shadow Copy, also called Volume Snapshot Service (VSS), is a Windows Server data backup feature for creating consistent point-in-time copies of data (called shadow copies).

When performing VSS quiescing while creating the snapshot of a Windows virtual machine, VMware Tools generate a vss-manifest.zip file containing the backup components document (BCD) and writer manifests. The host agent stores this manifest file in the snapshotDir of the virtual machine. Backup applications should get the vss-manifest.zip file so they can save it to backup media. There are several ways to get this file:

- Using the datastore access HTTPS protocol, for example by browsing to https://<server-or-host>/folder/ and continuing downward to the snapshot directory until you find the vss-manifest.zip file.
- By calling the CopyDatastoreFile_Task method in the vSphere API. This method accepts the URL formulated above for HTTPS, or a datastore path. (CopyVirtualDisk_Task is for VMDK files).
- With the vifs command in the vMA or vCLI (formerly RCLI).
- With the Copy—DatastoreItem cmdlet in the PowerCLI (requires PowerShell and VMware snap-in).

The type of quiescing used varies depending on the operating system of the backed-up virtual machine, as shown in Table 7-4. ESX/ESXi 4.1 added support for Windows 2008 guests using application level quiescing.

Table 7-4. Driver Type and Quiescing Mechanisms Used According to Guest Operating Systems

Guest Operating System	Driver Type Used	Quiescing Type Used
Windows XP 32-bit Windows 2000 32-bit	Sync Driver	File-system consistent quiescing
Windows Vista 32- or 64-bit Windows 7 32- or 64-bit	VMware VSS component	File-system consistent quiescing
Windows 2003 32- or 64-bit	VMware VSS component	Application-consistent quiescing
Windows 2008 32- or 64-bit Windows Server 2008 R2	VMware VSS component	Application-consistent quiescing. For application-consistent quiescing to be available, several conditions must be met:
		 Virtual machine must be running on ESXi 4.1 or later. The UUID attribute must be enabled. It is enabled by default for virtual machines created on 4.1 or later. For details about enabling this attribute see "Enable Windows 2008 Virtual Machine Application Consistent Quiescing" on page 85. The virtual machine must use SCSI disks only and have
		as many free SCSI slots as the number of disks. Application-consistent quiescing is not supported for virtual machines with IDE disks.
		■ The virtual machine must not use dynamic disks.
Windows Server 2012	VMware VSS component	Same as above.
Other guest operating system	Not applicable	Crash-consistent quiescing

Restore must be done using the backup application's guest agent. The vSphere APIs for Data Protection provide no host agent support for this. Applications authenticating with SSPI might not work right because HTTP access will demand a user name and password, unless the session was recently authenticated.

Windows 2008 application level quiescing is performed using a hardware snapshot provider. After quiescing the virtual machine, the hardware snapshot provider creates two redo logs per disk: one for the live virtual machine writes and another for the VSS and writers in the guest to modify the disks after the snapshot operation as part of the quiescing operations.

The snapshot configuration information reports this second redo log as part of the snapshot. This redo log represented the quiesced state of all the applications in the guest. This redo log must be opened for backup with VDDK 1.2 or later. The older VDDK 1.1 software cannot open the second redo log for backup.

Application consistent quiescing of Windows 2008 virtual machines is only available when those virtual machines are created in vSphere 4.1 or later. Virtual machines created in vSphere 4.0 can be updated to enable application consistent quiescing by modifying a virtual machine's enableUUID attribute.

For information about VSS, see the Microsoft TechNet article, *How Volume Shadow Copy Service Works*. For information about Security Support Provider Interface (SSPI), see the MSDN Web site.

Enable Windows 2008 Virtual Machine Application Consistent Quiescing

- 1 Start the vSphere Client, and log in to a vCenter Server.
- 2 Select Virtual Machines and Templates and click the Virtual Machines tab.
- 3 Right-click the Windows 2008 virtual machine for which you are enabling the disk UUID attribute, and select **Power > Power Off**.
 - The virtual machine powers off.
- 4 Right-click the virtual machine, and click Edit Settings.
- 5 Click the **Options** tab, and select the **General** entry in the settings column.
- 6 Click Configuration Parameters...
 - The Configuration Parameters window appears.
- 7 Click Add Row.
- 8 In the Name column, enter disk.EnableUUID.
- 9 In the Value column, enter **TRUE**.
- 10 Click **OK** and click **Save**.
- 11 Power on the virtual machine.

Application consistent quiescing is available for this virtual machine after the UUID property is enabled.

Linux HotAdd and SCSI Controller ID

When using HotAdd backup, always add SCSI controllers to Linux virtual machines in numeric order.

Linux systems lack an interface to report which SCSI controller is assigned to which bus ID, so HotAdd assumes that the unique ID for a SCSI controller corresponds to its bus ID. This assumption could be false. For instance, if the first SCSI controller on a Linux VM is assigned to bus ID 0, but you add a SCSI controller and assign it to bus ID 3, HotAdd advanced transport mode may fail because it expects unique ID 1. To avoid problems, when adding SCSI controllers to a VM, the bus assignment for the controller must be the next available bus number in sequence.

Also note that VMware implicitly adds a SCSI controller to a VM if a bus:disk assignment for a newly created virtual disk refers to a controller that does not yet exist. For instance, if disks 0:0 and 0:1 are already in place, adding disk 1:0 is fine, but adding disk 3:0 breaks the bus ID sequence, implicitly creating out-of-sequence SCSI controller 3. To avoid HotAdd problems, you should also add virtual disks in numeric sequence.

Virtual Disk Programming Guide

Virtual Disk Mount API



As of the VDDK 1.1 release, you can use the disk mount API (vixMntapi) for local and remote mounting of virtual disks. The vmware–mount command does this too. VixMntapi involves a separate library for loading.

- "The VixMntapi Library" on page 87
- "Programming with VixMntapi" on page 92
- "Sample VixMntapi Code" on page 93
- "Restrictions on Virtual Disk Mount" on page 93



CAUTION The vixMntapi library for Windows supports advanced transport for SAN and HotAdd, but for Linux the vixMntapi library supports only local and LAN transport (file, nbd, nbdssl).

The VixMntapi Library

The VixMntapi library supports guest operating systems on multiple platforms. On POSIX systems it requires FUSE mount, available on recent Linux systems, and freely available on the SourceForge Web site.

Definitions are contained in the following header file, installed in the same directory as vixDiskLib.h:

#include "vixMntapi.h"

Types and Structures

This section summarizes the important types and structures.

Operating System Information

The VixOsInfo structure encapsulates the following information:

- Family of the guest operating system, VixOsFamily, one of the following:
 - Windows (NT-based)
 - Linux
 - Netware
 - Solaris
 - FreeBSD
 - OS/2
 - Mac OS X (Darwin)
- Major version and minor version of the operating system
- Whether it is 64-bit or 32-bit
- Vendor and edition of the operating system
- Location where the operating system is installed

Disk Volume Information

The VixVolumeInfo structure encapsulates the following information:

- Type of the volume, VixVolumeType, one of the following:
 - Basic partition.
 - GPT GUID Partition Table. However, VixMntapi does not support GPT partitions.
 - Dynamic volume, including Logical Disk Manager (LDM).
 - LVM Logical Volume Manager disk storage.
- Whether the guest volume is mounted on the proxy.
- Path to the volume mount point on the proxy, or NULL if the volume is not mounted.
- On Windows, numGuestMountPoints is the number of times a basic volume is mapped to a drive letter, or 0 if the volume is not mounted. IDE and boot disk come first. Unimplemented on Linux.
- Mount points for the volume in the guest.

Function Calls

To obtain these functions, load the vixMntapi library separately from the vixDiskLib library. On Windows, compile with the vixMntapi.lib library so your program can load the vixMntapi.dll runtime.

These calls can be used to mount and read Windows virtual disks on Windows hosts (with at least one NTFS volume) or Linux virtual disks on Linux hosts. Cross-mounting is restricted, though it is possible to mount a virtual disk with a mix of formats, if the mounted partition was formatted with Windows.

IMPORTANT You should run only one vixMntapi program at a time on a virtual machine, to avoid conflict between registry hives. See "Multithreading Considerations" on page 41 for advice on worker threads.

The remainder of this section lists the available function calls in the vixMntapi library. Under parameters, [in] indicates input parameters, and [out] indicates output parameters. All functions that return vixError return VIX_OK on success, otherwise a suitable VIX error code.

VixMntapi_Init()

Initializes the library. Similar to VixDiskLib_InitEx - see "Initialize Virtual Disk API" on page 35.

Parameters:

- majorVersion [in] VixMntapi major version number, currently must be 1 (one).
- minorVersion [in] VixMntapi minor version number, currently must be 0 (zero).
- log [in] Callback function to write log messages.
- warn [in] Callback function to write warning messages.
- panic [in] Callback function to report fatal errors.
- libDir [in] and configFile [in] as for VixDiskLib_InitEx(), allowing you to tmpDirectory.

VixMntapi_Exit()

Cleans up the VixMntapi library. void VixMntapi_Exit();

VixMntapi OpenDiskSet()

Opens the set of disks for mounting on a Windows or Linux virtual machine. All the disks for a dynamic volume or Logical Disk Manager (LDM) must be opened together.

The VixDiskLibHandle type, defined in vixDiskLib.h, is the same as for the diskHandle parameter in the VixDiskLib_Open() function, but here it is an array instead of a single value.

Parameters:

- diskHandles [in] Array of handles to open disks.
- numberOfDisks [in] Number of disk handles in the array.
- openMode [in] Must be 0 (zero).
- diskSet [out] Disk set handle to be filled in.

If you want to mount from a Windows system, first call VixDiskLib_Open() for every disk, then use the returned disk handle array to call VixMntapi_OpenDiskSet(), which returns a disk set handle.

If you want to mount from a Linux system, call the function VixMntapi_OpenDisks(), which opens and creates the disk set handle, all in one function.

VixMntapi_OpenDisks()

Opens disks for mounting on a Windows or Linux virtual machine. On Linux, the Logical Volume Manager (LVM) is not supported.

VixError

Parameters:

- connection [in] The VixDiskLibConnection to use for opening the disks. Calls VixDiskLib_Open() with the specified flags for each disk to open.
- diskNames [in] Array of disk names to open.
- numberOfDisks [in] Number of disk handles in the array. Must be 1 for Linux.
- flags [in] Flags to open the disk.
- handle [out] Disk set handle to be filled in.

VixMntapi_GetDiskSetInfo()

Retrieves information about the disk set.

VixError

Parameters:

- handle [in] Handle to an open disk set.
- diskSetInfo [out] Disk set information to be filled in.

VixMntapi_FreeDiskSetInfo()

Frees memory allocated by VixMntapi_GetDiskSetInfo().

void VixMntapi_FreeDiskSetInfo(VixDiskSetInfo *diskSetInfo);

Parameter:

■ diskSetInfo [in] OS info to be freed.

VixMntapi CloseDiskSet()

Closes the disk set.

VixError

VixMntapi_CloseDiskSet(VixDiskSetHandle diskSet);

Parameter:

diskSet [in] Handle to an open disk set.

VixMntapi_GetVolumeHandles()

Retrieves handles to volumes in the disk set. The third parameter VixVolumeHandle can be a volume handle or an array of volume handles. If you pass an array this function returns the volume handle for the first volume only. If you pass a pointer (such as VixVolumeHandle *volumeHandles) it returns all the volume handles.

VixError

Parameters:

- diskSet [in] Handle to an open disk set.
- numberOfVolumes [out] Number of volume handles.
- volumeHandles [out] Volume handles to be filled in.

VixMntapi_FreeVolumeHandles()

Frees memory allocated by VixMntapi_GetVolumeHandles().

void VixMntapi_FreeVolumeHandles(VixVolumeHandle *volumeHandles);

Parameter:

■ volumeHandles [in] Volume handle to be freed.

VixMntapi_GetOsInfo()

Retrieves information about the default operating system in the disk set.

To get operating system information, VixMntapi_GetOsInfo() requires the system and boot volumes to be already mounted. It does not dismount the system volume at the end of this function. Your application should be prepared to handle the "volume already mounted" error gracefully.

This function is effective only when used with operating systems of the same type. For instance, a VixMntapi program running on Windows can provide information about the VMDK of a Windows virtual machine, but not about the VMDK of a Linux virtual machine.

Parameters:

- diskSet [in] Handle to an open disk set.
- info [out] OS information to be filled in.

VixMntapi_FreeOsInfo()

Frees memory allocated by VixMntapi_GetOsInfo().

void VixMntapi_FreeOsInfo(VixOsInfo* info);

Parameter:

■ info [in] OS info to be freed.

VixMntapi_MountVolume()

Mounts the volume. After mounting the volume, use VixMntapi_GetVolumeInfo() to obtain the path to the mounted volume. This mount call locks the source disks until you call VixMntapi_DismountVolume(). The VixMntapi_MountVolume() function cannot mount Linux swap or extended partitions.

VixError

Parameters:

- volumeHandle [in] Handle to a volume.
- isReadOnly [in] Whether to mount the volume in read-only mode. Does not override openMode.

VixMntapi DismountVolume()

Unmounts the volume.

VixError

Parameters:

- volumeHandle [in] Handle to a volume.
- force [in] Force unmount even if files are open on the volume.

VixMntapi_GetVolumeInfo()

Retrieves information about a disk volume. Some information, such as the number of mount points, requires you to set the open read-only flag. Some information is available only if a volume was previously mounted by VixMntapi_MountVolume(). The Windows registry returns volume information only for mounted disks. On Windows the VixMntapi_GetVolumeInfo() call returns a symbolic link from the VixVolumeInfo structure in the form \\.\vstor2-mntapi10-shared-<longhexnum>\. You can transform this symbolic link into a target path by replacing \\. with \Device and deleting the final backslash, then map a drive letter with DefineDosDevice(DDD_RAW_TARGET_PATH,...) and proceed as if you have a local drive. Alternatively on Windows, you can open a volume with CreateFile() and traverse the file system with FindFirstFile().

VixError

Parameters:

- volumeHandle [in] Handle to a volume.
- info [out] Volume information to be filled in.

VixMntapi_FreeVolumeInfo()

Frees memory allocated in VixMntapi_GetVolumeInfo().

void VixMntapi_FreeVolumeInfo(VixVolumeInfo *info);

Parameter:

■ info [in] Volume info to be freed.

Programming with VixMntapi

At the top of your program, include vixMntapi.h along with any other header files you need. Structures and type definitions are declared in the include file, so you do not need to create them or allocate memory for them.

Call VixMntapi_Init() to initialize the library in your application. This function takes major and minor version number to account for future extensions. You can provide your own logging, warning, or panic functions to substitute for the default VixMntapi handlers, and custom library and temporary directories.

Call VixMntapi_OpenDiskSet() to open a set of virtual disks for mounting. Pass a set of disk handles obtained from the VixDiskLib_Open() call. The VixMntapi_OpenDiskSet() function also expects number of disks to open, an optional open mode, and a parameter to pass back the resulting disk-set handle.

File System Support

Windows file systems (FAT, FAT32, and NTFS) are supported. The vixMntapi library depends on the operating system for file system attributes such as compression, encryption, hidden, ACL, and alternate streams. If a vixMntapi-linked application runs on a virtual machine that supports these attributes, it supports them. The following volume types are supported: Simple, Spanned, Striped (RAID 0), and Mirrored (RAID 1). RAID 5 (parity striped) is not supported.

You must open a disk set read/write to obtain the OS information for dynamic volume types including LDM and LVM. If you cannot open a base disk read/write, create a child disk in front, and open it read/write. In a multi-boot setup, only the first entry #0 is opened.

The order of mounting is important. For instance, mount top-level directories before subdirectories, and drives with dependencies after drives that they depend on. Mount points are not enumerated, nor are they restored. When you mount one volume, the other volumes are not implicitly mounted also.

Read-Only Mount on Linux

The VixMntapi library can emulate mounting disks read-only, as in the Linux procedure below. A similar procedure, with different temporary filename, could be used on Windows.

To mount disks read-only

- 1 Open the base disk with VixDiskLib_Open(), passing the flag VIXDISKLIB_FLAG_OPEN_READ_ONLY.
- 2 Call VixDiskLib_CreateChild() to create a child of the base disk. VMware recommends creating a file such as /tmp/<uniqueName> using mkstemp() to formulate a unique name for the redo log.
- 3 Call VixDiskLib_Close() to close the base disk, which is no longer needed.
- 4 Now use VixMntapi_OpenDisks() as you normally would with diskSet[0] = /tmp/<uniqueName> and openFlags = 0 (meaning read/write).

This allows writing to the redo log (for journal reply and so forth) without affecting the base disk.

Software developers should inform customers that the mounted disk set seems writable, although the effect of changing files and altering directories is only temporary. The base disk is read-only.

To unmount read-only disks

- 1 Call VixMntapi_CloseDiskSet() to close the disk set.
- 2 Call VixDiskLib_Unlink() to remove the redo log, /tmp/<uniqueName>.

VMware Product Platforms

Applications written using this release of VixMntapi can manipulate virtual disks created with ESX and ESXi, VMware Server, VMware Fusion, VMware Player, VMware Workstation, and GSX Server.

Sample VixMntapi Code

You call the VixMntapi functions after initializing VixDiskLib, connecting to a virtual machine, and opening a disk handle. Here is sample code for Windows showing correct order of function calls.

```
MountTest() {
    vixError = VIX_ERR_CODE(VixDiskLib_Init() );
    vixError = VIX_ERR_CODE(VixMntapi_Init() );
   VixDiskLib_ConnectEx(&connectParams, TRUE, NULL, NULL, &connection));
    diskHandles = GetMyDiskHandles(diskPaths, connection, &connectParams, flags, &numberOfDisks);
    vixError = VIX_ERR_CODE(VixMntapi_OpenDiskSet(diskHandles, numberOfDisks, flags, &diskSet));
    GetOsInfo(diskSet);
    vixError = VIX_ERR_CODE(VixMntapi_GetVolumeHandles(diskSet, &numberOfVolumes,
                   &volumeHandles));
    for(size_t i = 0; i < numberOfVolumes; i++) {</pre>
        VixVolumeHandle volumeHandle = volumeHandles[i];
        VixVolumeInfo *volumeInfo;
        vixError = VIX_ERR_CODE( VixMntapi_MountVolume(volumeHandle, TRUE) );
        vixError = VIX_ERR_CODE( VixMntapi_GetVolumeInfo(volumeHandle, &volumeInfo) );
        VixMntapi_FreeVolumeInfo(volumeInfo);
        VerifyMountedVolume();
        CleanUpMountedVolume(volumeHandle, volumeInfo);
   VixMntapi_FreeVolumeHandles(volumeHandles);
    vixError = VIX_ERR_CODE( VixMntapi_CloseDiskSet(diskSet) );
    FreeMyDiskHandles(diskHandles, numberOfDisks);
   VixMntapi_Exit();
   VixDiskLib_Exit();
}
```

Restrictions on Virtual Disk Mount

The following limitations apply when mounting virtual disks:

- You cannot mount virtual disks that are in use by a running or suspended virtual machine. You can mount disks from a powered off virtual machine, disks not associated with a virtual machine, or base disks when a Windows virtual machine is running off a snapshot (read-only).
- On Windows virtual machines you can mount previous snapshots read-only. On Linux virtual machines you cannot mount previous snapshots.
- If you specify a virtual disk with snapshots on a powered off virtual machine, VixMntapi locates and mounts the last snapshot in the disk chain. While a disk is mounted, do not revert to a previous snapshot using another VMware interface this would make it impossible to unmount the partition.
- You cannot mount virtual disk if any of its .vmdk files are encrypted, compressed, or read-only. However you can change these attributes and then mount the virtual disk.
- With Windows, you must mount virtual disks on drive D: or greater, and choose a drive letter not in use.
- With Linux, kernel version 2.6 or higher is required to run the FUSE (file system in user space) module. You cannot mount Linux swap or extended partitions. Logical Volume Manager (LVM) is not supported.
- You can mount Windows virtual disks on Windows hosts (with an NTFS volume) or Linux virtual disks on Linux hosts. Cross-mounting is restricted but may be allowed for cross-formatted file systems.

Virtual Disk Programming Guide

Errors Codes and Open Source



This appendix contains the following sections:

- "Finding Error Code Documentation" on page 95
- "Troubleshooting Dynamic Libraries" on page 95
- "Open Source Components" on page 96

Finding Error Code Documentation

For a list of Virtual Disk API error codes, see the online reference guide Introduction to the VixDiskLib API:

- Windows C:\Program Files\VMware\VMware Virtual Disk Development Kit\doc\intro.html
- Linux /usr/share/doc/vmware-vix-disklib/intro.html

In a Web browser, click the **Error Codes** link in the upper left frame, and click any link in the lower left frame. The right-hand frame displays an alphabetized list of error codes, with explanations.

Association With VIX API Errors

The Virtual Disk API shares many errors with the VIX API, which explains the VIX prefix. The error codes for the VIX API are likely to be the same, or almost the same as, a comparable release of the VDDK.

For information about the VIX API, including its online reference guide to functions and error codes, see the developer support section of the VMware Web site:

https://www.vmware.com/support/developer/vix-api/index.html

Interpreting Errors Codes

A VIX error is a 64-bit value. A value of VIX_OK indicates success, but otherwise (if there is an error), several bit regions in the 64-bit value might be set. The least significant 16 bits are set to the error code described for VIX errors. More significant bit fields might be set to other values.

As for the VIX API, use the macro VIX_ERROR_CODE(err) to mask off bit fields not used by the VDDK.

Troubleshooting Dynamic Libraries

On Windows, the SSL library is placed in the same directory as other vixDiskLib dynamically loaded libraries. On Linux, functions that load the libraries libssl.so.0.9.8 and librarypto.so.0.9.8 do the following:

- 1 Attempt to load them from the environment's LD_LIBRARY_PATH location.
- 2 Next, attempt to load them from the directory where libvixDiskLib.so is located.
- 3 Next, attempt to load them from the directory where the executable is located.
- 4 Failing that, exit with an error.

On install, VDDK creates the directory /usr/lib/vimware-vix-disklib, populated with 32-bit and 64-bit executables and libraries placed into subdirectories bin32, bin64, lib32, and lib64. On determining the OS type, VDDK copies the vixDiskLib and vixMntapi libraries into /usr/lib. It does not copy libssl.so.0.9.8 or libcrypto.so.0.9.8 into /usr/lib.

On execution, the root user normally has no LD_LIBRARY_PATH, and /usr/lib is ahead of /opt/vmware/lib in the path. Running the ldd command can help diagnose where a program is getting libvixDiskLib.so and other libraries. The /opt/vmware/lib directory is neither created nor updated by the VDDK install script.

If you see the error "Failed to load library libcrypto.so.0.9.8" there are several solutions:

- Set or reset the LD_LIBRARY_PATH environment so it contains one of the directories above, either /lib32 or /lib64, before it contains /usr/lib.
- Change the symbolic link in /opt/vmware/lib (or elsewhere) so it points to one of the directories above, either /lib32 or /lib64 depending.
- Copy the libssl and libcrypto libraries from /usr/lib/vmware-vix-disklib/lib32 (or /lib64) into /usr/lib.

Open Source Components

VDDK contains the following open source components, with license types indicated:

- Boost (BSD style license)
- Curl (MIT/X derivative license)
- Expat (BSD style license)
- FreeBSD (BSD license)
- ICU, International Components for Unicode (BSD style license)
- LibXML2 (MIT style license)
- OpenLDAP (OpenLDAP v 2.8 license)
- OpenSSL (OpenSSL license)
- Zlib (BSD license)

These open source components have the GNU library general public license:

- GetText (LGPL2.0)
- Glib (LGPL 2.0)
- LibFuse (LGPL2.0)
- LibIconv (LGPL2.0)

Glossary

D differential backup

Saving system data changed since the last full backup, so only two restore steps are necessary.

E extent

In the context of VMDK, a split portion of virtual disk, usually 2GB.

F flat

Space in a VMDK is fully allocated at creation time (pre-allocated). Contrast with sparse.

H hosted disk

A virtual disk stored on a hosted product, such as VMware Workstation, for its guest operating system.

I incremental backup

Saving system data changed since the last backup of any type.

M managed disk

A virtual disk managed by an ESX/ESXi host or VMware vCenter, contained within a VMFS volume.

monolithic

The virtual disk is a single VMDK file, rather than a collection of 2GB extents. Contrast with split.

N NBD

Network block device, a VMware method for over-the-network access.

P proxy

A physical or virtual machine running an operating system with third-party backup software. The proxy is used to perform file-level and image-level virtual machine backups.

Q quiescing

A method of bringing the on-disk data of a physical or virtual computer into a state suitable for backups. Quiescing may include flushing disk buffers from the operating system's in-memory cache or other tasks.

R RDM (Raw Device Mapping)

Enables a virtual machine to directly access a LUN on the physical storage subsystem (SAN connected by Fibre Channel, iSCSI, or SAS). At the same time, the virtual machine has access to the disk that is using a mapping file in the VMFS name space. Performance is similar to VMDK.

S sparse

Space in a VMDK is allocated only when needed to store data. Contrast with flat.

split

The virtual disk is a collection of VMDK files containing 2GB extents. Contrast with monolithic.

V VMDK (Virtual Machine DisK)

The virtual counterpart to a guest operating system's physical disk. A file or group of files that can reside on the host machine or on a remote file system.

VMFS (Virtual Machine File System)

A file system optimized for storing virtual machines. One VMFS partition is supported for each SCSI storage device or LUN.

VMX (virtual machine configuration file)

A file containing a virtual machine's configuration. This .vmx file is created with its virtual machine and is used to identify and run a specific virtual machine.

Index

Numerics incremental backup 40, 97 incremental restore 80 32-bit and 64-bit 12 installation on Linux 16 Α installation on Windows 16 access and credentials 22 internationalization (i18n) 21 application consistent quiescing, Windows 2008 85 L В licensing for advanced transports 41 backing information for virtual disk 68 limitations of vixMntapi library 93 backup algorithms 39 Linux installation 16 backup process, overview of 57 localization (I10n) 21 best practices for SAN transport 81 M BIOS customizations, saving 54 managed disk 13, 19, 28, 41, 48, 51, 97 C managed object reference (moRef) 59 change ID 40 Microsoft Shadow Copy 84 changed block tracking (CBT) 70 monolithic VMDK 19, 20, 32, 47, 48, 50, 97 code sample walk-through 45 MONOLITHIC FLAT 19, 20 configFile settings for VixDiskLib_InitEx 35 MONOLITHIC_SPARSE 19, 20 CopyThread 46, 48 moref and unique ID 59 credentials and access 22 mounting virtual disk for backup 63 Ν development platforms 15 nonpersistent disk mode 20 differential backup 40 NVRAM backup and restore 54 disassociate host from vCenter Server 81 0 disaster recovery 39 ObjectSpec and PropertySpec 59 disk manager See virtual disk manager open read-only disk 92 disk mount (vmware-mount) 12 open source components in VDDK 96 Ε Ρ error codes, finding explanations for 95 packaging of Virtual Disk API 16 ESX/ESXi and VMware vCenter 11, 22 persistent disk mode 20 extent 19, 34, 50, 97 platforms supported for development 15 privileges needed in vCenter Server 22 flat VMDK 19, 20, 31, 34, 97 products from VMware that are supported 15 property collector, use of 64 PropertySpec and ObjectSpec 59 gcc (GNU C compiler) 15 queryChangedDiskAreas 40 hosted disk 11, 13, 19, 28, 30, 42, 46, 48, 51, 54, 97 R RDM (raw device mapping) 31, 53, 60, 72, 80 iconv() convert UTF-8 to and from UTF-16 21 read-only disk mount 92 iconv_open() initialize codeset conversion 21 re-creating a virtual machine from backup 62

redo logs and snapshots 12, 20, 22, 32, 52 restore process, overview of 61 restoring a virtual machine to previous state 62 restrictions on vixMntapi library 93 role and privileges in vCenter Server 22	VixDiskLib_Close 28, 30, 46 VixDiskLib_Combine 34 VixDiskLib_Connect 28, 29, 41, 46, 48, 52 VixDiskLib_Create 28, 30, 41, 47, 50, 51, 53 VixDiskLib_CreateChild 28, 32, 33, 47
S sample program walk-through 45	VIXDISKLIB_CRED_UID 52 VixDiskLib_Defragment 28, 34, 41 VixDiskLib_Disconnect 28, 35
SAN and the Virtual Disk API 13, 27	VIXDISKLIB_DISK_SPLIT_SPARSE 50
SCSI controller and Hot Add 85	VixDiskLib EndAccess 28
session object for server communication 58	VixDiskLib_Exit 28, 35
snapshot	VixDiskLib_FreeErrorText 28, 31
backing up a virtual disk 69	VixDiskLib_FreeInfo 28, 31, 46
creating 69	VixDiskLib_GetErrorText 28, 31
deleting 69	VixDiskLib_GetInfo 28, 30, 46, 49, 50
restoring virtual disk 73	VixDiskLib_GetMetadataKeys 28, 31, 47
temporary 60	VixDiskLib_Grow 28, 34, 41
snapshot management 53	VixDiskLib_Init 28, 29, 35, 46, 52, 55
snapshots and redo logs 12, 20, 22, 32, 52	VixDiskLib_Open 28, 30, 46
sparse VMDK 19, 20, 32, 34, 44, 47, 48, 50, 97	VixDiskLib_Read 28, 30, 48, 49, 50, 51
split VMDK 19, 20, 50, 97	VixDiskLib_ReadMetadata 28, 31, 47
SPLIT_FLAT 19, 20	VixDiskLib_Rename 28, 34, 52
SPLIT_SPARSE 19, 20	VixDiskLib_Reparent 35
SSL certificate 25	VIXDISKLIB_SECTOR_SIZE 30, 49, 51
STREAM_OPTIMIZED 19	VixDiskLib_Shrink 28, 34
supported platforms for development 15	VixDiskLib_SpaceNeededForClone 28, 31
supported VMware products 15	VixDiskLib_Unlink 28, 34, 42, 52
_	VixDiskLib_Write 28, 30, 34, 47, 51
Т	VixDiskLib_WriteMetadata 28, 31, 47
technical support resources 10	VixHost_Connect 55
thumbprint, SSL 25	VixHost_FindItems 55
U	VM configuration information 39
	VMDK (virtual machine disk) file 11, 12, 19, 21, 22,
UEFI (unified extensible firmware interface) 54	31, 46, 47, 49, 50, 51, 52, 55, 56
Unicode UTF-8 support 21 unique ID and moRef 59	VMFS_FLAT 19, 20, 51
unique iD and moker 39	VMFS_THIN 19, 20
V	VMware Consolidated Backup (VCB) 11
vCloud and vCloud Director 12	VMware vCenter and ESX/ESXi 22
verify SSL certificate 25	VMX specification (vmxSpec) 29
VHD from Microsoft 22	Volume Snapshot Service (VSS) 84
Vim find_entity_views in Perl toolkit 55	vSphere APIs for Data Protection (VADP) 57
Vim get_inventory_path in Perl toolkit 55	W
virtual disk manager (vmware-vdiskmanager) 12	
VirtualMachineConfigInfo 39	walk-through of sample program 45
VirtualMachineConfigSpec 73	Windows 2008 application consistent quiescing 85
Visual Studio 15	Windows On Windows 64 13
VixDiscoveryProc 55	Windows On Windows 64 12
VIXDISKLIB_ADAPTER_IDE 23, 50	
VIXDISKLIB_ADAPTER_SCSI_BUSLOGIC 23, 50	
VIXDISKLIB_ADAPTER_SCSI_LSILOGIC 23	
VixDiskLib_Attach 28, 33, 47, 53	
VixDiskLib_Clone 28, 32, 41, 48, 51	