



# User Manual

## Phase 4 Implementation 3

Reviewed: 13.02.2001

Status: Final version

Approved by: Jere Molander

Author: Anders Stenback, Thomas Grenman

Revision: 2.0

---

## Changelog

---

**Phase 3**

08.12.2000 Index added

**Phase 4**

13.02.2001 Updated to reflect work done during Phase 4

---

## Disclaimer

---

Copyright Tripoli Project 2000-2001. All rights reserved. This documentation is provided "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of merchantability, fitness for a particular purpose, or non-infringement. The Tripoli Group will not, in any event, be responsible for possible errors in this document or for any damages, incidental or consequential (including, but not limited to monetary losses), that might arise from the use of or inability to use the document or the information in it, even if the Tripoli Group has been advised of the possibility of such damages.

The document could include technical inaccuracies or typographical errors. The Tripoli Group welcomes customer comments as part of the process of continuous development of this document. Any such comments shall become the property of the Group without any duty of compensation or obligation to use.

Changes are periodically added to the information herein; these changes will be incorporated in new editions of the document. The Tripoli Group may at any time make improvements and/or changes to the product(s) and/or the program(s) described in the present document.

Nokia and Nokia Activ Server are registered trademarks of Nokia Corporation. Ericsson and Mobile Internet are registered trademarks of Ericsson Mobile Phones. Other product and company names mentioned herein may be trademarks of their respective owners, and are mentioned for identification purposes only.

## **Index**

---

- 1 Preface
  - 1.1 Audience
  - 1.2 Compatibility
  - 1.3 Purpose
  - 1.4 Overview
  - 1.5 Definitions and abbreviations
  - 1.6 Typographical conventions
  - 1.7 References
  - 1.8 Reporting bugs and improvements
- 2 Getting Started
  - 2.1 Installation procedure
  - 2.2 Installing Windows operating system
  - 2.3 ISDN interface drivers
  - 2.4 Java Runtime Environment
  - 2.5 Java HotSpot Server VM
  - 2.6 Nokia Activ Server
  - 2.7 Adding a user
  - 2.8 Configuring the Ericsson MC218
  - 2.9 Configuring the Ericsson T18s
  - 2.10 Configuring the Nokia 6210 / 7110
  - 2.11 Starting procedures
- 3 User Guides
  - 3.1 Getting Started Guide
  - 3.2 Activ Server Advanced Guides
  - 3.3 Using the Ericsson MC218
- 4 Known bugs
- 5 Error messages
- 6 Additional references
- 7 Terms and abbreviations
- 8 Index

# 1 Preface

---

This document describes how to set up the Tripoli WAP server environment, including hardware configurations and how to configure the Nokia Activ Server 2.0. Setup instructions for commonly used handheld WAP terminals are also provided.

## 1.1 Audience

This document is intended for administrators creating and maintaining WAP services for the Tripoli WAP server. The Tripoli WAP server enables quick deployment of existing services and their business logic. The document aids the administrator in setting up the Tripoli production environment, including configuration of the Nokia Activ Server and necessary accessories. Detailed instructions for end-users must be provided by the administrators, since settings vary from application to application. Administrators are expected to be familiar with basic Windows system administration.

## 1.2 Compatibility

System requirements:

Nokia Activ Server 2.0 requirements:

- Microsoft Windows NT 4.0 with Service Pack (SP) 5 or later
- Pentium-class 266 MHz or faster processor
- Minimum 128 Mb RAM (256 Mb recommended)
- Minimum 100 Mb free hard disk space
- CD-ROM drive
- TCP/IP compatible network interface card
- Java Runtime Environment (JRE) 1.2.2 or later
- Java HotSpot Server 2.0

See section "References" for component download locations.

Network connection requirements:

- For GSM-CSD (Circuit Switched Data), a dial-up server that provides an IP connection must be installed (Windows Remote Access Server (RAS) will do). The Nokia Activ Server must be in the same IP network. Normally a ISDN dial-up connection with either BRI (basic rate interface: 2\*64kbit/s) or PRI (primary rate interface 30\*64kbit/s) interface would be used.
- The ISDN interface **MUST** support the v.110 protocol. Not all ISDN cards do.

Handheld terminal device:

Any terminal supporting the WAP 1.1 specification, data calls and the v.110 protocol. (For more information about the WAP specification see <http://www.wapforum.org>). Examples are Nokia 7110, Nokia 6210,

Ericsson R380s.

## 1.3 Purpose

The purpose of this document is to show, by example, how to set up the Tripoli WAP service environment, using as an example the Ericsson T18s mobile phone, Ericsson MC218 EPOC PDA and Nokia Activ 2.0 server.

## 1.4 Overview

The "Getting Started" section describes in a walk-through fashion how to setup the Nokia Activ Server. The section is divided into subsections each describing in detail different parts of the installation starting with the operating system.

The "User Guides" section gives a short description of the most important settings and options in the Activ Server. The user is referred to additional documents for more advanced features and options. This section also describes briefly how to use the Ericsson MC218 handheld device.

The "Known bugs" and "Error messages" sections describes what can go wrong and how the user can handle such situations. The most common error messages reported by the Ericsson handheld are described in the "Error messages" section. The user is referred to additional sources for advanced troubleshooting.

The "Additional references" sections refers to helpful and related sources of information.

The "Glossary" contains a short description of the used abbreviations and terms in this document.

## 1.5 Definitions and abbreviations

GSM Global System for Mobile Communication

CSD Circuit Switched Data

BRI Basic Rate Interface

PRI Primary Rate Interface

JRE Java Runtime Environment

WAP Wireless Application Protocol

PDA Personal Digital Assistant

v.110 WAP bearer protocol

RAS Remote Access Server

## 1.6 Typographical conventions

The following typographical conventions are used in this document:

Notation Explanation:

`Courier` Program code, file and directory names, function names.

*Italic* References to other guides and documents, as well as other parts of this documentation.

**Bold** Names of applications and Windows menus, commands, buttons and icons.

## 1.7 References

References to other documents and software:

Nokia Activ Server 2.0

<http://forum.nokia.com/> (Requires registration)

Java Runtime Environment 1.2.2\_006

[http://java.sun.com/products/archive/j2se/1.2.2\\_006/jre/](http://java.sun.com/products/archive/j2se/1.2.2_006/jre/)

Java HotSpot Server VM 2.0

<http://java.sun.com/products/hotspot/2.0/download.html>

Mobile Internet Ericsson WAP Browser 1.21

[http://mobileinternet.ericsson.com/emi\\_download/MC218/MobileInternet.sis](http://mobileinternet.ericsson.com/emi_download/MC218/MobileInternet.sis)

Ericsson EPOC Connect 1.0 Build 136

Found on Ericsson MC218 CD-ROM

## 1.8 Reporting bugs and improvements

Please send comments, bugs and suggestions for improvements to the Tripoli Project group [tripoli@tky.hut.fi](mailto:tripoli@tky.hut.fi). Frequently asked questions can be found at <http://dev.tky.hut.fi/tripoli>

---

# 2 Getting Started

---

## 2.1 Installation procedure

System requirements must be fulfilled. Please see section "Compatibility" above. Prior to installation check that you have the basic components needed: an ISDN or other dial-in connection, the necessary software mentioned in section "References" and hardware meeting the requirements. A WAP terminal is also recommended to test the functionality of the WAP Gateway.

The installation procedure is as follows:

1. Windows operating system
2. ISDN interface drivers
3. Java Runtime Environment 1.2.2\_006
4. Java HotSpot Server VM 2.0
5. Nokia Activ Server 2.0
6. Adding a user with dial-in access rights
7. Configuration of handheld terminal

Please reserve one afternoon for software installation and configuration. Each component can be removed using the Windows **Control Panel** -> **Add/Remove Programs** feature.

## 2.2 Installing Windows operating system

Before you install the Windows 2000 Server operating system on your computer, make sure the system meets the minimum hardware requirements found in the section "Compatibility".

Please see your Windows 2000 Server Users Manual for details on how to install the software on your system.

You need to configure the TCP/IP protocol (installed by default) and bind it to a network adapter. Configure the IP settings according to instructions provided by your network administrator.

## 2.3 ISDN interface drivers

Follow the instructions included with the ISDN adapter. If it is possible to configure the ISDN interface the following settings should be used:

D-channel protocol: European-ISDN (DSS1)

WAN Miniport (Incoming Calls): Auto detect B-Channel protocol (alternatively use v.110 and make sure that D-Channel LCC signalling is NOT required)

Protocol settings: Protocol = v.110, bits per second = 9600, data bits = 8, parity = none, stop bits = 1, Answer = on

These settings are configured (Windows 2000) under **Control Panel** -> **System** -> **Hardware** -> **Device Manager...** -> **Network Adapters** -> ISDN adapter name -> **Properties**.

These settings may also be found in the **Control Panel** depending on the ISDN card manufacturer.

## 2.4 Java Runtime Environment

Download the package (address found in section "References" above) and install it according to instructions found on Sun's webpage.

## 2.5 Java HotSpot Server VM

Download the package (address found in section "References" above) and install it according to instructions found on Sun's webpage.

## 2.6 Nokia Activ Server

Download the package (address found in section "References" above) or install it from the Nokia Activ Server CD-ROM. The installation program is started by running `Setup.exe`. Follow the onscreen instructions and respond to the prompts until the installation is complete. Be sure to enter the license number correctly.

The Nokia Activ Server installation program installs the Server software in the specified directory. The default directory is `C:\Program Files\Nokia\Nokia Activ Server 2.0 Professional`. You can



also specify another directory. The installation program also adds a Nokia Activ Server menu to the **Programs** section of the Windows **Start Menu**.

A successful installation is best tested using a WAP Toolkit. Nokia and Ericsson, among others, provide debugging tools which simulate working WAP browsers. For download sites see the section "Additional References" at the end of this document. Installing such a debugging tool and accessing the default mapping eg. <http://yourdomain/files/> will check whether the Activ Server has been successful. For additional information about mappings, refer to section "Getting Started".

## 2.7 Adding a user

To add a user with rights to dial-in choose **Control Panel -> Administrative Tools -> Computer Management -> Local Users and Groups -> Users -> New User...** Input the user name, eg. wap and a password. Optionally a description such as Dial-in client can be added. Deselect "User must change password at next logon". When the user is created open the user's properties and select **Dial-in . Allow Remote Access Permissions (Dial-in)** for the user.

## 2.8 Configuring the Ericsson MC218

The mobile phone modem needs to be configured so as to use the v.110 protocol used by WAP bearers.

Configuration of the Ericsson MC218 is done starting from **Desktop -> Tools -> Control Panel -> Modems -> Current Modem = Ericsson infrared modem -> Edit.**

Under **Modem** select speed = 9600 baud. Under **Initialisation** for **Data init. string** input `AT+CBST=71`. The `AT+C` is a special command set used by GSM modems. The `+CBST` means the bearer service type and 71 is the mode (9600 bps v.110). The init (reset) string should be `ATZ`. Under advanced settings, the flow control should be Hardware (RTS/CTS), Terminal detect (DSR/DTR) should be set to on and Carrier detect (DCD) should be set to on. The modem type should be Mobile.

Next, choose **Desktop -> Tools -> Control Panel -> Internet -> New > Based upon = Standard Settings -> OK.** Then select **Service -> Name** = Choose a suitable name for the connection, then change the **Standard dial-up number**. This should be the ISDN dial-in number. Next, select **Account**, deselect **Manual login**, fill in the **Username** and **Password**, as defined in the previous section "Adding a User".

Now we are ready to install the WAP browser called Ericsson Mobile Internet. The software is downloaded through the link found above in the section "References". Connect the serial cable to the MC218 and a serial port on the computer where the Ericsson EPOC connect software is installed. Start the EPOC Connect software and select **EPOC -> Install new program**. This opens a selection box where you should choose the

software you just downloaded, that is the Mobile Internet. The software is downloaded to the terminal.

Next, to configure the WAP browser, select **Extras -> Mobile -> Tools > Preferences -> Access**. Add a new gateway by selecting **New -> IP address**, the same address as defined in the section "Installing Windows operating system", eg. 130.233.224.1. Normally a username and password is not required. Optionally a name for the gateway may be specified.

## 2.9 Configuring the Ericsson T18s

You need to set the mobile is to use Data Calls by default. This is done by scrolling to **Next call type** and pressing **YES**. The default is **Speech**. Scroll through the options and select **Data**. Press **YES** to store the changes.

## 2.10 Configuring the Nokia 6210 / 7110

The WAP services can be configured in a Nokia 6210 and 7110 phone by the following procedure. Select **Menu -> Services -> Settings -> Connection Settings**. Select a desired connection and select **Options -> Edit**. The following values has to be entered: Homepage shall be set to the desired starting page (eg. <http://dev.tky.hut.fi/tripoli/internal/StartingPage.wml>), Connection type is Continuous, Connection security is Off, Bearer is Data, Dial-up number is the ISDN dial-up phone number for the Activ Server, IP address should be set to 127.0.0.1, Authentication type is Normal, Data call type is ISDN and Data call speed is 9600. You should also specify the user name and the password as defined in the "Adding a User" section.

## 2.11 Starting procedures

This section describes how to start the required services (Remote Access Service and Nokia Activ Server).

The Remote Access Service is started through **Control Panel -> Administrative Tools -> Routing and Remote Access**. Select your local server from the presented list and choose **Action -> Configure and Enable Routing and Remote Access**. A setup wizard will start to guide you through the Access Server setup. Click **Next** and choose **Remote access server**. Click **Next** and verify that the TCP/IP protocol is available. On the next screen, choose the Network interface you wish to assign to the remote client. Click **Next**. The next screen allows you to specify IP addresses for the remote dial-in connections. Select **From a specific range of addresses** and click **Next**. Depending on the amount of dial in lines, specify the range for the clients. Click **New...** and type for instance 1.2.3.4 to 1.2.3.33 for a IP address range with 30 addresses. Click **OK** and **Next**. Choose **I don't want to setup this server to use RADIUS now**. Click **Next** once and **Finnish** to complete the setup.

When the setup is complete you still need to check that the WAN ports for your ISDN accept dial-in connections. Select **Ports** under your local server and choose **Action - > Properties**. Select the device you are using and choose **Configure**. Make sure that **Remote access connections** is selected.

The Nokia Activ Server is started by selecting **Start - > Programs - > Nokia Activ Server 2.0 Professional - > Nokia Activ Server Service Installation**. Reply **yes** to the question asked.

---

## 3 User Guides

---

The purpose of this chapter is to give a brief overview of daily administration of the Nokia Activ Server software.

### 3.1 Getting Started Guide

A thorough User Guide is included with the Nokia Activ Server installation. Please install Acrobat 4, which is found on the installation CD-ROM and in the downloaded zip file. The Getting Started Guide is found in the documentation folder of the Nokia Activ Server program folder and is called *GettingStarted.pdf*.

The most useful functions in the Activ Server will be found in the **Servlets** and the **Bearers** menu. To be able to access locally stored HTML or WML pages the **FileServlet** must be set up. This servlet is installed by default but the mappings must be made to suit the installation. Mappings can be configured with **Servlets - > Mappings**.

The most likely bearer to be used is the UDP bearer. This (and additional) bearers can be added with **Bearers - > Configure - > Create**.

If the Activ server (and the user) should be able to access pages stored on the World Wide Web a HTTP Client must be set up. The Client can be configured by selecting **Settings - > HTTP**.

### 3.2 Activ Server Advanced Guides

An advanced user guide is found in the same directory as described above with the name *AdministrationGuide.pdf*. There is also an advanced programmer's manual with the name *ProgrammersGuide.pdf*.

### 3.3 Using the Ericsson MC218

The device is turned on and off by opening and closing the lid. To view WAP content choose **Desktop - > Extras - > Mobile**. Type in the desired address in the box at the bottom of the page eg. <http://dev.tky.hut.fi/tripoli/internal/StartingPage.wml> and press **Enter**. The modem should start dialing, the phone shows **Data** to indicate a data call and the dialled number. To end the call, press the red button on the phone

to disconnect.

---

## 4 Known bugs

---

Known bugs are announced in the FAQ found at <http://dev.tky.hut.fi/tripoli/faq.html>.

---

## 5 Error messages

---

This section describes common error messages and simple solutions to them. More information can be found in the FAQ at <http://dev.tky.hut.fi/tripoli/faq.html>

Error message: "Problem initializing modem. Check your modem settings in the Control Panel."

Solution: Check that the modem is connected securely to the T18s and that it is situated close enough to the MC218 (2-10cm).

Error message: "No carrier".

Solution: Check that the AT command AT+CBST=71 is entered in modem data init string.

Error message: "Could not open location. Tip check your 'Access' settings in 'Tools - > Preferences'."

Solution: Check that the phone is online and that the data call gets a connection in the other end.

---

## 6 Additional references

---

This section contains useful references that may be relevant when developing WAP services.

*Nokia Designer's Guide*. Found at <http://forum.nokia.com>. Gives design guidelines for developing WAP application for Nokia handsets.

*Nokia WAP Toolkit*. Found at <http://www.nokia.com/corporate/wap>. A toolkit containing good documentation and an introduction to WML as well as a debugging tool for WML pages.

---

## 7 Terms and abbreviations

---

### **Bearer**

A telecom service that is used to carry data from WAP enabled terminals to the Nokia Activ Server through the wireless network.

### **Bearer adapter**

A piece of software that makes it possible to use the Nokia Activ Server for offering WAP services through a bearer.

**Client**

A device that initiates a request for a connection with a server.

**Dial-up server**

A device that allows remote users to connect to the local area network or to the Internet.

**HTML (HyperText Markup Language)**

A subset of Standard Generalised Markup Language (SGML) used on the World Wide Web. HTML defines the page layout of a WWW-page, i.e. fonts, graphic elements and hypertext links.

**HTTP (HyperText Transfer Protocol)**

A protocol utilising TCP/IP that enables the transfer of HTML files. HTTP is used in WWW services.

**IP number/address**

A numerical identification number individualising a data processor or a data transferring device connected to the Internet or a network connection. Compare with TCP/IP.

**Servlet**

A servlet receives requests from the WAP terminal via the Nokia Activ Server and returns responses to them.

**TCP/IP (Transmission Control Protocol/Internet Protocol)**

A public protocol defined by the US department of defence offering roughly the functionality of an ISO class 4 transport protocol. TCP corresponds to the Open System Interconnection (OSI) layer 4, and IP to layer 3. In the US, the protocol is known as DoD/IP.

**UDP (User Datagram Protocol)**

A data-message-based transfer protocol related to the TCP/IP protocol.

**User agent**

A user agent is any software or device that interprets WML, WMLScript or other resources. This may include textual browsers, voice browsers, search engines, etc.

**WAP Gateway**

A network element in WAP specifications that converts WAP requests to HTTP (or other origin server) requests, converts the responses to WAP, and encodes content for binary representation. The Nokia Activ Server can also serve as a WAP gateway.

---

## 8 Index

---

Please use the **Find** feature in Acrobat Reader to find the text you are looking for.