Overture Technical Report Series No. TR-002

April 2013

Overture VDM-10 Tool Support: User Guide

by

Peter Gorm Larsen, Kenneth Lausdahl, Peter Jørgensen, Joey Coleman and Sune Wolff Aarhus University, Department of Engineering Finlandsgade 22, DK-8000 Århus C, Denmark

> Nick Battle Fujitsu UK Lovelace Road, Bracknell, Berkshire. RG12 8SN, UK

Overture – Open-source Tools for Formal Modelling





Overture VDM-10 Tool Support: User Guide

Document history				
Month	Year	Version	Version of Overture.exe	
January	2010		0.1.5	
March	2010		0.2	
May	2010	1	0.2	
February	2011	2	1.0.0	
June	2011	3	1.0.1	
April	2013	4	2.0.0	

Contents

1	Intro	oduction	n	3		
2	Gett	Setting Hold of the Software				
3	Usin	g the V	DM Perspective	7		
	3.1		standing Eclipse Terminology			
	3.2	Additio	onal Eclipse Features Applicable in Overture			
		3.2.1	Opening and Closing Projects			
		3.2.2	Adding Additional VDM File Extensions			
		3.2.3	Filtering Project Contents			
		3.2.4	Including line numbers in the Editor	10		
4	Man	aging C	Overture Projects	13		
	4.1	Import	ting Overture Projects	13		
	4.2	Creatin	ng a New Overture Project	13		
	4.3	Creatin	ng Files	14		
	4.4	Adding	g Standard Libraries	15		
	4.5	Setting	g Project Options	15		
5	Edit	ing VDI	M Models	19		
	5.1	VDM I	Dialect Editors	19		
	5.2	Using	Templates	19		
6	Inte	rpretati	ion and Debugging in Overture	21		
	6.1	Run an	nd Debug Launch Configurations	21		
	6.2	The De	ebug Perspective	24		
		6.2.1	The Debug View	25		
		6.2.2	The Variables View	25		
		6.2.3	The Breakpoints View	26		
		6.2.4	Conditional Breakpoints			
		6.2.5	The Expressions View	26		

7 Collecting Test Coverage Information



8	Pretty Printing to LATEX	31
9	Managing Proof Obligations	33
10	Combinatorial Testing 10.1 Using the Combinatorial Testing GUI	35 35
11	Mapping VDM++ To and From UML	37
12	Moving from VDM++ to VDM-RT	39
13	Analysing Logs from VDM-RT Executions	41
	Expanding VDM Models Scope and Functionality by Linking Java and VDM 14.1 Defining Your Own Java Libraries to be used from Overture 14.1 External Library Example 14.2 Enabling Remote Control of the Overture Interpreter 14.2.1 Example of a Remote Control Class 14.3 Using a GUI in a VDM model: Linking Example 14.3.1 The Modelled System 14.3.2 External Java Library 14.3.3 Remote Control 14.3.4 Deployment of the Java Program to Overture 15.1 Starting Overture at the Command-Line 15.2 Parsing, Type Checking, and Proof Obligations Command-Line 15.3 The Command-Line Interpreter and Debugger References	45 45 46 47 47 48 48 49 52 54 57 57 58 59 68
A	Templates in Overture	69
B	Internal Errors	73
С	Lexical Errors	75
D	Syntax Errors	77
E	Type Errors and Warnings	91
F	Run-Time Errors	107
G	Categories of Proof Obligations	115
Н	Mapping Rules between VDM++/VDM-RT and UML Models	119

CONTENTS



Ι	Usin	g VDM Values in Java 1	23
	I.1	The Value Class Hierarchy	23
	I.2	Primitive Values	23
	I.3	Sets, Sequences and Maps	25
	I.4	Other Types	27
	I.5	Function values	27
	I.6	Object Values	27
	I.7	Record Values	28
	I.8	Token Values	28
	I.9	Tuple Values	29
	I.10	Invariant Values	29
	I.11	Void Values	29

Index



ABSTRACT

This document is the user manual for the Overture Integrated Development Environment (IDE) for VDM. It serves as a reference for anybody wishing to make use of the tool with one of the VDM dialects (VDM-SL, VDM++ or VDM-RT). Overture tool support is built on top of the Eclipse platform. The objective of the Overture initiative is to create and support an open source platform that can be used for both experimentation with new VDM dialects, as well as new features for analysing VDM models in different ways. The tool is entirely open source, so anybody can join the development team and influence future developments. The long term goal is to ensure that stable versions of the tool suite can be used for large scale industrial applications of VDM technology.

Introduction

The Vienna Development Method (VDM) is one of the longest established model-oriented formal methods for the development of computer-based systems and software [Bjørner&78a, Jones90, Fitzgerald&08a]. It consists of a group of mathematically well-founded languages for expressing system models during early design stages, before expensive implementation commitments are made. The construction and analysis of a model using VDM helps to identify areas of incompleteness or ambiguity in informal system specifications, and provides some level of confidence that a valid implementation will have key properties, especially those of safety or security. VDM has a strong record of industrial application, in many cases has been used by practitioners who were not specialists in the underlying formalism or logic [Larsen&96, Clement&99, Kurita&09]. Experience with the method suggests that the effort expended on formal modelling and analysis can be recovered in reduced rework costs arising from design errors.

VDM models are expressed in a specification language (VDM-SL) which supports the description of data and functionality [ISOVDM96, Fitzgerald&98, Fitzgerald&09]. Data are defined by means of types built using constructors that define structured data and collections such as sets, sequences and mappings from basic values such as Booleans and natural numbers. These types are very abstract, allowing you to add any relevant constraints using data type invariants. Functionality is defined in terms of operations over these data types. Operations can be defined implicitly by preconditions and postconditions that characterize their behavior, or explicitly by means of specific algorithms. An extension of VDM-SL, called VDM++, supports object-oriented structuring of models and permits direct modelling of concurrency [Fitzgerald&05]. A further extension to VDM++, called VDM Real Time (VDM-RT¹), includes support for discrete time models [Mukherjee&00, Verhoef&06]. All three VDM dialects are supported by Overture.

Since VDM modelling languages have a formal mathematical semantics, a wide range of analyses can be performed on models, both to check internal consistency and to confirm that models have emergent properties. Analyses may be performed by inspection, static analysis, testing or mathematical proof. To assist in this process, Overture offers tool support for building models in collaboration with other modelling tools, to execute and test models and to carry out different forms of static analysis [Larsen&10]. It can be seen as an open source version of the closed (but

¹Formerly called VDM In a Constrained Environment (VICE).



now freely available) tool called VDMTools [Elmstrøm&94, Larsen01, Fitzgerald&08b] although features to generate executable code in high-level programming languages are not yet available in Overture.

This guide explains how to use the Overture IDE for developing models for different VDM dialects. It starts with an explanation of how to get hold of the software in Chapter 2. This is followed in Chapter 3 with an introduction to the Eclipse workspace terminology. Chapter 4 explains how projects are managed in the Overture IDE. Chapter 5 covers the features for creating and editing VDM models. This is followed in Chapter 6 with an explanation of the interpretation and debugging capabilities in Overture. Chapter 7 illustrates how test coverage information can be gathered when models are interpreted. Chapter 8 shows how models with test coverage information can be written as LATEX and automatically converted to PDF format. Chapters 9 to 13 cover various VDM specific features: Chapter 9 explains the notion of proof obligations and their support in Overture; Chapter 10 explains combinatorial testing and the automation support for that; Chapter 11 explains the support for mapping between object-oriented VDM models and UML models; Chapter 12 shows how a VDM++ project can be converted into a new VDM-RT project; Chapter 13 shows how to analyse and display execution logs from VDM-RT models; Chapter 14 demonstrates how Java can be used in combination with VDM models and Chapter 15 gives an overview of the features of Overture which are also available from a command-line interface. Appendix A provides a list of all the standard templates built into Overture. Appendixes B to G give complete lists of possible errors, warnings and proof obligation categories. Appendix H provides an overview of the VDM++/VDM-RT to UML mapping rules. Appendix I provides details about how to represent VDM values in order to combine Java with VDM as described in Chapter 14. Finally, Appendix I.11 is an index of significant terms used in the user manual.

Getting Hold of the Software

Overture: This is an open source tool, developed by volunteers and built on the Eclipse platform. The project is managed on SourceForge¹. The best way to run Overture is to download a special version of Eclipse with the Overture functionality already pre-installed. If you go to:

http://sourceforge.net/projects/overture/files/

you will find pre-installed versions of Overture for Windows, Linux and Mac².

Modelio: This is a tool that is both available in a commercial version as well as in an open source setting from a company called Softeam. Just like Overture this tool is built on top of the Eclipse platform. The product can be obtained from

http://www.modelio.org/.

For Overture you can use the *Download Now* button to automatically download pre-installed versions of Overture for your operating system. Supported systems are: Windows, Linux and Mac. Simply extract the zip file downloaded and run the Overture executable file at the top level to start the tool. Note that in order to be able to execute Overture you need to have Java Runtime Environment (minimum version 1.7) installed on your computer. When you start Overture for the first time, it will request a workspace location. We recommend that you choose the default location proposed by Overture and tick the box for "Use this as the default and do not ask again". A welcome screen will introduce you to the overall mission of the Overture open source initiative the first time that you run the tool and provide you with a number of interesting pointers of additional material (see Figure 2.1). You can always get back to this page using $Help \rightarrow Welcome$.

Large libraries of sample VDM-SL, VDM++ and VDM-RT models are available and can be downloaded from SourceForge under the files/Examples section using the URL³:

¹https://sourceforge.net/projects/overture/

²It is planned to develop an update facility, allowing updates to be applied directly from within the Overture tools without requiring a reinstallation. However, this can be a risky process because of the dependencies on non-Overture components and so is not yet supported.

³The library files are intended to be used with Eclipse, but can also be opened with file compression programs like Winrar on Windows



Overture VDM-10 Tool Support: User Guide

lit Navigate Search Project Run Window Help	
	₩ 🗢 🔿
Overture Tools for Formal Modelling in VDM	
<u>o</u>	
e Overture Platform	
erture is an open source tool for the Vienna Development Method (VDM). The tool supports different VDM dialects which include the ISO VDM-SL standard, as well as t ension VDM++ and the real-time extension of that called VDM-RT.	ne object-oriented
tting Started	
 See the help containing: the VDM Language Manual, the User Guide and a collection of examples. Goto Help->Help Contents and look for Overture. 	
 Documentation: Download user guides, tutorials, language manuals etc from the Overture SourceForge Documentation Download page 	
Visit the Overture website for general news: <u>OvertureTool.org</u> Visit the Wiki for both language and tool specific FAQs: <u>wiki.OvertureTool.org</u>	
Visit the wind to both language and tool specific rads. <u>Wind over the Pool of Q</u> New releases, examples, documentation and source are available at: <u>Source Forge</u>	
grading workspaces from earlier versions	
new Overture IDE is not compatible with workspaces from earlier versions, such as 0.2.x and earlier. Follow these steps to move your projects to the new IDE:	
. Select a new empty workspace (Not an existing one used by Overture IDE 0.2.x)	
. Select Import> Existing Projects into Workspace -> Next	
 Select browse next to "Select root directory" and navigate to your old workspace 	
. Check the projects which should be moved	
. Tick the "Copy projects into workspace" box . Click Finish and the projects will be copied into the new workspace	
. Circk Finish and the projects will be copied into the new workspace	
more info see the <u>Overture IDE online FAQ</u>	

Figure 2.1: The Overture Welcome Screen

https://sourceforge.net/projects/overture/files/Examples/

Such existing projects can be imported into Overture as described in section 4.1.

Finally, in order to make use of the test coverage feature described in Section 7 it is necessary to have the text processing system called $\[Mathbb{LATEX}\]$ and its pdflatex feature. This can for example be obtained from:

```
http://miktex.org/2.9/
```

Using the VDM Perspective

3.1 Understanding Eclipse Terminology

Eclipse is an open source platform based around a *workbench* that provides a common look and feel to a large collection of extension products. If you are familiar with one Eclipse product, you will generally find it easy to start using other products that use the same workbench. The Eclipse workbench consists of several panels known as *views*, such as those shown in Figure 3.1. A particular arrangement of views is called a *perspective*, for example Figure 3.1 shows the standard VDM perspective. This consists of a set of views for managing Overture projects and viewing and editing files in a project. Different perspectives are available in Overture as will be described later, but for the moment think of a perspective as a useful composition of views for conducting a particular task.

The VDM Explorer view lets you create, select, and delete Overture projects and navigate between the files in these projects, as well as adding new files to existing projects. A new VDM project is created choosing the $File \rightarrow New \rightarrow Project$ option which results in the dialog shown in Figure 3.2. Select the desired VDM dialect and press Next. Finally, the project needs to be given a name. Click Finish to create the project. Depending upon the dialect of VDM used in a given project, a corresponding Overture Editor view will be available to edit the files of your new project. Dialect editors are sensitive to the keywords used in each particular dialect, and simplify the task of working on the specification.

The *Outline* view, on the right hand side of Figure 3.1, presents an outline of the file selected in the editor. The outline shows all VDM definitions, such as state definitions, values, types, functions and operations. The type of each definition is also shown in the view and the colour of the icons in front of the names indicates the accessibility of each definition. Red is used for private definitions, yellow for protected definitions and green for public definitions. Triangles are used for type definitions, small squares are used for values, state components and instance variables, functions and operations are represented by larger circles and squares, permission predicates are shown with small lock symbols and traces are shown with a "T". Functions have a small "F" superscript over the icons and static definitions have a small "S" superscript. Record types have a small arrow in front of the icon, and if that is clicked the fields of the record can be seen.



P VDM - AlarmPP/plant.vdmpp - Overture Tools	
File Edit Navigate Search Project Run Window Help	
🗈 - 🗟 🖄 🗁 🎄 - 🛛 - 🏊 - 🔗 - Switch perspective 🖵 🖹 🖻 Proof Ob	liga 😋 Combinatori 🕸 Debug [VDM 🤇
🚼 VDM Explorer 🛛 🗧 🔲 🛃 alarm.vdmpp 🛛 😸 expert.vdmpp 🔀 🍟 plant.vdmpp 🔀 👘 🗖	🗄 Outline 🛛 🧼 🖓 🖓 🔌 👻 🗖 🗖
VDM Projects mberOfExperts(p) == return card schedule(p) ADT ADT AlarmEn AlarmPP Generated alarm.vdmpp Plantvdmpp README.txt S9 Plantvdmpp S1 Pit pre p in set dom schedule; S2 S3 public ExpertIsOnDuty: Expert ==> set of Period S4 ExpertIsOnDuty(ex) == S5 return (p p in set dom schedule 6 S6 ex in set schedule (p)); S7 S8 public Plant: set of Alarm * S9 map Period to set of Expert ==> Plant G0 Plant (als, sch) == S1 elaccource als; WDM Model files ""	 Plant alarms : set of Alarm st1 : nat schedule : map Period to set of Expert PlantInv(set of Alarm, map Period to set of Exp Period : token ExpertToPage(Alarm, Period) : Expert NumberOfExperts(Period) : nat ExpertIsOnDuty(Expert) : set of Period Plant(set of Alarm, map Period to set of Expert.
V DIVI VIOCETITIES V DIVI EU	Outline view
3 errors, 606 warnings, 0 others (Filter matched 103 of 609 items)	
Description Location Type Secrors (3 items) Problem view Location Type	
□ [•] Writable Insert 52:1	

Figure 3.1: The VDM Perspective

S New Project	
Select a wizard	
Wizards:	
type filter text	
	h Cancel

Figure 3.2: Creating a New VDM Project

Figure 3.3 illustrates the different outline icons. At the top of the view there are buttons to filter what is displayed, for instance it is possible to hide non-public members.

Clicking on the name of a definition in the outline will navigate to the definition and highlight the name in the Editor view.

The *Problems* view at the bottom of Figure 3.1 displays information messages about the projects you are working on, such as warnings and syntax or type checking errors.

The VDM Quick Interpreter view has a small command-line at the bottom where a plain VDM expression (not depending upon the definitions in the VDM model you are working with but for that you can use the "Console" launch mode explained in Section 6.1) can be entered. When return



CHAPTER 3. USING THE VDM PERSPECTIVE




Figure 3.3: Icons in the Outline View

is pressed, the expression will be evaluated and the result shown above the command-line.

Most of the other features of the workbench, such as the menus and toolbars, are similar to other Eclipse applications, with the exception of a special menu with Overture specific functionality.

3.2 Additional Eclipse Features Applicable in Overture

3.2.1 Opening and Closing Projects

To de-clutter the workspace and reduce the risk of accidental changes, it may be helpful to close projects that are not used being worked on. This can be done by right clicking such projects and then selecting the *Close Project* entry in the menu. Projects can similarly be re-opened using the same menu.

3.2.2 Adding Additional VDM File Extensions

So

It is possible to associate additional or different filename extensions with a particular VDM dialect editor, instead of the standard .vdmsl, .vdmpp and .vdmrt. This is done using the *Window* \rightarrow *Preferences* menu. Click the Add button for the appropriate content type.




Figure 3.4: Adding Additional Contents Types

3.2.3 Filtering Project Contents

It is possible to filter out certain file types from the VDM Explorer view. This is done by clicking the small downward pointing arrow at the top right-most corner of the view. See Figure 3.5. The *Filters...* option allows various files or directories to be hidden, including directories that have no source files.

3.2.4 Including line numbers in the Editor

If line numbers are required in the dialect editors, right click in the left-hand margin of the editor and select show line numbers as shown in Figure 3.6. Note that the current line number and cursor position are displayed in the eclipse status bar, at the bottom of the workspace, when an editor has focus.








Figure 3.5: Filtering Directories without source files

Toggle Breakpoint Enable/Disable breakpoint	
 Show Quick Diff Show Line Numbers 	Ctrl+Shift+Q
Preferences	
Breakpoint properties	

Figure 3.6: Adding Line Numbers in Editor



Managing Overture Projects

4.1 Importing Overture Projects

It is possible to import Overture projects by right-clicking in the Explorer view and selecting *Import*, followed by *General* \rightarrow *Existing Projects into Workspace*. In this way the projects from . zip files mentioned in Chapter 2 can be imported very easily.

4.2 Creating a New Overture Project

Follow these steps to create a new Overture project:

- 1. Create a new project by choosing $File \rightarrow New \rightarrow Project \rightarrow Overture$;
- 2. Select the VDM dialect you wish to use (VDM-SL, VDM-PP or VDM-RT);
- 3. Click Next;
- 4. Type in a project name;
- 5. Choose whether you would like the contents of the new project to be in your workspace or outside (browse to the appropriate directory);
- 6. The next step enables references to other projects (but this is not used at the moment);
- 7. The next step enables inclusion of VDM libraries and
- 8. Click the Finish button (see Figure 4.1).

Se New Project	
VDM++ Project Chose location for VDM++ project	
Project name: Tour Vise default location	
Location: C:\TEMP\OvertureIde-0.3.0\workspace\Tour Working sets	Browse
Add project to working sets Working sets:	Select
? < Back Next > Finish	Cancel

Figure 4.1: Create Project Wizard

4.3 Creating Files

Go

Switching to the VDM perspective will change the layout of the user interface to focus on VDM development. To change perspective, go to the menu $Window \rightarrow Open \ perspective \rightarrow Other...$ and choose the VDM perspective. From this perspective you can create files using one of the following methods:

- 1. Choose $File \rightarrow New \rightarrow VDM$ -SL Module or VDM-PP Class or VDM-RT Class or
- 2. Right click on the Overture project where you would like to add a new file and then choose *New* → *VDM-SL Module* or *VDM-PP Class* or *VDM-RT Class*.

In both cases you need to choose a file name and optionally choose a directory if you do not want to place the file in the home directory of the chosen Overture project. Then a new file with the appropriate file extension (according to the chosen dialect, .vdmsl, .vdmpp or .vdmrt) will be created in the directory. This file will use the appropriate module/class template to get you started. Naturally, keywords that are not required can be deleted from the template.



4.4 Adding Standard Libraries

In addition to adding new empty files it is possible to add existing standard libraries. This can be done by right-clicking on the project where the library is to be added and then selecting *New* \rightarrow *Add VDM Library*. That will make a new window as shown in Figure 4.2. Here the different standard libraries provide different standard functionalities. In the body of many of these functions/operations are declared as "is not yet specified" but the actual functionality for all of these are hard-coded into Overture so the user can get access to this when the respective standard libraries are included. This can be summarised as:

- **IO:** This library provides functionality for input and output from/to files and the standard console.
- Math: This library provides functionality for standard mathematical functions such as sine and cosine.
- **Util:** This library provides functionality for converting different kind of VDM values mainly to and from files and strings.
- **CSV:** This library is an extension of the IO library which provides additional functionality for saving and reading VDM values to/from comma separate format used by excel spreadsheets.
- **VDM-Unit:** This library provides functionality for unit testing of VDM models similar to the well-known JUnit library.

These libraries are available for all VDM dialects also when a flat VDM-SL specification is used.

4.5 Setting Project Options

There are various VDM specific settings for an Overture project. You can change these by selecting a project in the *Explorer* view and then right clicking and selecting *Properties*. See Figure 4.3. The options that can be set for each VDM project are:

Language version: Here the default is to use the *classic* version which is similar to that used in VDMTools. Alternatively you can select VDM-10 which is a new improved (but not necessarily backwards compatible) version of the VDM dialects developed by the Overture Language Board.

Suppress type checking warnings: Warnings are enabled by default but you can change it here.

Overture allows VDM specifications to be embedded in LATEX files that form part of the documentation of a project as seen in Figure 4.4. The project settings allow you to define a main LATEX file for the project, and define the order in which the different VDM source files shall be included. Note that if the "Insert coverage tables" and "Mark coverage" options are selected

Se Add Library Wizard		
Add Library Select the libraries to include		
Select libraries to include IO Math Util CSV VDM-Unit		
?	Finish	Cancel

So

Figure 4.2: Adding New Libraries

Properties for Hotel		
type filter text	VDM Settings	↓ ↓ ↓ ▼
Resource Builders Project References Refactoring History Run/Debug Settings VDM Build Path	Language options Language version classic Type checking Suppress warnings	•
VDM Settings		Restore Defaults Apply
?		OK Cancel

Figure 4.3: Overture Project Settings

the LATEX pretty printing will include test coverage information as well as provide test coverage tables for each class/module in the VDM model. It is also possible to define your own main document instead of making use of the standard one suggested by Overture (which is the name of the project followed by .tex). Finally, the "Model only" option is used to select if you wish to



CHAPTER 4. MANAGING OVERTURE PROJECTS

include only the VDM model or also the text that can be written outside	\begin{vdm_al}" and
"\end{vdm_al}" environments (see Chapter 8 for more details).	

Properties for Smoking		
 Resource Builders Project References Run/Debug Settings VDM Build Path VDM Settings Latex 	Latex options Main document Browse Insert coverage tables Model only	 ← ▼ → ▼ ▼ Smoking.tex ✓ Generate main document ✓ Mark coverage Restore Defaults Apply
?		OK Cancel

Figure 4.4: Overture Project Settings for LATEX

It is also possible to set various preferences that apply to all projects. This is done in the general VDM preferences dialog under *Window* \rightarrow *Preferences* \rightarrow *VDM*. Here, for example, it is possible to link projects to VDMTools if you have the appropriate SCSK executables installed on the computer. Figure 4.5 shows how it is possible to set up paths to the corresponding VDMTools executables. If these paths have been set, it is possible to right click on a project in the VDM Explorer view and select *VDM Tools* \rightarrow *Open project in VDMTools*. Then a project file for VDMTools will automatically be generated with all the files from the Overture project and VDMTools will be opened.

The *Preferences* dialog also allows you to switch off continuous syntax checking while editing and to set the path to *pdflatex* if this is not automatically visible from the Overture application. It is also possible to set a few other areas (debugger and dot) but these are mostly used by the developers. Finally it is possible to manage VDM templates, but that is described in Section 5.2.

In the same fashion it is possible to set preferences for the way VDM++ and VDM-RT models are mapped to UML. This can be seen in Figure 4.6. More information about these preferences can be found in Chapter 11.



Preferences				_ 0 X
type filter text	SCSK/VDM Tools			⇔ - ⇔
⊳ General ⊳ Help	Path to VDM Tools for VDM-SL (vdmgde):	C:\Program Files\The VDM-SL Toolbox \	9.0.2\bin\vdmgde.exe	Browse
 Install/Update Run/Debug 	Path to VDM Tools for VDM-PP (vppgde):	C:\Program Files\The VDM++ Toolbox v	9.0.2\bin\vppgde.exe	Browse
⊳ Team ⊿ VDM				
Combinatorial Testing Debugger				
Dot				
Editor Latex				
SCSK/VDM Tools Templates				
UML Translation			Restore Defaults	Apply
?			ОК	Cancel

Figure 4.5: Overture Preferences for connections to VDMTools

Preferences			x
Editor Latex	UML Translation Image: Prefer associations during translation Image: Disable perfected at ife static Darkerment Disable perfected at ife static Darkerment Disable perfected at iteration	← ← → →	•
Templates UML Translation	Disable nested artifacts in Deployment Dia	Restore Defaults Apply	
?		OK Cancel	

Figure 4.6: Overture Preferences for mapping to UML

Editing VDM Models

5.1 VDM Dialect Editors

VDM model files are always changed in the dialect Editor view. Syntax checking is carried out continuously as source files are changed (even before the files are saved). Whenever files are saved, assuming there are no syntax errors, a full type check of the *entire* VDM model is performed. Problems and warnings will be listed in the Problems view as well as being highlighted directly in the Editor view where the problems have been identified.

5.2 Using Templates

Eclipse templates can be particularly useful when writing VDM models. If you press *CTRL+space* after typing the first few characters of a template name, Overture will offer a proposal. For example, if you type "fun" followed by *CTRL+space*, the IDE will propose the use of an implicit or explicit function template as shown in Figure 5.1. The IDE includes several templates: cases, quantifications, functions (explicit/implicit), operations (explicit/implicit) and many more. The use of templates makes it much easier for users to create models, even if they are not deeply familiar with the VDM syntax.

It is possible to adjust or add to the templates defined in Overture. This can be done in the general VDM preferences under $Window \rightarrow Preferences \rightarrow VDM \rightarrow Templates$. Figure 5.2 shows where to adjust templates in Overture. Note that new templates can be added and the existing ones can be edited or removed. A full list of the standard Overture templates is available in Appendix A.



```
30 functions
 31
 32
      NumberOfExperts: Period * Plant -> nat
 33
     NumberOfExperts(peri,plant) ==
34
       card plant.schedule(peri)
35
      pre peri in set dom plant.schedule;
 36
 37
      ExpertIsOnDuty: Expert * Plant -> set of Period
 38
      ExpertIsOnDuty(ex,mk Plant(sch,-)) ==
 39
        (peri| peri in set dom sch & ex in set sch(peri));
 40
 41
      ExpertToPage(a:Alarm,peri:Period,plant:Plant) r: Expert
 42
      pre peri in set dom plant.schedule and
 43
         a in set plant.alarms
 44
      post r in set plant.schedule(peri) and
 45
          a.quali in set r.quali;
 46
 47
      QualificationOK: set of Expert * Qualification -> bool
 48
      QualificationOK(exs,reqquali) ==
 49
        exists ex in set exs & reqquali in set ex.quali
 50
851
      functionName : parameterTypes -> resultType
52
      functionName (parameterNames) == expression
53
      pre preCondition
 54
      post postCondition
55
```

Figure 5.1: Explicit function template

elp nstall/Update N un/Debug eam	eate, edit or remove templa Name V act	Context VDM-PP Template context type	Description	Auto Ins	•	New
nstall/Update N Run/Debug Team	✓ act			Auto Ins	^	New
		VDM-PP Template context type				TACAA!
	-		The number of times that operation name operatio	on	Е	Edit
	✓ act	VDM-RT Template context type	The number of times that operation name operatio	on		
	✓ active	VDM-PP Template context type	The number of operation name operations that are	on		Remove
CSK Debugger	✓ active	VDM-RT Template context type	The number of operation name operations that are	on		
Templates	V bus	VDM-RT Template context type	BUS (Priority <csmacd>, capacity,set of connecte</csmacd>	on		Restore Rem
rempores 5	caseExpression	VDM-PP Template context type	Case Expression	on		Revert to De
	caseExpression	VDM-RT Template context type	Case Expression	on		
	caseExpression	VDM-SL Template context type	Case Expression	on		Import
	✓ class	VDM-PP Template context type	Class Definition	on		
	✓ class	VDM-RT Template context type	Class Definition	on		Export
	classSkeleton	VDM-PP Template context type	Class Definition full skeleton	on		
5	classSkeleton	VDM-RT Template context type	Class Definition full skeleton	on		
5	🗸 cpu	VDM-RT Template context type	CPU (Priority <fp fcfs="">, capacity)</fp>	on	-	
Pre	eview:					

Figure 5.2: Adjusting templates for Overture

Interpretation and Debugging in Overture

This chapter describes how to run and debug a model using the Overture IDE.

6.1 **Run and Debug Launch Configurations**

To execute or debug a VDM model, you must first create a launch configuration. To do this, go to the main Run menu and select $Run \rightarrow Run$ Configurations. Select the type of project you want to launch, click the New icon to create a new launch specification of that type and give it a name. The launch dialog requires you to identify the VDM project name, the class/module name and the initial operation/function to call in that class/module. Figure 6.1 shows a launch dialog. The standard Eclipse strategy is the launch mode called "Entry point" and then you simply click the Browse button and it will let you select a project from those available in the workspace. Clicking the Search button will search the chosen project for classes and modules to select a public operation or function from. If the chosen operation or function has parameters, the types and names of those parameters will be copied into the Operation box – these *must* be replaced with valid argument values¹.

However, there are other launch mode possibilities here as well. The "Remote Control" launch mode is advanced but it is explained in more detail in Section 14.2. The "Console" launch mode enables you to get a special debug console where you can enter multiple entry points (one after another) instead of deciding upon the single entry point at launch time². The commands that can be used in the "Console" view correspond to the commands you can give at command-line when it has been started in interpreter mode (see Section 15.3).

Your new launch configuration can be started immediately by clicking the *Run* button at the bottom of the dialog. Alternatively, the configuration can simply be saved by clicking *Apply*. Once a launch configuration has been defined, it can be re-run at any time by using the small downward arrow next to the run or debug icons (**) in the IDE toolbar.

¹You will see type checking errors at the top of the dialog if you do not do this, such as "Error 3063: Too few arguments in ..."

²Those familiar with VDMTools will recognise this functionality as initialising a specific VDM model and then having a prompt where different expressions can be evaluated making use of the definitions from the model.

A launch configuration can either be started normally, which will simply evaluate the expression given and stop, or it can be started in debug mode, which will stop the evaluation at any breakpoints you may have set. The same launch configuration can be used for either purpose, though by default those created through the *Run Configurations* dialog will appear in the favourites list under the *Run* toolbar icon. Similarly, a launch configuration created under the *Debug Configurations* dialog will appear under the favourites of the debug toolbar icon. You can control which icons display the launch configuration in the *Common* tab on the dialog. This is standard Eclipse behaviour.

B VDM-PP Launch Configuration		x
Create, manage, and run c	onfigurations	d)
type filter text VDM PP Model AlarmPP ArchitectureStateMa CMRT MDM RT Model CMRT Run WDM SL Model AlarmSL	Name: AlarmSL Image: Main Runtime Image: Project Project: AlarmSL Browse Launch Mode: Image: Image: Entry Point Remote Control Console Entry Point: Module: Function/Operation: Search Fully qualified remote control class: Other: Image: Other: Image: Generate coverage	
Filter matched 8 of 8 items	Apply Revert	
?	Debug Close	

Figure 6.1: The launch configuration dialog

Whenever a launch configuration is started up it is also possible to decide upon which additional run-time checks to carry out. By default all possible run-time checks are swiched on but if desired (some of) these can be swiched off using the "Runtime" pane (see Figure 6.2). Note that for VDM-RT debugging it is also possible to switch off the logging of all events appearing during the debugging. The different run-time checks that can be performed are:

Dynamic type checks: This is an option for the interpreter (default on) to continuously type check values during interpretation of a VDM model. It is possible to switch off the check here³.



³However a consequence of doing that can be that you may get internal Java errors (null pointer or class cast exceptions typically) rather than nice clean VDM type errors about mismatched types.



- **Invariant checks:** This is an option for the interpreter (default on) to continuously check both state and type invariants. It is possible to switch off this check here, but note that option requires dynamic type checking also to be switched off.
- **Pre condition checks:** This is an option for the interpreter (default on) to continuously check pre-conditions for all functions and operations during interpretation of a VDM model. It is possible to switch off this check here.
- **Post condition checks:** This is an option for the interpreter (default on) to continuously check post-conditions for all functions and operations during interpretation of a VDM model. It is possible to switch off this check here.
- **Measure checks:** This is an option for the interpreter (default on) to continuously check recursive functions, for which a measure function has been defined. It is possible to switch off this check here⁴.

In the launch configuration the "Debugger" pane shown in Figure 6.3 can also be useful in rare cases where one has particularly deep recursion for example. This is an advanced setting where one can decide the arguments given to the Java virtual machine for allocation of maximum amounts of space per thread in a VDM model. However, this option is rarely needed.

VDM-PP Launch Configura	ations
Create, manage, and re Debug	un configurations
Image: Second system Image: Second system type filter text Java Applet Java Application Remote Java Applic Image: VDM PP Model Image: VDM RT Model Image: CMRT Run Image: VDM SL Model	Name: CMRT Run Main Runtime Interpreting Interpreting Invariants checks Image: Post condition checks Image: Post condition checks VDM Real-Time options Image: Log Real-Time Events
Filter matched 13 of 13 item	Apply Revert Debug Close
	Close

Figure 6.2: The launch configuration dialog

⁴Note that this feature may not work correctly with the presence of mutually recursive function definitions.

So VDM-PP Launch Configura	ations
Create, manage, and r Debug	un configurations
Image: Second system Image: Second system type filter text Image: Second system Im	Name: AlarmSL Main Runtime Source Common Develop Java Virtual Machine custom arguments (e.g: -Xmx1024M -Xss20M): Arguments: Arguments: Arguments: Apply Revert
?	Debug Close

Figure 6.3: The launch configuration dialog

Button	Explanation
	Resume debugging
	Suspend debugging
	Terminate debugging
P .	Step into
0	Step over
_ 🖻	Step return
T.	Use step filters

Table 6.1: Overture debugging buttons

6.2 The Debug Perspective

So

The Debug Perspective contains all the views commonly needed for debugging in VDM. Breakpoints can easily be set in the model by double clicking in the left margin of the Editor view at the chosen line. When the debugger reaches the location of a breakpoint and stops, you can inspect the values of different identifiers and step through the VDM model line by line.

The Debug Perspective is illustrated in Figure 6.4.



Debug - POP3/messagechannel.vdmpp - Overture Tools	Martin Martin Martin Co.	Contraction of the local distance of the loc	
File Edit Navigate Search Project Run Window Help			
📑 • 🔛 🐚 👘 • 🕢 • 🗛 • 🧶 •] = {] = \$ ~ \$ ~ \$	E	PO Proof Obliga 📴 Combinatori 🌾 Debug 🚼 VDM
🏂 Debug 😫 🦉	m = Mla o A = let V P A	🕬 Variables 🕴 💁 Breakpoints	
POP3 Test1 [VDM PP Model] VDM Application Main - WAITING	Call traces in debug	Vame > @ Global Variables @ Instance Variables	Value Inspecting variables
ObjectThread-6 on vCPU - RUNNABLE ObjectThread-7 on vCPU - RUNNING messagechannel.vdmpp line: 94		 ↓ Instance variables ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓ ↓	POP3Types'USER "paul"
 pop3clienthandler.vdmpp line: 400 pop3server.vdmpp line: 130 ObjectThread-4 on vCPU - WAITING 		 ♦ io ♦ #fin(ClientSend) 	true IO(#66) 1
ObjectThread-S on vCPU - RUNNABLE VDMJ debugger			0
B plant.vdmpp	🚼 pop3test.vdmpp 🛛 🚼 pop3message.vdn	npp 📓 messagechannel.vdmpp 🛛 🔭	□
91 92 (begin(vdm_el) 93 ymc 94 (per ServerListen -> #fin(ClientSend) 95 #fin(ServerListe 96 (bed(vdm_el) 97 (begin(vdm_el) 98 (begin(vdm_el) 100 (begin(vdm_el) 102 (begin(vdm_el) 102 (begin(vdm_el) 102 (begin(vdm_el) 102 (begin(vdm_el) 103 (begin(vdm_el) 103 (begin(vdm_el) 104 (begin(vdm_el) 105 (begin(vdm_el) 105 (begin(vdm_el)) 105 (begin(vdm_el)) 105 (begin(vdm_el)) 106 (begin(vdm_el)) 107 (begin(vdm_el)) 108 (begin(vdm_el)) 109 (begin(vdm_el)) 109 (begin(vdm_el)) 109 (begin(vdm_el)) 100 (begin(vdm	n);	VDM Editor	MessageChand data:[ClentCommand] ServerResponse] data:[ClentCommand] ServerResponse] debug: bool ServeSendServerResponse] ServeSendServerResponse ClentSend(InterCommand) 0 ServeSendServerResponse ClentSend(InterCommand) pre_ServerInterponse mediate mediate
Creating POP3ClientHandler***> ClientSend**	*> fin ClientSendClient c says -> s	k_FOP3Types'USER("paul")	Debug console

Figure 6.4: Debugging perspective

6.2.1 The Debug View

The *Debug* view is located in the upper left corner in the Debug perspective – see Figure 6.4. The view shows all running models and whether a given model is stopped, suspended or running. It shows the call stack of models that are suspended, and for VDM++ and VDM-RT stacks for all threads are shown. At the top of the view, there are buttons for debugging such as: stop, step into, step over, resume, etc. (see Table 6.1). Note that in case a multi-threaded VDM model is debugged it is possible in this view to change to another thread to inspect where it is currently and inspect the local variables at that thread since they are all stopped when a breakpoint is reached.

6.2.2 The Variables View

The *Variables* view shows all the variables in a thread context, allowing them to be examined after a breakpoint (or an error) has been reached. The variables and their values are automatically updated when stepping through a model. The view is located in the upper right hand corner in the Debug perspective. It is possible to inspect compound variables, expand nested structures and so on. Note that when you stop at a permission predicate it is also possible to see the value of the relevant history counters (in Figure 6.4 #fin(ClientSend) and #fin(ServerListen)). By right-clicking on a variable it is possible to select a "watch point". As a result a window like Figure 6.5 will occur. Using this it is possible to watch the value of such a variable easily whenever a new stop is reached in the debugging process.

Name	Value
^{¥+y} "b2"	map[4]
Maplet 1	{ <d> -> 4}</d>
Maplet 2	{ <e> -> 1}</e>
Maplet 3	{ <a> -> 1}
Maplet 4	{ <c> -> 5}</c>
🕂 Add new expression	

Figure 6.5:	Example of a	watchpoint
	r	······································

6.2.3 The Breakpoints View

So

Breakpoints can be added in any perspective from the Editor view⁵. The debug perspective also has a *Breakpoints* view that lists all current breakpoints, allowing you to navigate easily to the location of a given breakpoint, disable it or delete it. The view is located in the same panel as the Variables view in the upper right hand corner.

6.2.4 Conditional Breakpoints

Breakpoints can be conditional. This is a powerful feature for the developer since it allows you to specify a conditional expression which has to be true for the debugger to stop at the given breakpoint. As well as using an expression, a conditional breakpoint may specify a hit count and whether the breakpoint should stop when the hit count is equal to, greater than, or a multiple of the given value, or a general expression using the variables in scope at the breakpoint.

A normal breakpoint can be made conditional by right clicking on the breakpoint mark in the Editor view⁶ and selecting *Breakpoint Properties*. This opens a dialog like the one shown in Figure 6.6.

6.2.5 The Expressions View

The *Expressions* view allows you to define expressions that are evaluated whenever the debugger stops. Watched expressions can be added to the view directly, or created by selecting *Watch* when right-clicking a variable in the Variables view. It is also possible to edit existing expressions. The view sits in the same panel as the Breakpoints view and the Variables view.

⁵Note that breakpoints can only be set on lines that contain executable code.

⁶Note this is not possible from the Breakpoint view



Properties for		
Breakpoint properties	Line Breakpoint	<p th="" ⇒="" ▼="" ▼<=""></p>
	Filename: flarecontroller.vdmrt	
	Line: 45 Charle	
	Hit Counter:	
	Enable Condition	
	evid = 4	•
	4	Ŧ
	Suspend when:	4
	condition is 'true'	
	value of condition changes	
?		OK Cancel

Figure 6.6: Conditional breakpoint options



Collecting Test Coverage Information

When a VDM model is being interpreted, it is possible to automatically collect test coverage information. Test coverage measurements help you to see how well a given test suite exercises your VDM model.

In order to enable the collection of test coverage data, go to the debug launch configuration and select the *Generate coverage* option. After running this configuration, a new file with a .cov extension will be created for each file in the project. These files are written into a project subfolder named generated/coverage/<date and time>. Double-clicking the .cov files will open a special editor window that displays the source with coverage coloured in red/green (red is executable but not covered). Alternatively, a PDF file containing the entire model with coloured test coverage summarised for all runs can be generated by right-clicking on the project name and selecting *Latex* \rightarrow *Latex Coverage*.



Pretty Printing to IAT_EX

It is possible to use literate programming/specification [Johnson96] with Overture just as you can with VDMTools. To take advantage of this, you need to use the $\[Mathbb{LTEX}\]$ text processing system with plain VDM models mixed with textual documentation. The VDM model parts must be enclosed within "\begin{vdm_al}" and "\end{vdm_al}". The text-parts outside these specification blocks are ignored by the VDM parser, though note that each source file must start with a recognizable $\[Mathbb{LTEX}\]$ construct: a \documentclass, \section, \subsection or a $\[Mathbb{LTEX}\]$ comment.



Managing Proof Obligations

In all VDM dialects, Overture can identify places where run-time errors *could* potentially occur if the model was to be executed. The analysis of these areas can be considered as a complement to the static type checking that is performed automatically. Type checking accepts specifications that are *possibly* correct, but we also want to know the places where the specification could possibly fail.

Unfortunately, it is not always possible to statically check if such potential problems will *actually* occur at run-time error or not. So Overture creates *Proof Obligations* for all the places where run-time errors *could* occur. Each proof obligation (PO) is formulated as a predicate that must hold at a particular place in the VDM model if it is error-free, and so it may have particular context information associated with it. POs can be considered as constraints that will guarantee the internal integrity of a VDM model if they are all met. In the long term, it will be possible to prove these constraints with a proof component in Overture, but this is not yet available.

POs can be divided into different categories depending upon their nature. The full list of categories can be found in Appendix G along with a short description for each of them.


The proof obligation generator is invoked either on a VDM project (and then POs for all the VDM model files will be generated) or for one selected VDM file. Right-click the project or file in the Explorer view and then select *Proof Obligations* \rightarrow *Generate Proof Obligations*. Overture will change into a special *Proof Obligations* perspective as shown in Figure 9.1.

Note that in the *Proof Obligation Explorer* view, each proof obligation has four components:

- A unique number in the list shown;
- The name of the definition in which the proof obligation is located;
- The proof obligation category (type); and
- A status field indicating whether the proof obligation is trivially correct or would have to be proved by a proof engine.

At the top of the *Proof Obligation Explorer* the *Filter proved* button allows you to filter away all the proof obligations that are trivially correct.





pre_ExpertToPage(a, peri, plant) => exists r:Expert & post_ExpertToPage(a, peri, plant, r))

Figure 9.1: The Proof Obligation perspective

Combinatorial Testing

In order to better automate the testing process, a notion of test *traces* has been introduced into VDM++ (and subsequently VDM-SL and VDM-RT)¹. Traces are effectively regular expressions that can be expanded to a collection of test cases. Each test case comprises a sequence of operation calls. If a user defines a trace it is possible to make use of a special *Combinatorial Testing* perspective to automatically expand the trace and execute all of the resulting test cases. Subsequently, the results from the tests can be inspected and erroneous test cases easily found. You can then fix problems and re-run the trace to check they are fixed.

10.1 Using the Combinatorial Testing GUI

The syntax for trace definitions is defined in the VDM-10 Language Manual. If you have created a traces entry for a module or class it can be executed via the *Combinatorial Testing* perspective. See Figure 10.1.

Different icons are used to indicate the verdict in a test case. These are:

- \wp : This icon is used to indicate that the test case has not yet been executed.
- \checkmark : This icon is used to indicate that the test case has a pass verdict.
- (): This icon is used to indicate that the test case has an inconclusive verdict.
- **K**: This icon is used to indicate that the test case has a fail verdict.
- S4 (2800 skipped 120): If any test cases result in a run-time error, other test cases with the same sequence of calls will be filtered and automatically skipped in the test execution. The number of skipped test cases is indicated after the number of test cases for the trace definition name.

In the CT Overview view, you can right-click on any individual test case and then execute it with the interpreter (see Figure 10.2). This is particularly useful for failed test cases since the interpreter allows you to step through the evaluation to the place where it is failing. You can inspect the exact circumstances of the failure, including the values of the different variables in scope.

¹Note that this is only available for VDM-SL and VDM-RT models if the VDM-10 language version has been selected.




Figure 10.1: Using Combinatorial Testing

concfactorial.vdmpp 🛛 🔛 World.vdmrt 🛛 🔛 IO.vdmrt 🛛 🚼 usetree.vdmpp 🛙 🔪	😸 tree.vdmpp 👌 " 🗖 🔽 CT Overview 🛛 👘
class UseTree	🔶 🛛 🐣 💟 A Kefresh 🛃 💽 😽 📎
	a 📂 POP3Test
instance variables	💿 Two (0)
<pre>t1 : BinarySearchTree := new BinarySearchTree();</pre>	🔺 🗁 SAFERPP
<pre>t1 : BinarySearchTree := new BinarySearchTree(); t2 : Tree := new BinarySearchTree()</pre>	a 🗁 Test
cz . Hee new BinarySearchitee()	> 🍥 BT (162)
traces	iiiiiiiiiiiiiiiiiiiiiiiiiiiiiiiiiiiiii
	a 🗁 SortPP
insertion BST :	a 📂 SortMachine
(let n in set {1,,5} in	 DiffSorting (0)
<pre>t1.Insert(n)</pre>	a 🗁 Tree
){2}; (t1.breadth_first_search()	a 📂 UseTree
<pre>t1.depth_first_search() </pre>	a 🌚 insertion_BST (100)
tl.inorder ()	🔀 Test 000001
t1.isEmpty()	Send to Interpreter
)	
end UseTree	🔀 Test 000004
end oserree	🔀 Test 000005
	🔶 Test 000006
	🔀 Test 000007
	🔀 Test 000008
	🔀 Test 000009
	🔀 Test 000010
	- V Test 000011
4	Fest 000012
Problems 📮 Console 📴 CT Test Case result 🕴 🛛 PO Proof Obligation Explorer	
race Test case R	lesult
.Insert(2) ())
.Insert(1) (
	rror 4087: Cannot convert <empty> at line 75:23</empty>

Figure 10.2: Moving test case from Combinatorial Testing to Interpreter



Mapping VDM++ To and From UML

VDM++ and VDM-RT projects can be converted automatically back and forth between VDM and the corresponding UML model. UML can be considered as different views of the same model. A UML model is typically used to give a graphical overview of the model using class diagrams. The VDM model is typically used to define the implementation and constraints for each class and is therefore used for detailed semantic analysis. Note that state charts, activity diagrams, sequence diagrams, objects charts, package charts are not used in the UML mapping. It is essentially only the information used statically inside classes and their usage in class diagrams that is used.

To convert a UML class diagram model to a VDM++ model, you first need to export the UML model from Modelio to the Eclipse XMI format, called UML using the EMF UML3.0.0 format At the moment, Modelio is the only UML tool supported. Export from Modelio is done as illustrated in Figure 11.1.




Figure 11.1: Exporting UML definitions from Modelio

Importing and exporting a UML model is an option in the Overture *Explorer* view, where rightclicking a VDM++ or VDM-RT project gives a submenu for *UML Transformation*. From here it is possible to *Convert to UML*. If the mouse is placed over a .uml file it is also possible to right-click and choose the submenu for *UML Transformation* and then select *Convert to VDM*.

The mapping rules between VDM++/VDM-RT and UML models are further explained in Ap-



pendix H. Note that the mapping depends on the settings selected in the *Preferences* menu (see Figure 4.6 above). The general explanation of these options are:

- **Prefer associations during translation:** If this option is chosen (ticked) references to instances of other classes will be modelled as associations between the classes in a class diagram. Otherwise these will be modelled as attributes.
- **Disable nested artifacts in Deployment Diagrams:** If this option is chosen (ticked) nested artifacts in a deployment diagram are disabled; otherwise it is enabled.

Moving from VDM++ to VDM-RT

The methodology for the development of distributed real-time embedded systems in VDM defines a step where you move from an initial VDM++ model to a VDM-RT model [Larsen&09]. This step is supported by the Overture tool which will convert a VDM++ project to create the starting point for a new VDM-RT project. This is done by right-clicking on the VDM++ project to be converted in the Explorer view, followed by the *Clone as VDM-RT* option. A new VDM-RT project is then automatically created and it will initially be given the same name as the one generated from with postfix with "_VDM_RT". It will have the same name as the original VDM++ project, but with VDM_RT appended. Inside the project, all the .vdmpp files will have been converted to a .vdmrt extension. The original VDM++ project is not changed at all. So this is simply a quick and easy way to get to the starting point for a VDM-RT model. You would then manually create a system class with appropriate declarations of CPUs and BUSses and proceed with the real time model development.



Analysing Logs from VDM-RT Executions

Whenever a VDM-RT model is executed a binary logfile with .rtbin extension is created in the generated/logs subfolder. In order to distinguish between multiple runs, the name of the logfile indicates the time at which the model was executed. Logfiles can be viewed with the built-in *RealTime Log Viewer*, by double-clicking the .rtbin file in the Explorer view. In addition, Overture provides a textual version of the log file with .rt extension, which can be inspected using any text editor.

The RealTime Log Viewer enables you to explore the simulated system execution in various ways. In Figure 13.1 the architectural overview of a system is shown, describing the CPU and BUS topology of the model.




Figure 13.1: Architectural overview

The RealTime Log Viewer also enables you to get an overview of the model execution at a system level – see Figure 13.2. This view shows how the different CPUs communicate via the BUSes of the system.

Since the complete execution of a model cannot generally be shown in a normal sized window, you have the option of jumping to a certain time index using the $\stackrel{\text{Move next}}{=}$ button or moving to the next time index using the Move next button. Also, Overture enables you to move to the previous time index using the Move Previous button. Finally, it is also possible to export all the generated views to JPEG formatted files using the $\stackrel{\text{Move next}}{=}$ button. All the generated images will be placed in the logfile directory, where each image holds a name indicating the time of execution and the specific view (Execution overview, CPU1, CPU2 etc.).

The RealTime Log Viewer also provides an overview of all executions on a single CPU. Each CPU shows a detailed description of all operations and functions invoked on the particular CPU as




Figure 13.2: Execution overview

well as the scheduling of concurrent processes — see Figure 13.3.

ලිං




Figure 13.3: Execution on a single CPU

Analyzing timing properties at the system level

The work of [Fitzgerald&07] presents an extension to VDM-RT, enabling the validation of systemlevel timing properties. *Validation conjectures* are descriptions of temporal relations between system level events, which can be evaluated over the execution trace. Later this work has been extended in [Ribeiro&11] to include run-time validation. Predefined standard forms of validation



conjectures have been defined, directly supporting the validation of a deadline or separation between two events, called the *trigger* and the *response*. The trigger event could be the press of a button, and the corresponding response may be the update of a display. From the standard forms, more specific validation conjectures can be constructed.

In Overture it is possible to specify validation conjectures as comments in the **system** class. Listing 13.1 provides an example of a validation conjecture requiring the separation of 500 ms between two subsequent screen updates.

```
system Distribution
... // Class content omitted
/* timing invariants
separate(#fin(MMI`UpdateScreen), #fin(MMI`UpdateScreen), 500 ms);
*/
end Distribution
```

Listing 13.1: Validation conjecture example

In Overture validation conjectures are evaluated over the execution trace at run-time and in case violations occur they will be written to a *violations file* with .txt extension. The violations file is located in the log file directory and named by the time of execution. When this file is loaded using the **button**, Overture will list the violations as shown in figure 13.4. In particular, this figure shows two violations of the validation conjecture in listing 13.1.

status	name	expression	src time	src thread	dest time	dest thread
FAIL	C1	separate(#fin(MMI`UpdateScreen),#fin(MMI`UpdateScreen),50000000)	118254267	14	209165360	15
FAIL	C1	separate(#fin(MMI`UpdateScreen),#fin(MMI`UpdateScreen),50000000)	209165360	15	300076453	16

Figure 13.4: Violations of validation conjectures will be listed in a table

In addition, the RealTime Log viewer will show the violations graphically by marking the trigger and corresponding response in the model execution overview. Figure 13.5 shows the two violations from figure 13.4, where the response and trigger of the first and second violation, respectively, occur at the same point in time. This explains why only tree markers, i.e. the circles, are visible in the figure.




Figure 13.5: Violations of validation conjectures shown in the model execution overview



Expanding VDM Models Scope and Functionality by Linking Java and VDM

In some cases the impact and value of VDM models can be immensely improved by expanding them with functionality which is not delivered directly by VDM. Examples of such functionality could be; (a) to associate the model with existing legacy systems, for which no model or specification exists, (b) to add a graphical representation of the model, or (c) to enable network communication, for instance in a client-server setup. In order to achieve this functionality Overture enables the possibility of linking a VDM model directly with the underlying Java-based Overture interpreter. In addition it is possible to link a Java implementation with a VDM model.

Overture supplies two different techniques for linking between VDM and Java; (1) the functionality which allow VDM to interact with an "External Java Library" is described in Section 14.1 and (2) the method used to allow a Java implementation to "Remote Control" a VDM model is explained in Section 14.2. An example of how these methods can be used to create a GUI for a model is supplied in Section 14.3.

14.1 Defining Your Own Java Libraries to be used from Overture

VDM models are not appropriate for describing everything. It is common to have existing legacy code that you may not wish to spend time modelling in VDM, but would like to make use of from a VDM model. Overture has a feature to link a VDM model with external Java libraries contained in a standard jar file¹. Using this feature it is possible to call functionality provided by jar files from a VDM model. This functionality corresponds to DL modules/classes in VDMTools [DLMan].

External jar libraries are linked to VDM via is not yet specified statements and expressions. Operations or functions of modules or classes can be delegated to an external jar, calling out to a Java class. The Java delegate, if present, has the same name as the VDM module/class name with underscores ("_") replaced with package naming dots ("."). For example, the VDM class

¹In fact the IO, MATH, Util, CSV and VDM-Unit libraries are implemented as such external jar files.



remote_lib_sensor becomes the class remote.lib.sensor in Java. The delegate lookup is only done once and only when an is not yet specified statement or expression is first reached in a class or module. The jar with the external library must be placed in the VDM project in a subfolder named lib where it will be put in the class-path of the interpreter when it is executed.

14.1.1 External Library Example

In this example, a remote sensor will be defined in VDM which can read a value from a real sensor. The VDM model interface of the sensor can be seen in listing 14.1 and the Java class implementing it can be seen in listing 14.2. The values that are to be exchanged between the Overture IDE and the jar file needs to be the internal *Value* objects used in Overture. Documentation about these classes can be found in Appendix I.

```
class remote_lib_sensor
operations
public getValue : int ==> int
getValue (id) == is not yet specified;
end remote_lib_sensor
```

Listing 14.1: Remote sensor VDM class

```
package remote.lib;
import org.overture.interpreter.runtime.ValueException;
import org.overture.interpreter.values.IntegerValue;
import org.overture.interpreter.values.Value;
public class sensor
{
    public Value getValue(Value id) throws ValueException
    {
        int result = ... // Read a value for sensor number "id"
        return new IntegerValue(result);
    }
}
```

Listing 14.2: Remote sensor Java class



14.2 Enabling Remote Control of the Overture Interpreter

In some situations, it may be valuable to establish a front end (for example a GUI or a test harness) for calling a VDM model. This feature corresponds roughly to the CORBA based API from VDMTools [APIMan].

A VDM model can be remotely controlled by implementing the Java interface RemoteControl. Remote control should be understood as a delegation of control of the interpreter, which means that the remote controller is in charge of the execution or debug session and is responsible for taking action and executing parts of the VDM model when needed. When finished, it should return and the session will stop. When a Remote controller is used, the Overture debugger continues working normally, so for example breakpoints can be used in debug mode. A debugging session with the use of a remote controller can be started by placing the jar with the RemoteControl implementation in a project subfolder called lib. The fully qualified name of the RemoteControl class must then be specified in the launch configuration in the *Remote Control* box.

14.2.1 Example of a Remote Control Class

In this example, we have a VDM class A which defines an operation that just returns its argument. As seen in listing 14.3, it is possible to call execute on the Overture interpreter via the RemoteInterpreter object which is passed to the RemoteControl implementation via the run method. The method returns a string with the result. A more advanced valueExecute method is also available which returns the internal Value type of the interpreter which is useful for more complex results. The values exchanged between the Overture IDE and the controller are the internal Values used in Overture. Documentation about these can be found in the Overture Design Specification [Battle10].

Listing 14.3: Remote Controller Java class



14.3 Using a GUI in a VDM model: Linking Example

This example describes how the linking functionality can be used to create a graphical representation of a VDM model.

14.3.1 The Modelled System

A GUI has been developed in Java Swing which will be used to both control and present the system which is described in the VDM model. In this example both the "External Java Library" technique as well as the "Remote Controller" technique is utilized. This is done to enable the VDM model to display data directly to the Java GUI, and to allow the VDM model to be controlled from the Java GUI.

The example is based on a VDM++ model of the smokers concurrency problem [Patil71]. Consider a scenario where three chain smokers and an agent, who does not smoke, are sitting at a table, infinitely going through the following lifecycle:

- 1. Each chain smoker continuously seeks to roll a cigarette and smoke it,
- 2. a smoker needs three ingredients: tobacco, paper and matches,
- 3. each smoker has an infinite supply of only one of the ingredients. One of the smokers has tobacco, the second has paper, and the third has matches,
- 4. the agent has an infinite supply of all three materials and randomly places two different ingredients on the table at a time,
- 5. the smoker who has the remaining ingredient then empties the table, rolls a cigarette and smokes it. The smokers never accumulate the ingredients and never grab an ingredient from the table which they are already in possession of,
- 6. when the table becomes empty, the agent puts another two random ingredients on the table, and the cycle repeats.

In this example a GUI has been created for the model in which the user of the GUI is considered to be the agent providing the smoker with ingredients, as illustrated in Figure 14.1. By clicking one of three buttons one of the respective ingredients will be placed on the table. Once the necessary ingredients are on the table, one smoker will grab them and start smoking.

The architecture of the example is illustrated on Figure 14.2, with a focus on the linking functionality. The diagram shows central classes and relations, and it places the different classes into a GUI, a Java and a VDM/Overture block. In the given context the *World* class represents the entire VDM model. In the diagram color highlights are used to distinguish the two linking techniques.





Figure 14.1: GUI of Smokers Example




Figure 14.2: Class diagram of the Smokers example architecture

14.3.2 External Java Library

To allow the GUI to be a true graphical representation of the model, the model itself will be able to update the GUI whenever it needs to by using the "External Java Library" technique. If only the remote controller was used, the model would be unable to update the GUI and it would rely on the



Java implementation to request data on any state changes in the model.

A VDM model interface has been created which allows the model to interact with the Java GUI, the interface is shown in Listing 14.4. The hierarchical naming pattern of Java packages, which normally are separated by periods (.), are denoted with underscores in the VDM model. Meaning that with this interface the External Java library must contain a *Graphics* class which is organized in the *gui* package.

```
class gui_Graphics
operations

public init : () ==> ()
    init() == is not yet specified;

    public tobaccoAdded : () ==> ()
    tobaccoAdded() == is not yet specified;

    public paperAdded : () ==> ()
    paperAdded() == is not yet specified;

    public matchAdded : () ==> ()
    matchAdded() == is not yet specified;

    public tableCleared : () ==> ()
    tableCleared() == is not yet specified;

    public nowSmoking : nat ==> ()
    nowSmoking(smokerNumber) == is not yet specified;
end gui_Graphics
```

Listing 14.4: VDM interface for external Java library

The Java class implementing the VDM interface is shown in Listing 14.5. This example will not go into detail with regards to actual GUI implementation, however it should be mentioned that the example utilizes the Model-View-Controller (MVC) design pattern and that the Java implementation of the VDM interface interacts with the graphical representation through the *model* object (this is the *model* in the MVC pattern and not a representation of the VDM model).

It should be noted that the names of the package and class can be directly related to VDM interface, i.e. *gui* and *Graphics*. Furthermore the imports should be noted; firstly the class must be marked as Serializable, secondly multiple packages from the Overture interpreter are imported as well. These are needed for the conversion between VDM values and Java values, as it can be seen in the *nowSmoking* method in Listing 14.5.

Please be aware that it is extremely important that there are no unused imports in the Java implementation, as this will result in an error when the Java library is loaded by Overture.

CHAPTER 14. EXPANDING VDM MODELS SCOPE AND FUNCTIONALITY BY LINKING JAVA AND VDM



```
package gui;
import java.io.Serializable;
import org.overture.interpreter.runtime.ValueException;
import org.overture.interpreter.values.Value;
import org.overture.interpreter.values.VoidValue;
public class Graphics implements Serializable {
   Controller ctrl;
   Model model;
   public Value init() {
        ctrl = new Controller(); //init the Controller of the MVC pattern
       model = ctrl.getModel();
        return new VoidValue();
    }
   public Value tobaccoAdded() {
        model.tobaccoAdded();
        return new VoidValue();
    }
 public Value nowSmoking(Value smokeid) throws ValueException {
       model.nowSmoking(smokeid.intValue(null)); //set smoker
        ctrl.DisableButtons();
                                                 //prevent new GUI input
                                                  //wait for smoker to finish
       model.finishedSmoking();
        ctrl.EnableButtons();
                                                  //enable GUI input
    }
```

Listing 14.5: Java implementation of the VDM interface for the external Java library

In order to use the VDM Types the Java implementation must have the Overture java library in its build path. The library can be found in Overture installation directory:

<Overturedir> Pluginsorg.overture.ide.generated.vdmj:_x.xlib, which can then be added to the Java build path, as shown in Figure 14.3.




Figure 14.3: Adding VDMJ library to the build path in Eclipse

14.3.3 Remote Control

Go

To enable the GUI to interact with the model the "Remote Control" technique is utilized, by implementing the *RemoteControl* interface, as shown in Listing 14.6. The *RemoteControl* interface also requires the Overture Java library to be included in the Java build path, as explained above. From listing 14.6 it can be seen that the *RemoteControl* interface supplies protected access to the VDM interpreter, that is passed to the *SmokingControl* object which functions as the bridge between the GUI and the running VDM model. The *SmokingControl* class is specific for this example, and its implementation could essentially be implemented directly in the *RemoteControl* realization.

It is important the *finish* method is called on the interpreter when the GUI is disposed, this will allow Overture to do a controlled shut-down of the remote interpretation, keeping the debugger alive for post execution communication such as coverage writing.

```
public class SmokerRemote implements RemoteControl {
    RemoteInterpreter interpreter;
    @Override
    public void run(RemoteInterpreter intrprtr) throws Exception {
        interpreter = intrprtr;
        SmokingControl ctrl = new SmokingControl(interpreter);
        ctrl.init();
    }
}
```

Listing 14.6: Java implementation of the RemoteControl interface



The implementation of the *SmokingControl* is shown in Listing 14.7. In the *init* method it can be seen how VDM statements are executed as strings commands, the *World* class is created and the *Run* operation is invoked. This is the basic way of interacting with a model through the remote control functionality. The finish method informs the interpreter that the remote GUI is being disposed and that execution should be stopped. The *AddPaper* method shows how the variables defined in the *init* method can be used for invoking an operation. The *AddPaper* method is called directly from the GUI Button click action, as shown in Listing 14.8.

```
public class SmokingControl {
 RemoteInterpreter interpreter;
 public SmokingControl(RemoteInterpreter intrprtr) {
    interpreter = intrprtr;
    Controller.smoke = this;
  }
 public void init() {
    interpreter.create("w", "new World()");
    interpreter.valueExecute("w.Run()");
  }
public void AddPaper() {
    interpreter.valueExecute("w.agent.AddPaper()");
   }
public void finish() {
   interpreter.finish();
}
```

Listing 14.7: Java implementation of the bridge between the GUI and the interpreter executing the VDM model

```
addPaperButton.addActionListener(new ActionListener() {
   public void actionPerformed(ActionEvent e) {
     smoke.AddPaper();
   }
});
```

Listing 14.8: Java implementation of the Button click action invoking the remote intepreter

The last thing to note in Listing 14.7 is the constructor which adds itself to a public static field in the *Controller* class. This step is necessary to brigde the objects created by the "Remote Control" technique with the objects created in connection with the "External Java Library" technique. To understand why this construct is needed, some insight into the initialization steps is necessary. Firstly the entire VDM model, and thereby the *Graphics* object, is created via the *RemoteControl* interface by *SmokingControl*. Now recall from Listing 14.5 that the *Controller* class, of the MVC pattern, is created when the *init* method of the *Graphics* class is invoked from the VDM model,



meaning that the actual graphical Java components, are also created when *init* is called. Now in order to connect a click on the GUI buttons with the commands that can be executed in the model, the *Controller* needs to have access to the interpreter, i.e. the *SmokingControl* object. Meanwhile the Graphics object is created deep inside the VDM model and the *SmokingControl* object cannot be passed to it through the interpreters execute method. Instead the bridge between the *Controller* object will eventually be created from inside the model, is used to justify the static reference. This is a special case when combining the "Remote Control" technique with the "External Java Library" method.

Example of how to shut-down a JFrame when using the remote controller interface

It is important that the execution of a remote GUI is stopped in a controlled manner e.g. not just by calling System.exit(0). One way to allow the finish method to be called from a JFrame is shown in listing 14.9; The in the constructor of the JFrame a the default close operation is changed to be DISPOSE_ON_CLOSE, this will change the closing of the window so that the dispose method is called where call to the interpreter finish can be placed.

```
public MyJFrame() {
    // Allow Overture to do a controlled shutdown
    setDefaultCloseOperation(WindowConstants.DISPOSE_ON_CLOSE);
    ...
}
    ...
@Override
public void dispose() {
    interpreter.finish();
}
```

Listing 14.9: Java implementation of a finish method for a JFrame.

14.3.4 Deployment of the Java Program to Overture

Once the Java program has been implemented, it must be exported to a Jar file and placed in the lib directory in the Overture/VDM projects directory, in order for Overture to find it. In Eclipse a Jar file can be created through the Export function, as illustrated on Figures 14.4 and 14.5.

Note that it can be very beneficial to check "Save the description of this JAR", illustrated on Figure 14.6, as this saves the export configuration and makes it a lot faster to redeploy the JAR file to VDM project during development.

Before running the model in Overture the debug configuration needs to be changed to use the Remote Control. "The Launch Mode" must be change to "Remote Control", and the fully qualified name of the class implementing the remote control interface must be supplied. The debug configuration for the current example is supplied in Figure 14.7.



Export	X
Select Export resources into a JAR file on the local file system.	2
Select an export destination:	
Archive File File System File System Java JAR file Javadoc Runnable JAR file Breakpoints Launch Configurations Tasks Team XML	E
(?) < Back Next > Finish Car	cel

Figure 14.4: Exporting in Eclipse






Figure 14.5: Exporting to a Jar in Eclipse





So

Figure 14.6: Saving the description of the export for future use

reate, manage, and run Debug	configurations		Ĩ,
Image: Second	Name: SmokingEx Main Runtime & Source Project Project: SmokingEx Launch Mode: © Entry Point @ Remote Cor		Browse
	Entry Point: Class: Function/Operation: Remote Control: Fully qualified remote control o	World(nat simtime) Run() Jass: gui.SmokerRemote	Search
	Other:		
ilter matched 5 of 5 items		4	Apply Revert

Figure 14.7: Changing the Overture debug configuration into using the remote controller

A Command-Line Interface to Overture

At the centre of the Overture tool there is a Java implementation of VDM forming a core. This provides a command-line interface that may be valuable as it can be used independently of the Eclipse interface of Overture.

15.1 Starting Overture at the Command-Line

The Overture-2.0.0.jar file contains a MANIFEST that identifies the main class to start the tool, so the minimum command line invocation is as follows:

```
$ java -jar Overture-2.0.0.jar
Overture: You must specify either -vdmsl, -vdmpp or -vdmrt
Usage: Overture <-vdmsl | -vdmpp | -vdmrt> [<options>] [<files>]
```

The first parameter indicates the VDM dialect to use and then various extra options can be used. These are:

- **-r**: This indicates the VDM release number (classic or vdm10).
- -w: This will suppress all warning messages.
- -q: This will suppress all information messages, such as the number of source files processed etc.
- -i: This will start the command line interpreter if the VDM model is successfully parsed and type checked, otherwise the errors discovered will be listed.
- -p: This will generate all proof obligations for the VDM model (if it is syntax and type correct) and then stop.
- -e <exp>: This will evaluate the <exp>, print the result, and stop.
- -c <charset>: This will select a file character set, to allow a specification written in languages other than the default for your system.



- -t <charset>: This will select a console character set. The output terminal can use a different character set to the specification files.
- -o <filename>: This will save the internal representation of a parsed and type checked specification. Such files are effectively libraries, and can be can be re-loaded without the parsing/checking overhead. If files are sufficiently large, this may be faster.

-pre: This will disable all pre-condition checks.

-post: This will disable all post-condition checks.

-inv: This will disable type/state invariant checks.

-dtc: This will disable all dynamic type checking.

-measures: This will disable recursive measure checking.

-log: This will enable VDM-RT real-time event logging (see Chapter 13).

-remote: This enables remote control of the Overture executable.

Alternatively a script file is also made for the different platforms (script and bat files) wrapping this so one does not need to set up paths and call java directly.

Normally, a VDM model will be loaded by identifying all of the VDM source files to include. At least one source file must be specified unless the -i option is used, in which case the interpreter can be started with no specification. If a directory is specified rather than a file, then Overture will load all files in that directory with a suffix that matches the dialect (e.g. *.vdmpp files for VDM++). Multiple files and directory arguments can be mixed.

If no -i option is given, the tool will only parse and type check the VDM model files, giving any errors and warnings on standard output, then stop.

The -p option will run the proof obligation generator and then stop, assuming the specification has no type checking errors.

For batch execution, the -e option can be used to identify a single expression to evaluate in the context of the loaded specification, assuming the specification has no type checking errors.

15.2 Parsing, Type Checking, and Proof Obligations Command-Line

All specification files loaded are parsed and type checked automatically by the command-line tool. There are no type checking options; the type checker always uses possible semantics. If a specification does not parse and type check cleanly, the interpreter cannot be started and proof obligations cannot be generated (though warnings are allowed). All warnings and error messages are printed on standard output, even with the -q option.



A source file may contain VDM definitions embedded in a $L^{A}T_{E}X$ file using vdm_al environments (see Chapter 8); the markup is ignored by the parser, though reported line numbers will be correct. Note that each source file must start with a recognizable $L^{A}T_{E}X$ construct: a \documentclass, \section, \subsection or a $L^{A}T_{E}X$ comment.

The Overture Java process will return with an exit code of zero if the specification is clean (ignoring warnings). Parser or type checking errors result in an exit code of 1. The interpreter and PO generator always exit with a code of zero.

15.3 The Command-Line Interpreter and Debugger

Assuming a specification does not contain any parse or type checking errors, the interpreter can be started by using the -i command line option. The interpreter is an interactive command line tool that allows expressions to be evaluated in the context of the specification loaded. For example, to load and interpret a VDM-SL specification from a single file called shmem.vdmsl, the following options would be used:

```
$ java -jar Overture-2.0.0.jar -vdmsl -i shmem.vdmsl
Parsed 1 module in 0.14 secs. No syntax errors
Warning 5000: Definition 'i' not used in 'M' (shmem.vdmsl)
   at line 129:7
Type checked in 0.078 secs. No type errors
Initialized 1 module in 0.046 secs.
Interpreter started
```

The interpreter prompt is ">". The interactive interpreter commands are as follows (abbreviated forms are permitted for some, shown in square brackets):

- **modules:** This command lists the loaded module names in a VDM-SL specification. For a flat VDM-SL model, the single name DEFAULT is used. The default module will be indicated in the list displayed.
- **classes:** This command lists the loaded class names in VDM++ and VDM-RT specifications. The default class will be indicated in the list displayed.
- **default** <module/class>: This command sets the default module/class name as the prime scope for which the lookup of identifiers appear (i.e. names in the default module do not need to be qualified, so you can say "print xyz" rather than "print M'xyz").
- **create <id>** := **<exp>:** This command is only available for the VDM++ and VDM-RT dialects. It creates a global variable that can be used subsequently in the interpreter. It is mostly used for creating global instances of classes.
- log [<file> | off]: This command can only be used with VDM-RT models. It starts to log real-time events to the file indicated. By default, event logging is turned off. Logging can be directed to the console by using log with no arguments, or to a file using log



<filename>. Logging can subsequently be turned off again by using log off. The events logged include requests, activations and completions of all functions and operations, as well as all object creations, creation of CPUs and BUSses, deployment of objects to specific CPUs and the swapping in/out of threads.

- **state:** This command can only be used for the VDM-SL dialect and shows the default module state. The value of the state can be changed by operations called.
- [p]rint <expression>: This command evaluates the expression provided in the current context.
- runtrace <name> [test number]: This command runs the trace called <name>. This
 will expand the combinatorial test and execute the resulting operation sequences. If a specific
 test number is provided, only that one test from the expansion will be executed.
- **debugtrace** <name> [test number]: This command is the same as runtrace, except that if a runtime exception is encountered during the execution of a test, control will enter the debugger. With runtrace, runtime exceptions are recorded as the result of a (failed) test, rather than trapping into the debugger.
- filter %age | <reduction type>: This command reduces the size of expanded CT traces to a given percentage (eg. 10%). There are various options for making the actual selection of tests to remove: "RANDOM", "SHAPES_NOVARS", "SHAPES_VARNAMES" or "SHAPES_VARVALUES" (the names are not case sensitive).
- **assert <file>:** This command runs assertions from the file provided. The assertions in the file must be Boolean expressions, one per line. The command evaluates every assertion in the file, raising an error for any which is false.
- **init:** This command re-initializes the global environment. Thus all state components will be initialised to their initial value again, created variables are lost and code coverage information is reset.
- **env:** This command lists the value of all global symbols in the default environment. This will show the signatures for all functions and operations as well as the values assigned to identifiers from value definitions and global state definitions (in VDM++ terminology, public static instance variables). Note that this includes invariant, initialization and pre/postcondition functions. In the VDM++ and VDM-RT dialects, the identifiers created using the create command will also be included.
- **pog** [**<fn/op>]:** This command generates a list of all proof obligations for the VDM model that is loaded. There is an optional argument to indicate one function or operation name.
- **break** [**<file>**:]**<line#>** [**<condition>**]**:** This command creates a breakpoint at a specific file and line and optionally makes it a conditional breakpoint.



- break <function/operation> [<condition>]: This command creates a breakpoint
 at the start of the body of a named function or operation and optionally makes it a conditional
 breakpoint.
- trace [<file>:]<line#> [<exp>]: This command creates a tracepoint for a specific file and line. A tracepoint prints the value of the expression given whenever the tracepoint is reached, and then continues.
- trace <function/operation> [<exp>]: This command create a tracepoint at the start of a function or operation body. See trace above for an explanation of tracepoints.
- remove <breakpoint#>: This command removes a trace/breakpoint by referring to its number (given by the list command).
- **list:** This command provides a list of all current trace/breakpoints by number.
- coverage [clear|write <dir>|merge <dir>|<filenames>]: This command manages test coverage information. The coverage command displays the source code of the loaded VDM model (by default, all source files are listed), with "+" and "-" signs in the left hand column indicating lines which have been executed or not. The percentage coverage of each source file is displayed. Typically, the testing of a specification will be incremental, and so it is convenient to be able to "save" the coverage achieved in each test session, and subsequently merge the results together. This can be achieved with the write <dir> and merge <dir> options to the coverage command. The write option saves the current coverage information in <dir> for each specification file loaded; the merge option reads this information back, and merges it with the current coverage information. For example, each day's test coverage could be written to a separate "day" directory, and then all the days merged together for review of the overall coverage at the end.
- latex|latexdoc [<files>]: This command generates LATEX coverage files. These are LATEX versions of the source files with parts of the specification highlighted where they have not been executed. The LATEX output also contains a table of percentage cover by module/class and the number of times functions and operations were hit during the execution. The latexdoc command is the same, except that output files are wrapped in LATEX document headers. The output files are written to the same directory as the source files, one per source file, with the extension .tex. Coverage information is reset when a specification is loaded, when an init command is given, or when the command coverage clear is executed, otherwise coverage is cumulative. If several files are loaded, the coverage for just one source file can be listed with coverage <file> or latex <file>.
- files: This command lists the names of all source files loaded.
- **reload:** This command will reload, parse and type check the VDM model files currently loaded. Note that if there are any errors in the parse or type check of the files, the interpreter will exit after the reload.



load <files>: This command replaces the current loaded VDM model files. Note that if there are any errors in the parse or type check of the files, the interpreter will exit after the load.

[q] uit: This command leaves the interpreter.

> modules
M (default)

> print rand(100)
= 71
Executed in 0.063 secs.

```
> print rand(100)
= 44
Executed in 0.0 secs.
```

> init
Global context initialized

> env

```
fragments = (M'Quadrant -> nat)
```

```
combine = (M'Quadrant -> M'Quadrant)
tryBest = (nat ==> nat)
seed = (nat1 ==> ())
reset = (() ==> ())
bestfit = (nat1 * M'Quadrant -> nat1)
add = (nat1 * nat1 * M'Quadrant -> M'Quadrant)
firstFit = (nat1 ==> bool)
rand = (nat1 ==> nat1)
tryFirst = (nat ==> nat)
main = (nat1 * nat1 ==> seq of (<SAME> | <BEST> | <FIRST>))
MAXMEM = 10000
delete = (M'M * M'Quadrant -> M'Quadrant)
inv_M = (M M +> bool)
CHUNK = 100
bestFit = (nat1 ==> bool)
least = (nat1 * nat1 -> nat1)
fits = (nat1 * M'Quadrant -> nat1)
init_Memory = (M 'Memory +> bool)
pre_add = (nat1 * nat1 * M'Quadrant +> bool)
```

This example shows a VDM-SL specification called shmem.vdmsl being loaded. The help command lists the interpreter commands available. Note that several of them regard the setting of breakpoints, which is covered in the next section.

The **state** command lists the content of the default module's state. This can be changed by operations, as can be seen by the two calls to rand which change the rseed value in the state (a pseudo-random number generator). The init command will re-initialize the state to its original value, illustrated by the fact that two subsequent calls to rand return the same results as the first two did.

The print command can be used to evaluate any expression. The env command lists all the values in the global environment of the default module. This shows the functions, operations and constant values defined in the module. Note that it includes invariant, initialization and pre/postcondition functions. The pog command (proof obligation generator) generates a list of proof obligations for the specification.

When the execution of a VDM model is stopped at a breakpoint, there are additional commands that can be used. These are:

[s]tep: This command steps forward until the current expression/statement is on a new line. The command will step into function and operation calls.

[n]ext: This command is similar to step except function and operation calls are stepped over.

[o]ut: This command runs to the return of the current function or operation.



- [c]ontinue: This command resumes execution and continues until the next breakpoint or completion of the thread that is being debugged.
- **stack:** This command displays the current stack frame context (i.e. the call stack).
- up: This command moves the stack frame context up one frame to allow variables to be seen.
- **down:** This command moves the stack frame context down one frame.
- source: This command lists VDM source around the current breakpoint.
- **stop:** This command terminates the execution immediately.
- **threads:** This command can only be used for the VDM++ and VDM-RT dialects. It lists the active threads with status information for each thread.

References

[APIMan]	The VDM Tool Group. <i>VDM Toolbox API</i> . Technical Report, CSK Systems, January 2008.
[Battle10]	Nick Battle. VDMJ Design Specification. Available from the Overture SourceForge repository, September 2010. 59 pages.
[Bjørner&78a]	D. Bjørner and C.B. Jones, editors. <i>The Vienna Development Method: The Meta-Language</i> . Volume 61 of <i>Lecture Notes in Computer Science</i> , Springer-Verlag, 1978.
	This was the first monograph on <i>Meta-IV</i> . See also entries: [Bjørner78b], [Bjørner78c], [Lucas78], [Jones78a], [Jones78b], [Henhapl&78]
[Bjørner78b]	D. Bjørner. Programming in the Meta-Language: A Tutorial. <i>The Vienna Development Method: The Meta-Language</i> , 24–217, 1978.
	An informal introduction to Meta-IV
[Bjørner78c]	D. Bjørner. Software Abstraction Principles: Tutorial Examples of an Operating System Command Language Specification and a PL/I-like On-Condition Language Definition. <i>The Vienna Development Method: The Meta-Language</i> , 337–374, 1978.
	Exemplifies so called exit semantics uses of <i>Meta-IV</i> to slightly non-trivial examples.
[Clement&99]	Tim Clement and Ian Cottam and Peter Froome and Claire Jones. The Development of a Commercial "Shrink-Wrapped Application" to Safety Integrity Level 2: the DUST-EXPERT Story. In <i>Safe- comp'99</i> , Springer Verlag, Toulouse, France, September 1999. LNCS 1698, ISBN 3-540-66488-2.
[DLMan]	The VDM Tool Group. <i>The Dynamic Link Facility</i> . Technical Report, CSK Systems, January 2008.



[Elmstrøm&94]	René Elmstrøm and Peter Gorm Larsen and Poul Bøgh Lassen. The IFAD VDM-SL Toolbox: A Practical Approach to Formal Specifications. <i>ACM Sigplan Notices</i> , 29(9):77–80, September 1994. 4 pages.
[Fitzgerald&05]	John Fitzgerald and Peter Gorm Larsen and Paul Mukherjee and Nico Plat and Marcel Verhoef. <i>Validated Designs for Object–oriented Systems</i> . Springer, New York, 2005.
[Fitzgerald&07]	John Fitzgerald and Peter Gorm Larsen and Simon Tjell and Mar- cel Verhoef. <i>Validation Support for Distributed Real-Time Embed-</i> <i>ded Systems in VDM</i> ++. Technical Report CS-TR:1017, School of Computing Science, Newcastle University, April 2007. 18 pages.
[Fitzgerald&08a]	J. S. Fitzgerald and P. G. Larsen and M. Verhoef. Vienna Develop- ment Method. <i>Wiley Encyclopedia of Computer Science and Engi-</i> <i>neering</i> , 2008. 11 pages. edited by Benjamin Wah, John Wiley & Sons, Inc.
[Fitzgerald&08b]	John Fitzgerald and Peter Gorm Larsen and Shin Sahara. VDM- Tools: Advances in Support for Formal Modeling in VDM. <i>ACM</i> <i>Sigplan Notices</i> , 43(2):3–11, February 2008. 8 pages.
[Fitzgerald&09]	John Fitzgerald and Peter Gorm Larsen. <i>Modelling Systems – Prac- tical Tools and Techniques in Software Development</i> . Cambridge University Press, The Edinburgh Building, Cambridge CB2 2RU, UK, Second edition, 2009. ISBN 0-521-62348-0.
[Fitzgerald&98]	John Fitzgerald and Peter Gorm Larsen. <i>Modelling Systems – Prac- tical Tools and Techniques in Software Development</i> . Cambridge University Press, The Edinburgh Building, Cambridge CB2 2RU, UK, 1998. ISBN 0-521-62348-0.
[Henhapl&78]	W. Henhapl, C.B. Jones. A Formal Definition of ALGOL 60 as described in the 1975 modified Report. In <i>The Vienna Development Method: The Meta-Language</i> , pages 305–336, Springer-Verlag, 1978.
	One of several examples of ALGOL 60 descriptions.



[ISOVDM96]	Information technology – Programming languages, their environ- ments and system software interfaces – Vienna Development Method – Specification Language – Part 1: Base language. December 1996.
[Johnson96]	C.W. Johnson. Literate Specifications. <i>Software Engineering Jour-</i> nal, 225–237, July 1996.
[Jones78a]	C.B. Jones. The Meta-Language: A Reference Manual. In <i>The Vienna Development Method: The Meta-Language</i> , pages 218–277, Springer-Verlag, 1978.
[Jones78b]	C.B. Jones. The Vienna Development Method: Examples of Com- piler Development. In Amirchachy and Neel, editors, <i>Le Point sur</i> <i>la Compilation</i> , INRIA Publ. Paris, 1979.
[Jones90]	Cliff B. Jones. <i>Systematic Software Development Using VDM</i> . Prentice-Hall International, Englewood Cliffs, New Jersey, second edition, 1990. 333 pages. ISBN 0-13-880733-7.
	This book deals with the Vienna Development Method. The approach explains formal (functional) specifications and verified design with an emphasis on the study of proofs in the development process.
[Kurita&09]	T. Kurita and Y. Nakatsugawa. The Application of VDM++ to the Development of Firmware for a Smart Card IC Chip. <i>Intl. Journal of Software and Informatics</i> , 3(2-3), October 2009.
[Larsen01]	Peter Gorm Larsen. Ten Years of Historical Development: "Boot- strapping" VDMTools. <i>Journal of Universal Computer Science</i> , 7(8):692–709, 2001.
	http://www.jucs.org/jucs_7_8/ten_years_of_historical—
[Larsen&09]	Peter Gorm Larsen and John Fitzgerald and Sune Wolff. Meth- ods for the Development of Distributed Real-Time Systems using VDM. <i>Intl. Journal of Software and Informatics</i> , 3(2-3), October 2009.



[Larsen&10]	Peter Gorm Larsen and Kenneth Lausdahl and Nick Battle and John Fitzgerald and Sune Wolff and Shin Sahara. <i>VDM-10 Language Manual</i> . Technical Report TR-001, The Overture Initiative, www.overturetool.org, April 2013. 208 pages.
[Larsen&96]	Peter Gorm Larsen and Bo Stig Hansen. Semantics for Underde- termined Expressions. <i>Formal Aspects of Computing</i> , 8(1):47–66, January 1996.
[Lucas78]	P. Lucas. On the Formalization of Programming Languages: Early History and Main Approaches. In <i>The Systematic Development of Compiling Algorithm</i> , INRIA Publ. Paris, 1978.
	An historic overview of the (VDL and other) background for VDM.
[Mukherjee&00]	Paul Mukherjee and Fabien Bousquet and Jérôme Delabre and Stephen Paynter and Peter Gorm Larsen. Exploring Timing Properties Us- ing VDM++ on an Industrial Application. In J.C. Bicarregui and J.S. Fitzgerald, editors, <i>Proceedings of the Second VDM Workshop</i> , September 2000. Available at www.vdmportal.org.
[Patil71]	S. S. Patil. <i>Limitations and Capabilities of Dijkstra's Semaphore</i> <i>Primitives for Coordination among Processes</i> . Cambridge, Mass.: MIT, Project MAC, Computation Structures Group Memo 57, Febru- ary 1971.
[Ribeiro&11]	Augusto Ribeiro and Kenneth Lausdahl and Peter Gorm Larsen. Run-Time Validation of Timing Constraints for VDM-RT Models. In 9th Overture Workshop, June 2011, Limerick, Ireland, 2011.
[UMLSuperstructure2.1.2]	OMG. <i>OMG Unified Modeling Language (OMG UML) Superstruc-</i> <i>ture, V2.1.2.</i> Technical Report, http://www.omg.org/spec/UML/- 2.1.2/Infrastructure/PDF/, 2007. OMG Available Specification with- out Change Bars, formal/2007-11-02.
[Verhoef&06]	Marcel Verhoef and Peter Gorm Larsen and Jozef Hooman. Modeling and Validating Distributed Embedded Real-Time Systems with VDM++. In Jayadev Misra and Tobias Nipkow and Emil Sekerinski, editors, <i>FM 2006: Formal Methods</i> , pages 147–162, Springer-Verlag, 2006.

Appendix A

Templates in Overture

Overture defines a number of standard Eclipse templates. You can add your own as well. The keys and descriptions of the pre-defined templates are:

Кеу	Description
caseExpression	Case Expression
dclStatement	Declare
defExpression	def pattern = expression1 in expression2
exists	exists bindList & predicate
forall	forall bind list & predicate
forallLoop	for identifier = expression1 to expression2 do state-
	ment
forallinset	forall in set
functions	Function block
ifthen	if predicate then expression1 else expression2
let	let pattern = expression1 in expression2
operations	Operation block
while	while predicate do statement
functionExplicit	Explicit function
functionImplicit	Implicit function
module	Module
moduleSkeleton	Module Full skeleton of a module
operationExplicit	Explicit Operation
operationImplicit	Implicit operation
act	The number of times that operation name operation
	has been activated
active	The number of operation name operations that are
	currently active.
class	Class Definition
classSkeleton	Class Definition full skeleton

Key	Description
fin	The number of times that the operation name opera-
	tion has been completed
functionExplicit	Explicit function
functionImplicit	Implicit function
instancevariables	Instance Variables block
isnotyetspecified	is not yet specified
isofbaseclass	Test if an object is of a specific base class
isofclass	Test if an object is of class
issubclassof	Is subclass of
issubclassresponsibility	Is subclass responsibility
mutex	Mutex operation
operationExplicit	Explicit Operation
operationImplicit	Implicit operation
per	Permission predicate for an operation, history coun-
•	ters can be used: #fin, #act, #active, #req, #waiting
req	The number of requests that has been issued for the
1	operation name operation
samebaseclass	Test if two objects are of the same type
self	Get a reference to the current object
sync	Synchronization block
values	Values block
waiting	The number of outstanding requests for the operation
	name operation
act	The number of times that operation name operation
	has been activated
active	The number of operation name operations that are
	currently active.
bus	BUS (Priority <csmacd>, capacity,set of con-</csmacd>
	nected CPUs)
class	Class Definition
classSkeleton	Class Definition full skeleton
cpu	CPU (Priority <fp fcfs="">, capacity)</fp>
cycle	Cycles (number of cycles) statement
duration	Duration (time in nanoseconds) statement
fin	The number of times that the operation name opera-
1111	tion has been completed
functionExplicit	Explicit function
functionImplicit	Implicit function
instancevariables	Instance Variables block
isnotyetspecified isofbaseclass	is not yet specified Test if an object is of a specific base class
1501045561455	Test if an object is of a specific base class

G

APPENDIX A. TEMPLATES IN OVERTURE



Key	Description
isofclass	Test if an object is of class
issubclassof	Is subclass of
issubclassresponsibility	Is subclass responsibility
mutex	Mutex operation
operationExplicit	Explicit Operation
operationImplicit	Implicit operation
per	Permission predicate for an operation, history coun-
	ters can be used: #fin, #act, #active, #req, #waiting
periodic	periodic(periode, jitter, delay, offset)(operation name)
req	The number of requests that has been issued for the
	operation name operation
samebaseclass	Test if two objects are of the same type
self	Get a reference to the current object
sync	Synchronization block
system	System skeleton
time	Get the current time
values	Values block
waiting	The number of outstanding requests for the operation
	name operation



Appendix B

Internal Errors

This appendix gives a list of the internal errors in Overture and the circumstances under which each internal error can be expected. Most of these errors should *never* be seen, so if they appear please report the occurrence via the Overture bug reporting utility (https://sourceforge.net/tracker/?group_id=141350&atid=749152).

- **0000:** File IO errors, eg. "File not found" This typically occurs if a specification file is no longer present.
- 0001: "Mark/reset not supported use push/pop"
- 0002: "Cannot change type qualifier: <name><qualifiers> to <qualifiers>"
- 0003: "PatternBind passed <class name>"
- 0004: "Cannot get bind values for type <type>"
- 0005: "Illegal clone"
- 0006: "Constructor for <class> can't find <member>"
- 0007: "Cannot write to IO file <name>"
- **0009:** "Too many syntax errors" This error typically occurs if one have included a file that is in a non VDM format and by mistake have given it a vdm file extension (vdmsl, vdmpp or vdmrt).
- **0010:** "Too many type checking errors"
- 0011: "CPU or BUS creation failure"
- 0052: "Cannot set default name at breakpoint"
- 0053: "Unknown trace reduction type"



0054: "Cannot instant	iate native object: <reason>"</reason>
0055: "Cannot access	native object: <reason>"</reason>
0056: "Native method	cannot use pattern arguments: <sig>"</sig>
0057: "Native member	not found: <name>"</name>
0058: "Native method	does not return Value: "
0059: "Failed in nati	ve method: <reason>"</reason>
0060: "Cannot access	native method: <reason>"</reason>
0061: "Cannot find na	ative method: <reason>"</reason>
0062: "Cannot invoke	native method: <reason>"</reason>
0063: "No delegate cl	ass found: <name>"</name>
0064: "Native method	should be static: <name>"</name>
0065: "Illegal Lock s	state"
0066: "Thread is not	running on a CPU"
0067: "Exported type	<name> not structured"</name>
0068: "Periodic threa	ds overlapping"

Appendix C

Lexical Errors

When a VDM model is parsed, the first phase is to gather the single characters into tokens that can be used in the further processing. This is called a lexical analysis and errors in this area can be as follows:

1000: "Malformed quoted character"
1001: "Invalid char <ch> in base <n> number"
1002: "Expecting '|->'"
1003: "Expecting '...'"
1004: "Expecting '<-:'"
1005: "Expecting close double quote"
1006: "Expecting close quote after character"
1007: "Unexpected tag after '#'"
1008: "Malformed module'name"
1009: "Unexpected character 'c'"
1010: "Expecting <digits>[.<digits>][e<+-><digits>]"
1011: "Unterminated block comment"



Appendix D

Syntax Errors

If the syntax of the file you have provided does not meet the syntax rules for the VDM dialect you wish to use, syntax errors will be reported. These can be as follows:

2000: "Expecting 'in set' after pattern in set binding" 2001: "Expecting 'in set' in set bind" 2002: "Expecting ':' in type bind" 2003: "Expecting 'in set' after pattern in binding" 2004: "Expecting 'in set' or ':' after patterns" 2005: "Expecting list of 'class' or 'system' definitions" 2006: "Found tokens after class definitions" 2007: "Expecting 'end <class>'" 2008: "Class does not start with 'class'" 2009: "Can't have instance variables in VDM-SL" 2010: "Can't have a thread clause in VDM-SL" 2011: "Only one thread clause permitted per class" 2012: "Can't have a sync clause in VDM-SL" 2013: "Expected 'operations', 'state', 'functions', 'types' or 'values'" **2014:** "Recursive type declaration" This is reported in type definitions such as T = Τ. 2015: "Expecting =<type> or ::<field list>"



2016: "Function name cannot start with 'mk_'"
2017: "Expecting ':' or '(' after name in function definition"
2018: "Function type is not a -> or +> function"
2019: "Expecting identifier <name> after type in definition"</name>
2020: "Expecting '(' after function name"
2021: "Expecting ':' or '(' after name in operation definition"
2022: "Expecting name <name> after type in definition"</name>
2023: "Expecting '(' after operation name"
2024: "Expecting external declarations after 'ext'"
2025: "Expecting <name>: exp->exp in errs clause"</name>
2026: "Expecting 'rd' or 'wr' after 'ext'"
2027: "-"
2028: "Expecting 'per' or 'mutex'"
2029: "Expecting <set bind=""> = <expression>"</expression></set>
2030: "Expecting simple field identifier"
2031: "Expecting field number after .#"
2032: "Expecting field name"
2033: "Expected 'is not specified' or 'is subclass responsibility'"
2034: "Unexpected token in expression"
2035: "Tuple must have >1 argument"
2036: "Expecting mk_ <type>"</type>
2037: "Malformed mk_ <type> name <name>"</name></type>
2038: "Expecting is_ <type>"</type>
2039: "Expecting maplet in map enumeration"
2040: "Expecting 'else' in 'if' expression"




- 2041: "Expecting two arguments for 'isofbase'" **2042:** "Expecting (<class>,<exp>) arguments for 'isofbase'" 2043: "Expecting two arguments for 'isofclass'" **2044:** "Expecting (<class>,<exp>) arguments for 'isofclass'" 2045: "Expecting two expressions in 'samebaseclass'" 2046: "Expecting two expressions in 'sameclass'" 2047: "Can't use history expression here" **2048:** "Expecting #act, #active, #fin, #req or #waiting" 2049: "Expecting 'end <module>'" 2050: "Expecting library name after 'uselib'" 2051: "Expecting 'end <module>'" 2052: "Expecting 'all', 'types', 'values', 'functions' or 'operations'" 2053: "Exported function is not a function type" 2054: "Expecting types, values, functions or operations" **2055:** "Imported function is not a function type" 2056: "Cannot use module'id name in patterns" 2057: "Unexpected token in pattern" 2058: "Expecting identifier" 2059: "Expecting a name" **2060:** "Found qualified name <name>. Expecting an identifier" **2061:** "Expecting a name" **2062:** "Expected 'is not specified' or 'is subclass responsibility'" 2063: "Unexpected token in statement" 2064: "Expecting <object>.identifier(args) or name(args)"
- **2065:** "Expecting <object>.name(args) or name(args)"




2066: "Expecting object field name"
2067: "Expecting 'self', 'new' or name in object designator"
2068: "Expecting field identifier"
2069: "Expecting <identifier>:<type> := <expression>"</expression></type></identifier>
2070: "Function type cannot return void type"
2071: "Expecting field identifier before ':'"
2072: "Expecting field name before ':-'"
2073: "Duplicate field names in record type"
2074: "Unexpected token in type expression"
2075: "Expecting 'is subclass of'"
2076: "Expecting 'is subclass of'"
2077: "Expecting 'end' after class members"
2078: "Missing ';' after type definition"
2079: "Missing ';' after function definition"
2080: "Missing ';' after state definition"
2081: "Missing ';' after value definition"
2082: "Missing ';' after operation definition"
2083: "Expecting 'instance variables'"
2084: "Missing ';' after instance variable definition"
2085: "Missing ';' after thread definition"
2086: "Missing ';' after sync definition"
2087: "Expecting '==' after pattern in invariant"
2088: "Expecting '@' before type parameter"
2089: "Expecting '@' before type parameter"
2090: "Expecting ']' after type parameters"



2091: "Expecting ')' after function parameters" **2092:** "Expecting '==' after parameters" **2093:** "Missing colon after pattern/type parameter" **2094:** "Missing colon in identifier/type return value" 2095: "Implicit function must have post condition" **2096:** "Expecting <pattern>[:<type>]=<exp>" 2097: "Expecting 'of' after state name" **2098:** "Expecting '==' after pattern in invariant" **2099:** "Expecting '==' after pattern in initializer" 2100: "Expecting 'end' after state definition" **2101:** "Expecting ')' after operation parameters" 2102: "Expecting '==' after parameters" 2103: "Missing colon after pattern/type parameter" 2104: "Missing colon in identifier/type return value" **2105:** "Implicit operation must define a post condition" 2106: "Expecting ':' after name in errs clause" 2107: "Expecting '->' in errs clause" 2108: "Expecting <pattern>=<exp>" 2109: "Expecting <type bind>=<exp>" 2110: "Expecting <pattern> in set <set exp>" 2111: "Expecting <pattern> in set <set exp>" 2112: "Expecting '(' after periodic" 2113: "Expecting ')' after period arguments" **2114:** "Expecting '(' after periodic(...)" 2115: "Expecting (name) after periodic(...)"





So



2141: "Expecting '}' after map enumeration" 2142: "Expecting ']' after list comprehension" 2143: "Expecting ']' after list enumeration" 2144: "Missing 'then'" 2145: "Missing 'then' after 'elseif'" 2146: "Expecting ':' after cases expression" 2147: "Expecting '->' after others" 2148: "Expecting 'end' after cases" **2149:** "Expecting '->' after case pattern list" 2150: "Expecting 'in' after local definitions" 2151: "Expecting 'st' after 'be' in let expression" **2152:** "Expecting 'in' after bind in let expression" 2153: "Expecting '&' after bind list in forall" 2154: "Expecting '&' after bind list in exists" 2155: "Expecting '&' after single bind in exists1" 2156: "Expecting '&' after single bind in iota" 2157: "Expecting '&' after bind list in lambda" 2158: "Expecting 'in' after equals definitions" 2159: "Expecting '(' after new class name" 2160: "Expecting '(' after 'isofbase'" 2161: "Expecting ')' after 'isofbase' args" 2162: "Expecting '(' after 'isofclass'" 2163: "Expecting ')' after 'isofclass' args" 2164: "Expecting '(' after 'samebaseclass'" 2165: "Expecting ')' after 'samebaseclass' args"



2166: "Expecting '(' after 'sameclass'" 2167: "Expecting ')' after 'sameclass' args" 2168: "Expecting <#op>(name(s))" **2169:** "Expecting <#op>(name(s))" 2170: "Expecting 'module' at module start" 2171: "Expecting 'end' after module definitions" 2172: "Expecting 'dlmodule' at module start" 2173: "Expecting 'end' after dlmodule definitions" 2174: "Malformed imports? Expecting 'exports' section" 2175: "Expecting ':' after export name" 2176: "Expecting ':' after export name" 2177: "Expecting ':' after export name" 2178: "Expecting 'imports'" 2179: "Expecting 'from' in import definition" 2180: "Mismatched brackets in pattern" 2181: "Mismatched braces in pattern" 2182: "Mismatched square brackets in pattern" 2183: "Expecting '(' after mk_ tuple" 2184: "Expecting ')' after mk_ tuple" 2185: "Expecting '(' after <type> record" 2186: "Expecting ')' after <type> record" 2187: "Expecting 'is not yet specified" 2188: "Expecting 'is not yet specified" 2189: "Expecting 'is subclass responsibility'" 2190: "Expecting 'exit'"



2191:	"Expecting	'tixe'"
2192:	"Expecting	'{' after 'tixe'"
2193:	"Expecting	' ->' after pattern bind"
2194:	"Expecting	'in' after tixe traps"
2195:	"Expecting	'trap'"
2196:	"Expecting	'with' in trap statement"
2197:	"Expecting	'in' in trap statement"
2198:	"Expecting	'always'"
2199:	"Expecting	'in' after 'always' statement"
2200:	"Expecting	/ / "
2201:	"Expecting	'(' after ' '"
2202:	"Expecting	')' at end of ' ' block"
2203:	"Expecting	'atomic'"
2204:	"Expecting	'(' after 'atomic'"
2205:	"Expecting	')' after atomic assignments"
2206:	"Expecting	'(' after call operation name"
2207:	"Expecting	'(' after new class name"
2208:	"Expecting	'while'"
2209:	"Expecting	'do' after while expression"
2210:	"Expecting	'for'"
2211:	"Expecting	'in set' after 'for all'"
2212:	"Expecting	'in set' after 'for all'"
2213:	"Expecting	'do' after for all expression"
2214:	"Expecting	'in' after pattern bind"
2215:	"Expecting	'do' before loop statement"



2216: "Expecting '=' after for variable"
2217: "Expecting 'to' after from expression"
2218: "Expecting 'do' before loop statement"
2219: "Missing 'then'"
2220: "Missing 'then' after 'elseif' expression"
2221: "Expecting ':=' in object assignment statement"
2222: "Expecting ':=' in state assignment statement"
2223: "Expecting ')' after map/seq reference"
2224: "Expecting statement block"
2225: "Expecting ';' after statement"
2226: "Expecting ')' at end of statement block"
2227: "Expecting ';' after declarations"
2228: "Expecting name:type in declaration"
2229: "Expecting 'return'"
2230: "Expecting 'let'"
2231: "Expecting 'in' after local definitions"
2232: "Expecting 'st' after 'be' in let statement"
2233: "Expecting 'in' after bind in let statement"
2234: "Expecting 'cases'"
2235: "Expecting ':' after cases expression"
2236: "Expecting '->' after case pattern list"
2237: "Expecting '->' after others"
2238: "Expecting 'end' after cases"
2239: "Expecting 'def'"
2240: "Expecting 'in' after equals definitions"



2241: "Expecting '['" 2242: "Expecting ']' after specification statement" 2243: "Expecting 'start'" 2244: "Expecting 'start('" 2245: "Expecting ')' after start object" 2246: "Expecting 'startlist'" 2247: "Expecting 'startlist('" 2248: "Expecting ')' after startlist objects" 2249: "Missing 'of' in compose type" 2250: "Missing 'end' in compose type" 2251: "Expecting 'to' in map type" 2252: "Expecting 'to' in inmap type" 2253: "Expecting 'of' after set" 2254: "Expecting 'of' after seq" 2255: "Expecting 'of' after seq1" 2256: "Bracket mismatch" 2257: "Missing close bracket after optional type" **2258:** "Expecting '==>' in explicit operation type" 2259: "Operations cannot have [@T] type parameters" 2260: "Module starts with 'class' instead of 'module'" **2261:** "Missing comma between return types?" 2262: "Can't have traces in VDM-SL" 2263: "Missing ';' after named trace definition" 2264: "Expecting ':' after trace name" 2265: "Expecting 'n1, n2' after trace definition"



- **2266:** "Expecting 'n' or 'n1, n2' after trace definition" 2267: "Expecting 'obj.op(args)' or 'op(args)'" 2268: "Expecting 'id.id(args)'" 2269: "Expecting '(trace definitions)'" 2270: "Only value definitions allowed in traces" 2271: "Expecting 'duration'" 2272: "Expecting 'duration('" 2273: "Expecting ')' after duration" 2274: "Expecting 'cycles'" 2275: "Expecting 'cycles('" 2276: "Expecting ')' after cycles" 2277: "Can't have state in VDM++" 2278: "Async only permitted for operations" 2279: "Invalid breakpoint hit condition" 2280: "System class cannot be a subclass" 2290: "System class can only define instance variables and a constructor" 2291: "'reverse' not available in VDM classic" **2292:** "Expecting '|| (...)'" 2293: "Expecting '|| (a, b,...)'" 2294: "Expecting ')' ending || clause" 2295: "Can't use old name here" 2296: "Block cannot be empty" 2297: "Expecting ' |->' in map pattern" 2298: "Map patterns not available in VDM classic"
- **2299:** "Expecting {|->} empty map pattern"



- 2300: "mk_<type> must have a single argument"
- **2301:** "Expecting narrow_(expression, type)"
- 2302: "Expecting ')' after narrow_ expression"
- 2303: "Narrow not available in VDM classic"



Appendix E

Type Errors and Warnings

If the syntax rules are satisfied, it is still possible to get errors from the type checker. The errors can be as follows:

- 3000: "Expression does not match declared type"
- 3001: "Class inherits thread definition from multiple supertypes"
- **3002:** "Circular class hierarchy detected: <name>"
- 3003: "Undefined superclass: <supername>"
- 3004: "Superclass name is not a class: <supername>"
- 3005: "Overriding a superclass member of a different kind: <member>"
- **3006:** "Overriding definition reduces visibility" This error message typically are caused by using a more restrictive access modifier (or none which is interpreted as private) at this place compared to for example an inherited definition.
- 3007: "Overriding member incompatible type: <member>"
- 3008: "Overloaded members indistinguishable: <member>"
- 3009: "Circular class hierarchy detected: <class>"
- 3010: "Name <name> is ambiguous"
- 3011: "Name <name> is multiply defined in class"
- **3012:** "Type <name> is multiply defined in class"
- 3013: "Class invariant is not a boolean expression"
- **3014:** "Expression is not compatible with type bind"

- 3015: "Set bind is not a set type?"
- 3016: "Expression is not compatible with set bind"
- 3017: "Duplicate definitions for <name>"
- **3018:** "Function returns unexpected type"
- **3019:** "Function parameter visibility less than function definition" This error message typically are caused by using a more restrictive access modifier (or none which is interpreted as private) at this place compared to for example an inherited definition.
- 3020: "Too many parameter patterns"
- 3021: "Too few parameter patterns"
- 3022: "Too many curried parameters"
- 3023: "Too many parameter patterns"
- 3024: "Too few parameter patterns"
- **3025:** "Constructor operation must have return type <class>"
- 3026: "Constructor operation must have return type <class>"
- **3027:** "Operation returns unexpected type"
- **3028:** "Operation parameter visibility less than operation definition" This error message typically are caused by using a more restrictive access modifier (or none which is interpreted as private) at this place compared to for example an inherited definition.
- 3029: "Function returns unexpected type"
- **3030:** "Function parameter visibility less than function definition" This error message typically are caused by using a more restrictive access modifier (or none which is interpreted as private) at this place compared to for example an inherited definition.
- 3031: "Unknown state variable <name>"
- **3032:** "State variable <name> is not this type"
- 3033: "Polymorphic function has not been instantiated: <name>"
- 3034: "Function is already instantiated: <name>"
- **3035:** "Operation returns unexpected type"



- 3036: "Operation parameter visibility less than operation definition" This error message typically are caused by using a more restrictive access modifier (or none which is interpreted as private) at this place compared to for example an inherited definition.
 3037: "Static instance variable is not initialized: <name>"
 3038: "<name> is not an explicit operation"
 3039: "<name> is not in scope"
 3040: "Cannot put mutex on a constructor"
 3041: "Duplicate mutex name"
 3042: "<name> is not in scope"
 3043: "<name> is not an explicit operation"
 3043: "<name> is not in scope"
 3044: "Duplicate permission guard found for <name>"
 3045: "Cannot put guard on a constructor"
 3046: "Guard is not a boolean expression"
 3047: "Only one state definition allowed per module"
 3048: "Expression does not return a value"
- 3049: "Thread statement/operation must not return a value"
- 3050: "Type <name> is infinite"
- 3051: "Expression does not match declared type"
- **3052:** "Value type visibility less than value definition" This error message typically are caused by using a more restrictive access modifier (or none which is interpreted as private) at this place compared to for example an inherited definition.
- 3053: "Argument of 'abs' is not numeric"
- **3054:** "Type <name> cannot be applied"
- 3055: "Sequence selector must have one argument"
- 3056: "Sequence application argument must be numeric"
- 3057: "Map application must have one argument"
- **3058:** "Map application argument is incompatible type"




3059: "Too many arguments"
3060: "Too few arguments"
3061: "Inappropriate type for argument <n>"</n>
3062: "Too many arguments"
3063: "Too few arguments"
3064: "Inappropriate type for argument <n>"</n>
3065: "Left hand of <operator> is not <type>"</type></operator>
3066: "Right hand of <operator> is not <type>"</type></operator>
3067: "Argument of 'card' is not a set"
3068: "Right hand of map 'comp' is not a map"
3069: "Domain of left should equal range of right in map 'comp'"
3070: "Right hand of function 'comp' is not a function"
3071: "Left hand function must have a single parameter"
3072: "Right hand function must have a single parameter"
3073: "Parameter of left should equal result of right in function 'comp'"
3074: "Left hand of 'comp' is neither a map nor a function"
3075: "Argument of 'conc' is not a seq of seq"
3076: "Argument of 'dinter' is not a set of sets"
3077: "Merge argument is not a set of maps"
3078: "dunion argument is not a set of sets"
3079: "Left of '<-:' is not a set"
3080: "Right of '<-:' is not a map"
3081: "Restriction of map should be set of <type>"</type>
3082: "Left of '<:' is not a set"
3083: "Right of '<:' is not a map"






3109: "Argument to 'inds' is not a sequence" 3110: "Argument of 'in set' is not a set" 3111: "Argument to 'inverse' is not a map" 3112: "Iota set bind is not a set" 3113: "Unknown type name <name>" 3114: "Undefined base class type: <class>" 3115: "Undefined class type: <class>" 3116: "Argument to 'len' is not a sequence" 3117: "Such that clause is not boolean" 3118: "Predicate is not boolean" 3119: "Map composition is not a maplet" 3120: "Argument to 'dom' is not a map" 3121: "Element is not of maplet type" 3122: "Argument to 'rng' is not a map" 3123: "Left hand of 'munion' is not a map" 3124: "Right hand of 'munion' is not a map" 3125: "Argument of mk_<type> is the wrong type" 3126: "Unknown type <type> in constructor" **3127:** "Type <type> is not a record type" 3128: "Record and constructor do not have same number of fields" 3129: "Constructor field <n> is of wrong type" **3130:** "Modifier for <tag> should be <type>" 3131: "Modifier <tag> not found in record" 3132: "mu operation on non-record type" 3133: "Class name <name> not in scope"





3159: "Predicate is not boolean" **3160:** "Left hand of $' \setminus '$ is not a set" **3161:** "Right hand of $' \setminus '$ is not a set" **3162:** "Left and right of '\' are different types" **3163:** "Left hand of <operator> is not a set" 3164: "Right hand of <operator> is not a set" 3165: "Left and right of intersect are different types" 3166: "Set range type must be an number" 3167: "Set range type must be an number" 3168: "Left hand of <operator> is not a set" **3169:** "Right hand of <operator> is not a set" 3170: "Map iterator expects nat as right hand arg" 3171: "Function iterator expects nat as right hand arg" **3172:** "' **' expects number as right hand arg" 3173: "First arg of '**' must be a map, function or number" **3174:** "Subsequence is not of a sequence type" 3175: "Subsequence range start is not a number" 3176: "Subsequence range end is not a number" 3177: "Left hand of <operator> is not a set" **3178:** "Right hand of <operator> is not a set" 3179: "Argument to 'tl' is not a sequence" **3180:** "Inaccessible member <name> of class <name>" **3181:** "Cannot access <name> from a static context" 3182: "Name <name> is not in scope" 3183: "Exported function <name> not defined in module"



3194: "Type of value import <name> does not match export from <module>"

3195: "Cannot import from self"

3196: "No such module as <module>"

3197: "Expression matching set bind is not a set"

3198: "Type bind not compatible with expression"

3199: "Set bind not compatible with expression"

3200: "Mk_ expression is not a record type"

3201: "Matching expression is not a compatible record type"

3202: "Record pattern argument/field count mismatch"

3203: "Sequence pattern is matched against <type>"

3204: "Set pattern is not matched against set type"

3205: "Matching expression is not a product of cardinality <n>"

3206: "Matching expression is not a set type"

3207: "Object designator is not an object type"

3208: "Object designator is not an object type"



- 3209: "Member <field> is not in scope"
- **3210:** "Object member is neither a function nor an operation"
- 3211: "Expecting <n> arguments"
- 3212: "Unexpected type for argument <n>"
- **3213:** "Operation <name> is not in scope"
- 3214: "Cannot call <name> from static context"
- 3215: "<name> is not an operation"
- 3216: "Expecting <n> arguments"
- 3217: "Unexpected type for argument <n>"
- 3218: "Expression is not boolean"
- 3219: "For all statement does not contain a set type"
- 3220: "From type is not numeric"
- 3221: "To type is not numeric"
- 3222: "By type is not numeric"
- 3223: "Expecting sequence type after 'in'"
- 3224: "If expression is not boolean"
- 3225: "Such that clause is not boolean"
- 3226: "Incompatible types in object assignment"
- 3228: "<name> is not in scope"
- **3229:** "<name> should have no parameters or return type"
- 3230: "<name> is implicit"
- 3231: "<name> should have no parameters or return type"
- 3232: "<name> is not an operation name"
- 3233: "Precondition is not a boolean expression"
- 3234: "Postcondition is not a boolean expression"



3235: "Expression is not a set of object references"
3236: "Class does not define a thread"
3237: "Class does not define a thread"
3238: "Expression is not an object reference or set of object references"
3239: "Incompatible types in assignment"
3241: "Body of trap statement does not throw exceptions"
3242: "Map element assignment of wrong type"
3243: "Seq element assignment is not numeric"
3244: "Expecting a map or a sequence"
3245: "Field assignment is not of a record type"
3246: "Unknown field name, <name>"</name>
3247: "Unknown state variable <name> in assignment"</name>
3248: "Cannot assign to 'ext rd' state <name>"</name>
3249: "Object designator is not a map, sequence, function or operation"
3250: "Map application must have one argument"
3251: "Map application argument is incompatible type"
3252: "Sequence application must have one argument"
3253: "Sequence argument is not numeric"
3254: "Too many arguments"
3255: "Too few arguments"
3256: "Inappropriate type for argument <n>"</n>
3257: "Too many arguments"
3258: "Too few arguments"
3259: "Inappropriate type for argument <n>"</n>
3260: "Unknown class member name, <name>"</name>



Overture VDM-10 Tool Support: User Guide

3261: "Unknown field name, <name>"</name>
3262: "Field assignment is not of a class or record type"
3263: "Cannot reference 'self' from here"
3264: "At least one bind cannot match set"
3265: "At least one bind cannot match this type"
3266: "Argument is not an object"
3267: "Empty map cannot be applied"
3268: "Empty sequence cannot be applied"
3269: "Ambiguous function/operation name: <name>"</name>
3270: "Measure <name> is not in scope"</name>
3271: "Measure <name> is not an explicit function"</name>
3272: "Measure result type is not a nat, or a nat tuple"
3273: "Measure not allowed for an implicit function"
3274: "External variable is not in scope: <name>"</name>
3275: "Error clause must be a boolean"
3276: "Ambiguous names inherited by <name>"</name>
3277: "Trace repeat illegal values"
3278: "Cannot inherit from system class <name>"</name>
3279: "Cannot instantiate system class <name>"</name>
3280: "Argument to deploy must be an object"
3281: "Arguments to duration must be nat"
3282: "Arguments to cycles must be nat"
3283: "System class constructor cannot be implicit"
3284: "System class can only define instance variables and a constructor"
3285: "System class can only define a default constructor"

APPENDIX E. TYPE ERRORS AND WARNINGS



3286: "Constructor cannot be 'async'" 3287: "Periodic thread must have <n> argument(s)" 3288: "-" 3289: "-" 3290: "Argument to setPriority must be an operation" 3291: "Argument to setPriority cannot be a constructor" 3292: "Constructor is not accessible" 3293: "Asynchronous operation <name> cannot return a value" 3294: "Only one system class permitted" 3295: "Argument to 'reverse' is not a sequence" **3296:** "Cannot use '" + typename + "' outside system class" **3297:** "Cannot use default constructor for this class" 3298: "Cannot inherit from CPU" 3299: "Cannot inherit from BUS" **3300:** "Operation <type> cannot be called from a function" **3301:** "Variable <name> in scope is not updatable" **3302:** "Variable <name> cannot be accessed from this context" 3303: "Measure parameters different to function" 3304: "Recursive function cannot be its own measure" 3305: "CPU frequency to slow: <speed> Hz" 3306: "CPU frequency to fast: <speed> Hz" 3307: "Errs clause is not bool -> bool" 3308: "Cannot mix modules and flat specifications" 3309: "Measure must not be polymorphic" 3310: "Measure must also be polymorphic"

103



- 3311: "Pattern cannot match"
- 3312: "Void operation returns non-void value"
- 3313: "Operation returns void value"
- 3314: "Map pattern is not matched against map type"
- 3315: "Matching expression is not a map type"
- 3316: "Expecting number in periodic argument"
- 3317: "Expression can never match narrow type"
- 3318: "Measure's type parameters must match function's"

Warnings from the type checker include:

5000: "Definition <name> not used"

5001: "Instance variable is not initialized: <name>"

- **5002:** "Mutex of overloaded operation" This warning is provided if one defined a mutex for an operation that is defined using overloading. The users needs to be aware that all of the overloaded operations will now by synchronisation controlled by this constraint.
- 5003: "Permission guard of overloaded operation"
- 5004: "History expression of overloaded operation"
- 5005: "Should access member <member> from a static context"
- 5006: "Statement will not be reached"
- 5007: "Duplicate definition: <name>"
- 5008: "<name/location> hides <name/location>"
- 5009: "Empty set used in bind"
- 5010: "State init expression cannot be executed"
- **5012:** "Recursive function has no measure" Whenever a recursive function is defined the user have the possibility defining a measure (i.e. a function that takes the same parameters as the recursive function and returns a natural number that should decrease at every recursive call). If such measures are included the proof obligation generator can provide proof obligations that will ensure termination of the recursion.

- **5014:** "Uninitialized BUS ignored" This warning appears if one has defined a BUS that is not used.
- 5015: "LaTeX source should start with %comment, \document, \section or \subsection"
- 5016: "Some statements will not be reached"



Appendix F

Run-Time Errors

When using the interpreter/debugger it is possible to get run-time errors, even if there are no type checking errors. The possible errors are as follows:

4000: "Cannot instantiate abstract class <class>" 4002: "Expression value is not in set bind" 4003: "Value <value> cannot be applied" 4004: "No cases apply for <value>" 4005: "Duplicate map keys have different values" 4006: "Type <type> has no field <field>" 4007: "No such field in tuple: #<n>" 4008: "No such type parameter @<name> in scope" 4009: "Type parameter/local variable name clash, @<name>" 4010: "Cannot take head of empty sequence" 4011: "Illegal history operator: <#op>" 4012: "Cannot invert non-injective map" 4013: "Iota selects more than one result" 4014: "Iota does not select a result" 4015: "Let be st found no applicable bindings" 4016: "Duplicate map keys have different values: <domain>"



4017:	"Duplicate map keys have different values: <domain>"</domain>
4018:	"Maplet cannot be evaluated"
4019:	"Sequence cannot extend to key: <index>"</index>
4020:	"State value is neither a <type> nor a <type>"</type></type>
4021:	"Duplicate map keys have different values: <key>"</key>
4022:	"mk_ type argument is not <type>"</type>
4023:	"Mu type conflict? No field tag <tag>"</tag>
4024:	"'not yet specified' expression reached"
4025:	"Map key not within sequence index range: <key>"</key>
4026:	"Cannot create post_op environment"
4027:	"Cannot create pre_op environment"
4028:	"Sequence comprehension pattern has multiple variables"
4029:	"Sequence comprehension bindings must be numeric"
4030:	"Duplicate map keys have different values: <key>"</key>
4031:	"First arg of '**' must be a map, function or number"
4032:	"'is subclass responsibility' expression reached"
4033:	"Tail sequence is empty"
4034:	"Name <name> not in scope"</name>
4035:	"Object has no field: <name>"</name>
4036:	"ERROR statement reached"
4037:	"No such field: <name>"</name>
4038:	"Loop, from <value> to <value> by <value> will never terminate"</value></value></value>
4039:	"Set bind does not contain value <value>"</value>
4040:	"Let be st found no applicable bindings"
4041:	"'is not yet specified' statement reached"

APPENDIX F. RUN-TIME ERRORS



- **4042:** "Sequence does not contain key: <key>"
- **4043:** "Object designator is not a map, sequence, operation or function"
- 4045: "Object does not contain value for field: <name>"
- 4046: "No such field: <name>"
- 4047: "Cannot execute specification statement"
- **4048:** "'is subclass responsibility' statement reached"
- 4049: "Value <value> is not in set bind"
- 4050: "Value <value> is not in set bind"
- 4051: "Cannot apply implicit function: <name>"
- 4052: "Wrong number of arguments passed to <name>"
- 4053: "Parameter patterns do not match arguments"
- **4055:** "Precondition failure: <pre_name>" This error occurs if a pre-condition to a function or operation is violated.
- **4056:** "Postcondition failure: <post_name>" This error occurs if a post-condition to a function or operation is violated.
- **4057:** "Curried function return type is not a function"
- 4058: "Value <value> is not a nat1"
- 4059: "Value <value> is not a nat"
- **4060:** "Type invariant violated for <type>"
- 4061: "No such key value in map: <key>"
- 4062: "Cannot convert non-injective map to an inmap"
- **4063:** "Duplicate map keys have different values: <domain>"
- 4064: "Value <value> is not a nat1 number"
- 4065: "Value <value> is not a nat"
- 4066: "Cannot call implicit operation: <name>"
- 4067: "Deadlock detected"



4068: "Wrong number of arguments passed to <name>"</name>
4069: "Parameter patterns do not match arguments"
4071: "Precondition failure: <pre_name>"</pre_name>
4072: "Postcondition failure: <post_name>"</post_name>
4073: "Cannot convert type parameter value to <type>"</type>
4074: "Cannot convert <value> to <type>"</type></value>
4075: "Value <value> is not an integer"</value>
4076: "Value <value> is not a nat1"</value>
4077: "Value <value> is not a nat"</value>
4078: "Wrong number of fields for <type>"</type>
4079: "Type invariant violated by mk_{-} arguments"
4080: "Wrong number of fields for <type>"</type>
4081: "Field not defined: <tag>"</tag>
4082: "Type invariant violated by mk_{-} arguments"
4083: "Sequence index out of range: <index>"</index>
4084: "Cannot convert empty sequence to seq1"
4085: "Cannot convert tuple to <type>"</type>
4086: "Value of type parameter is not a type"
4087: "Cannot convert <value> (<kind>) to <type>"</type></kind></value>
4088: "Set not permitted for <kind>"</kind>
4089: "Can't get real value of <kind>"</kind>
4090: "Can't get rat value of <kind>"</kind>
4091: "Can't get int value of <kind>"</kind>
4092: "Can't get nat value of <kind>"</kind>
4093: "Can't get nat1 value of <kind>"</kind>

110

APPENDIX F. RUN-TIME ERRORS



4094: "Can't get bool value of <kind>" 4095: "Can't get char value of <kind>" 4096: "Can't get tuple value of <kind>" 4097: "Can't get record value of <kind>" 4098: "Can't get quote value of <kind>" 4099: "Can't get sequence value of <kind>" 4100: "Can't get set value of <kind>" 4101: "Can't get string value of <kind>" 4102: "Can't get map value of <kind>" 4103: "Can't get function value of <kind>" 4104: "Can't get operation value of <kind>" 4105: "Can't get object value of <kind>" 4106: "Boolean pattern match failed" 4107: "Character pattern match failed" 4108: "Sequence concatenation pattern does not match expression" 4109: "Values do not match concatenation pattern" 4110: "Expression pattern match failed" 4111: "Integer pattern match failed" 4112: "Quote pattern match failed" 4113: "Real pattern match failed" 4114: "Record type does not match pattern" 4115: "Record expression does not match pattern" 4116: "Values do not match record pattern" 4117: "Wrong number of elements for sequence pattern" 4118: "Values do not match sequence pattern"



- 4119: "Wrong number of elements for set pattern" 4120: "Values do not match set pattern" 4121: "Cannot match set pattern" 4122: "String pattern match failed" 4123: "Tuple expression does not match pattern" 4124: "Values do not match tuple pattern" 4125: "Set union pattern does not match expression" 4126: "Values do not match union pattern" 4127: "Cannot match set pattern" 4129: "Exit <value>" 4130: "Instance invariant violated: <inv_op>" 4131: "State invariant violated: <inv_op>" 4132: "Using undefined value" 4133: "Map range is not a subset of its domain: <key>" 4134: "Infinite or NaN trouble" 4135: "Cannot instantiate a system class" 4136: "Cannot deploy to CPU" 4137: "Cannot set operation priority on CPU" 4138: "Cannot set CPU priority for operation" 4139: "Multiple BUS routes between CPUs <name> and <name>" 4140: "No BUS between CPUs <name> and <name>" 4141: "CPU policy does not allow priorities" 4142: "Value already updated by thread <n>" 4143: "No such test number: <n>"
- 4144: "State init expression cannot be executed"

112



- **4145:** "Time: <n> is not a nat1"
- 4147: "Polymorphic function missing @T"
- 4148: "Measure function is called recursively: <name>"
- 4149: "CPU frequency to slow: <speed> Hz"
- 4150: "CPU frequency to fast: <speed> Hz"
- 4151: "Cannot take dinter of empty set"
- 4152: "Wrong number of elements for map pattern"
- 4153: "Values do not match map pattern"
- 4154: "Cannot match map pattern"
- 4155: "Map union pattern does not match expression"
- 4156: "Cannot match map pattern"
- 4157: "Expecting +ive integer in periodic argument <n>"
- 4158: "Period argument must be non-zero"
- 4159: "Delay argument must be less than the period"



Appendix G

Categories of Proof Obligations

This appendix provides a list of the different proof obligation categories generated by Overture, and an explanantion of the circumstances under which each category can be expected.

- **map apply:** Whenever a map application is made you need to be certain that the argument is in the domain of the map.
- **function apply:** Whenever a function application is used you need to be certain that the list of arguments to the function satisfies the pre-condition of the function, assuming such a predicate is present.
- **sequence apply:** Whenever a sequence application is used you need to be certain that the argument is within the indices of the sequence.

post condition:

function satisfiability: For all implicit function definitions this proof obligation will be generated to ensure that it is possible to find an implementation satisfying the post-conditions for all arguments satisfying the pre-conditions.

function parameter patterns:

- **let be st existence:** Whenever a let-be-such-that expression/statement is used you need to be certain that at least one value will match the such-that expression.
- **unique existence binding:** The iota expression requires one unique binding to be present and that is guranteed by proof obligations from this category.

function iteration:

map iteration:

function compose:



map compose:

non-empty set: This kind of proof obligation is used whenever non-empty sets are required.

- **non-empty sequence:** This kind of proof obligation is used whenever non-empty sequences are required (eg. taking the head of a sequence)
- non-zero: This kind of proof obligation is used whenever zero cannot be used (e.g. in division).
- **finite map:** If a type binding to a type that potentially has infinitely many elements is used inside a map comprehension, this proof obligation will be generated because all mappings in VDM must be finite.
- **finite set:** If a type binding to a type that potentially has infinitely many elements is used inside a set comprehension, this proof obligation will be generated because all sets in VDM must be finite.
- **map compatible:** Mappings in VDM represent a unique relationship between the domain values and the corresponding range values. Proof obligations in this category are meant to ensure that such a unique relationship is guranteed.

map sequence compatible:

map set compatible:

sequence modification:

tuple selection: This proof obligation category is used whenever a tuple selection expression is used to gurantee that the length of the tuple is at least as long as the selector used.

value binding:

- **subtype:** This proof obligation category is used whenever it is not possible to statically detect that the given value falls into the subtype required.
- **cases exhaustive:** If a cases expression does not have an others clause it is necessary to ensure that the different case alternatives catch all values of the type of the expression used in the case choice.
- **type invariant:** Proof obligations from this category are used to ensure that invariants for elements of a particular type are satisfied.
- **recursive function:** This proof obligation makes use of the measure construct to ensure that a recursive function will terminate.
- **state invariant:** If a state (including instance variables in VDM++) has an invariant, this proof obligation will be generated whenever an assignment is made to a part of the state.



- while loop termination: This kind of proof obligation is a reminder to ensure that a while loop will terminate.
- **operation post condition:** Whenever an explicit operation has a post-condition there is an implicit proof obligation generated to remind the user that you have to ensure that the explicit body of the operation satisfies the post-condition for all possible inputs.

operation parameter patterns:

operation satifiability: For all implicit operation definitions this proof obligation will be generated to ensure that it is possible to find an implementation satisfying the post-condition for all arguments satisfying the pre-conditions.



Appendix H

Mapping Rules between VDM++/VDM-RT and UML Models

Transformation Rule 1

VDM classes are mapped as the UML meta-class Class

Transformation Rule 2

The visibility of VDM instance variables, values, functions and operations are mapped as a *subset* of the UML enumeration VisibilityKind comprising public, private and protected.

Transformation Rule 3

VDM static is mapped as the isStatic property of the UML meta-class Class, Property or Operation respectively.

Transformation Rule 4

Data type definitions are mapped as the UML meta-class Class and are referenced, and thus nested, through the meta-attribute nestedClassifier of the owning class. Notice that this rule is not specified or implemented.

Transformation Rule 5

Instance variable and value definitions are mapped as the UML meta-class Association, if:

- 5 a: The type is an *object reference type*, or
- **5 b:** The type is *not* a basic *data type* [Fitzgerald&05, p64,71].

Transformation Rule 6

So

Instance variable and value definitions are mapped as the UML meta-class Property [UMLSuperstructure2.1.2, p48,p139], if the type is a *basic data type* [Fitzgerald&05, p71]. Instance variables and values are distinguished by the meta-attribute isReadOnly. Notice: rule 10 is an exception to this rule.

VDM concept	Property::isReadOnly	
Instance variables	false	
Values	true	

 Table H.1: The meta-attribute isReadOnly distinguishes

 instance variables and values

Transformation Rule 7

The initial value of instance variables and values definitions are mapped as the property default of the UML metaclass Property.

Transformation Rule 8

The VDM optional type is mapped to the properties lower = 0 and upper = 1 of the UML meta-class.

Transformation Rule 9

The VDM constructs set, seq and seq1 is mapped as the UML meta-class Association which may be decorated with a textual constraint defined by the meta-attribute isOrdered¹ in addition to a multiplicity at both ends. Table H.2 shows how the above-mentioned VDM constructs are mapped.

VDM construct	Ordered	Target class Multiplicity
set	false	0*
seq	true	0*
seq1	true	1*

Table H.2: Transformation rules for VDM constructs modeling collections



Transformation Rule 10

The VDM constructs map and inmap are mapped as the UML meta-class Association with a qualifier. The domain is specified by the qualifier, which is located at the source class. The range is specified by the target class. Notice, that if the range is specified by a *basic type* it is mapped as a separate class. This is an exception to rule 6.

VDM construct	Qualifier end	Target class end
v Divi construct	isUnique	isUnique
map	false	true
inmap	true	true

Table H.3: Transformation rules for VDM constructs modeling relationships between two sets.

Transformation Rule 11

A VDM class with a thread compartment is mapped as the UML meta-class Class with the meta-attribute isActive set to true.

Transformation Rule 12

A VDM class with the keyword is subclass of followed by class-names is mapped as the UML meta-class Generalization, with the attributes general and specific referencing the superclass and subclass, respectively. More than one subclass results in more than one instance of Generalization.

Transformation Rule 13

A VDM class with the keyword is subclass responsibility as a function or operation body is mapped as the UML metaclass Class with the meta-attribute isAbstract set to true.

Transformation Rule 14

A VDM generic class maps to the UML meta-class Class with the attribute templateSignature referencing a set of TemplateParameter having the name property set to the name of the parameter.

Transformation Rule 15

A VDM operation and function are mapped to the UML meta-class Operation where the property isQuery determine whether the Operation represents a VDM function or operation:

true

• for a function.

false

• for a operation.

The return type of a function and operation is mapped collectively as the property type and the multiplicity² of the Operation meta-class. The parameters of the operation or function is mapped to the UML meta-class Parameter represented as the property ownedParameters of the Operation meta-class.

The name and type of a VDM parameter are mapped to the property name, type and the multiplicity² of the Parameter meta-class.



Appendix I

Using VDM Values in Java

As described in Chapter 14 integration between Overture and Java code can be established, either by writing native libraries in Java that can be called from VDM, or giving a Java program overall control of a VDM model, making calls to that model as a user interacts with a GUI.

In both cases, internal VDM values have to be handled by Java - either because they are passed as arguments to a Java library and returned as results to VDM, or because they are returned from a VDM model evalution to a controlling Java program.

This appendix describes the internal class hierarchy used by Overture to represent internal VDM model values, and describes how a Java program can convert these to native Java values (int, long, String etc.) as well as creating internal values for returning to the VDM model (e.g. as the return value of library methods).

I.1 The Value Class Hierarchy

All internal VDM values in Overture are held by instances of the Value class - fully qualified name, org.overturetool.vdmj.values.Value. The Value class itself is abstract, but subclasses can be instantiated to represent any VDM value, such as a "seq of char" or a "nat1" or a value of an arbitrarily complex type. The hierarchy is shown in Figure I.1.

Generally, the name of the Value subclass for a VDM type is NameValue, for example BooleanValue or SeqValue.

The following sections describe how to obtain Java values from a Value object, and how to create Value objects from basic Java values (or iteratively from other Values).

I.2 Primitive Values

Most primitive VDM types have subclasses with simple constructors that take a Java primitive type as an argument:

```
public BooleanValue(boolean value)
public CharacterValue(char value)
```






Figure I.1: Java Value Hierarchy

```
public RealValue(double value) throws Exception
public RationalValue(double value) throws Exception
public IntegerValue(long value)
public NaturalValue(long value) throws Exception
public NaturalOneValue(long value) throws Exception
public QuoteValue(String value)
public NilValue()
```

The constructors that throw exceptions are ones for which some Java value would not be legal for the VDM type concerned. For example, a RealValue or RationalValue cannot take the Java values Double.NaN or Double.POSITIVE_INFINITY as a constructor argument. Similarly, NaturalValue and NaturalOneValue cannot take a negative long as an argument.

Note that a QuoteValue is constructed with a string. This is simply the string value that would appear between angle brackets in VDM, for example <FAIL> would be constructed with the Java string "FAIL".



To convert a VDM Value into a Java value, the Value class provides a number of conversion methods, each of which either returns the corresponding Java primitive value, or throws an exception if the conversion cannot be made for the VDM type concerned:

```
public boolean boolValue(Context ctxt) throws ValueException
public char charValue(Context ctxt) throws ValueException
public double realValue(Context ctxt) throws ValueException
public double ratValue(Context ctxt) throws ValueException
public long intValue(Context ctxt) throws ValueException
public long natValue(Context ctxt) throws ValueException
public long natValue(Context ctxt) throws ValueException
public long natValue(Context ctxt) throws ValueException
public String quoteValue(Context ctxt) throws ValueException
```

Note that all of these conversion functions takes a Context parameter and can throw a ValueException. The context parameter is used internally by Overture and represents the call stack during the evaluation of an expression. This parameter can be set to null when using these methods in Java code outside Overture. The ValueExceptions are thrown if the VDM value cannot be converted into the Java type requested. For example, calling booleanValue on a RealValue object will raise a ValueException with the message text "Cannot get bool value of real".

I.3 Sets, Sequences and Maps

VDM allows primitive types to be built into more complex aggregations and collections, and these can also be converted to and from Java types, though the process is a little more involved. Three classes are provided to help with this conversion: ValueSet, ValueList and ValueMap (all within the same org.overturetool.vdmj.values package). These classes are, respectively, a Java Set, List and Map of VDM Values:

```
public class ValueSet extends Vector<Value>
public class ValueList extends Vector<Value>
public class ValueMap extends LinkedHashMap<Value, Value>
```

Note that the ValueSet class is actually based on a Java Vector, not a Java Set type, though the class does have set semantics (no duplicates). This is an implementation detail and allows Overture to permute set orderings in certain circumstances.

These three classes have obvious constructors, and allow Values (or Value pairs) to be added to the collection subsequently, using standard Java collection methods:

```
public ValueSet()
public ValueSet(int size)
public ValueSet(ValueSet from)
public ValueSet(Value v)
public ValueList()
```



```
public ValueList (ValueList from)
public ValueList (Value v)
public ValueList (int size)
public ValueMap()
public ValueMap(ValueMap from)
public ValueMap(Value k, Value v)
```

Using these three helper classes, it is now possible to create VDM set, sequence and map values, using constructors for the SetValue, SeqValue and MapValue classes:

```
public SetValue()
public SetValue(ValueSet values)

public SeqValue()
public SeqValue(ValueList values)
public SeqValue(String s)

public MapValue()
public MapValue(ValueMap values)
```

Note that there is a special constructor for SeqValue that takes a Java string. This creates a VDM "seq of char", but without the need to create a ValueList with CharacterValues.

If the ValueList (or other) collection passed to these constructors contains a mixture of VDM types - i.e. a mixture of VDM Value subclasses, such as a BooleanValue and a NaturalOneValue - then the type of the constructed VDM value is the union of the various types passed, in this example "seq of (bool | nat1)". If this VDM type is not compatible with the use of the value in the rest of the VDM model, runtime type exceptions may occur when the value is processed by the model.

Lastly, as before, to get the primitive Java values of a VDM collection, the following methods are provided:

```
public ValueList seqValue(Context ctxt) throws ValueException
public String stringValue(Context ctxt) throws ValueException
public ValueSet setValue(Context ctxt) throws ValueException
public ValueMap mapValue(Context ctxt) throws ValueException
```

Note that, as with the SeqValue constructor, there is a special method to return a Java String from a "seq of char" SeqValue, rather than a ValueList of CharacterValues. As before, if the Value being used is not a sequence or set or map, then these methods will throw a ValueException.



I.4 Other Types

The sections above describe enough to create or deconstruct simple VDM values in Java, and simple collections of those values (collections of collections etc.). The remainder of this section describes the remaining unusual cases, for more sophisticated types.

I.5 Function values

Overture has an internal FunctionValue class, and this is used to hold the values of functions (e.g. the value of a "lambda" expression or the value of a function defined within a module). But as far as Java is concerned, these values are opaque - there is no equivalent Java construct, and the only way to evaluate a VDM function is to let Overture perform that evaluation. Similarly, Java cannot construct a FunctionValue.

The only operation that Java can reasonably perform with a FunctionValue is to create a composite function (eg. "f1 comp f2" in VDM) or a function iteration (e.g. "f ** 3" in VDM) using existing FunctionValues. To do this, there are two subclasses of FunctionValue, called CompFunctionValue and IterFunctionValue, the constructors for which are as follows:

```
public CompFunctionValue (FunctionValue f1, FunctionValue f2)
public IterFunctionValue (FunctionValue function, long count)
```

These both create new FunctionValues, which when evaluated by Overture act as the composition and iteration of the arguments, respectively.

There is a method to obtain a FunctionValue from a Value, but note that this is not an internal Java value (unlike other methods on Value, like realValue). It is used as a more convenient method than casting the Value to a FunctionValue, but that is all it does.

public FunctionValue functionValue(Context ctxt)

I.6 Object Values

When VDM++ and VDM-RT create new objects using the "new" operator, the resulting values are held as ObjectValues in Overture. These are complex types that involve function and operation definitions for the object as well as any type, value, sync, thread or traces sections defined. Therefore, like FunctionValues, ObjectValues are really opaque to Java and cannot be used directly.

Like FunctionValues, ObjectValues have a method to convert a Value into an ObjectValue. But this only performs a cast:

```
public ObjectValue objectValue(Context ctxt)
```



I.7 Record Values

A VDM record is just a collection of typed field values. A RecordValue can be obtained from a Value using the following method, which like FunctionValue and ObjectValue, just returns a RecordValue rather than some other Java representation:

public RecordValue recordValue(Context ctxt)

To get individual field Values from a RecordValue, two more Java helper types have to be introduced, called FieldMap and FieldValue. A FieldValue has the following constructor, and represents on field in a record:

public FieldValue(String name, Value value, boolean comparable)

The comparable argument indicates whether this field is used in the value comparison between record values. A field declared with ":-" in VDM would have a false argument, but normally this would be true, and the value must match the record type being used. FieldValues are added to a FieldMap, which is just a Java List of FieldValues.

So given a RecordValue, its FieldMap can be obtained from a public final field in the object, called fieldMap¹, and from there, individual FieldValues obtained - e.g. fieldMap.get(0).name and fieldmap.get(0).value.

To create a RecordValue, the record type is obtained from the RemoteInterpreter:

type = remoteInterpreter.getInterpreter().findType(Name)

The type is then passed to the RecordValue constructor, along with a FieldMap or a ValueList (of the fields in order).

```
public RecordValue(RecordType type, ValueList values, Context ctxt)
public RecordValue(RecordType type, FieldMap mapvalues, Context ctxt)
```

The Context parameter is needed to allow records with invariants to check the invariant before the value is constructed. Note that currently, record types with an invariant cannot be constructed in Java. The Context parameter can be passed as null from Java.

The caller is responsible for passing field Values that matches their expected type. If they do not match, Overture will throw a dynamic type exception during subsequent evaluations.

I.8 Token Values

Token values are really just wrappers around normal VDM Values, reflecting the way they are created in VDM, like mk_token("hello"), which would be a wrapper to a "seq of char". There is no special way to get a TokenValue from a Value, other than to cast it. Having cast the value, the wrapped value can be obtained from the public final Value field called "value".

Constructing a TokenValue is just a matter of passing the Value required:

¹Really this ought to have a get method.



```
public TokenValue(Value exp)
```

I.9 Tuple Values

A TupleValue in Overture is just a wrapper for a ValueList. The following method and constructor are used as expected:

```
public TupleValue(ValueList argvals)
public ValueList tupleValue(Context ctxt)
```

I.10 Invariant Values

A VDM type can be given a name and an invariant, wrapping an otherwise more primitive type without an invariant. Overture has a separate Value subclass for values of such types that simply put the primitive Value together with a FunctionValue for the invariant. However, as with RecordValues (which can also have invariants), it is not currently possible to create InvariantValues from Java for types that have an invariant.

For types without an invariant, the constructor is as follows:

public InvariantValue(NamedType type, Value value, Context ctxt)

The NamedType is obtained in a similar way to the RecordType above, using the Remote-Interpreter. Note that the caller is responsible for passing a Value that matches the expected type. If they do not match, Overture will throw a dynamic type exception during subsequent evaluations.

I.11 Void Values

Operations which do not return a value in VDM (i.e. ==> ()) return an instance of VoidValue in Java. The constructor has no arguments.

Index

architecture overview, 41 assert, 60 break, 60 BUS, 41 classes, 59 combinatorial testing, 35, 60 command assert, 60 break, 60 classes, 59 continue, 64 coverage, 61 create, 59 default, 59 down, 64 env, 60 files, 61 init, 60 latex, 61 latexdoc, 61 list, 61 load, 62 log, 60 modules, 59 next, 63 out, 63 pog, 60 print, 60 quit, 62 reload, 61 remove, 61 source, 64 stack, 64 state, 60

step, 63 stop, 64 threads, 64 trace, 61 up, 64 continue, 64 Convert to UML, 37 Convert to VDM, 37 coverage, 61 CPU, 41 create, 59 create real time project, 39 creating VDM++ class, 14 VDM-RT class, 14 VDM-SL module, 14 debug configuration, 21 debug perspective, 24 default, 59 down, 64 env, 60, 63 explorer, 7 export image button, 41 file extension, 10 files, 61 filter proved, 33 Go to time, 41 icon fail verdict, 35 inconclusive verdict, 35 not yet executed, 35 pass verdict, 35



resume debugging, 24 skipped test case, 35 step into, 24 step over, 24 step return, 24 suspend debugging, 24 terminate debugging, 24 use step filters, 24 init, 60 latex, 61 latexdoc, 61 launch configuration mode, 21 line number, 10 line numbers, 10 list, 61 load, 62 log, 60 model execution overview, 41 Modelio, 37 modules, 59 next, 63 out, 63 outline, 7 perspective, 7 combinatorial testing, 35 debug, 24 proof obligation, 33 VDM, 7 pog, 60 print, 60, 63 problems, 8 project close, 9 create, 13 import, 13 open, 9 options, 15 proof obligation perspective, 33

proof obligation, 33 categories, 33 quick interpreter, 8 quit, 62 RealTime Log viewer, 41 reload, 61 remove, 61 single CPU overview, 42 source, 64 stack, 64 state, 60 step, 63 stop, 64 Test Coverage Test suite, 29 threads, 64 trace, 61 traces, 35 UML transformation, 37 up, 64 VDM dialect, 13 vdm file extension, 14, 73 view, 7 welcome screen, 5 workbench, 7 XMI, 37