USER MANUAL FOR LIGHTING SYSTEM

Date: 01-01-2015 Version: 1.7.5

QUICK START

Rez the "Single prim" example cube. Touch to turn light on or off, touch and hold mouse button (> 1 sec.) to show menu. For a linkset example, rez the "Standing lamp" and touch the stand.

TWO SCRIPTS: SWITCH AND LIGHT

Two menus: main menu and color/alpha menu. The main menu only makes sense if the light is ON, the color/alpha menu comes in two flavours, making it possible to set color and alpha for both ON and OFF states. For example, you can have a red and transparent light that turns green and opaque when off.

TWO MODES: LINKSET AND REGION

Linkset mode:

- scripts can only function within the same linkset
- switch and light can either be in the same prim or in different prims
- there are no open listeners

Region mode:

- scripts can function anywhere within the same region
- switch and light cannot be in the same prim
- there is an open listener for every light

Use linkset mode whenever possible, and region mode only if there is no other option.

LIGHT GROUPS

Lights can be grouped by setting the prim description in both switch and light(s) to the same word or phrase, for example Bedroom or Kitchen. Keep it short and sweet so the text won't scroll to the next line in the menu. Use one switch for one light group. If the description is empty or "(No Description)", both switch and light(s) will be in the Default group.

LINK CONTROL (SECONDARY SWITCH FOR LINKSET MODE)

Now you can have multiple switches for a single light group. Drop the link control script in any prim (within the same linkset) and the link receiver script into the prim where the switch is located. Touch for on/off, long touch for menu.

Because a link control is part of a light group, the prim description in switch, light(s) and link control must be identical. There can be several secondary switches but only one primary switch.

REMOTE CONTROL (UNIVERSAL SECONDARY SWITCH)

The remote control can be used in both linkset and region mode.

A remote control can be anywhere within the same region. Drop the remote control script in an external object and the remote receiver script into the prim where the switch is located. Touch for on/off, long touch for menu.

Because a remote control is part of a light group, the prim description in switch, light(s) and remote control must be identical. There can be several secondary switches but only one primary switch.

Every receiver has an open listener.

NETWORK CONTROL (CONTROL PANEL FOR LIGHT GROUPS)

Drop the network control script in an empty prim and the network receiver script in every prim that contains a switch. It can control up to 9 light groups, turn them on or off all at the same time, or pull up

the menu for individual light groups. Touch for menu.

There are two versions: linkset and region. When using the region version, every receiver has an open listener.

ADVANCED CONTROLS

The following controls require a fair amount of patience and may not yield the result you expect. But they will save a lot of script memory.

LIGHT CONTROL (LIGHT WITHOUT BULBS)

Useful in situations where many light bulbs are needed and you don't want to use a large number of scripts. Imagine a switch and half a dozen light bulbs, seven scripts altogether. You can reduce this to two scripts by not using any light bulbs at all and dropping switch and light control in the same prim. Before you flip the switch, set the prim description of the switch and use the same description for all prims you intend to use as a light source. If you don't, every single prim in the linkset will be lit (possibly with the exception of the switch, see below).

Limitations: linkset only, no particles.

The switch itself won't light up unless it's the only prim, or the root prim.

CONFIGURATION AND SWITCH CONTROL

Features:

- one tiny script for any number of light sources
- every light source can have its own settings

Limitations: linkset only, no particles, no plugins, no other controls, no security, no linking with other scripts, one switch/group. All settings will be "hard-coded" into the object. End users can only switch the light on or off.

Scripts needed:

- during configuration: config_control, switch
- after configuration: switch_control

Configuration:

- drop "switch" in a child prim and "config_control" in every prim you want to use as a light source
- use the menu to set light, color, alpha, etc. (both ON and OFF settings are supported)
- remove the config control scripts
- for different light sources, drop them in other prims and pull up the menu again
- if a prim was unintentionally marked as a light prim, erase the description

WARNING: For a hassle-free experience, it is recommended to use a separate, non-root prim for the switch.

Finishing the product:

- remove the switch, the configuration notecard and all config control scripts
- drop "switch_control" in the prim of your choice
- touch for on/off

EXTENDED CONFIGURATION AND SWITCH CONTROL

This is the "extended" version of the configuration and switch control. The only difference is that it supports particles (making light bulbs required).

Features:

- switch replaced by very small script
- particle support

Limitations: linkset only, no plugins, no other controls, no security, no linking with other scripts, one switch/group. All settings will be "hard-coded" into the object. End users can only switch the light on or off.

Scripts needed:

- during configuration: ext_config_control, switch, light, particle script
- after configuration: ext_switch_control, light, particle script

Configuration:

- set up your linkset in the usual way, using one "switch" and one or more "light" scripts
- drop a particle script in one or more light prims
- drop "ext_config_control" in the switch prim
- use the menu to set light, color, alpha, etc. (both ON and OFF settings are supported)

WARNING: For a hassle-free experience, it is recommended to use a separate, non-root prim for the switch. For the sake of clarity, this prim should contain both "switch" and "ext_config_control".

Note that the particle size will be read from the notecard. If there is no notecard, the default size will be used (see "CONFIGURATION NOTECARD"). You can still use the particle menu (see "PARTICLES") to get an indication of what to enter in the notecard.

Finishing the product:

- remove the switch, the configuration notecard and the ext_config_control script
- replace them with "ext_switch_control" in the same prim
- touch for on/off

COMMUNICATION WITH OTHER SCRIPTS

The switch can both send and receive link messages.

Sending: create a custom menu button by entering a short text after "extButton = " in the notecard, replacing "On/Off" in the menu. When the button is touched, it will send the number 10958 and the button text in a link message. The message can be caught by another script within the same linkset. The other script can call the main menu by sending the number 10957 and the word "menu".

Receiving: other scripts can control the switch and menu by sending the number 10957 and a command. See "CONFIGURATION NOTECARD" for all possible commands. Useful for plugins, of which two examples are included: nightlight and proximity.

Intercepting existing messages: if you created a script and the need arises to perform some action when the light is switched on/off, or parameters are changed, check for number -10957.

PLUGIN SCRIPTS

Regular plugins (nightlight, proximity) go in the same prim where the SWITCH is located. Particle plugins (halo, starburst) go in the same prim where the LIGHT is located.

All plugins are compatible with both linkset and region scripts.

PARTICLES

Rez the "Example: particle test" lamp and touch it. A small halo will appear around the bulb. To try out other particle effects, remove "Particle:Halo" from the lamp and add another particle script by dragging it from your inventory. Both adding and removing can be done with the light on or off. The particle size can be changed in the particle menu or in the notecard. Please note that you have to set particleMenu to YES in the notecard in order to use it. The "On/Off" button will be replaced by "Particles".

There can be no more than one particle script in any light prim at any given time.

Every particle effect has its own minimum and maximum size. The "Min" and "Max" buttons in the particle menu will resize the particles to the smallest and largest possible size for the current particle effect.

CANDLE FLAMES

Candle flames always need a transparent prim to work. The best way to accomplish this is using the default transparent texture. Setting both Alpha values to 0% in the notecard will work as well, but will allow changing the transparency from the color menu.

The flame will default to white. You can either change this in the Color menu or in the notecard. Using the notecard is the preferred method. An example with candle-specific settings is included.

TEXTURES

Several textures have been included as a replacement for the default particle texture. Use them to improve the quality of candle flames, or as halo textures.

How to obtain a texture UUID: right-click on a texture in your inventory, choose "Copy Asset UUID" and paste it into the notecard.

How to preload a texture: apply the particle texture to a single face of your product, somewhere out of sight, so it will be loaded before you turn on the light.

TOOLS

In the Tools folder you will find the following scripts:

- Color converter: converts RGB colors to the format used in the notecard
- Face picker: identify face numbers by touch
- Remove floating text: removes floating text from examples

TROUBLESHOOTING: WHY DON'T I SEE ANY LIGHT?

- unless you have advanced lighting enabled, the viewer can only handle 6 light sources at a time, see the following forum post: http://community.secondlife.com/t5/LSL-Scripting/Light-script/m-p/1710339 #M13791
- description of switch prim and light prim(s) are not identical
- prim description was accidentally entered in name field
- incompatible script modes (linkset + region) are used together
- the nightlight plugin (turns off light during the day) is begin used

CONFIGURATION NOTECARD

The switch script uses a notecard (default name "config:Default") with some lesser-used, but powerful options. The notecard is optional. If not present, default values will be used as indicated below.

There can be up to 11 notecards. The naming convention is "config:Name". If you intend to use more than one notecard, set notecardMenu to YES. The "On/Off" button will be replaced by "Presets" and all available notecards will appear in a menu. For faster loading, remove whatever lines you don't need (do not remove "notecardMenu = YES").

In 1.7.2, the lightGroups parameter was added so the group feature can be turned off. If this parameter is set to NO, the prim description will be ignored and everything will be in one single group (one switch and one or more lights). None of the control scripts can be used in this setup.

The "baseIntensity" parameter requires some further explanation. When using many light sources in close proximity, you will be forced to lower the intensity in order to prevent light flooding, leaving you with very little flexibility. By setting the baseIntensity instead, you will maintain full control (0-100%) while the overall intensity is lower.

verbose = YES	<pre># show more/less info during startup</pre>
switchAccess = PUBLIC	# access level for switch (PUBLIC, GROUP, OWNER, GROUP+OWNER)
menuAccess = PUBLIC	# access level for menu (PUBLIC, GROUP, OWNER, GROUP+OWNER)
menuPercent = 10	<pre># increase/decrease percentage for +/- buttons</pre>
changePrimColor = YES	# YES = prim color changes with light color
changeParticleColor = YES	# YES = particle color changes with light color
particleTexture =	# texture UUID for particle effect
particleMenu = NO	# YES = "On/Off" replaced by "Particles" (particle menu)
notecardMenu = NO	# YES = "On/Off" replaced by "Presets" (notecard menu)
lightGroups = YES	# YES = use description for light groups, NO = ignore description

```
face = -1
                                # color/glow/fullbright on all faces (-1) or just one
baseIntensity = 100
                               # base percentage for light intensity
# Menu defaults
colorOn = < 100, 100, 100 > # color percentage (red, green, blue) when ON
colorOff = < 100, 100, 100 > \# color percentage (red, green, blue) when OFF
alphaOn = 100
                               # alpha percentage when ON
alphaOff = 100
                               # alpha percentage when OFF
intensity = 100
                               # light intensity percentage
radius = 50
                               # light radius percentage
                               # light falloff percentage
falloff = 40
glow = 0
                              # glow percentage
fullbright = YES
                               # fullbright when ON (YES or NO)
particleSize = 20
                               # size percentage for particle effect
# Link messages: in
msqNumber = 10957
                               # number part of incoming link messages
msgSwitch = switch
                               # string part of incoming link message: switch (on/off)
                               # string part of incoming link message: switch on
# string part of incoming link message: switch off
msgOn = on
msgOff = off
msgMenu = menu
                               # string part of incoming link message: show menu
# Link messages: out
                                # "On/Off" replaced by button text (sends link message)
extButton =
extNumber = 10958
                                # number part of outgoing link message
```

ACCESS CONTROL

Both switch and menu have 4 access levels: public, group, owner and group+owner. For example, you could have a public light switch with limited access to the menu so no one can mess with your settings.

Access levels:

PUBLIC = anyone GROUP = avatars with same active group as object OWNER = object owner GROUP+OWNER = group members and owner

SILENT STARTUP

Near the top of (almost) every script you will see the following line:

integer silent = FALSE; // silent startup

Even with verbose set to NO you will still see some whispers during startup. For a completely silent startup, set silent to TRUE.

CHANGE HISTORY

1.0, 01-08-2011:

- initial version

1.1, 30-04-2012:

- changed license from CC BY-SA to CC BY
- added license notecard, configuraton notecard and examples
- bugfix: light script not resetting on rez due to state change

1.2, 20-05-2012

- access control: owner, group, public

1.3, 02-02-2013

- added additonal permissions to license
- particle effects
- menu defaults

- enable/disable prim color

1.4, 24-02-2013

- optional particle menu

- particle texture
- enable/disable particle color

1.5, 31-03-2013

- textures

- moved "verbose" setting to notecard
- bugfix: particle resizing buttons not responding

1.5.1, 17-05-2013

- removed author name from configuration notecard

1.6, 31-05-2013

- link control (secondary switch for LINKSET mode)

- remote control (secondary switch for REGION mode)
- network control (control panel for multiple light groups)
- bugfix: link messages from plugins could bypass access control

1.6.1, 07-09-2013

- bugfix: initial particle size too small (minimum instead of default)

1.6.2, 24-12-2013

This is a bugfix release. All changes pertain to the network control and are the result of user feedback.

- added linkset version: region version is inconvenient for rentals

- removed access limitation (owner/group): inconvenient for rentals
- fixed node discovery: sometimes incomplete, depending on rez order

- fixed sorting of menu buttons

1.6.3, 12-01-2014

- added color converter (RGB to notecard format) in Tools folder
- cosmetic changes in network control

1.7, 24-01-2014

- support for up to 11 configuration notecards
- light control (light without bulbs)

- user-definable extension button

1.7.1, 21-03-2014

- configuration controls: configure individual light bulbs, store settings, save script memory
- bugfix: notecard menu not showing when menu is called from plugin
- bugfix: notecard menu pops up if object is touched before notecard has finished loading
- bugfix: changePrimColor/changeParticleColor = NO (notecard) using white, should be "off" color
- removed all debug code
- final code cleanup

1.7.2, 17-08-2014

- the use of light groups (prim description) can now be disabled in the notecard

1.7.3, 24-08-2014

- rounding error in config_control and ext_config_control

1.7.4, 05-10-2014

- slightly improved startup messages
- more efficient notecard loading

1.7.5, 01-01-2015

- access levels in notecard no longer require numbers
- new notecard option "baseIntensity": reduce overall intensity, yet maintain full control
 new notecard option "face": limit color/glow/fullbright to one single face
 added face picker in Tools folder