



## **JetFlex Genomic DNA Purification Kits**

**For fast and reliable purification of genomic  
DNA from blood, mammalian cells, tissue,  
buffy coat, and all types of body fluids**

**Cat. nos. 600100 and 600500**

**Rev. Date: 12 Aug 2010**  
**Manual part no.: 70-15019**

MAN0001744

**User Manual**



# Table of Contents

- Kit Contents and Storage .....iv
- Introduction..... 1**
  - System Overview ..... 1
  - Experimental Outline ..... 3
- Methods ..... 4**
  - General Information ..... 4
  - Purifying gDNA from Blood..... 6
  - Purifying gDNA from Mammalian Cells ..... 11
  - Purifying gDNA from Tissues ..... 15
  - Purifying gDNA from Body Fluids..... 18
  - Purifying gDNA from Swabs..... 23
  - Purifying gDNA from Bacteria ..... 27
  - Purifying gDNA from Yeast..... 31
  - Estimating DNA Yield ..... 35
  - Troubleshooting..... 36
- Appendix ..... 38**
  - Procedure for Pellet Compacting ..... 38
  - Purifying Impure DNA..... 39
  - Accessory Products ..... 40
  - Technical Support..... 41
  - Purchaser Notification ..... 42

# Kit Contents and Storage

---

## Types of Kits

This manual is supplied with the following products.

Product	Quantity	Cat. no.
JetFlex Genomic DNA Purification Kit	100	600 100
	500	600 500

---

## Intended Use

**For research use only.** Not intended for human or animal diagnostic or therapeutic uses.

---

## Shipping and Storage

Each kit is shipped at room temperature.

Upon receipt, store all buffers at room temperature and store all enzymes at 4°C.

**Note:** For long-term storage, aliquot RNase A in single use tubes and store at -20°C.

All components are guaranteed stable for 6 months when stored properly.

---

*Continued on next page*

## Kit Contents and Storage, Continued

### Kit Contents

The components included in the JetFlex genomic DNA (gDNA) Purification Kits are listed below.

Reagents	100 preps	500 preps
	600 100	600 500
Red Blood Cell Lysis Buffer (RBC)	33 mL	165 mL
Cell Lysis Buffer (CLB)	33 mL	165 mL
Protein Precipitation Buffer (PPT)	17 mL	83 mL
Pellet Compactor	8 mL	30 mL
DNA Dissolving Buffer (TE)	22 mL	110 mL
Proteinase K (lyophilized powder)	2 × 21 mg	10 × 21 mg
RNase A (4 mg/mL)	1 mL	5 × 1 mL



### Note

Sufficient reagents are included in the kit for 100 or 500 preparations. For larger starting sample volumes, the number of preparations will be decreased and for smaller starting sample volumes, the number of preparations per kit will be increased.

*Continued on next page*

## Kit Contents and Storage, Continued

---

### Buffer Composition

The composition of buffers included in the JetFlex gDNA Kits is listed below.

Buffer	Composition
Red Blood Cell Lysis Buffer	Proprietary Formulation
Cell Lysis Buffer	Proprietary Formulation
Protein Precipitation Buffer	Proprietary Formulation
Pellet Compactor	Proprietary Formulation
DNA Dissolving Buffer (TE)	10 mM Tris-HCl, 0.1 mM EDTA, pH 8.5
Proteinase K	Lyophilized powder
RNase A	4 mg/mL in 50 mM Tris- HCl, 10 mM EDTA, pH 8.0

---

# Introduction

## System Overview

---

### Introduction

The JetFlex Genomic DNA Purification Kits allow for the rapid and efficient purification of high quality, high molecular weight, RNA-free genomic DNA (gDNA). The kits are designed to efficiently isolate genomic DNA from mammalian cells and tissues, blood samples, plant tissue, bacteria, and yeast in a single tube without the use of spin columns or a vacuum manifold. The procedure is readily scaled up or down, making it adaptable for a wide variety of starting sample volumes. DNA up to 150 kb in size may be purified.

---

### System Summary

Genomic DNA is purified with the JetFlex gDNA Purification Kits by lysing nuclei with a cell lysis buffer and if necessary, treating the sample with RNase A and Proteinase K to degrade RNA and proteins. DNA is then precipitated under high salt conditions to remove impurities. Following ethanol removal, the DNA is redissolved in the DNA Dissolving Buffer (TE).

---

### Advantages

The advantages of using JetFlex Genomic DNA Purification Kits are:

- Efficient purification of genomic DNA up to 150 kb from a variety of samples such as mammalian cells and tissues, blood samples, body fluids, plant tissue, bacteria, and yeast
  - Rapid purification of high-quality DNA within 30 minutes without using any organic or toxic reagents
  - Minimal contamination from RNA
  - Reliable performance of the purified DNA in PCR, restriction enzyme digestion, and Southern blotting
- 

*Continued on next page*

## System Overview, Continued

### Sample treatment and DNA Yield

The table below lists the expected yield and necessary sample treatment according to the starting material.

Species & Material	Typical DNA yield	Proteinase K treatment	RNase A treatment	Page no.
Human Whole Blood <ul style="list-style-type: none"> <li>• 300 µL</li> <li>• 2 mL</li> <li>• 10 mL</li> <li>• 50 mL</li> </ul>	<ul style="list-style-type: none"> <li>• 5–10 µg</li> <li>• 50–100 µg</li> <li>• 250–500 µg</li> <li>• 1.25–2.5 mg</li> </ul>	Optional	Optional	6
Non-Mammalian Blood	2.5–7.5 mg/mL	Optional	Required	6
Cultured Cells	10–30 µg per $3 \times 10^6$ cells	Optional	Required	11
Animal Tissue	20–150 µg per 10 mg	Required	Required	15
Plant Tissue	10–15 µg per 40 mg	Required	Required	15
Body Fluids	2–50 µg/mL	Optional	Optional	18
Swabs (Buccal, Pharyngeal, Nasal, Vaginal, etc.)	0.5–3.5 µg	Optional	Optional	23
Gram-Negative Bacteria	20 µg/mL of culture	Optional	Required	27
Gram-Positive Bacteria	10 µg/mL of culture	Optional	Required	27
Yeast	5–7 µg/mL	No	Required	31



# Experimental Outline

---

## Introduction

The figure below illustrates the basic steps necessary to use the kit.



Collect sample and pretreat as directed for blood, swabs, tissue, bacteria, and yeast



Add 300  $\mu$ L Cell Lysis Buffer



Optional: Treat sample with Proteinase K and RNase A



Add 150  $\mu$ L Protein Precipitation Buffer



Add an equal volume of isopropanol to the supernatant



Wash DNA pellet with 1 mL 70% Ethanol



Air dry the pellet and resuspend with DNA Dissolving Buffer (TE)

# Methods

## General Information

---



Follow the recommendations below to obtain the best results:

- Maintain a sterile environment when handling DNA to avoid any contamination from DNases and ensure that no DNases are introduced into the sterile solutions of the kit
  - Make sure all equipment that comes in contact with DNA is sterile, including pipette tips and microcentrifuge tubes
  - To minimize DNA degradation, perform lysate preparation steps quickly, and avoid repeated freezing and thawing of DNA samples
  - Perform all centrifugation steps at room temperature
  - Incubate sample overnight with DNA Dissolving Buffer
- 

## Safety Information

Follow the safety guidelines below when using the kit.

- Treat all reagents supplied in the kit as potential irritants.
  - Wear a suitable lab coat, disposable gloves, and goggles.
  - Handle all blood and tissue samples in compliance with established institutional guidelines and take the appropriate precautions (wear a laboratory coat, disposable gloves, and eye protection). Since safety requirements for use and handling of blood and tissue samples may vary at individual institutions, consult the health and safety guidelines and/or officers at your institution.
  - When processing blood and tissue samples, dispose of the waste appropriately as biohazardous waste.
- 

*Continued on next page*

## General Information, Continued

---

### **Before Starting**

Resuspend Proteinase K in double-distilled or Milli-Q<sup>®</sup>-grade water to a final concentration of 20 mg/mL. Store the reconstituted enzyme in single-use aliquots at -20°C. Avoid repeated freezing and thawing.

---

Milli-Q<sup>®</sup> is a registered trademark of Millipore Corporation

# Purifying gDNA from Blood

---

## Starting Sample

JetFlex Genomic DNA Purification Kits are designed to purify genomic DNA from fresh or frozen whole blood, or buffy coat samples which may be collected in the presence of anti-coagulants such as EDTA, heparin, or citrate. Since EDTA also reduces DNA degradation, EDTA is the optimal anti-coagulant.

To obtain high-quality genomic DNA, follow the guidelines recommended on page 4.

---

## Materials Needed

- Sample for DNA isolation
- Sterile, DNase-free microcentrifuge tubes (for small preparations) or sterile, DNase-free 15 mL or 50 mL tubes (for larger sample preparation)
- Vortex mixer (multi-tube vortexer recommended)
- Water baths or heat blocks
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

*Components supplied with the kit*

- Red Blood Cell Lysis Buffer (RBC)
  - Cell Lysis Buffer (CLB)
  - Proteinase K (lyophilized powder, see **Before Starting**, page 5)
  - RNase A (4 mg/mL)
  - Protein Precipitation Buffer (PPT)
  - DNA Dissolving Buffer (TE)
- 

*Continued on next page*

# Purifying gDNA from Blood, Continued

---

## Preparing Blood Lysate

Prepare lysate from blood samples as described below.

1. Add fresh or frozen blood or buffy coat to an equal volume of RBC Lysis Buffer. Common starting volumes are shown in the table below.

Starting Sample Vol.	RBC Lysis Buffer Vol.
300 $\mu$ L	300 $\mu$ L
2 mL	2 mL
10 mL	10 mL
50 mL	50 mL

2. Mix well by inverting the tube until the mixture is homogenous.

**Note:** If the blood sample is fresh (drawn within 1 hour), incubate at room temperature for one minute to ensure complete lysis of erythrocytes.

3. Centrifuge the sample according to the conditions in the table.

Centrifugation Conditions	Starting Sample Vol. 300 $\mu$ L	Starting Sample Vol. $\geq$ 2 mL
Acceleration	12,000 $\times$ g	2,000 $\times$ g
Time	30 seconds	10 minutes

4. Remove the red supernatant, leaving behind a pellet of DNA-containing white blood cells. Bump vortex the white cell pellet vigorously to loosen the cells from the wall, which enhances cell lysis (next step).

---

*Continued on next page*

# Purifying gDNA from Blood, Continued

---

## Preparing Blood Lysate, Continued

5. Add an equal volume of Cell Lysis Buffer (CLB) to the disrupted cell pellet (i.e., for a 300  $\mu$ L starting sample, add 300  $\mu$ L CLB). Lyse the cells by pipetting up and down.

**Note:** Usually no incubation is required. However, if cell clumps are visible after mixing, incubate at 37°C or room temperature until the lysate is homogeneous and clear. Samples are stable in CLB for several months at room temperature.

6. *Optional:* For every 300  $\mu$ L starting sample volume, add 20  $\mu$ L Proteinase K. Incubate at 58°C for 1 hour to overnight until the mixture is clear, indicating complete lysis.

**Note:** The optional Proteinase K digestion is necessary if the blood sample is partially or completely clotted.

7. *Optional:* For every 300  $\mu$ L starting sample volume, add 1.5  $\mu$ L RNase A (i.e., add 1  $\mu$ L RNase A to a 200  $\mu$ L starting sample). Incubate at 37°C for 5 minutes.
8. Allow the lysate to cool to room temperature and then proceed directly to **Purifying gDNA**, next page.

---

*Continued on next page*

# Purifying gDNA from Blood, Continued

---

## Purifying gDNA

The following procedure is for purifying DNA from 300  $\mu$ L blood lysate. To purify DNA from different starting sample volumes, scale up or down the buffer and reagent volumes proportionately.

1. Add 150  $\mu$ L Protein Precipitation Buffer (PPT) to 300  $\mu$ L of blood lysate from Step 8, previous page.
2. Mix thoroughly by vortexing for 20 seconds until a homogenous suspension is obtained.
3. Centrifuge at 12,000  $\times g$  for 3 minutes at room temperature.

**Note:** The precipitated proteins form a compact pellet and the supernatant should be clear. If the protein pellet is loose or insignificant, proceed to **Procedure for Pellet Compacting**, page 38.

4. Transfer the supernatant into a clean, sterile microcentrifuge tube.
5. Add an equal volume of isopropanol. Mix thoroughly by inverting the tube until the mixture is homogenous. Do not vortex.
6. Centrifuge at 12,000  $\times g$  for 3 minutes at room temperature.

**Note:** The precipitated DNA is visible as a white pellet.

7. Decant the supernatant. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
8. Add 1 mL 70% ethanol and wash the DNA pellet by inverting the tube several times.
9. Centrifuge at 12,000  $\times g$  for 1 minute at room temperature.

10. Carefully decant the supernatant.

**Note:** Be careful not to discard the DNA as the DNA pellet may be loosely adherent to the tube.

11. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.

---

*Continued on next page*

# Purifying gDNA from Blood, Continued

---

## Purifying gDNA, Continued

12. Evaporate residual ethanol by incubating the sample at 50 °C to 55°C for 10 minutes.

**Note:** If desired, you may evaporate residual ethanol at room temperature, but in this case, increase the incubation time.

13. After ethanol evaporation is complete (i.e., DNA pellet appears dry and the ethanol odor is undetectable), resuspend the DNA pellet in a suitable volume of DNA Dissolving Buffer (TE).
14. Incubate the tube at room temperature overnight or at 65°C for up to one hour to completely resuspend the DNA.

The DNA should be completely dissolved as a clear, colorless solution. If precipitates are present, the  $A_{260}/A_{280}$  ratio is  $<1.70$ , or the DNA is contaminated with buffer, protein, or RNA, re-purify the DNA sample (see **Purifying Impure DNA**, page 39).

---

## Storing DNA

To avoid repeated freezing and thawing of DNA,

- Store the purified DNA at 4°C for immediate use or
  - Aliquot the DNA and store at -20°C for long-term storage.
-



# Purifying gDNA from Mammalian Cells

---

## Introduction

The JetFlex Genomic DNA Purification Kits are designed to purify genomic DNA from  $1-2 \times 10^6$  to  $1-2 \times 10^7$  mammalian cells.

To obtain high-quality genomic DNA, follow the guidelines recommended on page 4.

---

## Materials Needed

- Sample for DNA isolation
- Phosphate Buffered Saline (PBS), see page 40 for ordering information
- Sterile, DNase-free microcentrifuge tubes (for small preparations) or sterile, DNase-free 15 mL or 50 mL tubes (for larger sample preparation)
- Vortex mixer (multi-tube vortexer recommended)
- Water baths or heat blocks
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

*Components supplied with the kit*

- Cell Lysis Buffer (CLB)
  - Proteinase K (lyophilized powder, see **Before Starting**, page 5)
  - RNase A (4 mg/mL)
  - Protein Precipitation Buffer (PPT)
  - DNA Dissolving Buffer (TE)
- 

*Continued on next page*

# Purifying gDNA from Mammalian Cells,

## Continued

### Preparing Cell Lysate

Place cells on ice immediately before processing.

1. Collect  $1-2 \times 10^6$  to  $1-2 \times 10^7$  cells in a balanced salt solution (i.e., PBS).
2. Centrifuge the cells according to the conditions in the table.

Centrifugation Conditions	Starting Sample $1-2 \times 10^6$ cells	Starting Sample $1-2 \times 10^7$ cells
Acceleration	$12,000 \times g$	$2,000 \times g$
Time	15 seconds	2 minutes

3. Remove the supernatant.
4. Add Cell Lysis Buffer (CLB) to the disrupted cell pellet.

Starting Cell Count	Buffer CLB
$1-2 \times 10^6$	300 $\mu$ L
$1-2 \times 10^7$	3 mL

5. Lyse the cells by pipetting up and down.

**Note:** Usually no incubation is required. However, if cell clumps are visible after mixing, incubate at  $58^\circ\text{C}$  until the lysate is homogeneous and clear. Samples are stable in CLB for several months at room temperature.

6. *Optional:* Add Proteinase K (20 mg/mL). Incubate at  $58^\circ\text{C}$  for 1 hour to overnight until the mixture is clear, indicating complete lysis.

Starting Cell Count	Proteinase K
$1-2 \times 10^6$	20 $\mu$ L
$1-2 \times 10^7$	200 $\mu$ L

*Continued on next page*

# Purifying gDNA from Mammalian Cells, Continued

## Preparing Cell Lysate, Continued

7. Add RNase A. Incubate at 37°C for 5 minutes.

Starting Cell Count	RNase A
$1-2 \times 10^6$	10 $\mu$ L
$1-2 \times 10^7$	100 $\mu$ L

8. Allow the lysate to cool to room temperature and then proceed directly to **Purifying gDNA**, below.

## Purifying gDNA

The following procedure is for purifying DNA from 300  $\mu$ L cellular lysate. To purify DNA from a different starting sample volume, scale up or down the buffer and reagent volumes proportionately.

1. Add 150  $\mu$ L Protein Precipitation Buffer (PPT) to 300  $\mu$ L of cellular lysate from Step 8, above.
2. Mix thoroughly by vortexing for 20 seconds until a homogenous suspension is obtained.
3. Centrifuge at  $12,000 \times g$  for 3 minutes at room temperature.

**Note:** The precipitated proteins form a compact pellet and the supernatant should be clear. If the protein pellet is loose or insignificant, proceed to **Procedure for Pellet Compacting**, page 38.

4. Transfer the supernatant into a clean, sterile microcentrifuge tube.
5. Add an equal volume of isopropanol. Mix thoroughly by inverting the tube until the mixture is homogenous. Do not vortex.
6. Centrifuge at  $12,000 \times g$  for 3 minutes at room temperature.

**Note:** The precipitated DNA is visible as a white pellet.

*Continued on next page*

# Purifying gDNA from Mammalian Cells, Continued

## Purifying gDNA, Continued

- 
7. Decant the supernatant. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
  8. Add 1 mL 70% ethanol and wash the DNA pellet by inverting the tube several times.
  9. Centrifuge at  $12,000 \times g$  for 1 minute at room temperature.
  10. Carefully decant the supernatant.  
**Note:** Be careful not to discard the DNA as the DNA pellet may be loosely adherent to the tube.
  11. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
  12. Evaporate residual ethanol by incubating the sample at 50 °C to 55°C for 10 minutes.  
**Note:** If desired, you may evaporate residual ethanol at room temperature, but in this case, increase the incubation time.
  13. After ethanol evaporation is complete (i.e., DNA pellet appears dry and the ethanol odor is undetectable), resuspend the DNA pellet in a suitable volume of DNA Dissolving Buffer (TE).
  14. Incubate the tube at room temperature overnight or at 65°C for up to one hour to completely resuspend the DNA.  
The DNA should be completely dissolved as a clear, colorless solution. If precipitates are present, the  $A_{260}/A_{280}$  ratio is  $<1.70$ , or the DNA is contaminated with buffer, protein, or RNA, re-purify the DNA sample (see **Purifying Impure DNA**, page 39).
- 

## Storing DNA

To avoid repeated freezing and thawing of DNA,

- Store the purified DNA at 4°C for immediate use or
  - Aliquot the DNA and store at -20°C for long-term storage.
-

# Purifying gDNA from Tissues

---

## Introduction

The JetFlex Genomic DNA Purification Kits are designed to purify genomic DNA from fresh, frozen, fixed, or paraffin-embedded animal (including mouse tail) and plant tissues. To obtain high-quality genomic DNA, follow the guidelines recommended on page 4.

---

## Materials Needed

- Sample for DNA isolation
- Sterile, DNase-free microcentrifuge tubes (for small preparations) or sterile, DNase-free 15 mL or 50 mL tubes (for larger sample preparation)
- Vortex mixer (multi-tube vortexer recommended)
- Water baths or heat blocks
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

### *Components supplied with the kit*

- Cell Lysis Buffer (CLB)
  - Proteinase K (lyophilized powder, see **Before Starting**, page 5)
  - RNase A (4 mg/mL)
  - Protein Precipitation Buffer (PPT)
  - DNA Dissolving Buffer (TE)
- 

*Continued on next page*

# Purifying gDNA from Tissues, Continued

---

## Preparing Tissue Lysate

The following procedure is for purifying DNA from up to 10 mg fresh, frozen, fixed, or paraffin-embedded tissue sample. To purify DNA from a larger tissue sample, scale up the buffer and reagent volumes proportionately.

1. Grind the tissue sample in liquid nitrogen with mortar and pestle. Keep the sample on ice to minimize DNase activity.
  2. Add 300  $\mu$ L Cell Lysis Buffer (CLB) to the tissue sample.  
**Note:** *Optional:* Homogenize the sample thoroughly using 30–50 strokes with a tube pestle.
  3. Add 20  $\mu$ L Proteinase K. Incubate at 58°C for 1 hour to overnight until the mixture is clear, indicating complete lysis.
  4. Add 10  $\mu$ L RNase A. Incubate at 37°C for 5 minutes.
  5. Allow the lysate to cool to room temperature and then proceed directly to **Purifying gDNA**, below.
- 

## Purifying gDNA

1. Add 150  $\mu$ L Protein Precipitation Buffer (PPT) to 300  $\mu$ L of tissue lysate from Step 5, above.
  2. Mix thoroughly by vortexing for 20 seconds until a homogenous suspension is obtained.
  3. Centrifuge at 12,000  $\times g$  for 3 minutes at room temperature.  
**Note:** The precipitated proteins form a compact pellet and the supernatant should be clear. If the protein pellet is loose or insignificant, proceed to **Procedure for Pellet Compacting**, page 38.
  4. Transfer the supernatant into a clean, sterile microcentrifuge tube.
  5. Add an equal volume of isopropanol. Mix thoroughly by inverting the tube until the mixture is homogenous. Do not vortex.
- 

*Continued on next page*

# Purifying gDNA from Tissues, Continued

---

## Purifying gDNA, Continued

6. Centrifuge at  $12,000 \times g$  for 3 minutes at room temperature.  
**Note:** The precipitated DNA is visible as a white pellet.
  7. Decant the supernatant. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
  8. Add 1 mL 70% ethanol and wash the DNA pellet by inverting the tube several times.
  9. Centrifuge at  $12,000 \times g$  for 1 minute at room temperature.
  10. Carefully decant the supernatant.  
**Note:** Be careful not to discard the DNA as the DNA pellet may be loosely adherent to the tube.
  11. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
  12. Evaporate residual ethanol by incubating the sample at  $50^\circ\text{C}$  to  $55^\circ\text{C}$  for 10 minutes.  
**Note:** If desired, you may evaporate residual ethanol at room temperature, but in this case, increase the incubation time.
  13. After ethanol evaporation is complete (i.e., DNA pellet appears dry and the ethanol odor is undetectable), resuspend the DNA pellet in a suitable volume of DNA Dissolving Buffer (TE).
  14. Incubate the tube at room temperature overnight or at  $65^\circ\text{C}$  for up to one hour to completely resuspend the DNA.  
The DNA should be completely dissolved as a clear, colorless solution. If precipitates are present, the  $A_{260}/A_{280}$  ratio is  $<1.70$ , or the DNA is contaminated with buffer, protein, or RNA, re-purify the DNA sample (see **Purifying Impure DNA**, page 39).
- 

## Storing DNA

To avoid repeated freezing and thawing of DNA,

- Store the purified DNA at  $4^\circ\text{C}$  for immediate use or
  - Aliquot the DNA and store at  $-20^\circ\text{C}$  for long-term storage.
-

# Purifying gDNA from Body Fluids

---

## Introduction

JetFlex Genomic DNA Purification Kits are designed to purify genomic DNA from body fluids such as plasma, saliva, serum, milk, urine, cerebrospinal fluid, and sputum. To obtain high-quality genomic DNA, follow the guidelines recommended on page 4.

---

## Materials Needed

- Sample for DNA isolation
- Sterile, DNase-free microcentrifuge tubes (for small preparations) or sterile, DNase-free 15 mL or 50 mL tubes (for larger sample preparation)
- Vortex mixer (multi-tube vortexer recommended)
- Water baths or heat blocks
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

### *Components supplied with the kit*

- Cell Lysis Buffer (CLB)
  - Proteinase K (lyophilized powder, see page 5)
  - RNase A (4 mg/mL)
  - Protein Precipitation Buffer (PPT)
  - DNA Dissolving Buffer (TE)
- 

*Continued on next page*



# Purifying gDNA from Body Fluids, Continued

---

## Preparing Concentrated Lysates

1. If the body fluid sample is dilute or has few DNA-containing cells, concentrate the cells by centrifugation according to the conditions listed in the table below.

Centrifugation Conditions	Starting Sample Volume $\leq 1.5$ mL	Starting Sample Volume $> 1.5$ mL
Acceleration	$12,000 \times g$	$5,000 \times g$
Time	30 seconds	2 minutes

2. Following centrifugation, aspirate the supernatant and resuspend the cell pellet in PBS using the volumes listed in the table below.

Starting Volume	PBS
$\leq 1.5$ mL	200 $\mu$ L
$> 1.5$ mL	3–10 mL

3. Proceed directly to **Preparing Body Fluid Lysate**, next page.

---

*Continued on next page*

# Purifying gDNA from Body Fluids, Continued

---

## Preparing Body Fluid Lysate

1. Add 5 volumes of Cell Lysis Buffer (CLB) to 1 volume of body fluid (i.e., add 250  $\mu$ L CLB to 50  $\mu$ L body fluid). Lyse the cells immediately by pipetting up and down.  
**Note:** Samples may be fresh or frozen and may contain cellular debris. If the sample has a high protein content, increase the CLB ratio to 11:1 (i.e., 550  $\mu$ L CLB for a 50  $\mu$ L body fluid sample).
2. Incubate at 58°C until the lysate is homogeneous and clear.
3. *Optional:* Add 1  $\mu$ L Proteinase K for every 2.5  $\mu$ L of starting body fluid (i.e., add 20  $\mu$ L Proteinase K to a 50  $\mu$ L body fluid starting sample).
4. Incubate at 58°C for 1 hour to overnight until the mixture is clear, indicating complete lysis.  
**Note:** If any cellular debris or particulate matter is still present after lysis, centrifuge the sample and transfer the clear supernatant to a clean tube.
5. *Optional:* Add 1  $\mu$ L RNase A for every 5  $\mu$ L starting sample volume, (i.e., add 10  $\mu$ L RNase A to a 50  $\mu$ L body fluid starting sample). Incubate at 37°C for 5 minutes.
6. Allow the lysate to cool to room temperature and then proceed directly to **Purifying gDNA**, next page.

---

*Continued on next page*

# Purifying gDNA from Body Fluids, Continued

---

## Purifying gDNA

The following procedure is for purifying DNA from 300  $\mu$ L cellular lysate. To purify DNA from a different starting sample volume, scale up or down the buffer and reagent volumes proportionately.

1. Add 150  $\mu$ L Protein Precipitation Buffer (PPT) to 300  $\mu$ L of cellular lysate from Step 6, previous page.
2. Mix thoroughly by vortexing for 20 seconds until a homogenous suspension is obtained.
3. Centrifuge at 12,000  $\times g$  for 3 minutes at room temperature.

**Note:** The precipitated proteins form a compact pellet and the supernatant should be clear. If the protein pellet is loose or insignificant, proceed to **Procedure for Pellet Compacting**, page 38.

4. Transfer the supernatant into a clean, sterile microcentrifuge tube.
  5. Add an equal volume of isopropanol. Mix thoroughly by inverting the tube until the mixture is homogenous. Do not vortex.
  6. Centrifuge at 12,000  $\times g$  for 3 minutes at room temperature.
- Note:** The precipitated DNA is visible as a white pellet.
7. Decant the supernatant. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
  8. Add 1 mL 70% ethanol and wash the DNA pellet by inverting the tube several times.
  9. Centrifuge at 12,000  $\times g$  for 1 minute at room temperature.

10. Carefully decant the supernatant.

**Note:** Be careful not to discard the DNA as the DNA pellet may be loosely adherent to the tube.

---

*Continued on next page*

# Purifying gDNA from Body Fluids, Continued

---

## Purifying gDNA, Continued

11. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
12. Evaporate residual ethanol by incubating the sample at 50 °C to 55°C for 10 minutes.  
**Note:** If desired, you may evaporate residual ethanol at room temperature, but in this case, increase the incubation time.
13. After ethanol evaporation is complete (i.e., DNA pellet appears dry and the ethanol odor is undetectable), resuspend the DNA pellet in a suitable volume of DNA Dissolving Buffer (TE).
14. Incubate the tube at room temperature overnight or at 65°C for up to one hour to completely resuspend the DNA.

The DNA should be completely dissolved as a clear, colorless solution. If precipitates are present, the  $A_{260}/A_{280}$  ratio is  $<1.70$ , or the DNA is contaminated with buffer, protein, or RNA, re-purify the DNA sample (see **Purifying Impure DNA**, page 39).

---

## Storing DNA

To avoid repeated freezing and thawing of DNA,

- Store the purified DNA at 4°C for immediate use or
  - Aliquot the DNA and store at -20°C for long-term storage.
-

# Purifying gDNA from Swabs

---

## Introduction

The JetFlex Genomic DNA Purification Kits are designed to purify genomic DNA from swabs, including buccal, pharyngeal, nasal, and vaginal.

To obtain high-quality genomic DNA, follow the guidelines recommended on page 4.

---

## Materials Needed

- Sample for DNA isolation
- Sterile, DNase-free microcentrifuge tubes (for small preparations) or sterile, DNase-free 15 mL or 50 mL tubes (for larger sample preparation)
- Vortex mixer (multi-tube vortexer recommended)
- Water baths or heat blocks
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

### *Components supplied with the kit*

- Cell Lysis Buffer (CLB)
  - Proteinase K (lyophilized powder, see **Before Starting**, page 5)
  - RNase A (4 mg/mL)
  - Protein Precipitation Buffer (PPT)
  - DNA Dissolving Buffer (TE)
- 

*Continued on next page*

# Purifying gDNA from Swabs, Continued

---

## Preparing Swab Lysate

1. Collect the buccal swab with a suitable tool, such as a T-swab Kit, Dacron swab, C.E.P. Omni swab, or Cotton swab according to standard collection procedures. Nasal, pharyngeal, or vaginal swabs can be collected in a similar manner.
2. Set a water bath or heat block at 58°C.
3. Place the buccal swab into a capped 2 mL microcentrifuge tube (not provided with the kit).
  - For C.E.P. Omni swabs, press the stem end towards the swab to eject it into the microcentrifuge tube.
  - For swabs from other suppliers, snap or cut the swab at the break point.

The swab should fit entirely inside the tube so that the cap may close.
4. Pipet 300  $\mu$ L Cell Lysis Buffer (CLB) into a 1.5 mL reaction tube. Dip the collection brush into the CLB aliquot and rotate the swab 10–20 times to release as many cells as possible. Squeeze out the swab against the wall of the tube to recover the maximum amount of liquid.
5. Incubate at 58°C until the lysate is homogeneous and clear, vortexing the sample periodically to facilitate lysis.
6. *Optional:* Add 10  $\mu$ L Proteinase K. Incubate at 58°C for 30 minutes to overnight until the mixture is clear, indicating complete lysis.
7. *Optional:* Add 10  $\mu$ L RNase A. Incubate at 37°C for 5 minutes.
8. Allow the lysate to cool to room temperature and then proceed directly to **Purifying gDNA**, next page.

---

*Continued on next page*

# Purifying gDNA from Swabs, Continued

---

## Purifying gDNA

1. Add 150  $\mu$ L Protein Precipitation Buffer (PPT) to 300  $\mu$ L of swab lysate from Step 8, previous page.
2. Mix thoroughly by vortexing for 20 seconds until a homogenous suspension is obtained.
3. Centrifuge at  $12,000 \times g$  for 3 minutes at room temperature.  
**Note:** The precipitated proteins form a compact pellet and the supernatant should be clear. If the protein pellet is loose or insignificant, proceed to **Procedure for Pellet Compacting**, page 38.
4. Transfer the supernatant into a clean, sterile microcentrifuge tube.
5. Add an equal volume of isopropanol. Mix thoroughly by inverting the tube until the mixture is homogenous. Do not vortex.
6. Centrifuge at  $12,000 \times g$  for 3 minutes at room temperature.  
**Note:** The precipitated DNA is visible as a white pellet.
7. Decant the supernatant. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
8. Add 1 mL 70% ethanol and wash the DNA pellet by inverting the tube several times.
9. Centrifuge at  $12,000 \times g$  for 1 minute at room temperature.
10. Carefully decant the supernatant.  
**Note:** Be careful not to discard the DNA as the DNA pellet may be loosely adherent to the tube.
11. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.

---

*Continued on next page*

# Purifying gDNA from Swabs, Continued

---

## Purifying gDNA, Continued

12. Evaporate residual ethanol by incubating the sample at 50 °C to 55°C for 10 minutes.

**Note:** If desired, you may evaporate residual ethanol at room temperature, but in this case, increase the incubation time.

13. After ethanol evaporation is complete (i.e., DNA pellet appears dry and the ethanol odor is undetectable), resuspend the DNA pellet in a suitable volume of DNA Dissolving Buffer (TE).
14. Incubate the tube at room temperature overnight or at 65°C for up to one hour to completely resuspend the DNA.

The DNA should be completely dissolved as a clear, colorless solution. If precipitates are present, the  $A_{260}/A_{280}$  ratio is  $<1.70$ , or the DNA is contaminated with buffer, protein, or RNA, re-purify the DNA sample (see **Purifying Impure DNA**, page 39).

---

## Storing DNA

To avoid repeated freezing and thawing of DNA,

- Store the purified DNA at 4°C for immediate use or
  - Aliquot the DNA and store at -20°C for long-term storage.
-



# Purifying gDNA from Bacteria

---

## Introduction

The JetFlex Genomic DNA Purification Kits are designed to purify genomic DNA from bacterial cultures.

To obtain high-quality genomic DNA, follow the guidelines recommended on page 4.

---

## Materials Needed

- Sample for DNA isolation
- Lysozyme, 2 mg/mL, in 50 mM Tris-HCl, pH 8.0, 10 mM EDTA buffer (for gram-positive bacteria only)
- Lysozyme, 2 mg/mL, and Lysostaphin, 1 mg/mL, in 50 mM Tris-HCl, pH 8.0, 10 mM EDTA buffer (for *Staphylococcus* only)
- Sterile, DNase-free microcentrifuge tubes (for small preparations) or sterile, DNase-free 15 mL or 50 mL tubes (for larger sample preparation)
- Vortex mixer (multi-tube vortexer recommended)
- Water baths or heat blocks
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

*Components supplied with the kit*

- Cell Lysis Buffer (CLB)
  - Proteinase K (lyophilized powder, see **Before Starting**, page 5)
  - RNase A (4 mg/mL)
  - Protein Precipitation Buffer (PPT)
  - DNA Dissolving Buffer (TE)
- 

*Continued on next page*

# Purifying gDNA from Bacteria, Continued

## Preparing Bacterial Lysate

---

The following procedure is for purifying gDNA from a 500  $\mu$ L culture sample. To purify DNA from a larger sample, scale up the buffer and reagent volumes proportionately.

1. Collect 500  $\mu$ L of an overnight bacterial culture into a 1.5 mL microcentrifuge tube.
2. Centrifuge the sample at  $12,000 \times g$  for 1 minute. Remove the supernatant.
3. For gram-negative bacteria, proceed directly to Step 4. For gram-positive bacteria, disrupt cell walls with enzymatic pretreatment:
  - a. Resuspend the cells in 300  $\mu$ L 50 mM Tris-HCl, pH 8.0, 10 mM EDTA, 2 mg/mL lysozyme.  
**Note:** For *Staphylococcus*, add 1 mg/mL lysostaphin to the 50 mM Tris-HCl, pH 8.0, 10 mM EDTA, 2 mg/mL lysozyme buffer.
  - b. Mix thoroughly and incubate for 30 minutes at 37°C.
  - c. Centrifuge for 1 minute at  $12,000 \times g$  (or at  $2,000 \times g$  for 5 minutes, for cultures  $>500 \mu$ L).
  - d. Remove the supernatant and proceed to Step 4..
4. Add 300  $\mu$ L Cell Lysis Buffer (CLB) to the bacterial pellet.
5. Lyse the cells by pipetting up and down.  
**Note:** Usually no incubation is required. However, if cell clumps are visible after mixing, incubate at 58°C until the lysate is homogeneous and clear. Samples are stable in CLB for several months at room temperature.
6. *Optional:* Add 10  $\mu$ L Proteinase K. Incubate at 58°C for 30 minutes to overnight until the mixture is clear, indicating complete lysis.
7. Add 10  $\mu$ L RNase A. Incubate at 37°C for 5 minutes.
8. Allow the lysate to cool to room temperature and then proceed directly to **Purifying gDNA**, next page.

---

*Continued on next page*

# Purifying gDNA from Bacteria, Continued

---

## Purifying gDNA

1. Add 150  $\mu$ L Protein Precipitation Buffer (PPT) to 300  $\mu$ L of bacterial lysate from Step 8, previous page.
2. Mix thoroughly by vortexing for 20 seconds until a homogenous suspension is obtained.
3. Centrifuge at  $12,000 \times g$  for 3 minutes at room temperature.  
**Note:** The precipitated proteins form a compact pellet and the supernatant should be clear. If the protein pellet is loose or insignificant, proceed to **Procedure for Pellet Compacting**, page 38.
4. Transfer the supernatant into a clean, sterile microcentrifuge tube.
5. Add an equal volume of isopropanol. Mix thoroughly by inverting the tube until the mixture is homogenous. Do not vortex.
6. Centrifuge at  $12,000 \times g$  for 3 minutes at room temperature.  
**Note:** The precipitated DNA is visible as a white pellet.
7. Decant the supernatant. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
8. Add 1 mL 70% ethanol and wash the DNA pellet by inverting the tube several times.
9. Centrifuge at  $12,000 \times g$  for 1 minute at room temperature.
10. Carefully decant the supernatant.  
**Note:** Be careful not to discard the DNA as the DNA pellet may be loosely adherent to the tube.
11. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.

---

*Continued on next page*

# Purifying gDNA from Bacteria, Continued

---

## Purifying gDNA, Continued

12. Evaporate residual ethanol by incubating the sample at 50 °C to 55°C for 10 minutes.

**Note:** If desired, you may evaporate residual ethanol at room temperature, but in this case, increase the incubation time.

13. After ethanol evaporation is complete (i.e., DNA pellet appears dry and the ethanol odor is undetectable), resuspend the DNA pellet in a suitable volume of DNA Dissolving Buffer (TE).

14. Incubate the tube at room temperature overnight or at 65°C for up to one hour to completely resuspend the DNA.

The DNA should be completely dissolved as a clear, colorless solution. If precipitates are present, the  $A_{260}/A_{280}$  ratio is  $<1.70$ , or the DNA is contaminated with buffer, protein, or RNA, re-purify the DNA sample (see **Purifying Impure DNA**, page 39).

---

## Storing DNA

To avoid repeated freezing and thawing of DNA,

- Store the purified DNA at 4°C for immediate use or
  - Aliquot the DNA and store at -20°C for long-term storage.
-

# Purifying gDNA from Yeast

---

## Introduction

The JetFlex Genomic DNA Purification Kits are designed to purify genomic DNA from yeast cultures.

To obtain high-quality genomic DNA, follow the guidelines recommended on page 4.

---

## Materials Needed

- Sample for DNA isolation
- Buffer YS1, see below for recipe
- Zymolyase
- Sterile, DNase-free microcentrifuge tubes (for small preparations) or sterile, DNase-free 15 mL or 50 mL tubes (for larger sample preparation)
- Vortex mixer (multi-tube vortexer recommended)
- Water baths or heat blocks
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

*Components supplied with the kit*

- Cell Lysis Buffer (CLB)
  - Proteinase K (lyophilized powder, see **Before Starting**, page 5)
  - RNase A (4 mg/mL)
  - Protein Precipitation Buffer (PPT)
  - DNA Dissolving Buffer (TE)
- 

## Buffer YS1

Prepare Buffer YS1:

0.9 M sorbitol

0.1 M EDTA, pH 7.5

14 mM  $\beta$ -mercaptoethanol

---

*Continued on next page*

# Purifying gDNA from Yeast, Continued

---

## Prepare Zymolyase

Preparing the cell lysate includes an incubation step with Zymolyase (see Step 5, below). Zymolyase digests cell walls of yeast cells enzymatically during incubation. An equivalent enzyme to Zymolyase is Lyticase (Sigma, Cat. No. L2524). Dilute Zymolyase or Lyticase in distilled water to a final concentration of 1,000 U/mL. Store stock solutions of both enzymes in aliquots at  $-20^{\circ}\text{C}$  and use only once.

---

## Preparing Yeast Cell Lysate

The following procedure is for purifying gDNA from a 1 mL culture sample. To purify DNA from a larger sample, scale up the buffer and reagent volumes proportionately.

1. Grow the *Saccharomyces* (or any other yeast) culture to saturation in YPD or YEPD to a final concentration of  $1-2 \times 10^8$  cells/mL.
2. Harvest 1 mL of the yeast culture by centrifugation at  $12,000 \times g$  for 1 minute. Discard the supernatant.  
**Note:** For  $>1$  mL – 10 mL yeast culture samples, centrifuge at  $2,000 \times g$  for 3 minutes.
3. Wash the cells in 300  $\mu\text{L}$  Buffer YS1.
4. Centrifuge again at  $12,000 \times g$  for 1 minute. Discard the supernatant. Resuspend the cells in 1 mL Buffer YS1.
5. Add 10  $\mu\text{L}$  Zymolyase or Lyticase (1,000 U/mL) and incubate at  $37^{\circ}\text{C}$  for 30 minutes.

**Note:** Monitor spheroplast formation by examining detergent sensitivity: dilute a small sample of cells in 1% SDS. Spheroplasting is sufficient when greater than 90% of the cells burst when examined under the microscope.

6. Centrifuge the spheroplasts at  $12,000 \times g$  for 1 minute. Discard the supernatant.
7. Add 300  $\mu\text{L}$  Cell Lysis Buffer (CLB) to the yeast pellet.

---

*Continued on next page*

# Purifying gDNA from Yeast, Continued

---

## Preparing Lysate, Continued

8. Lyse the spheroplasts by pipetting up and down.  
**Note:** Usually no incubation is required. However, if cell clumps are visible after mixing, incubate at 58°C until the lysate is homogeneous and clear. Samples are stable in CLB for several months at room temperature.
  9. Add 10  $\mu$ L RNase A. Incubate at 37°C for 5 minutes.
  10. Allow the lysate to cool to room temperature and then proceed directly to **Purifying gDNA**, below.
- 

## Purifying gDNA

1. Add 150  $\mu$ L Protein Precipitation Buffer (PPT) to 300  $\mu$ L of yeast cell lysate from Step 10, above.
  2. Mix thoroughly by vortexing for 20 seconds until a homogenous suspension is obtained.
  3. Centrifuge at 12,000  $\times g$  for 3 minutes at room temperature.  
**Note:** The precipitated proteins form a compact pellet and the supernatant should be clear. If the protein pellet is loose or insignificant, proceed to **Procedure for Pellet Compacting**, page 38.
  4. Transfer the supernatant into a clean, sterile microcentrifuge tube.
  5. Add an equal volume of isopropanol. Mix thoroughly by inverting the tube until the mixture is homogenous. Do not vortex.
  6. Centrifuge at 12,000  $\times g$  for 3 minutes at room temperature.  
**Note:** The precipitated DNA is visible as a white pellet.
  7. Decant the supernatant. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
- 

*Continued on next page*

# Purifying gDNA from Yeast, Continued

---

## Purifying gDNA, Continued

8. Add 1 mL 70% ethanol and wash the DNA pellet by inverting the tube several times.
9. Centrifuge at  $12,000 \times g$  for 1 minute at room temperature.
10. Carefully decant the supernatant.
11. Allow residual liquid to drain on a sheet of absorbent paper towel for a few minutes.
12. Evaporate residual ethanol by incubating the sample at  $50^\circ\text{C}$  to  $55^\circ\text{C}$  for 10 minutes.

**Note:** Be careful not to discard the DNA as the DNA pellet may be loosely adherent to the tube.

**Note:** If desired, you may evaporate residual ethanol at room temperature, but in this case, increase the incubation time.

13. After ethanol evaporation is complete (i.e., DNA pellet appears dry and the ethanol odor is undetectable), resuspend the DNA pellet in a suitable volume of DNA Dissolving Buffer (TE).
14. Incubate the tube at room temperature overnight or at  $65^\circ\text{C}$  for up to one hour to completely resuspend the DNA.

The DNA should be completely dissolved as a clear, colorless solution. If precipitates are present, the  $A_{260}/A_{280}$  ratio is  $<1.70$ , or the DNA is contaminated with buffer, protein, or RNA, re-purify the DNA sample (see **Purifying Impure DNA**, page 39).

---

## Storing DNA

To avoid repeated freezing and thawing of DNA,

- Store the purified DNA at  $4^\circ\text{C}$  for immediate use or
  - Aliquot the DNA and store at  $-20^\circ\text{C}$  for long-term storage.
-



# Estimating DNA Yield

---

## DNA Yield

Perform DNA quantitation using UV absorbance at 260 nm or Quant-iT™ DNA Assay Kits (see page 40 for ordering information).

### UV Absorbance

1. Prepare a dilution of the DNA solution in 10 mM Tris-HCl, pH 7.5. Mix well. Measure the absorbance of the dilution at 260 nm ( $A_{260}$ ) in a spectrophotometer (using a cuvette with an optical path length of 1 cm) blanked against 10 mM Tris-HCl pH 7.5.
2. Calculate the concentration of DNA using the formula:

$$\text{DNA } (\mu\text{g/mL}) = A_{260} \times 50 \times \text{dilution factor}$$

For DNA,  $A_{260} = 1$  for a 50  $\mu\text{g/mL}$  solution measured in a cuvette with an optical path length of 1 cm.

### Quant-iT™ DNA Assay Kits

The Quant-iT™ DNA Assay Kits (page 40) provide a rapid, sensitive, and specific method for dsDNA quantitation with minimal interference from RNA, protein, ssDNA (primers), or other common contaminants that affect UV absorbance.

The kit contains a state-of-the-art quantitation reagent, pre-diluted standards for standard curve, and a pre-made buffer. The assay is designed for reading in standard fluorescent readers/fluorometer or Qubit® Fluorometer.

---

# Troubleshooting

---

## Introduction

Refer to the table below to troubleshoot problems that you may encounter when using the JetFlex Genomic DNA Purification Kits.

<b>Problem</b>	<b>Cause</b>	<b>Solution</b>
Low DNA yield	Starting blood or body fluid sample too dilute	Concentrate samples by centrifugation at $2,000 \times g$ for 10 minutes prior to processing
	Poor quality of starting material	Use fresh samples and process immediately after collection or freeze the samples at $-80^{\circ}\text{C}$ or in liquid nitrogen. The yield and quality of DNA isolated is dependent on the type and age of the starting material.
	Incorrect lysis conditions	For blood samples, use a 1:1 ratio of sample:Red Blood Cell Lysis Buffer. For all samples, use the recommended volume of Cell Lysis Buffer, as directed in the protocol.
	Low starting DNA content	If the DNA yield is expected to be low, use a carrier (i.e., 10 $\mu\text{g}$ Glycogen per 300 $\mu\text{L}$ isopropanol) to enhance DNA precipitation.
DNA contaminated with protein	Protein not precipitated during protein precipitation step, indicated by a loose or small protein pellet	Precipitate the protein with the <b>Procedure for Pellet Compacting</b> , page 38

---

*Continued on next page*

## Troubleshooting, Continued

Problem	Cause	Solution
Low DNA yield	DNA is sheared or degraded	<p>Avoid repeated freezing and thawing of samples to prevent any DNA damage.</p> <p>Maintain a sterile environment while working to avoid any contamination from DNases.</p>
Dark colored eluate (mammalian tissue, mouse tails, or blood samples only)	Pigments from tissues or heme from blood co-precipitate with DNA	<ul style="list-style-type: none"> <li>• Use RBC Buffer at room temperature. Chilled RBC Buffer may prevent lysis.</li> <li>• Purify DNA using <b>Purifying Impure DNA</b>, page 39.</li> </ul>
Blood sample is coagulated or contains clots	Frozen blood samples thawed too slowly	<ul style="list-style-type: none"> <li>• If the blood sample contains clots or is coagulated, mince the sample with a pestle.</li> <li>• Thaw frozen blood samples quickly at 37°C to minimize clotting, white blood cell lysis and DNase activity.</li> <li>• Purify DNA from the unclotted portion of the sample.</li> </ul>
Impure DNA: $A_{260}/A_{280} < 1.70$ or insoluble particles present with dissolved DNA	Excess starting material	Purify DNA using <b>Purifying Impure DNA</b> , page 39.

# Appendix

## Procedure for Pellet Compacting

---

### Introduction

The procedure described below may be used when the protein precipitation pellet is loose or not adequately formed following treatment of the nuclear lysate with Protein Precipitation Buffer (PPT).

---

### Materials Needed

- Centrifuge capable of centrifuging  $>12,000 \times g$
- Ice (optional)

*Components supplied with the kit*

- Pellet Compactor
- 

### Pellet Compacting

The procedure described below is based on a 300  $\mu\text{L}$  starting sample volume, but may be scaled up or down proportionately. To compact the protein precipitation mixture, use one or both of the following methods:

- Vortex the protein precipitate mix (from Step 3, **Purifying gDNA**). Chill the mixture on ice for 5 minutes. Centrifuge at  $12,000 \times g$  for 3 minutes. Resume the purification procedure.
  - For every 450  $\mu\text{L}$  protein precipitation mix (from Step 3, **Purifying gDNA**), add 50  $\mu\text{L}$  Pellet Compactor. Vortex until mixture is homogenous. Centrifuge at  $12,000 \times g$  for 3 minutes. Resume the purification procedure.
-

# Purifying Impure DNA

---

## Introduction

The procedure described below may be used to re-purify DNA when the redissolved DNA contains insoluble particles, is discolored, or is impure or contaminated. The procedure is based on a 100  $\mu\text{L}$  starting sample volume, but may be scaled up or down proportionately.

---

## Materials Needed

- Purified DNA sample
- Centrifuge capable of centrifuging  $>12,000 \times g$
- Isopropanol
- 70% ethanol

*Components supplied with the kit*

- Cell Lysis Buffer (CLB)
  - Protein Precipitation Buffer (PPT)
  - Pellet Compactor
  - DNA Dissolving Buffer (TE)
- 

## Repurifying DNA

1. Add 500  $\mu\text{L}$  Cell Lysis Buffer for every 100  $\mu\text{L}$  purified DNA sample. Mix thoroughly by inverting tube or pipetting up and down.

**Note:** If DNA sample contains particulates, incubate at  $37^\circ\text{C}$ . Cool sample to room temperature before proceeding.

2. Add 300  $\mu\text{L}$  Protein Precipitation Buffer. Vortex vigorously for 20 seconds to homogenize the mixture.
3. Centrifuge at  $12,000 \times g$  for 3 minutes to pellet any precipitated impurities.

**Note:** If a pellet is not visible, proceed to **Pellet Compacting**, previous page, making certain to use the appropriate amount of Pellet Compactor based on your sample volume.

4. Proceed to Step 4, **Purifying gDNA**, for the specific sample type (i.e., page 9, for blood).
-

# Accessory Products

---

## Additional Products

The table below lists additional products available from Genomed or Invitrogen that may be used with the JetFlex Genomic DNA Purification Kit.

Product	Amount	Cat. no.
<b>Products below are available from Genomed. See <a href="http://www.genomed-dna.com">www.genomed-dna.com</a></b>		
Red Blood Cell Buffer (RBC)	200 mL	RBC-200
Cell Lysis Buffer (CLB)	125 mL	CLB-125
Protein Precipitation Buffer (PPT)	50 mL	PPT-050
DNA Dissolving Buffer (TE)	100 mL	TE-100
Proteinase K	40 mg	GN-PK-040
	200 mg	GN-PK-200
Ribonuclease A	50 mg	GN-RN-50
	100 mg	GN-RN-100
<b>Products below are available from Invitrogen. See <a href="http://www.invitrogen.com">www.invitrogen.com</a></b>		
Phosphate Buffered Saline (PBS), 1X	500 mL	10010-023
Luria Broth Base (Miller's LB Broth Base), powder	500 g	12795-027
	2.5 kg	12795-084
Ampicillin Sodium Salt, irradiated	200 mg	11593-027
Carbenicillin, Disodium Salt	5 g	10177-012
Quant-iT™ DNA Assay Kit, High Sensitivity	1,000 assays	Q33120
Quant-iT™ DNA Assay Kit, Broad-Range	1,000 assays	Q33130
Qubit® Fluorometer	1 each	Q32857

---

# Technical Support

---

## World Wide Web



Visit the website at [www.genomed-dna.com](http://www.genomed-dna.com) for:

- Technical resources, including manuals, MSDSs, FAQs
  - Complete technical support contact information
  - Access to the Online Catalog
  - Additional product information and special offers
- 

## Contact Us

For more information or technical assistance, call, write, fax, or email. Additional international offices are listed on [www.genomed-dna.com](http://www.genomed-dna.com).

### **GENOMED GmbH**

Poststr. 22

D-32584 Löhne, Germany

Tel: +49-(0)5732-904700

Fax: +49-(0)5732-9047010

E-mail: [techservice@genomed-dna.com](mailto:techservice@genomed-dna.com)

---

# Purchaser Notification

---

## Limited Warranty

GENOMED (a part of Life Technologies Corporation) is committed to providing our customers with high-quality goods and services. Our goal is to ensure that every customer is 100% satisfied with our products and our service. If you should have any questions or concerns about an Invitrogen product or service, contact our Technical Support Representatives.

All GENOMED products are warranted to perform according to specifications stated on the certificate of analysis. The Company will replace, free of charge, any product that does not meet those specifications. This warranty limits the Company's liability to only the price of the product. No warranty is granted for products beyond their listed expiration date. No warranty is applicable unless all product components are stored in accordance with instructions. The Company reserves the right to select the method(s) used to analyze a product unless the Company agrees to a specified method in writing prior to acceptance of the order.

GENOMED makes every effort to ensure the accuracy of its publications, but realizes that the occasional typographical or other error is inevitable. Therefore the Company makes no warranty of any kind regarding the contents of any publications or documentation. If you discover an error in any of our publications, report it to our Technical Support Representatives.

**Life Technologies Corporation shall have no responsibility or liability for any special, incidental, indirect or consequential loss or damage whatsoever. The above limited warranty is sole and exclusive. No other warranty is made, whether expressed or implied, including any warranty of merchantability or fitness for a particular purpose.**

---

*Continued on next page*



# Purchaser Notification, Continued

---

## Limited Use Label License No. 5: Invitrogen Technology

The purchase of this product conveys to the buyer the non-transferable right to use the purchased amount of the product and components of the product in research conducted by the buyer (whether the buyer is an academic or for-profit entity). The buyer cannot sell or otherwise transfer (a) this product (b) its components or (c) materials made using this product or its components to a third party or otherwise use this product or its components or materials made using this product or its components for Commercial Purposes. The buyer may transfer information or materials made through the use of this product to a scientific collaborator, provided that such transfer is not for any Commercial Purpose, and that such collaborator agrees in writing (a) not to transfer such materials to any third party, and (b) to use such transferred materials and/or information solely for research and not for Commercial Purposes. Commercial Purposes means any activity by a party for consideration and may include, but is not limited to: (1) use of the product or its components in manufacturing; (2) use of the product or its components to provide a service, information, or data; (3) use of the product or its components for therapeutic, diagnostic or prophylactic purposes; or (4) resale of the product or its components, whether or not such product or its components are resold for use in research. For products that are subject to multiple limited use label licenses, the terms of the most restrictive limited use label license shall control. Life Technologies Corporation will not assert a claim against the buyer of infringement of patents owned or controlled by Life Technologies Corporation which cover this product based upon the manufacture, use or sale of a therapeutic, clinical diagnostic, vaccine or prophylactic product developed in research by the buyer in which this product or its components was employed, provided that neither this product nor any of its components was used in the manufacture of such product. **If the purchaser is not willing to accept the limitations of this limited use statement, Life Technologies is willing to accept return of the product with a full refund. For information about purchasing a license to use this product or the technology embedded in it for any use other than for research use please contact Out Licensing, Life Technologies, 5791 Van Allen Way, Carlsbad, California 92008 or [outlicensing@lifetech.com](mailto:outlicensing@lifetech.com)**

---

©2010 Life Technologies Corporation. All rights reserved. The trademarks mentioned herein are the property of Life Technologies Corporation or their respective owners.

# Notes





**Corporate Headquarters**

Genomed GmbH

Poststr. 22

D-32584 Löhne, Germany

Tel:+49-(0)5732-904700

Fax:+49-(0)5732-9047010

techservice@genomed-dna.com

**[www.genomed-dna.com](http://www.genomed-dna.com)**

