

CF_EDIT

D. Lindler, February 2004
V. Dixon, May 2004

1.0 Introduction

CF_EDIT is an Interactive Data Language (IDL) visualization tool for the examination and modification of *Far Ultraviolet Spectrographic Explorer (FUSE)* intermediate data files (IDF) containing calibrated time-tag photon lists. It is started from IDL by typing `cf_edit` at the command prompt. Figure 1.1 shows the layout of the primary CF_EDIT interface. It contains




Figure 1.1: CF_EDIT

Table 1
Summary of the CF_EDIT Menu Bar

			Section
File			
	Read IDF File(s)	Select and read CALFUSE intermediate data files.	2.1
	Write IDF File	Write intermediate data file.	2.2
	Default Parameters	Modify CF_EDIT control parameters	11.0
	PS Output	Produce PostScript file of the current display	2.3
	Exit	Exit CF_EDIT	
Colors			
		Load Pseudo-color table	3.1
Scale			
		Select contrast scaling	3.2
Display			
		Select time-tag event X/Y coordinates	3.5
Plot			
	Row	Plot a row of the displayed image	4.0
	Column	Plot a column of the displayed image	4.0
	Row Sum	Plot a sum of rows of the displayed image	4.0
	Column Sum	Plot a sum of columns of the displayed image	4.0
	PHA	Plot a histogram of the pulse heights of the time-tag events	4.0
Overlay			
		Control overlaid graphics on the displayed image	3.6
Event Selection			
		Select criteria for good events	5.1
GTI Selection			
		Select/Modify Good-time intervals	5.2
Extract Spectrum			
		Perform unweighted slit extraction of the specified aperture	4.0
Background			
	Adjust Region	Adjust region used for scaling the background	6.0
	Create New Region	Create a new background region	6.0
	Delete Region	Delete a background region	6.0
Header			
	Display	Display FITS Header of the input IDF file(s)	7.0
	Add Comments	Add comments that will appear in the output header.	7.0
Register			
		Wavelength registration	8.0
Y CENTROID			
		Calculate Y centroid of a target spectrum	9.0
TTAG Analysis			
		Analyze time-tag list (count rates, centriods, movies)	10.0
Exptime			
		Displays total exposure time for current good time intervals	

three graphic windows (labeled 1, 2, and 3). The long window at the bottom (number 1) shows the entire detector image, the large window (number 2) shows a portion of the image with one data pixel per screen pixel, and the small window in the upper right corner (number 3) is a zoom

window. Commands are issued using the two-row menu bar at the top of the widget (labeled 4 in Figure 1). A summary of the menu bar commands is given in Table 1. The region of the interface labeled 5 contains the minimum and maximum image values and can be used to control the contrast of the displayed images. Region 6 shows the X and Y position of the cursor position along with the image's intensity value at that point.

2.0 File Input/Output

2.1 Reading input IDF files

Your first step when using CF_EDIT is to read one or more input IDF files. Select **Read IDF File(s)** from the **FILE** menu. A standard file Selection interface will appear. You can move to the directory containing the data file(s) that you want. Select the data files and exit. Multiple files are selected by holding down the <shift> key (to select a continuous range of files) or the <Ctrl> key to select individual files. It is sometimes helpful to limit the files on the Selection list by modifying the filter. For example, you might change the filter from ***idf.fit** to ***1a*idf.fit** to limit the list to segment 1a. You can then quickly highlight the files you want by selecting the first file followed by the last file (while pushing the shift key).

If you select multiple input files, they must all be from the same detector segment. Each segment must be processed independently.

2.2 Writing the output IDF file

Once you have completed your operations on the input IDF files, you can write a merged IDF file. Select **Write IDF File(s)** on the **FILE** menu. The standard file selection interface will appear. Use the default output filename or create your own. The output file contains the events from all of the input files and may be reread by CF_EDIT. However, if you have changed the selection of good events with CF_EDIT, you may have to go back to the original data to make additional changes. For example, if you told CF_EDIT to ignore the burst event flag, it will be set to zero for all events in the output IDF file. If you want to turn it back on, you must go back and reread the original data.

2.3 Postscript output of the displayed images.

Select **PS output** on the **FILE** menu to create a postscript file of the current images displayed by CF_EDIT. It has three options: **B/W** for black and white, **B/W reversed**, and **Color**.

3.0 Controlling the Displayed Images

3.1 Selection of pseudo-colors

Push the **Color** button on the menu bar to change the pseudo-color table used to display the images. The standard IDL color table Selection interface will appear. Select the desired color table and exit.

3.2 Image Contrast

Contrast can be controlled using the **Scale** pull-down menu to the right of the **Scale** label button. Four intensity transformations are available (linear, square root, logarithmic, and histogram equalization). Further control of the intensity scaling is accomplished with the **MIN** and **MAX** fields (see the region labeled with the number 5 in Figure 1.1). Anything with a value less than **MIN** is set to zero in the display. Anything with a value greater than **MAX** is set to the maximum display value. If you change the **MIN** or **MAX** value, the new value does not take effect until you either hit a carriage return while in the **MIN** or **MAX** window or select a new intensity transformation with the **Contrast** menu button. If you plan to change both the **MIN** and **MAX** values, you can save time by not hitting the carriage return until both values are changed. The **Reset Min/Max** button will reset the **MIN** and **MAX** fields to the original image minimum and maximum values.

The **MIN** and **MAX** fields are reset to the minimum and maximum image values whenever a new image is loaded. If you want to freeze values to the current levels, push the **Freeze Min/Max** button. The **MIN** and **MAX** values will be left unchanged when new images are loaded. When hit, the **Freeze Min/Max** button will change to an **UnFreeze Min/Max** button. Hit the button again when you want to change back to normal operation.

3.3 Controlling the region of the image displayed

The long bottom display window (region 1 in Figure 1.1) always shows the entire image binned to the window size. Note that the x and y aspect ratios do not match. Window number 2 in Figure 1 shows a portion of the image with the display pixel size equal to the image pixel size (as binned during file reading; see Section 11.0). There are two ways to control what region of the image is displayed in this window.

1. Use the scroll bars on the side of the window. If no scroll bar is present, it indicates that the image fits within the display in either or both the X and Y directions.
2. Move the cursor to the lower window and hit any mouse button. The position of the cursor in the lower window will be the center of the region displayed in display window 2. You can hold down the mouse button while moving the cursor in the lower window to roam around the image.

There are two ways to control the region of the image that is displayed in the zoomed image window (number 3 in Figure 1.1).

1. Move the cursor to the large window (number 2 in Figure 1.1) and hit any mouse button. The position of the cursor in the large window will be the center of the region displayed in the zoomed image window.
2. Position the cursor at any point within the zoomed image window and push a mouse button. The position of the image selected will be moved to the center of the zoomed image window.

The zoom factor of the zoomed image window can be changed using the **Zoom Factor** button above the zoom window.

3.5 The image coordinate system

Any of four coordinate systems can be selected with the **Display** button:

1. Raw X/Y
2. XFARF/YFARF
3. Final X/Y
4. Wavelength/Y

Click on the current coordinate system name to the right of the **Display** label and select the desired coordinate system from the pop-up menu. **Raw X/Y** are the original raw X and Y coordinate system, **XFARF/YFARF** are the coordinates after correction for various detector distortions, and **Final X/Y** are the coordinates after the image-motion correction. In the **Wavelength/Y** coordinate system, the horizontal axis is constructed by linearizing the wavelengths of the time-tag events. Only events with assigned wavelengths (those within the aperture extraction regions) are displayed. The **Wavelength/Y** coordinate system will show the results of the astigmatism correction.

You can adjust the binning of the data when constructing the image using the **Default Parameters** option on the menu **File** button (Section 11.0). The default 2 x 2 binning is recommended, as 1x1 binning may cause memory problems on some machines.

3.6 Graphic Overlays

The Overlay button on the menu bar can be used to turn on and off graphic overlays on the images. It will display the interface shown in Figure 3.1. Push the buttons to turn the overlays on and off. If an extraction region is selected, CF_EDIT must have access to the extraction limit calibration file listed in the FITS header (keyword CHID_CAL). The calibration file must be in the directory specified in the default parameters (controlled by the **Default Parameters** option on the FILE button; Section 11.0). The default value of this directory is the definition of the environment variable CF_CALDIR.




Figure 3.1
Graphic Overlays

4.0 Generation of Plots

Plots of the data can be generated using the **Plot** button or the **Extract Spectrum** button on the menu bar. The plot button offers five types of plots: **row**, **column**, **row sum**, **column sum**, and **PHA**. After selecting either the **row** or **column** option, place the cursor on a row or column in any of the three display windows and push a mouse button. When selecting a **row sum** or **column sum**, place the cursor on the first row or column and push a mouse button. Select the last row or column and push a mouse button again. **PHA** will display a histogram of the pulse heights of the events.

With the **Extract Spectrum** button, you must select the channel/aperture to extract. The spectrum will be extracted in wavelength bins versus flux or counts as specified in **File/Default Parameters** (Section 11.0).

WARNING: While spectra generated with the **Extract Spectrum** button may be written to an external file, they are not background subtracted and are not meant for scientific analysis. Instead, we recommend that you write out your modified IDF file and use the CalFUSE extraction software to extract a final spectrum.

When a plot is requested with **Plot** or **Extract Spectrum**, a plotting tool, LINEPLOT, will appear containing the plot. This tool can remain active while you continue using CF_EDIT. This will allow you to generate overplots. If you leave the plotting tool active, new plots will appear in the same window. For example, you could use the tool to compare an extraction of a spectrum with and without the daytime events included. If you do not want the new plot to be overplotted, you must exit the plotting tool before generating the new plot. Up to 10 overplots are supported. See the documentation for LINEPLOT in the FUSE_SCAN reference manual for additional information on the use of the plotting tool.

5.0 Selection of Time-Tag Events

The **Event Selection** and **GTI Selection** buttons on the menu bar control which events are displayed in the image, extracted with **Extract Spectrum**, or flagged as usable in the output IDF file. **Event Selection** allows you to turn Selection criteria on and off (Section 5.1). **GTI Selection** allows you to specify the good and bad time intervals interactively using plots of various observation parameters versus time (Section 5.2).

5.1 Event Selection

When you push **Event Selection**, the interface shown in Figure 5.1 will appear. Events are flagged with eight conditions that may make an event unusable or suspect:

1. User Defined
2. Jitter
3. Not in OPUS good time interval
4. Bursts
5. High Voltage
6. SAA
7. Limb Angle
8. Day/Night

To reject events with any of these conditions, select the “**Good**” button. To ignore the condition, press “**Either.**” If you want to investigate what the bad events look like without the good ones, select the “**Bad.**” For example, if you want to display an image of the burst events, set **Bursts** to “**Bad.**” You can limit the range of displayed pulse heights by entering new values in the **PHA Range** minimum and maximum fields. **Use my GTI Selection** allows you to turn off and on the use of any good-time interval Selection that you may have done with the **GTI Selection** button (Section 5.2).



Figure 5.1
Event Selection

When you have completed your Selections, push **Done**. The displayed images will be updated using only the events that you have selected. Your Selections will also be used when **Extract Spectrum** or **FILE/Write IDF file** are performed. To exit the event Selection tool without




Figure 5.2
Selection of Good Time Intervals

modifying the data, press **Abort**. **Reset** can be used to reset the Selections to those upon entry into the **Event Selection** interface. **Select All** will cause all conditions to be ignored and all events selected.

5.2 Selection of good time intervals

The **GTI Selection** button on the menu bar allows you to reject events from time periods selected using plots of any of the following parameters:

1. Time since sunrise
2. Time since sunset
3. Limb Angle
4. Spacecraft Longitude
5. Spacecraft Latitude
6. Orbital Velocity
7. High Voltage
8. LiF count rate
9. SiC count rate
10. FEC count rate
11. AIC count rate

12. Background count rate
13. Y centroid of the LiF target spectrum
14. Y centroid of the SiC target spectrum

When you select a condition on the pull-down menu of the **GTI Selection** button, the tool shown in Figure 5.2 will appear. Time regions that you flag as bad will appear in red. Regions that are bad for other conditions (as specified by the **Event Selection** tool; Section 5.1) will appear as green. As you move the cursor over a green region, the condition that causes it to be bad is displayed below the menu bar.

To mark data as bad, use the **Delete All** or **Delete Region** buttons. **Delete All** marks all data as bad. It is useful if most of the data is bad and you would prefer to mark it as all bad and then select the regions of good data. **Delete Region** marks data within a user specified box as bad. After pushing the button, you must position the cursor on the first corner of the box and press the left mouse button. Next position the cursor on the opposite corner and again press the left mouse button. All data points lying within the box will be marked as bad. If you make a mistake in this process, just hit the **UNDO** button or use **Keep Region** to select the portion of the data that you did not want marked as bad. **Keep Region** works the same as **Delete Region**. All data points within the selected box will be marked as good. **Keep All** will mark all data points as good.

The X and Y ranges of the plot can be changed using the **Zoom** and **UnZoom** buttons on the menu bar. After pushing the **Zoom** button, position the cursor in the plot window at one corner of the rectangular region you want to expand. Push the left mouse button and repeat for the opposite corner of the region. Alternately, you can zoom without first pushing the **Zoom** button by placing the cursor at one corner of the box, pushing and holding the center mouse button while dragging the cursor to the opposite corner, and releasing the center mouse button. Another method of changing the X and Y ranges of the plot is to enter values into the **X Min**, **X Max**, **Y Min**, and **Y Max** fields at the bottom of the widget.

Zooming in on selected regions allows you to refine the data masks. By zooming to very small regions, you can easily mark good and bad data points individually. When zoomed to a sufficiently small region of the data, individual data points will be marked as diamonds.

To change the X or Y axis to logarithmic scaling, push the **X Log** or **Y Log** button. The plot will change, and the button will be renamed **X Linear** or **Y Linear**. It can now be used to change back to linear scaling.

When you exit from the **GTI Selection** tool, the displayed images will be updated to remove data from the bad time intervals that you have selected (provided that you have not turned off the “**Use my GTI Selection**” in the **Event Selection**; Section 5.0). Any spectral extractions or output IDF files will also have your good/bad time intervals flagged. You may re-enter the **GTI**

Selection tool to make changes to your good time intervals or to apply additional selection criteria using a different plotted parameter.

6.0 Background Region Selection

With the **Background** button on the main menu, you can adjust the background regions used to scale the background reference file in CalFUSE. It has three options: **Adjust Region**, **Create New Region**, and **Delete Region**. When any of these options are selected, the background overlay will be turned on and the background regions displayed on the images as rectangles.

Hint: Change the X binning to 32 in the File/Default Parameters (Section 11.0) when changing the background regions. This causes the entire spectral range to appear in the large display window.

If **Adjust Region** is selected, place the cursor on one of the horizontal boundaries of a background region, click a mouse button, move cursor to the new location for the boundary, and click again. You need not worry about the light from the airglow lines. These regions are automatically ignored by CalFUSE.

If **New Region** is selected, place the cursor at the first Y boundary and click a mouse button. Move to the second position and click again. The new region will be added. If it overlaps with an existing region, the boundary of the existing region will be adjusted to resolve the overlap.

If **Delete Region** is selected, place the cursor in the region and push a mouse button.

WARNING: background regions are specified in Final X/Y coordinates. Be sure your images are displayed in these coordinates (Section 11.0) before adjusting the regions.

7.0 Header Manipulation

The **Header** button can be used to display the input headers and to add comments to an output header. To display an input header select the **Display** option on the pull-down menu. If you have read multiple input files, you will be requested to select which header to display. The header is displayed in a scrollable text window. When you finish examining the header, push the **DONE** button at the top of the window.

The **Add Comments** option on the **Header** pull-down menu allows you to enter comments to be placed into the output IDF file. A text window will appear. Enter the comments into the window and push **DONE**.

8.0 Wavelength Registration

The **Register** button allows you to register the wavelengths of spectra from multiple exposures interactively. Select the desired aperture from the pull-down menu. The requested spectra will be extracted and displayed in an interactive wavelength-registration tool. Refer to the FUSE_REGISTER user manual for instructions on using this tool. The registration tool will accept a maximum of ten spectra. If you have read more than ten, you will be asked to select up to 10 files to register (Figure 8.1). Use the Selection buttons to select or deselect the files to process and then push **DONE**. When you have registered the selected spectra, the Selection process will be repeated. The computed wavelength shifts will be applied to all photons in the desired aperture. Files previously processed will show the computed wavelength offsets (in Angstroms) to the right of the filename. This will assist you so that you do not repeat or miss any of the files. In the example in Figure 8.1, the first spectrum is used as a reference spectrum. You are free to choose any of the spectra as a reference. To exit the registration tool, press **DONE** without selecting any files.




Figure 8.1
Registration File Selection

Although all of the capabilities in the FUSE_REGISTER registration tool are available, only the wavelengths offsets are returned and have any effect on the output IDF file of CF_EDIT. You are welcome to rescale the data and coadd it. You can even write the coadded spectrum to a file. However, such actions have no effect on the operation of CF_EDIT. Also, note that no statistical errors are loaded into the registration tool by CF_EDIT. It is suggested that coaddition of extracted spectra be performed with the final CalFUSE outputs using FUSE_REGISTER.

9.0 Recomputing the Y Centroid

The **Y CENTROID** button will allow you to recompute the Y centroid for a particular aperture. Centroids for each aperture are stored in the IDF file header. By default, the header of the first input file is copied to any output IDF file created by CF_EDIT. If your target is faint, you may be able to improve on the YCENT values in the input header by recalculating centroids for the combined data set. To do it, press the **Y CENTROID** button and select an aperture. Then decide how the centroid should be determined:

Target events only	This is the standard.
Airglow events only	Useful for diffuse or faint targets.
Default	Reads value from aperture calibration file.
User select	Presents a window in which to enter the Y centroid value.

To check your result, use the **Overlay** button to plot the extraction window on the displayed image. The new value of YCENT will be written to the output IDF file and used by the CalFUSE spectral-extraction software.

10.0 Time-Tag Event Analysis

The **TTAG Analysis** button allows you to examine count rates and compute centroids of selected regions of the image. When pressed, it activates the tool shown in Figure 10.1. Initially, the image display will be blank and the buttons below the **PROCESS** button will not be active. To begin, first specify the range of data to be analyzed. The default upon entry is the area in the zoomed image of the main CF_EDIT display. The range can be changed by editing the **X Range** and **Y Range** fields. The area in the region will be centroided and the total counts within the region computed as a function of time. Next, you must specify a time interval by which to bin the time-tag events. The default is 120 seconds. The minimum counts needed within each time interval in order to attempt a centroid can also be changed. When you are ready, press the **PROCESS** button. The bottom display window will show the region of the image that you selected. You can now generate plots of the centroids, counts within the region, and total counts within the image versus time using one of the four plot buttons (**PLOT X Centroids**, **PLOT Y Centroids**, **PLOT Counts**, or **PLOT Total Counts**). Any of these buttons will bring up the line-plotting widget (LINEPLOT). Refer to the FUSE_SCAN users manual for documentation on the use of LINEPLOT. Exit the plotting widget if you do not want the next plot you request to be overplotted on the existing plot.

The **Movie** button on the time-tag analysis tool allows you to create a movie with the time-tag events. Pressing it will bring up the widget shown in Figure 10.2. There are four regions to this tool. The first (labeled 1 in Figure 10.2) controls the portion of the image and the time range to be displayed as a movie. The default image range is the zoom




Figure 10.1
TTAG Analysis

window in the CF_EDIT main display. The default time period is the entire observation. The second region (2) controls the binning of the image and the time intervals binned for each movie frame. Region 3 displays the size of the movie as specified and region 4 controls the contrast of the movie. The total size must be less than 128 megabytes and typically should be much smaller. If the movie is too large, adjust the binning or range to make it an appropriate size. Any time you edit one of the range or binning fields, you must enter a carriage return within the field to update the information in the movie-size region (3) of the widget.

When you are satisfied with your Selections, hit the **LIGHTS, CAMERA, ACTION** button. This will bring up the IDL animation tool. Initially the movie will appear slow as the frames are created and loaded. Once the frames are loaded, away it goes. Use the top buttons on the animation widget to stop the movie or change directions. The **Frames/Sec** slider can be used to control the speed of the movie. When done, hit the **End Animation** button to return to the **Movie Creator** widget.




Figure 10.2
Movie Creation

11.0 Default Parameters

The **Default Parameters** option on the **File** menu will allow you to a number of parameters used by CF_EDIT. When selected, the tool in Figure 11.1 is displayed. The **Image Binning** applied before displaying the images can be changed in the two pull-down menus. The **Extracted wavelength spacing** and **Extracted spectral units** give wavelength binsize and output units when spectra are extracted with the **Extract Spectrum** tool. The **Cal File Directory** is the location of the CalFUSE calibration files.

12.0 IDL Virtual Machine

CF_EDIT can be run either in the standard IDL environment or using the IDL Virtual Machine (VM). IDL VM allows users who do not have an IDL license to run IDL packages prepared for VM. To obtain IDL VM (free of charge), visit the Research Systems, Inc., web site




Figure 11.1: Default Parameters

(www.rsinc.com/idlvm). When installed, load the file `cf_edit.sav` into the IDL VM to start the program.

13.0 Additional Information

You'll find `CF_EDIT` easier to use if you know something about its internal logic. First of all, the program always ignores the status flags associated with individual photons in the first extension of an IDF file. Instead, it uses the status flags stored in the third extension (the timeline table) to determine the good and bad time intervals of an exposure or series of exposures. It uses these intervals to determine whether individual photons are good or bad based on their arrival times. If you use the **Event Selection** tool to change the definition of good and bad photons, or the GTI selection tool to define time intervals as good or bad, both the program's internal set of good-time intervals and the list of photons included in the image display are modified accordingly. Only when the program writes out a new IDF file are the status flags of individual photons updated.

Because we lack arrival-time information for data obtained in HIST mode, exposures affected by bursts, SAA's, or low limb angles must be accepted or rejected in total. These conditions are likely to increase the background level, but probably not enough to overwhelm bright HIST targets. `CF_EDIT` deals with such situations in two ways. First, if asked to read a file affected by one of these conditions (that is, if the header keyword `EXP_STAT > 0`), `CF_EDIT` issues a warning message, but does not reject the data set. Second, `CF_EDIT` by default ignores the `BRST`, `SAA`, and `LIMB` flags in the timeline table. You can see this in the **Event Selection** tool: for HIST data, the acceptance criteria for Bursts, SAA, and Limb Angle are set to "Either."