

User Manual

for

AutoUniConv SDK

A C/C++ software development kit to
automatically convert text encoded in various charsets to Unicode

Covers version 1.2.0



AutoUniConv SDK User Manual, published April 11, 2014.

Copyright © 2010-2014, Lingua-Systems Software GmbH

Lingua-Systems Software GmbH, Gerichtsstraße 42, 44649 Herne, Germany,
info@lingua-systems.com

All rights reserved, especially changing or publishing parts of this manual needs prior written permission of the copyright owner.

The rights to reproduce and publish unchanged copies in any form, to translate or to present the manual are granted.

Mentioned hard- and software as well as companies may be trademarks of their respective owners. Use of a term in this manual should not be regarded as affecting the validity of any trademark or service mark. A missing annotation of the trademark may not lead to the assumption that no trademark is claimed and may thus be used freely.

Great effort has been made in writing this manual. However, faults cannot be excluded in general. For any loss or damages caused or alleged to be caused directly or indirectly by errors or omissions in this manual, the authors and the publisher assume no responsibility and cannot be held liable. Neither can the authors or the publisher be held liable for the content or changes of content concerning the linked websites. The links have been carefully chosen and proved at the preparation of the manual.

If you have problems using the links or get aware of any faults, feel free to give a brief hint on it via *support@lingua-systems.com*.

Contents

1. Introduction	5
2. Supported Charsets	6
3. Installation	7
3.1. Requirements	7
3.2. What Will Be Installed	7
3.3. Installing the Software	7
3.4. Deinstalling the Software	7
4. Application Programming Interface	8
4.1. A Minimal Application	9
4.2. Important Data Structures	10
4.2.1. auc_bytes_t	10
4.2.2. auc_utf_t	10
4.2.3. auc_flag_t	10
4.3. Function Reference	11
4.3.1. auc_conv()	11
4.3.2. auc_nconv()	11
4.3.3. auc_free_bytes_t()	12
4.3.4. auc_strerror()	12
4.3.5. auc_utf_t_to_name()	12
4.3.6. auc_version()	12
4.3.7. auc_version_string()	12
5. Error Handling	13
5.1. Pseudo-Variable auc_errno	13
5.2. auc_errno_t Named Error Constants	14
6. Hints on Application Development	15
6.1. Achieving Optimal Conversion	15
6.2. Determining AutoUniConv's Version	15
A. Example Application	16
B. References	18

About this Manual

This manual addresses users with experience in C/C++ programming and at least a basic knowledge of library usage.

The manual provides a short introduction to the library, its supported character encodings (charsets) as well as instructions how to install the [AutoUniConv SDK](#) software package. Afterwards the complete API is introduced along with the possibilities of error handling. A complete usage example is attached in appendix A.

For a quickstart have a look at the function reference in the documentation of the application programming interface (chapter 4.3 on page 11).

Administrators who want to install the software get all necessary information in chapter 3, page 7.


Conventions used in this Manual

At several points of this manual it is necessary to make a distinction between strings that may not contain embedded *NUL* characters and those which may – due to their special charset – potentially contain *NUL* characters. In this manual, the former are called "*Strings*" while the latter are called "*Byte Strings*".

1. Introduction

AutoUniConv SDK provides a dynamic C/C++ library that provides the functionality to automatically identify a string's charset and convert it to Unicode afterwards, if the string is encoded in a supported charset. This way, documents can be processed with all the advantages of the modern Unicode standard even if they are stored in a potentially unknown charset.

The library features fast and reliable processing and conversion. It has no software dependencies other than the standard C and thread library of the system it is deployed on and is easy to integrate. Even on dated hardware it works quite efficiently.



2. Supported Charsets

AutoUniConv currently identifies 39 distinct charsets and converts them to one of the common Unicode Transformation Formats (UTF). The set of supported charsets covers both current and legacy charsets. This way, a maximum amount of documents can be converted automatically.

Family	Charsets
Unicode	UTF-8, -16LE, -16BE, -32LE, -32BE
ISO	ISO-8859-1, -2, -3, -4, -5, -6, -7, -15, -16
Windows	Windows-1250, -1251, -1252, -1253, -1256, -1257
IBM/DOS Code Pages	CP-720, -737, -775, -850, -852, -855, -866
Macintosh	MacArabic, -CentralEuropean, -Cyrillic, -Greek, -Roman, -Romanian, -Ukrainian
National	Big5, GB2312, KOI8-R, KOI8-U, ASCII

Figure 1: Supported Charsets (Input)

AutoUniConv supports UTF-16 and UTF-32 in both little- and big-endian byte order. As the byte order is chosen explicitly, the converted byte strings do – in conformance to official proposals – not contain any byte order mark ("BOM").

Family	Charsets
Unicode	UTF-8, -16LE, -16BE, -32LE, -32BE

Figure 2: Supported Charsets (Output)

3. Installation

3.1. Requirements

[AutoUniConv SDK](#) merely requires the system's standard C runtime environment.

3.2. What Will Be Installed

The [AutoUniConv SDK](#) contains a dynamic library (DLL/SO), its header file, the code of an example application and this manual.

The Software Development Kit for Linux contains the following files:

```
./doc :
example.c  LICENSE.txt  manual-sdk-eng.pdf

./include :
auc.h

./lib :
libauc.so@  libauc.so.1@  libauc.so.1.0.0
```

3.3. Installing the Software

[AutoUniConv SDK](#) is provided as a compressed archive, either in "Zip" or "tar.gz" form, depending on the target platform.

To install the software, just unpack the archive to a directory of your choice and add the library and header files to your project.

3.4. Deinstalling the Software

To deinstall the software, just remove the directory you unpacked [AutoUniConv SDK](#) to.

4. Application Programming Interface

The **AutoUniConv** C/C++ library provides an API that is intuitive to use and allows integration into applications easily. All functions and data structures are prefixed "auc_" to avoid confusions and collisions with other third party library functions and are defined in the header file *auc.h*.

AutoUniConv provides two main functions that allow to automatically convert text encoded in a supported charset to Unicode:

- *auc_conv()* – use a character string as input source (`const char *`)
- *auc_nconv()* – use a byte string of a given length as input source (`const char *`)

Both functions return the same data structure, a pointer to an `auc_bytes_t` structure. This data structure provides the converted bytes of the input and its length. For convenience, the structure also contains information on the Unicode Transformation Format used to encode the bytes (see chapter 4.2.1 on page 10).




Figure 3: Flowchart of the main **AutoUniConv** functions

In order to fulfill its purpose, **AutoUniConv** has to identify the charset of the input string internally. To ensure optimal identification results, an input string should not be too short, consist of different words and thus provide some degree of variance (see chapter 6.1 on page 15).

If the results are no longer needed, you should utilize the *auc_free_bytes_t()* function to free all memory used by the result's data structure.

To handle errors in applications that make use of **AutoUniConv**, the library provides *auc_strerror()*, that allows to obtain a natural language description of error codes stored in the pseudo-variable *auc_errno* (see chapter 4.3.4 on page 12 and chapter 5.2 on page 14).

All functions provided by the **AutoUniConv** library are thread-safe and can therefore be used by more than one thread simultaneously.

4.1. A Minimal Application

The following application gives a first overview on the usage of the [AutoUniConv](#) library. Every provided function and the `auc_bytes_t` data structure is described in detail in the subsequent chapters.

```
#include <stdio.h>
#include <stdlib.h>
#include <auc.h>

int main(int argc, char *argv[])
{
    int i = 0;

    if (argc < 2)
    {
        fprintf(stderr, "usage: %s string(s)\n", argv[0]);
        return EXIT_FAILURE;
    }

    for (i = 1; i < argc; i++)
    {
        auc_bytes_t *b = NULL;

        b = auc_conv(argv[i], AUC_UTF32BE, AUC_DEFAULT);

        if (b)
        {
            printf("String %d: %u %s bytes\n",
                i, (unsigned int) b->len,
                auc_utf_t_to_name(b->utf));
            auc_free_bytes_t(b);
        }
        else
        {
            fprintf(stderr, "auc_conv: %s\n",
                auc_strerror(auc_errno));
            return EXIT_FAILURE;
        }
    }

    return EXIT_SUCCESS;
}
```

The example application makes use of the function `auc_conv()` to automatically convert all argument strings to UTF-32BE and print their length. In case an error occurs during processing, the application prints an appropriate error message and terminates.

```
$ ./auc-mini \
"Alle Menschen sind frei und gleich an Würde und Rechten geboren." \
"Alla människor äro födda fria och lika i värde och rättigheter."
String 1: 256 UTF-32BE bytes
String 2: 252 UTF-32BE bytes
```

4.2. Important Data Structures

4.2.1. auc_bytes_t

`AutoUniConv`'s main functions return a pointer to an `auc_bytes_t` data structure as a result. The data structure comprises the byte string converted to the requested Unicode Transformation Format, its length and the type it has been converted to.

This way, `auc_bytes_t` provides all information necessary to process string data in a robust and effective manner – no matter which Unicode Transformation Format it has been converted to.

Member	Type	Description	Example
<code>bytes</code>	<code>char *</code>	UTF byte string	"Chaîne de caractères"
<code>len</code>	<code>size_t</code>	Length of the string (in bytes)	22
<code>utf</code>	<code>auc_utf_t</code>	Information on the used UTF	AUC_UTF8

Figure 4: `auc_bytes_t` Members

4.2.2. auc_utf_t

The `auc_utf_t` data structure provides named constants for all Unicode Transformation Formats supported by `AutoUniConv`:

Named Constant	Description
AUC_UTF8	UTF-8
AUC_UTF16LE	UTF-16 (Little-Endian)
AUC_UTF16BE	UTF-16 (Big-Endian)
AUC_UTF32LE	UTF-32 (Little-Endian)
AUC_UTF32BE	UTF-32 (Big-Endian)

Figure 5: `auc_utf_t` Named Constants

These named constants are particularly useful to request a special Unicode Transformation Format from one of `AutoUniConv`'s main functions.

4.2.3. auc_flag_t

The `auc_flag_t` data structure provides a set of named constants that allow to suite the mode of operation of `AutoUniConv`'s functions `auc_conv()` and `auc_nconv()`:

Named Constant	Description
AUC_DEFAULT	Default behaviour
AUC_STRICT	Abort on the first decoding error
AUC_WARN	Print a warning on each decoding error

Figure 6: `auc_flag_t` Named Constants

In default mode, both `auc_conv()` and `auc_nconv()` attempt to replace decoding errors with a common placeholder, the tilde character ("~") wherever possible. Processing will not be interrupted in these cases and no warnings will be issued. Otherwise an error will be thrown.

If this behaviour is not desired for a special application of yours, you can suite the function's behaviour to your needs using the flags described above. Please note that for maximum flexibility the flags can be combined by simply adding them to another (i.e. "AUC_STRICT + AUC_WARN").

4.3. Function Reference

All of **AutoUniConv**'s functions and data structures are defined within the header file *auc.h*. The header has to be included in all applications that make use of the following functions.

4.3.1. `auc_conv()`

```
auc_bytes_t * auc_conv (const char *str ,
                        auc_utf_t   utf ,
                        auc_flag_t   flags);
```

The function takes a pointer to a string (`const char *`), a specification of the desired Unicode Transformation Format (`auc_utf_t`) and (a combination of) flags (`auc_flag_t`) that may be used to suite the function's behaviour to special needs.

The function returns a pointer to an `auc_bytes_t` structure as a result (see chapter 4.2.1, page 10).

Any call of the function resets the value stored to `auc_errno`.

If an error occurs, the function returns a pointer to `NULL` and sets the pseudo-variable `auc_errno` to an appropriate value that indicates the error (see chapter 5, page 13).

For detailed explanation on the data structures `auc_utf_t` and `auc_flag_t`, refer to the chapters 4.2.2 and 4.2.3.

As soon as the results are not needed any longer, you should free the memory allocated by the `auc_bytes_t` structure using `auc_free_bytes_t()`.



Whenever a string may contain *NUL* bytes (for example in case of an UTF-16 or UTF-32 charset), use `auc_nconv()` instead of `auc_conv()`.

4.3.2. `auc_nconv()`

```
auc_bytes_t * auc_nconv (const char *bstr ,
                        size_t      blen ,
                        auc_utf_t   utf ,
                        auc_flag_t   flags);
```

The function takes a pointer to a byte string (`const char *`), its length, a specification of the desired Unicode Transformation Format (`auc_utf_t`) and (a combination of) flags (`auc_flag_t`) that may be used to suite the function's behaviour to special needs.

The function returns a pointer to an `auc_bytes_t` structure as a result (see chapter 4.2.1, page 10).

Any call of the function resets the value stored to `auc_errno`.

If an error occurs, the function returns a pointer to `NULL` and sets the pseudo-variable `auc_errno` to an appropriate value that indicates the error (see chapter 5, page 13).

For detailed explanation on the data structures `auc_utf_t` and `auc_flag_t`, refer to the chapters 4.2.2 and 4.2.3.

As soon as the results are not needed any longer, you should free the memory allocated by the `auc_bytes_t` structure using `auc_free_bytes_t()`.



As `auc_nconv()` handles byte strings appropriately, even if they contain "NUL" characters (ASCII 0x00), this function should be utilized instead of `auc_conv()` whenever the length of the input is already known.



The parameter `blen` has to be set to a value that is lower or equal to the length of the byte string excluding string termination characters. Due to the technical properties of a byte string, `auc_nconv()` cannot determine the correct length on its own. Severe exceptions may occur whenever `blen` is set to a value that exceeds the bounds of `bstr`, so setting this value deserves special care and attention.

4.3.3. `auc_free_bytes_t()`

```
void auc_free_bytes_t (auc_bytes_t *bs);
```

The function takes a pointer to an `auc_bytes_t` structure as an argument.

Like the `free(3)` function provided by the standard C library, `auc_free_bytes_t()` has no return value.

The memory allocated by `bs` is freed completely and will be available for the application again.

4.3.4. `auc_strerror()`

```
const char * auc_strerror (auc_errno_t errno);
```

The function takes an error number (`auc_errno_t`) as an argument and returns a pointer to a read-only string (`const char *`) containing the natural language error message.

If an error occurs, you should pass the value of `auc_errno` to this function in order to obtain the natural language error message associated with the error. A detailed explanation on error handling, error messages and predefined named constants can be found in chapter 5.2 on page 14.

The memory pointed to by the returned pointer must not be freed.

4.3.5. `auc_utf_t_to_name()`

```
const char * auc_utf_t_to_name(auc_utf_t utf);
```

The function takes a numeric representation corresponding to a Unicode Transformation Format as defined by `auc_utf_t` and returns a pointer to a read-only string (`const char *`) that contains the name of the Unicode Transformation Format referenced by `utf`.

The memory pointed to by the returned pointer must not be freed.

4.3.6. `auc_version()`

```
int auc_version();
```

The function does not take an argument and returns a numeric representation of [AutoUniConv's](#) version.

4.3.7. `auc_version_string()`

```
const char * auc_version_string();
```

The function does not take an argument and returns a pointer to a read-only string containing [AutoUniConv's](#) version (`const char *`), for example "1.2.0".

The memory pointed to by the returned pointer must not be freed.

5. Error Handling

In case an error occurs within one of the main functions of `AutoUniConv`, a pointer to `NULL` is returned and `auc_errno` is set to an appropriate value indicating the occurred error (\neq `AUC_OK`).

The general error handling policy should be implemented as follows:

1. Return value does not equal `NULL`? → No error
2. Return value equals `NULL`? → An error occurred
 - a) Evaluate `auc_errno`, handle the error and eventually
 - b) utilize `auc_strerror()` to obtain a natural language error message describing the occurred error




Figure 7: Flowchart of the `AutoUniConv` error handling

`AutoUniConv`'s error handling takes allocation of memory into account and frees all allocated memory in every known error path.

5.1. Pseudo-Variable `auc_errno`

`auc_errno` may be used by many threads simultaneously, because it is not implemented as a global variable. The memory necessary for `auc_errno` is allocated on a per-thread basis using Thread-Local Storage (TLS). This way each thread is able to utilize its own `auc_errno` variable.

Nevertheless `auc_errno` can be used as if it was a common global variable¹.

If an error occurs, `auc_errno` is set to a value that discriminates the error. On any call of one of `AutoUniConv`'s main functions, the value of `auc_errno` is reset to `AUC_OK`.

¹Each occurrence of `auc_errno` is replaced with a call to the function `auc_errno_location()`, which returns the address of the thread-local variable, by the C preprocessor. As a result, `auc_errno` can be used as if it was a global variable, although it is not. Therefore we call it a pseudo-variable.

5.2. auc_errno_t Named Error Constants

AutoUniConv uses the type `auc_errno_t` to provide named error constants for all error cases. There is a constant defined for any runtime error.

If an error occurs, `auc_errno` is set to a value of type `auc_errno_t` that indicates the error. This way, case dependent error handling can easily be implemented in any application using **AutoUniConv**.

The named error constant may, as well as `auc_errno`, be used to obtain a natural language error message describing the numeric error code (see chapter 4.3.4, page 12).

The following table comprises all named error constants used in **AutoUniConv** version 1.2.0, accompanied by the error messages returned if passed to `auc_strerror()`.

Constant	Error Message
AUC_OK	No error
AUC_ENOMEM	Memory allocation failed
AUC_EARG	Invalid argument
AUC_ESHORT	Insufficient input length
AUC_EIDENT	Identifying charset failed
AUC_ENODEC	No decoder available for charset
AUC_EDEC	Decoding failed
AUC_EENC	Encoding failed
AUC_EBINARY	Binary input data
AUC_EEMBNUL	Embedded NUL character

Figure 8: `auc_errno_t` Named Constants

6. Hints on Application Development

6.1. Achieving Optimal Conversion

The identification of a charset may be a very complex process, because most charsets do not contain any metadata that discriminates them. As a result, **AutoUniConv** relies on a set of algorithms to obtain this information from the text itself. Most of these algorithms, however, gain better results the more input is available for identification. We recommend an input length of at least 25 characters.

Besides that we recommend to pass the text to be processed by your application to **AutoUniConv** as early and as complete as possible, for example right before tokenization.

This way your application will not only be optimized in respect to the results' quality, but also with respect to runtime performance, because this approach helps saving overhead and a lot of (unnecessary) function calls.

6.2. Determining AutoUniConv's Version

After including the *auc.h* header, the macro `AUC_VERSION_STRING` is available and replaced by a character string containing **AutoUniConv**'s version by the C preprocessor *at compile time*.

To determine **AutoUniConv**'s version at runtime, use `auc_version_string()` (see chapter 4.3.7, page 12).

A. Example Application

```
/*
 * An example application introducing AutoUniConv's auc_nconv().
 */
#include <stdio.h>
#include <stdlib.h>
#include <string.h>

#include <auc.h>

#define BUFSIZE 2048

int main(int argc, char *argv[])
{
    FILE          *fp = NULL;
    auc_bytes_t   *b  = NULL;
    auc_utf_t     utf;
    char          buf[BUFSIZE + 1];
    size_t        read;

    if (argc != 3)
    {
        fprintf(stderr, "usage: %s UTF file\n", argv[0]);
        return EXIT_FAILURE;
    }

    /* map requested UTF string to auc_utf_t */
    if (strcmp(argv[1], "UTF-8") == 0)
    {
        utf = AUC_UTF8;
    }
    else if (strcmp(argv[1], "UTF-16LE") == 0)
    {
        utf = AUC_UTF16LE;
    }
    else if (strcmp(argv[1], "UTF-16BE") == 0)
    {
        utf = AUC_UTF16BE;
    }
    else if (strcmp(argv[1], "UTF-32LE") == 0)
    {
        utf = AUC_UTF32LE;
    }
    else if (strcmp(argv[1], "UTF-32BE") == 0)
    {
        utf = AUC_UTF32BE;
    }
    else
    {
        fprintf(stderr, "unhandled UTF value: %s\n", argv[1]);
        return EXIT_FAILURE;
    }
}
```



```

/* read the first BUFSIZE (or less) bytes from file */
if ((fp = fopen(argv[2], "rb")) == NULL)
{
    fprintf(stderr, "%s: failed to open\n", argv[2]);
    return EXIT_FAILURE;
}

read = fread(buf, 1, BUFSIZE, fp);
buf[read] = 0x00;
fclose(fp);

printf("%s: %u bytes\n", argv[2], (unsigned int) read);

if (! read)
{
    fprintf(stderr, "%s: no bytes read\n", argv[2]);
    return EXIT_FAILURE;
}

/* automatically convert the read bytes to the requested UTF */
b = auc_nconv(buf, read, utf, AUC_WARN);

if (b) /* not NULL -> success */
{
    printf("auc_nconv returned %u %s bytes\n",
        (unsigned int) b->len, auc_utf_t_to_name(b->utf));

    if (b->utf == AUC_UTF8) /* do not print UTF-16 & -32 */
    {
        printf("\n%s", b->bytes);
    }

    auc_free_bytes_t(b);
}
else /* NULL -> error */
{
    fprintf(stderr, "auc_nconv failed: %s\n",
        auc_strerror(auc_errno));
    return EXIT_FAILURE;
}

return EXIT_SUCCESS;
}

```

The following output shows an example execution of the application:

```
$ cat /tmp/french_iso-8859-1.txt
Tous les ?tres humains naissent libres et ?gaux en dignit? et
en droits.
$ ./auc-example UTF-8 /tmp/french_iso-8859-1.txt
/tmp/french_iso-8859-1.txt: 73 bytes
auc_nconv returned 76 UTF-8 bytes

Tous les êtres humains naissent libres et égaux en dignité et
en droits.
```

B. References

- Lingua-Systems' [AutoUniConv SDK](http://www.lingua-systems.com/unicode-converter/) product website,
- The Unicode Standard, <http://unicode.org/>
- RFC 2781: "UTF-16, an encoding of ISO 10646", <http://www.ietf.org/rfc/rfc2781.txt>
- RFC 2279: "UTF-8, a transformation format of ISO 10646", <http://www.ietf.org/rfc/rfc2279.txt>



<http://www.lingua-systems.com/unicode-converter/>

Index

A

auc_conv()	11
auc_errno	12, 13
auc_errno_t	14
AUC_EARG	14
AUC_EBINARY	14
AUC_EDEC	14
AUC_EEMBNUL	14
AUC_EENC	14
AUC_EIDENT	14
AUC_ENODEC	14
AUC_ENOMEM	14
AUC_ESHORT	14
AUC_OK	14
auc_flag_t	10
AUC_DEFAULT	10
AUC_STRICT	10
AUC_WARN	10
auc_free_bytes_t()	12
auc_nconv()	11
auc_strerror()	12
auc_utf_t	10
AUC_UTF16BE	10
AUC_UTF16LE	10
AUC_UTF32BE	10
AUC_UTF32LE	10
AUC_UTF8	10
auc_utf_t_to_name()	12
auc_version()	12
AUC_VERSION_STRING	15
auc_version_string()	12, 15

D

deinstalling the software	7
dependencies	<i>see requirements</i>

E

error codes	<i>see auc_errno_t</i>
error handling	13
auc_errno	13
named constants	14
example application	16

F

flags	<i>see auc_flag_t</i>
-------	-----------------------

I

input	8
byte string	8, 11
string	8, 11
installing the software	7

N

named error constants	14
-----------------------	----

O

optimization	15
--------------	----

R

references	18
requirements	7

S

supported character encodings	<i>see supported charsets</i>
supported charsets	6
input	6
output	6

U

Unicode Transformation Format	<i>see auc_utf_t</i>
-------------------------------	----------------------