



User's Manual

© 2003 - 2007 Digital Atlantic Corp.

CDRoller - User's Manual

© 2003 - 2007 Digital Atlantic Corp.

All rights reserved. No parts of this work may be reproduced in any form or by any means - graphic, electronic, or mechanical, including photocopying, recording, taping, or information storage and retrieval systems - without the written permission of Digital Atlantic Corp.

This document is as current as possible but the accompanying software product may have changed since its publication. The instructions in this document make no claim to describe all details or variations in the equipment, procedures or processes described, nor to provide directions for meeting every possible contingency during installation, operation or maintenance.

Digital Atlantic Corp. reserves the right to change any information contained in this document or accompanying software at any time without prior notice.

Table of Contents

Introduction.	3
1. Installing CDRoller.	4
2. Uninstalling CDRoller.	11
3. Opening and Closing CDRoller.	12
4. How to register the program.	13
5. How to upgrade CDRoller.	14
6. Recovering CD/DVD Data.	15
Overview.	15
6.1. Disk recognition.	15
6.2. Using Session Selector.	17
6.3. Searching the lost UDF files on CD-R/DVD-R/DVD+R disks.	18
6.4. Applying Scan UDF Disc.	19
6.5. Recovering files.	20
6.6. Reading mini DVD-R discs created by Hitachi or Panasonic DVD camcorders.	21
6.7. Recovering files from DVD discs created by Roxio Classic Creator 6.	22
6.8. Retrieving the photos from mini discs created by Sony Mavica CD cameras.	22
6.9. Recovering video data off the discs created by DVD recorders (standalone devices).	23
6.10. Reading mini DVD-R/RW discs created by Sony DVD Camcorders.	25
6.11. Identifying Raw ISO Data	25
6.12. Recovering DVD video data using Wizard interface.	26
6.12.1. Creating a new DVD with recovered video.	29
6.13 Burning recovered files.	30
7. Additional features.	33
Overview.	33
7.1. Testing disc.	33
7.2. Extracting Audio Tracks.	34
7.3. Extracting ISO Image File.	36
7.4. Creating Short CD/DVD Image.	36
8. Contacting Technical Support.	38

Annex A Controls and dialog boxes.	39
A.1. Main Window.	39
A.2. Main Menu Commands.	41
A.3. The Toolbars.	42
A.4. Preferences	43
A.4.1. Browser	43
A.4.2. UDF Reader	45
A.4.3. ISO Reader	49
A.4.4. CD/DVD Library	50
A.4.5. Audio Extraction	51
A.4.6. Disc Test	52
Annex B License Agreement	54

Introduction.

CDRoller is a powerful, easy-to-use and low-cost toolset for CD/DVD data recovery.

Powerful: CDRoller finds, retrieves and copies the lost data from CDs and DVDs that seem to be inaccessible for Windows standard tools. While this does not include the disks that are physically damaged, the program will:

- Effectively retrieve the data off the discs created by "drag and drop" CD/DVD writing software, such as well-known Roxio (Adaptec) and Ahead Nero software packages, CeQuadrat's PacketCD, Instant Write, B's CLiP and others.
- Recover CD and DVD data created by standalone devices that record directly onto disks, including: Sony digital cameras, Hitachi, Panasonic, Canon and Sony DVD camcorders, personal DVD recorders, etc.
- Includes a built-in Video Splitter. Splits the recovered VOB or VRO files into a several clips (scenes), automatically converting a "raw" DVD-video into MPEG files without loss of quality. Specially tested on the discs, created by Hitachi DVD camcorders.
- Includes a built-in CD/DVD data burner. Burns your data onto CDs and DVDs with the most compatible ISO/Joliet file system. There is no need to run 3-rd party CD/DVD writing software if you wish to backup your files and folders immediately after recovery. The "Burn" option is integrated into a common shell. Just write a new disc with recovered data within a couple of minutes, without leaving CDRoller!
- Erases CD and DVD re-writable media. Support of quick and full erase methods.
- Retrieve back up files from the discs recorded in the several stages (multisession discs).
- Include a built-in UDF Reader. There is no need to install a third-party software, for example Roxio (Adaptec) UDF Reader driver.
- Find and retrieve the lost files on UDF discs, including: accidentally deleted files, files on quick-formatted disc, files on incorrectly closed disc, etc.
- Identifies the lost files on ISO/Joliet discs with the damaged file system (volume descriptors, path tables and directories), using the raw data only.
- Simply retrieve data from scratched, damaged or defective discs.
- Extract tracks from audio CDs
- Test CD/DVD readability

Easy-to-use: All features are integrated into a common and easy-to-use intuitive shell.

Low-cost: A single user license costs only 34 USD.

Toolset: The program contains a set of instruments to work with different formats of CDs (DVDs) and file systems.

CD/DVD Data Recovery: Unfortunately, there is a lot of factors that can cause you to lose access to the data on your disks. System or power failures, hardware problems, media and CD/DVD mastering software problems... Often, when a disc becomes inaccessible more than a single factor has contributed to the problem. Fortunately, many of such problems that prevent "normal" access to the data can be bypassed when using CDRoller.

1. Installing CDRoller.

To install CDRoller, you need at least:

- Microsoft Windows 95/98/ME/NT4/2000/XP/2003/Vista operating system
- Intel Pentium or compatible CPU
- 256 MB of RAM
- 9 MB free hard disk space
- CD/DVD drive(s). The devices with IDE or SCSI interfaces are highly recommended.

Note. You must have administrator rights to install the program under Windows NT4, Windows 2000 or Windows XP.

There are no special considerations for installing CDRoller. It uses no .INI files, and only uses the registry for holding installation options. It will initially use default options that will be changed further via the user preferences.


To install CDRoller:

1. Run the installation file. The installation program displays a **Welcome** page similar to the one shown here.




Click the **Next** button.

2. The installation program displays a **License Agreement** page similar to the one shown here.




Read the license agreement displayed and if you agree to its terms click the **I accept the agreement**. You must agree to terms of the license agreement to install CDRoller.

3. The installation program displays a **Destination Location** page similar to the one shown here.




CDRoller consists of a number of files containing the program and help information. It is recommended that you accept the default folder structure provided in the installation program. When you're satisfied with the installation folder specification, click the **Next** button.

4. The installation program displays a **Select Start Menu Folder** page similar to the one shown here.




By default, the installation program creates an **CDRoller** folder on your start menu. This is what you'll see when you choose Start | Programs on the Windows taskbar. If you want to use an existing folder, choose it from the list shown; if you want to use a different name, type it in the text field. When you're satisfied with your start menu folder selection, click the **Next** button.

5. The installation program displays a **Select Additional Tasks** page similar to the one shown here.



If you work with CDRoller the first time, we recommend you to read the **Quick References** before start of the program. Please consult our **User's Manual** to read more about specific features of CD/DVD data recovery, for example: retrieving the data off the discs created by digital cameras, DVD camcorders, or standalone DVD recorders.

6. The installation program displays a **Ready To Install** page similar to the one shown here.



You've made all the choices necessary to begin installation. Click the **Install** button to begin installing CDRoller.

7. After the copying of files to your computer has been completed, the installation program displays a **Finish** page similar to the one shown here.



If you install CDRoller under Windows 95/98/ME, we recommend you to restart your computer. Click the **Finish** button. Installation of CDRoller is complete.

2. Uninstalling CDRoller.

To uninstall CDRoller you can either:

- Use the menu selection created for this purpose.
- Select the Add/Remove Programs applet from the Windows Control Panel.

CDRoller does not install any system DLLs and does not modify Windows in any manner. Uninstalling this program will not affect other applications. To uninstall CDRoller, click the **Start** button on the Windows Taskbar, then choose **Programs | CDRoller | Uninstall CDRoller**.

3. Opening and Closing CDRoller.

Opening CDRoller.

To open the program, click the **Start** button on the Windows Taskbar, then choose **Programs | CDRoller | CDRoller**.

Closing CDRoller.

Close CDRoller as you would any other Windows application by using the **File | Exit** menu item or **Alt+F4** keyboard shortcut.

4. How to register the program.

Unregistered version does not permit copying CD/DVD objects for the purposes of recovering data - the program checks readability of CD/DVD files, but it can not save the files to the destination drive. To enable the full functionality you have to purchase the software and register your copy of CDRoller with the help of your license key.

You can always order CDRoller using credit cards or another methods of payments if you visit web page at <http://www.cdroller.com/htm/purchase.html>.

To register the program:

1. Open CDRoller.
2. Select **Help | Register** option in the Main Menu.
3. Enter your name and personal license key.
4. Click Accept button and restart CDRoller.

5. How to upgrade CDRoller.

To upgrade CDRoller:

1. [Uninstall](#) an old version of the program.
2. Download a trial copy of CDRoller at <http://www.cdroller.com/htm/download.html> and [install](#) it.
3. [Register](#) a trial copy with the help of your licence key.

Note. To upgrade your previous version of CDRoller (3, 4, 5 or 6) to CDRoller 7, you should contact our Sales Dept at sales@cdroller.com. Please send us your personal license key, or the name and and e-mail address that you used when purchasing the software, or any other info (your order ID, post address, etc.) that may help us to identify your purchase status. Your request will be responded shortly, usually within 2 to 12 hours.

6. Recovering CD/DVD Data.

Overview.

The process of CD/DVD data recovery is not easy and, unfortunately, it's very hard to create a "magic" tool can retrieve all data in all cases on all discs. In this section, we will try to give you a base recommendations how to achieve a positive result quickly and with a high reliability. Also, you can always receive a technical support at support@cdroller.com, all your questions regarding the problems with CD/DVD data recovery will be responded within 2 to 24 hours.

We consider the following steps can be high-lighted:

1. [Disk recognition](#).
2. [Using Session Selector](#) to access to all sessions on multisession disk.
3. [Searching the lost UDF files on CD-R/DVD-R/DVD+R disks](#)
4. [Applying Scan UDF Disc](#) to search for the lost objects on all types of UDF disks.
5. [Recovering CD/DVD files](#).


Note. The 2nd...4th steps may be skipped. This depends on the disk type determined at the 1st step.

Separately, we high-light the following problems:

- [Reading mini DVD-R discs created by Hitachi or Panasonic DVD Camcorders](#)
- [Recovering the files from DVD discs created by Roxio Classic Creator 6](#)
- [Retrieving the photos from mini discs created by Sony Mavica CD cameras](#)
- [Recovering video data off the discs created by DVD recorders \(standalone devices\)](#)
- [Reading mini DVD-R/RW discs created by Sony DVD Camcorders](#)
- [Identifying Raw ISO Data](#)
- [Recovering DVD video data using Wizard interface](#).
- [Burning recovered files](#).

6.1. Disk recognition.

Open CDRoller and insert the disk into the drive. The program must analyse your CD/DVD immediately after insertion. After the disk has been verified, the **Main Window** displays it similar to the one shown here.



Look at the **File System** column. This may give us an important info about the type of the disk. In the picture shown above, this is a disk in which **UDF** file system has been placed onto a single session. We will name the disk has **one or more** such sessions as "**UDF disk**". If **all** sessions are displayed with "ISO/Joliet" in the **File System** column, we will name such disk as "**ISO disk**", i.e the disk with ISO 9660 file system.

At first, click the **Recover All** button in the Toolbar in order to retrieve all files and folders off the disc or selected (current) session. Also, check out a readability of the root directory (folder), just left double click on the disk name, or use the **Open** command from the Side Bar. Please answer to the following questions: Is the root folder readable or not? Can i browse the disk contents? The answers may be applicable at the next stages of cd/dvd data recovery.

Troubleshootings.

1. If the program can not recognize your disk automatically, click the **Refresh** button in the Tool Bar, or insert the disk first and then open CDRoller. Also, to read the unclosed disks, i.e the disks left "as-is" by CD/DVD mastering program we recommend you to use the following method:

- Uncheck **Detect disc insertion by Windows** under the [Browser](#) tab in the Preferences dialog and wait for the end of disk reading processed by another CD related program.
- Select the **Refresh** command from the **File** menu, or click the **Refresh** button in the Tool Bar.

2. To read **UDF** disks we recommend you to use CD-RW (DVD-) drives - the disks are recorded with so-called packet-written technology and old CD-ROM / DVD-ROM drives may not access to their data.

3. Some drives may not support our special methods. These devices may hang the program when analyzing the disk. In this case, uncheck **Always use a drive capabilities** under the [Browser](#) tab in the Preferences dialog, insert the disk and try to recognize it again.

4. If you get '**Unknown file system...**' message and you're sure the files data were placed on the disc, please try to scan your disc without using the file system structures:

- If you know **ISO/Joliet** file system was actually placed on the disc, try the [Identify Raw ISO Data](#) command.

- In case of **UDF** disc, if you know a name of CD/DVD mastering program (or standalone device),


which actually created your disc, try the **forced scan**, selecting the software or device profile in the forced scan list under the [UDF Reader](#) tab in the Preferences dialog.

6.2. Using Session Selector.

We often receive the emails similar to the following one:

"I have copied back up files to a CDR in several stages, but the last time I backed up, I was only able to see the most recent batch of files. The others seem to have disappeared... I presume they are still there on the CD but "hidden" in some way - may be a different volume?"

Fortunately, CDRoller offers the tool named as "**Session Selector**" to access to the data placed into different sessions (volumes) on your CD-R/DVD-R. These disks are known as **multisession CD/DVDs**. By default, CDRoller displays contents of the most recent session.



To select a new session, just click a new item with 'Disc Session' type in the main program window. Then, try to apply the **Recover All** command, or simply **Open** a new session. Probably, you will detect a new files that have been "hidden" before.

Note. **Recover All** retrieves all files from the selected (current) session only.

Hint.

Sessions Selector may be also extremely useful if the root folder of the last session seems to be unreadable at the "[Disk recognition](#)" stage, but some important files may be located (duplicated) in the previous session(s).

6.3. Searching the lost UDF files on CD-R/DVD-R/DVD+R disks.

A correct reading of UDF files and folders on write-once media (CD-R/DVD-R/DVD+R) is provided by Virtual Allocation Table (VAT). Each time, when you add, change or delete files on CD-R/DVD-R/DVD+R media, UDF mastering program creates a new VAT that reflects a new state of your disk. A new VAT is being placed on the disk physically, when you eject the disk from CD/DVD drive. VAT's location is crucial for the disks created with the help of drag & drop software, such as well-known Roxio (Adaptec) DirectCD and Drag-To-Disc. If the VAT can not be found or is corrupted, files will be missing.


If your CD-R/DVD-R/DVD+R **is recognized as UDF one**, but when you try to open the disk, you get the error message about **unreadable root folder** - this means the last VAT is not found. Also, if you have **accidentally deleted** some files, a new VAT does not point to them. To recover the deleted files, you should use the previous VATs.

There are two main ways to find the lost files:


1. Using **Scan UDF Disc** from the Tools menu.
2. Searching an old VATs in order to recover the files from the previous backups.

The first method is described in the section 6.4. To search all VATs, please do the following:

- Click the Preferences button in the Tool Bar or select the same option from the View menu. Check on the 'Search of all VATs' box on the UDF Reader tab in the Preferences dialog. Click the OK button to close the Preferences.
- Click the Refresh button in the Tool Bar. After a while the program will display a progress dialog similar to the one shown here:



- when the process is completed, you should see the confirmation message:



- Click the OK buttons in this and all further dialogs. The program considers an each backup as a **separate "session"**. When you will see a new disk image (icon) in the program window, please use built-in **Session Selector** (see the section 6.2) for access to all backups.

Note. Please do not search all VATs on the following disks:


- CD-RW/DVD-RW/DVD+RW,
 - DVD-R and DVD+R created by DVD personal recorder (standalone device) and DVD camcorder.
- These disks do not contain VAT at all.

6.4. Applying Scan UDF Disc.


In addition to another methods of CD/DVD data recovery, **Scan UDF Disc** gives you a good chance to retrieve several types of files, including:

- Files are not visible in Windows Explorer - the **writing process was interrupted by a system or power failure** before UDF folders were placed on the disc, but most or all of the files were written to the disk. This means that the files may be on the CD (DVD), but Windows Explorer cannot see them.
- Lost files - complete files that do not have a file name associated with them. They can also be files that you **accidentally deleted** from the CD (DVD).
- Files on the disks **quick-formatted** by Roxio DirectCD and Nero InCD.
- Files located in **unreadable** (damaged) **UDF folders**, including the root one.
- Files located on **Sony Mavica CD** finalized with failure on the camera.

To start **Scan UDF Disc** select the same option in the **Tools** menu or in the **Side Bar**. The program displays a progress dialog similar to the one shown here.



After CD/DVD scan is completed or canceled, found files and/or folders are displayed in the **Lost objects detected on disc...** window similar to the one shown here



You can rename the selected folders, open them with the help of **Open** command, or left double clicking on their names. If the lost folders have been found, try to open them first. This may give you a

chance to recover the files with original names that are located in the found folders.

When applying the **Recover All / Recover Selected** commands, the program automatically identifies the types of files, initially shown as FileXXXX ones, or the files having an intermediate extensions, such as .ole2 for MS Office ones.

If you know an original type, you can rename the selected files manually, with the help of **Rename** command, or/and use **New Extension** option to speed up the re-naming process in case of the large list.

Hints and Tips.

If you're going to retrieve UDF files from the same disc at the different times, you can save the table of contents (names, locations, attributes) of the found files into separate file by **Save Table Of Contents** command from the **File** menu. Further, check on the **Load Table Of Contents from file box** on the **UDF Reader** tab in the **Preferences** dialog. Next time, when you will run **Scan UDF Disc** the program will display the list of the found objects shortly, without scanning the disc, and you can continue to retrieve the files data.

Trouble Shooting.

If the program can not recognize UDF disk, but you are certainly sure the disk contains the files, we recommend you to try the **forced scan** of the disk. This may be useful if the disk was incorrectly finalized, and the system data are not accessible. For example, this problem often occurs on **Sony Mavica CD** when the finalization step failed on the camera.

To start the forced scan, you should initially know what CD/DVD mastering program (or device) formatted your disk. For example: Roxio (Adaptec) DirectCD, Nero InCD, PacketCD or Sony Mavica CD digital camera. Further, you should assign an appropriate profile in the **Forced scan** list under the [UDF Reader](#) tab in the Preferences dialog and click the **Refresh** button in the Tool Bar.


Note.

Obviously, there is no 100% guarantee to recover all displayed files completely, please keep in mind, that some files may be erased or partially re-written by a new ones. The program can restore those FILES DATA, which else it is possible to rescue.

6.5. Recovering files.

To recover the found files and folders, you can use **Recover All** and **Recover Selected** options, or simply drag and drop selected items to the destination you have chosen on your HDD.

When selecting **Recover All / Recover Selected** options, the program displays a **Data Recovery dialog** similar to the one shown here.



Key Features.

- **Saves recovered** data into intermediate file. Further, a recovery of the selected file can be continued with the help of **Resume Recovery** option in the program window.
- Displays the current results (recovery **details**).
- **Saves** recovery results (report) into HTML file.
- Changes a recovery **settings**, without leaving the process.
- **Skips** file during the recovery process, if you decide a file isn't so important.

6.6. Reading mini DVD-R discs created by Hitachi or Panasonic DVD camcorders.

6.6.1. Basic recommendations.

- We strongly recommend to use DVD-RW drives ("dvd writers"). DVD-ROM drives ("dvd readers") often can not access to the "troubled" or non-finalized DVD discs.
- You should uncheck the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes under the Browser tab in the Preferences dialog before you will insert the troubled disc into the drive.
- First, we strongly recommend to try the **Recover DVD Video** option. In addition, you can try to read the "troubled" discs, using a different settings under UDF Reader tab in the Preferences dialog (Chapters 6.6.2 and 6.6.3).

6.6.2. Reading non-finalized (open) DVD-R disc.

Symptom.

Disc was not finalized, you lost an access to the data due to **Disk Error** message when you turned on the camera.

Troubleshooting.

- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the **Preferences** button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes are UNCHECKED on the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the troubled DVD-R.
- Click the Preferences again. Set the **Forced scan** to **Hitachi DVD-R (O)** on the UDF reader tab. Click the OK button and close the Preferences again.
- Click the Refresh button in the Tool Bar. Do you see the **VTS_01_1.VOB file** in the **Lost objects detected...** window? If yes, go to the step 6.6.4.

6.6.3. Reading DVD-R disc that was finalized with error.

Symptom.

The disc finalization was accidentally interrupted, for example, due to the power failure.

Troubleshooting.

- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the **Preferences** button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes are UNCHECKED on the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the troubled DVD-R.
- Click the Preferences again. Set the **Forced scan** to **Hitachi DVD-R (F)** on the UDF reader tab. Click the OK button and close the Preferences again.
- Click the Refresh button in the Tool Bar. Does the program scan your disc? Are any files found within the first 100..200 sectors? If yes, try to select and **rename the largest file** to the .vob one with the help of **Rename** option in the Tool Bar and go to the step 6.6.4.

6.6.4. Recovering the found VOB files.

Select the VOB file(s) and apply the **Recover Selected** command. If a recovery process seems to be stalled ("frozen"), please click the **Save Recovered** button in the Data Recovery window.. When recovering, you can assign a new **settings** in the [Data Recovery](#) window, for example, selecting the **Fill sector by zeroes** in the **Overread** list.

6.6.5 Viewing the VOB files.

To view the VOB files, we recommend **PowerDVD** from CyberLink at <http://www.gocyberlink.com/>.

6.6.6. [Creating a new DVD with recovered video](#) .

6.7. Recovering files from DVD discs created by Roxio Classic Creator 6.

Symptom. The files and folders only from the first session (backup) seem to be shown on the DVD disc (DVD-R, DVD+R, DVD-RW, DVD+RW) created by Roxio Easy Creator Classic 6.

Cause & Troubleshooting.

If you have not changed the default settings in the Project Properties, Easy Creator Classic (EZ Classic) writes the both UDF and ISO (Joliet) file systems on the DVD discs. Unfortunately, probably due to the bug, EZ Classic hides a new files in UDF folders, but always shows them in ISO/Joliet ones. A solution is the following:

- Run CDRoller without any discs inserted.
- Click the **Preferences** button in the Tool Bar and check on **Read only ISO 9660 tracks box** on the [Browser](#) tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the DVD into the drive and click the **Refresh** button in the Tool Bar. Only ISO/Joliet files and folders will be shown.
- If the disc contains a several sessions, use the built-in [Session Selector](#).

6.8. Retrieving the photos from mini discs created by Sony Mavica CD cameras.

6.8.1. General requirements and settings.

- CD-RW or DVD-RW drives (cd or dvd "writers") are more preferable in comparing with CD-ROM or DVD-ROM drives (cd or dvd "readers").
- You should uncheck the **Detect disc insertion by Windows** box on the Browser tab in the Preferences dialog before you will insert the troubled disc into the drive.

6.8.2. Reading mini disc that was finalized with failure on the camera.

Symptom.

The disc finalization was accidently interrupted, for example, due to the power failure.

Troubleshooting.

- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the **Preferences** button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** is UNCHECKED on the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the troubled disc.
- Click the Refresh button in the Tool Bar.
- Does the program recognize your disc? If not, please go to the step 6.8.3
- If you can see the disc icon in the program window, try to open the disc by left-double clicking its name. Do you get the message about unreadable root folder? If yes, try to run Scan UDF Disc from the Tools menu and go to the step 6.8.4 if the program has found the lost files.

6.8.3. Reading non-finalized (open) disc.

Symptom.

Disc was not finalized, you lost an access to the data due to **Disk Error**. You was able to view the photos earlier (prior to the disk error).

Troubleshooting.

- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the **Preferences** button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** box is UNCHECKED on the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the troubled disc.
- Click the Preferences again. Select **Sony Mavica (O)** in the **Forced scan** list under the UDF reader tab. Click the OK button and close the Preferences again.
- Click the Refresh button in the Tool Bar. If dialog with **Step 1. Specify your scan area** caption appears, try to find and recover the lost photos step-by-step, using Wizard interface. Otherwise, the program tries to find the lost files, scanning "UDF partition". Are any files found? If yes, go to the step 6.8.4.

6.8.4. Recovering the found (indexed) files displayed in the "Lost objects detected..." window.

- Apply **Recover All / Recover selected** to retrieve the found files (photos) automatically.
- To view the found photos (JPEG files), you can use **View Image** option. Just select a JPEG file and click the **View Image** in the Side Bar (left panel of the "Lost objects detected..." window).
- Select file(s) and use **Rename** or/and **New Extension** commands to re-name the indexed files to .jpg ones, and then copy them to HDD with the help of **Recover selected** or **drag&drop** operations.

6.9. Recovering video data off the discs created by DVD recorders (standalone devices).

6.9.1. Basic recommendations.

- We strongly recommend to use DVD-RW drives ("dvd writers"). DVD-ROM drives ("dvd readers") often can not access to the "troubled" or non-finalized DVD discs.
- You should uncheck the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes under the Browser tab in the Preferences dialog before you will insert the troubled disc into the drive.
- First, we strongly recommend to try the **Recover DVD Video** option. In addition, you can try to read the "troubled" discs, using a different settings under UDF Reader tab in the Preferences dialog (Chapters 6.9.2 and 6.9.3).

6.9.2. Reading non-finalized (open) disc.

Symptom.

Disc was not finalized at all, you lost an access to the video data when you turned on the recorder.

Troubleshooting.

- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the **Preferences** button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes are UNCHECKED under the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the troubled disc.
- Click the Preferences again. Set the **Forced scan** to **Rec DVD+RW (O)** (in case of DVD+RW disc created by Thomson RCA, Philips, etc), or **LiteOn DVD+R (O)** or **Sanyo DVD+R (O)** (if the DVD+R disc was created by Lite-On or Sanyo DVD recorder) under the UDF reader tab. Click the OK button and close the Preferences again.
- Click the Refresh button in the Tool Bar. The **Lost objects detected...** window must appear

immediately. Do you see the **VTS_01_1.VOB** file? If yes, go to the step 6.9.5.

6.9.3. Reading the disc was finalized with error.

Symptom.

The disc finalization was accidentally interrupted, for example, due to the power failure.

Troubleshooting.

- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the **Preferences** button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes are **UNCHECKED** under the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the troubled DVD.
- Click the Preferences again. Set the **Forced scan** to **Rec DVD+RW (F)** (in case of DVD+RW disc created by Thomson RCA, Philips, etc), or **LiteOn DVD+R** or **Sanyo DVD+R (F)** (if the DVD+R disc was created by Lite-On or Sanyo DVD recorder) under the UDF reader tab. Click the OK button and close the Preferences again.
- Click the Refresh button in the Tool Bar. Does the program scan your disc? Are any files found within the first 100..200 sectors? If yes, try to select and **rename the largest file(s)** to the **.vob** one(s) with the help of **Rename** or/ and **New Extension** options and go to the step 6.9.5.

6.9.4. Reading quick-erased DVD-RAM disc.

Symptom.

Disc was accidentally quick-erased by DVD-RAM recorder. All movies seem to be lost.

Troubleshooting.

- Do not record any new movies.
- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the Preferences button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes are **UNCHECKED** under the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the troubled disc.
- Click the Preferences again. Set the **Forced scan** to **Rec DVD-RAM (E)** under the UDF reader tab. Click the OK button and close the Preferences again.
- Click the Refresh button in the Tool Bar. The **Lost objects detected...** window must appear immediately. Do you see the **VTS_01_1.VOB** file? If yes, go to the step 6.9.5.

Note. This feature was tested on the discs erased by Panasonic DVD-RAM recorder only. If you have any questions, please contact our Support Dept. at support@cdroller.com

6.9.5. Recovering the found VOB files.

Select the VOB file(s) and apply **Recover Selected** command. In case of non-finalized (open) disc (6.9.2) or quick-erased DVD-RAM (6.9.4), an actual length of the lost video data is unknown. If a recovery process seems to be stalled ("frozen"), please click the **Save Recovered** button in the [Data Recovery](#) window. Also, when recovering the files, you can assign a new settings in the **Data Recovery** window, for example, selecting the **Fill sector by zeroes** in the **Overread** list.

6.9.6. Viewing the VOB files.

To view the VOB files, we recommend **PowerDVD** from CyberLink at <http://www.gocyberlink.com/>.

6.9.7. [Creating a new DVD with recovered video](#) .

6.10. Reading mini DVD-R/RW discs created by Sony DVD Camcorders.

6.10.1. Basic recommendations.

- We strongly recommend to use DVD-RW drives ("dvd writers"). DVD-ROM drives ("dvd readers") often can not access to the "troubled" or non-finalized DVD discs.
- You should uncheck the **Detect disc insertion by Windows** and **Always use a drive capabilities** boxes under the Browser tab in the Preferences dialog before you will insert the troubled disc into the drive.
- First, we strongly recommend to try the [Recover DVD Video](#) option. In addition, you can try to read the "troubled" discs, using a different settings under UDF Reader tab in the Preferences dialog (Chapter 6.10.2).

6.10.2. Reading non-finalized (open) DVD-R/RW disc.

Symptom.

Disc was not finalized by your Sony DVD camcorder.

Troubleshooting.

- Remove any disks from your CD/DVD drive(s).
- Run CDRoller.
- Click the **Preferences** button in the Tool Bar or select the same option from the View menu. Make sure that the **Detect disc insertion by Windows** and **Always use a drive capabilities boxes** are **UNCHECKED** under the Browser tab in the Preferences dialog. Click the OK button to close the Preferences.
- Insert the non-finalized DVD-R or DVD-RW into the drive.
- Click the Preferences again. Set the **Forced scan** to **Sony DVD-R (O)**, **Sony DVD-RW (O)**, or **Sony DVD201-RW** under the UDF reader tab. Click the OK button and close the Preferences again.
- Click the Refresh button in the Tool Bar. Do you see some **VTS_01_XX.VOB files** in the **Lost objects detected...** window? If yes, go to the step 6.10.3.

Note. Each displayed VOB file can contain a few video clips

6.10.3. Recovering the found VOB files.

Select the file(s) and apply **Recover Selected** command. If a recovery process seems to be stalled ("frozen"), please click the **Save Recovered** button in the [Data Recovery](#) window. Also, when recovering the files, you can assign a new settings in the **Data Recovery** window, for example, selecting the **Fill sector by zeroes** in the **Overread** list.

6.10.4. Viewing the VOB files.

To view the VOB files, we recommend **PowerDVD** from CyberLink at <http://www.gocyberlink.com/>.

6.10.5. [Creating a new DVD with recovered video](#) .

6.11. Identifying Raw ISO Data


In addition to another methods of CD/DVD data recovery, **Raw ISO Data Identifier** gives you a good chance to find and retrieve the lost files from the troubled discs, created by Ahead Nero Burning ROM, Adaptec (Roxio) Easy CD/DVD Creator, Sonic software and other programs, including:

- CDs and DVDs with currently **unreadable system area** (so-called Primary and Secondary ISO Volume Descriptors). When trying to recognize these discs the first time, CDRoller generates "*Unknown file system...*" error message.
- Discs with the **damaged and corrupted folders**.
- UDF Discs having **ISO-alike files locations**.

Note. Please use this option only if another methods of CD/DVD data recovery have not given an effect

before.

To start Raw ISO Data Identifier, please select the **Identify Raw ISO Data** option from the **Tools** menu, or **Side Bar**. The program scans the disc and tries to find and identify the files on the track of "raw" CD/DVD sectors, without using the ISO/Joliet File System structures. After a process is completed or canceled, a found files are displayed in the **Lost objects detected ...** window similar to the one shown here




First, try to **Recover All** or **Selected** files. These commands also allow to complete an identification of files that have not been preliminary identified on the scan stage, or have an intermediate extensions. For example, **.ole2** for MS Office files. If you know an actual file name, you can **Rename** the selected file manually, or/and use **New Extension** command to speed the re-naming process in case of the large list of one-type files.

6.12. Recovering DVD video data using Wizard interface.


CDRoller Wizard interface is designed for novice users and allows to recover DVD videos and photos off the discs, created by standalone devices (camcorders, personal DVD recorders), using the simple "step by step" procedure. To display the Wizard dialog, just select the **Recover DVD Video** option from the **File** Menu.

Every Wizard dialog contains a brief instructions, describing a possible user actions in order to achieve the best results in DVD data recovery.

At the 1st step, please select your computer DVD drive. We recommend to use the computer DVD-RW drives (dvd writers) in order to read non-finalized or "troubled" DVD discs.




At the 2nd step, just insert your DVD and click the **Next** button.




At the 3rd step, please select DVD video recorder (camcorder or standalone dvd recorder) that placed a video or/and photos on your disc. You can use **Any recorder** setting and try to scan each of displayed tracks, starting on the track with the highest length.




At the 4th step, just click the Next button if you scan the selected area for the first time.



At the next step, you should see a dialog similar to the one shown here.




Finally, just recover the found video (VOB files). You can also try to scan another track, shown at the 3rd step.



Note. To view the VOB files, we recommend **PowerDVD** from CyberLink at <http://www.gocyberlink.com/>.

6.12.1. Creating a new DVD with recovered video.

Split video option splits a recovered VOB or VRO files into a several clips (scenes), automatically converting a "raw" DVD-video data into MPEG files without loss of quality. In contrast to VOB files, MPEG files can be simply viewed with the help of any DVD-compatible software (player) and also can be loaded into your DVD-authoring software, for example: Sonic MyDVD, Nero Vision, etc.




Before splitting, you should recover the found VOB or VRO files off DVD, for example with the help of **Recover All** or **Recover Selected** commands. Further, just select VOB or VRO file in the CDRoller window again, click the **Split Video** in the Side Bar (left panel of the window where you see the file) and assign the recovered file name in the next dialog. Or, just click the **Split Video** button in the [Main ToolBar](#).

6.13 Burning recovered files.


CDRoller Wizard interface allows to burn CD/DVD data, using a simple "step by step" procedure. To display the Wizard dialog, just click the **Burn** button in the [Main ToolBar](#) or select the same option from File Menu.

At the 1st step, please select your burner (computer CD or DVD drive) and click the **Next** button. The displayed drive features can help you to determine whether the selected device supports the type of CD or DVD media you want to burn. For example, do not try to burn DVD discs, using CD-RW drive.




At the 2nd step, just insert a new (blank) disc and click the **Next** button. For multisession disc, you can


select a prior session to be included into a current compilation.




At the 3rd step, please add files or/and folders into your current compilation and click the Next button. You can use **Add** button, or just drag files and folders from the Windows Explorer. To edit a current compilation, please use **Delete** and **Rename** options for the selected item(s).



At the 4th step, you can edit disc (session) name, assign writing speed and choose - whether you will add a new files on the same disc later or not. To start a burn process, just click the **Burn!** button.



Finally, you should see "Burning disc ..." dialog similar to the one shown here.



Notes.

1. We do not recommend to try to place a new files onto your "troubled" discs. Also, please do not try to close these discs, hoping to make them readable for Windows. The most safe way is to recover your files from the "troubled" disc to Hard Disk Drive (HDD) first, and then place (write) them onto a new blank disc.
2. To erase your re-writable disc, just click the **Erase** button in the [Main ToolBar](#) or use the same option from File Menu.

7. Additional features.

Overview.

- In addition to CD/DVD data recovery the program offers set of features for:
- [Testing Disc](#)
- [Extracting Audio Tracks](#)
- [Extracting ISO Image File](#)
- [Creating Short CD/DVD Image](#)

All mentioned features are integrated into a common intuitive shell of CDRoller.

7.1. Testing disc.

With the help of Disc Test, you can check if a CD or DVD contains errors. It can be useful to:

- Check the quality of the CD/DVD media.
- If you have a CD/DVD recorder, you can check whether the data (files and folders) on the CD/DVD-R(W) is written correctly.
- Get advanced information from the Disc Volume.


The test can be used for both CD-ROM and CD-Audio. It also examines Multisession and Mixed mode discs.

The list of tests includes **ISO 9660 File System** test, **Disc Surface** test and **Digital Audio Extraction (DAE) Quality** test. Since the program automatically determines the disc type, it always knows what the test from the list can be applied to the CD/DVD inserted into the drive. By [Disc Test](#) options, you can manually include (exclude) an appropriate test to (from) the list, set scan ratio while testing CD/DVD surface and also select checks of all sessions or only current session on multisession disc.


We recommend you to run the disc test periodically on the discs with ISO/Joliet file systems, in order to make sure a valuable files were really ("physically") placed on the disc, particularly in the following situations:

- if your DVD was created by **Nero Burning ROM**.
- if your CD with photos was burnt from **memory cards**.

To start the disc test, please select the **Test Disc** option in the **Tools** menu. The program displays a progress dialog similar to the one shown here.



After all tests have completed, the program generates the report(s). An example of ISO/Joliet File System report is shown here.




Note. The Disc Test is not available for the **UDF** disks.

7.2. Extracting Audio Tracks.

To extract ("rip") audio track(s):

1. Insert CD audio into the drive.
2. After disk recognition left double click on CD name in the Main Window. The program displays the **Main Window** similar to the one shown here.



3. Select the track(s).

4. Click the **Recover Selected** command in the Side Bar, or simply drag and drop selected track(s) to the destination on HDD.

5. The program displays a progress dialog similar to the one shown here.



To extract audio tracks the program utilize the method known as **Digital Audio Extraction (DAE)**. Key features:

- Applies a set of different extraction methods with Dynamic, Fixed synchronization with "jitter" correction, re-read block of sectors in case of error or/and lost of synchronization.
- Autodetects an appropriate read function for CD drive.
- Supports WAV, MP3, MP2, OGG or RAW formats of output file.
- Supports Windows ACM (Windows Audio Compression Manager).
- Supports Lame and Blade MP3 encoders (DLLs) and Ogg Vorbis, high-quality and patent-free audio codec.
- Extracts audio tracks "on-the-fly", directly to the output file without creating an intermediate WAV file.

Hint.

To change default settings (select another encoder, extraction method, etc.) use [Audio Extraction](#) tab in the Preferences dialog.


7.3. Extracting ISO Image File.

ISO Image is a single large file that is a representation of the whole set of data and programs as it will appear on a CD or DVD. A disc image refers to both content and logical format. It can be useful to:

- Replicate your CD (DVD) further using CD/DVD mastering programs such as Adaptec Easy CD Creator, Nero Burning ROM, Goldenhawk CDRWin, etc.
- Write the disc image to hard drive once, then record it several times to different CDs (DVDs) to save processing time.
- Create a disc image file to be written to CD (DVD) on another system (UNIX, Macintosh).
- Back up CD/DVD data.

To extract ISO Image File:

1. Insert the disc into the drive.
2. After disk recognition select **Tools | Extract to ISO Image File** option.
3. The program displays a progress dialog similar to the one shown here.




Key Features.

- **Saves recovered** data into intermediate file. Further, you can continue to Extract ISO Image File with the help of **Resume Recovery** option in the program window.
- Displays the current results (recovery **details**).
- **Saves** recovery results (report) into HTML file.
- Changes a recovery **settings**, without leaving the process.

Note. ISO image file can be created only if the disk with a **single data track** originally was created using ISO-9660 or Joliet format. UDF disks, such as those created with DirectCD, Nero InCD and PacketCD, cannot be copied in this manner.

7.4. Creating Short CD/DVD Image.

The Short CD/DVD Image is a file that contains **ALL DIRECTORY STRUCTURE** (directory tree) of the disk, including complete folders and files names with attributes. This enables you to browse through the folders, search for the files or/and folders which you need (with the help of **Tools | Find** option), detect the properties of them, using the **Properties** command, but in order to retrieve any file, you should insert a "real" CD or DVD. When you insert a disc that has the image that has been created before, CDRoller determines this image as a "**mirror**" of the real CD(DVD), displays it with an appropriate icon in the **Main window** and further, utilizes image to access to any folder quickly without reading of inserted CD(DVD). This is an extremely useful if your "real" CD (DVD) has become a disc with unreadable folder(s) and, therefore you can not access to its files.



To create Short CD/DVD Image:

1. Insert CD or DVD into the drive.
2. Select **Tools** | **Short CD/DVD Image** option.

You can create the image with CD (DVD) name (label) or manually assign a new name for each inserted disk. In case of **multisession** disc, you can create CD/DVD image for each session. All CD/DVD images automatically are placed into a separate directory assigned under the [CD/DVD Library](#) tab in the Preferences dialog.

8. Contacting Technical Support.

The goal of the CDRoller Support Team is to provide our users unrivaled technical assistance when implementing CDRoller technologies. Our commitment to you is very simple. Top-notch support and immediate solutions to your technical problems. Since we have customers throughout the globe, we will do our best to respond to requests 24 hours a day. In fact, our support staff works staggered shifts for just this purpose.

You do not have to purchase the software in order to receive support, all your questions regarding CDRoller will be responded within 2 to 24 hours.


If you have purchased the product, please include the email address that you used when purchasing the software - we use this to confirm your purchase status and support requests from customers receive priority over others.

You can contact our support department via email at: support@cdroller.com. To be notified about new versions of CDRoller and new products please subscribe to our mailing list at <http://www.cdroller.com>. All questions regarding orders, licenses or other services should be directed to sales@cdroller.com. If you have any suggestions or comments regarding CDRoller, we'd like to hear from you. Please feel free to send an e-mail to suggest@cdroller.com. All suggestions will be at least considered and you will probably see them as new program's features in the future releases. If you have any problem with our web site at <http://www.cdroller.com>, please do not hesitate to contact our webmaster at webmaster@cdroller.com.

Annex A Controls and dialog boxes.



A.1. Main Window.

The **main program window** consists of **List Window**, **Status Bar** at the bottom, **Side Bar** at the left, **List of available folders**, **Tool Bar** and **Main Menu** on the top.






The List Window displays the disc contents as main folder containing drives, discs, sub-folders, files or audio tracks. A graphic symbol, or icon associates with every folder, file or audio track. CDRoller assigns a proprietary icon to each type of CD/DVD media: CDROM, CD-R, CD-RW have the icon as



all types of DVD media -  icon, CD-DA (Audio CD) is displayed with  icon, symbol as



associates with Mixed CD (data plus audio) and empty drive (drive without any disc) has the icon as . **Short CD/DVD image** has appropriate icon as , and the icon as  is assigned to the image that is the "mirror" of inserted disc.

To select an item in the List Window, click on its icon or name. If you want to work with multiple items in a folder, you can select (mark) each of them, using the check box near an each item. The total size of selected files is displayed by the status bar. To select all items in the current folder, or return to the prior level in the directory structure, you may also use an options from the secondary Tool Bar.

Side Bar similar to Microsoft Outlook offers an intuitive list of commands depending on your situation (disc type, file system, data recovery problems, etc.).

To adjust a column's width, you may move the mouse pointer to the right border of the column heading box. The mouse pointer changes to a double-headed horizontal arrow with a vertical bar in the middle.

That means you move the border. Hold down the mouse button and drag the border left or right as needed. When the border is in its preferred location, release the mouse button.

Every item displayed in the List Window has its own **Pop-up menu** - if you right-click on it, a menu will show up by it, displaying all the options available over the selected item.

All buttons on the **Toolbar and Side Bar** have a hint - if you don't know what the button does, just place the mouse over it and wait for a second, and a short description will appear.

CDRoller supports drag-and-drop - meaning that any file and/or folder can be copied to desired location on HDD, or any audio track can be extracted to the output file by drag-and-drop.

A.2. Main Menu Commands.

A.2.1. File Menu (*shortcut Alt + F*)

Command	Shortcut	Description
Open	Ctrl + O	Opens current (selected) disc, session, folder or file.
Recover All	F9	Recovers all available objects.
Recover DVD Video	F7	Runs video data recovery using the wizard interface.
Split Video	Ctrl + S	Converts a recovered video into MPEG files.
Refresh	F5	Causes all discs in all drives to be examined.
Properties	-	Displays properties of the selected object(s).
Burn	Ctrl + B	Runs CD/DVD burning process.
Erase	F11	Erases re-writable disc.
Exit	Alt + F4	Ends your CDRoller session.

A.2.2. View Menu (*shortcut : Alt + V*)

Command	Shortcut	Description
Side Bar	-	Shows/Hides Side Bar.
Status Bar	-	Shows/Hides Status Bar.
Tool Bar Icons Size	-	Selects a size of icons in the Tool Bar (Small or Large).
Vertical Lines	-	Shows/Hides the vertical lines.
Horizontal Lines	-	Shows/Hides the horizontal line below every item in the window.
Highlight Full Row	-	If Checked, the whole line will have the selection or the focus rectangle around it. If Unchecked, only item's main text will be highlighted.
Sort By	-	Controls the sequence or order of the folder contents by Name, Type, Size, Date or in Reverse Order.
Preferences	Ctrl + P	Sets up program options.

A.2.3. Tools Menu (*shortcut : Alt + T*)

Command	Shortcut	Description
Find	F3	Activates the Search Window to search contents of the inserted discs and also in the collection of previously created Short CD/DVD Images.
Short CD/DVD Image	Ctrl + I	Creates and adds a new CD/DVD image to the library.
Test Disc	Ctrl + T	Runs Disc Test.
Extract To ISO Image File	Ctrl + E	Creates ISO 9660 Image File.
Scan UDF Disc	Ctrl + U	Runs Scan UDF Disc
Identify Raw ISO Data	Ctrl + R	Runs search and identification of ISO files, without using a system and directories structures.

A.2.4. Help Menu (shortcut : Alt + H)

Command	Shortcut	Description
Contents	F1	Opens the CDRoller online help.
Ordering Information	-	Displays information about ordering CDRoller.
FAQs	-	Displays Frequently Asked Questions (FAQs) with answers about CDRoller.
Technical Support	-	Displays information about technical assistance.
Home Page	-	Visits the CDRoller web page.
About CDRoller	-	Displays copyright notice and enables you to register.


A.3. The Toolbars.

A.3.1. Main ToolBar.



The buttons of the Main ToolBar duplicate the corresponding options in the [File](#), [View](#) and [Tools](#) menu.

A.3.2. Secondary ToolBar.



Up One Level button returns focus to the parent item, usually to the parent folder (opens the folder of the higher level) that contains current folder.


Select All selects all items (files, sub-folders or audio tracks) in the current folder.

Deselect All unselects all items (files, sub-folders or audio tracks) in the current folder.

Show/Hides files checkboxes shows/hides checkboxes near each file or folder.

A.4. Preferences

A.4.1. Browser



Hardware Access Method (default value is: *CDRoller proprietary driver* for Windows 9x/ME or *Windows NT native access* for Windows NT4/2000/XP)

Detects one of two methods to access hardware. We strongly recommend you using default settings, and select ASPI mode only if you have a serious problems with base method.

Note. This option sets the fundamental mode of application operating. To apply new setting you should restart the program.

Date Format (default value *Short Form*)

Sets the Date format used by the program to display the Date information.

Time Format (default value *Short Form*)

Sets the Time format used by the program to display the Time information.

Treat KByte as: (default value *1024 bytes*)

Detects the way of 'kilobyte consideration' as 1024 bytes exactly (in 1024 bytes mode) or as 1000 bytes (in 1000 bytes mode). It may be useful for correct file (folders or audio tracks) size calculation, before these items will be sent to hard disk.

Search of the lost data track (default value *Checked*)

If *Checked*, the program searches the lost data track when a new disc is inserted or after **Refresh** command, and, if found, displays its contents in the List Window.

Detect disc insertion by Windows (default value *Checked*)

If *Checked* the program detects arrival or removal of the CD (DVD) using Windows "standard" tools (messages). This starts disc recognition automatically, without requirement of the refresh. If the program can not recognize your disc automatically, try to uncheck this option and repeat examination of a new disc by clicking the **Refresh** button in the Tool Bar.

Read damaged sectors "as is" (default value *Unchecked*)

If *Checked*, when reading **system area** and **folders**, unreadable sectors will be accepted "as-is". This may be useful in some circumstances, but it should be understood that the content of these "accepted" sectors could be all zero or partially correct data – there is no way to tell. You should use this mode only if the program can not "recognize" your damaged CD/DVD or you vitally need an access to the unreadable folder. Please keep in mind that your CD/DVD drive may not support reading of disk sector "as is" or the content of that sector may be denied by the further checks in compliance with ISO 9660 and UDF requirements.

Read only ISO 9660 data tracks (default value *Unchecked*)

If *Checked*, the program searches and verifies only ISO system area on data tracks after insertion of new disc. Discs with another file system, such as UDF, require additional recovery procedures that may take a some time, especially while reading multisession ones. If you are sure that your disc is actually recorded in **ISO 9660** format, you should check on this option in order to accelerate the disc recognition. Obviously, to read the discs with **UDF** file system, this option has to be unchecked

Always use a drive capabilities (default value *Checked*)

If *Checked*, when reading the damaged sectors, the program will apply some low-level methods and algorithms based on the capabilities of your CD (DVD) drive. In some circumstances the drive can slow the process when meeting a bad zones (unreadable sectors). In this case we recommend you to uncheck this option.

Display deleted files and folders (default value *Checked*)

If *Checked*, the program displays files and folders having *deleted* characteristics on CD-RW/DVD-RW/DVD+RW/DVD-RAM disks with UDF system. The objects are shown with special *Inaccessible file* icon in the List Window. You can try to recover them with the help of **Scan UDF Disc** command from [Tools](#) Menu.

Apply MRW reader (default value *Unchecked*)


If *Checked*, the program automatically recognizes CD-RW disk formatted in the "[Mt.Rainier](#)" CD-RW format (CD-MRW) placed into non-Mt.Rainier drive, and presents the data portion of the disk as a "read only" UDF format disk. We also recommend you use this to read the disk inserted into CD-MRW drive if your MRW disk was not ejected (closed by cd mastering program). For example, if the writing process was interrupted by a system or power failure.

Hint. To check the drive capabilities, use **Properties** command applied to the "empty" drive in the List window and select **Features** tab in the Properties dialog.

Display adviser window (default value *Checked*)

If *Checked*, a separate panel ("adviser") with some recommendations and results of disc analysis will appear inside the program window.

A.4.2. UDF Reader



Lost objects (default value *Files and folders*)

Determines what objects (files and/or folders) will be looked for by Scan UDF Disc.

Forced scan (default value *Don't apply*)

If the selected setting is different from the default value, the program will force the drive to scan your CD/DVD in order to find the lost files without using the data of system area. We highly recommend you to use this only if the inserted disk has not been recognized by CDRoller before, and you are also sure the disk contains the files. This may be useful if the disk was incorrectly finalized and system area was not written properly. For example, this problem often occurs on Sony Mavica CD when the finalization step failed on the camera.

If you actually know the name of CD/DVD mastering program (or device) that formatted your disk, try to select an appropriate value from the list of the following profiles:

Value	Description
Sony Mavica CD	The disk was mastered by Sony Mavica CD digital camera
Sony Mavica (O)	The disk is still open (non-finalized) by Sony Mavica CD digital camera
DirectCD CD-R	CD-R was formatted by Roxio (Adaptec) DirectCD
DirectCD-RW74	CD-RW 74 min was formatted by Roxio (Adaptec) DirectCD
DirectCD-RW80	CD-RW 80 min was formatted by Roxio (Adaptec) DirectCD
InCD3 -RW74	CD-RW 74 min was formatted by Nero InCD v.3
InCD3 -RW80	CD-RW 80 min was formatted by Nero InCD v.3
PacketCD-R	CD-R was formatted by CEQUADRAT PacketCD
DirectCD-MRW	CD-MRW (" Mt. Rainier " CD-RW) was formatted by DirectCD
InCD3 -MRW	CD-MRW (" Mt. Rainier " CD-RW) was formatted by Nero InCD v.3
PacketCD-RW	CD-RW was formatted by CEQUADRAT PacketCD
InstWrite CD-RW	CD-RW was formatted by VOB InstantWrite
InCD4 -RW80	CD-RW 80 min was formatted by Nero InCD v.4
InCD4 -DVD-RW	DVD-RW was formatted by Nero InCD v.4
InCD4 -DVD+RW	DVD+RW was formatted by Nero InCD v.4
InCD4 -MRW	CD-MRW (" Mt. Rainier " CD-RW) was formatted by Nero InCD v.4
DragTo CD-RW	CD-RW was formatted by Roxio Drag-To-Disc
DragTo CD-MRW	CD-MRW (" Mt. Rainier " CD-RW) was formatted by Roxio Drag-To-
DragTo DVD-RW	DVD-RW was formatted by Roxio Drag-To-Disc
DragTo DVD+RW	DVD+RW was formatted by Roxio Drag-To-Disc
DragTo DVD-R	DVD-R was formatted by Roxio Drag-To-Disc
DragTo DVD+R	DVD+R was formatted by Roxio Drag-To-Disc
LiteOn DVD+R	DVD+R was mastering by LiteOn DVD recorder
LiteOn DVD+R (O)	DVD+R is still open (non-finalized) by LiteOn DVD recorder
Hitachi DVD-R (F)	DVD-R was created and finalized by Hitachi DVD camcorder
Hitachi DVD-R (O)	DVD-R is still open (non-finalized) by Hitachi DVD camcorder
Hitachi DVD-RAM	DVD-RAM was mastering by Hitachi DVD camcorder
Rec DVD+RW (F)	DVD+RW was created and finalized by standalone DVD Recorder (Thomson RCA, Philips, etc.)
Rec DVD+RW (O)	DVD+RW is still open (non-finalized) by standalone DVD Recorder (Thomson RCA, Philips, etc.)
Rec DVD-RAM	DVD-RAM disc was mastering by standalone DVD recorder
Rec DVD-RAM (E)	DVD-RAM disc was quick-erased by standalone recorder (e.g Panasonic DVD-RAM recorder)

Sanyo DVD+R (F)	DVD+R was created and finalized by Sanyo DVD+R/RW standalone recorder
Sanyo DVD+R (O)	DVD+R is still open (non-finalized) by Sanyo DVD+R/RW standalone recorder
Sony DVD-R (O)	DVD-R is still open (non-finalized) by SONY DVD Camcorder
Sony DVD-RW (O)	DVD-RW is still open (non-finalized) by SONY DVD Camcorder
Sony DVD201-RW	DVD-RW disc was created by Sony DCR-DVD201 camcorder
DragTo DVD-RAM	DVD-RAM disc (4.7GB) was formatted by Roxio Drag-To-Disc
B's CLiP DVD-RW	DVD-RW disc was formatted by BHA B's CLiP Software
B's CLiP DVD+RW	DVD+RW disc was formatted by BHA B's CLiP Software
Sony abCD CD-RW	CD-RW disc was formatted by Sony Vaio abCD software
Pan Rec DVD-R (O)	DVD-R disc is still open (non-finalized) by Panasonic standalone recorder
InCD4.3 CD-RW	CD-RW was formatted by Nero InCD v.4.3 or 5
InCD4.3 CD-MRW	CD-MRW (" Mt. Rainier " CD-RW) was formatted by Nero InCD v.4.3 or 5
InCD4.3 DVD-RAM	DVD-RAM was formatted by Nero InCD v.4.3 or 5
InCD4.3 DVD-RW	DVD-RW was formatted by Nero InCD v.4.3 or 5
InCD4.3 DVD+RW	DVD+RW was formatted by Nero InCD v.4.3 or 5
DragTo7 CD-R	CD-R was formatted by Roxio Drag-To-Disc v.7 (7.5 or 8)
DragTo7 CD-RW	CD-RW was formatted by Roxio Drag-To-Disc v.7 (7.5 or 8)
DragTo7 CD-MRW	CD-MRW (" Mt. Rainier " CD-RW) was formatted by Roxio Drag-To-Disc v.7 (7.5 or 8)
DragTo7 DVD-RW	DVD-RW was formatted by Roxio Drag-To-Disc v.7 (7.5 or 8)
DragTo7 DVD+RW	DVD+RW was formatted by Roxio Drag-To-Disc v.7 (7.5 or 8)
DragTo7 DVD+R	DVD+R was formatted by Roxio Drag-To-Disc v.7 (7.5 or 8)
DragTo7 DVD-RAM	DVD-RAM disc (4.7GB) was formatted by Roxio Drag-To-Disc v.7 (7.5 or 8)

Warning. Please use the forced scan at your own risk. There is no 100% guarantee to retrieve all files from all disks in all cases. Please keep in mind, that some files may be incorrectly written, erased or partially re-written by a new ones.

Unpack files after forced scan (default value *Unchecked*)

If *Checked*, the program will try to decode the files found by the forced scan on the disks compressed by Roxio (Adaptec) DirectCD. The found files can be recovered with the help of **Recover All**, **Recover Selected** or **drag & drop** commands in the "Lost objects detected..." window.

Hint. AIDEX RunTime decoder (aidex.dll) must be assigned in the **Path to external decoder (DLL)** to **unpack compressed files**.

Load Table Of Contents from file (default value *Unchecked*)

If *Checked*, you are prompted to select a file with the table of contents of the objects found by [Scan UDF Disc](#) before, instead of new scan of your disk.

Always try to identify file type (default value *Checked*)

If *Checked*, the program will try to identify the types of found files at the scan stage (preliminary identification). On some discs and drives this may slow the scan process.

Apply DVD Reader (default value *Checked*)

If *Checked*, the program will try to recognize and verify DVD disk automatically. However, in some circumstances, for example when the disk is extremely corrupted, it is more useful to present DVD disk as a "read only" UDF format CD. If *Unchecked*, only CD identification methods will be applied.

Search of all VATs (default value *Unchecked*)

Virtual Allocation Table (VAT) is an important part of the UDF File System. VAT's location is crucial for CD-R/DVD-R/DVD+R disks created with the help of drag & drop software, such as well-known Roxio (Adaptec) DirectCD and Drag-To-Disc. If the VAT can not be found or is corrupted, files will be missing.

If the option is *Checked*, the program will try to [search all VATs](#). This may give you a chance to find and recover the files from the previous backups, including the **files accidentally deleted** by drag & drop software. If some old VATs are found, the program displays their files and folders in a separate sessions. Further, all sessions can be viewed by the built-in [Session Selector](#).


Always check file integrity (default value *Checked*)

When *Checked* the program always test the file before decompression, using the data of file header. If an important file data seem to not be recovered, try to uncheck this option. Please keep in mind that you may get an unpredictable results, so try this only at your own risk.

Always read Full TOC (default value *Checked*)

Try to **uncheck** this box if CDRoller seems to hang up your system when analyzing the disc. This problem can be caused by DVD43 driver installed in your system. This driver is bundled with some DVD programs (DVD Idle Pro or DVD Region), and can prevent a normal work of CDRoller.

A.4.3. ISO Reader



Read Path Table (default value *Big Endian (Motorola)*)

By default, the program does use the Path Table because this is the most fast method to access the directories on your ISO 9660 CD. CDRoller uses the Big Endian addresses by default, because Windows doesn't use them, so CDRoller offers an alternative method at once, if your CD is not visible by Windows. However, for a particular disc, if the default settings doesn't work properly, you can try another settings. For example, if the Path Table seems to be invalid, you can select **Don't use path table**. This will force CDRoller to start from the Root directory and scan all directories on the CD.


Apply forced scan if Path Table is invalid (default value *Checked*)

If *Checked*, the program will automatically scan the directories in case of inaccessible Path Table.

Ignore Joliet file system (use only ISO 9660) (default value *Unchecked*)

If *Checked*, any Joliet directory information on the disc will be ignored and only the ISO-9660 directory will be displayed. This may be useful if the Joliet directory information is corrupted and the CD files seem to be inaccessible. With the help of ISO-9660 directories you can try to access the files data, bypassing the Joliet file system.

A.4.4. CD/DVD Library



Apply To CD/DVD Images, group of options :

- **"Open"** (default value *Checked*);
- **"Send"** (default value *Checked*);

When *Checked* the program tries to perform appropriate command for CD(DVD) image. If there is no disk inserted into CD/DVD drive, the program prompts you to insert the disk to perform Files Open and Files Copying.

File Name (default value *by Volume Name*)

The File Name can be created either by choosing the Disk Volume Name (*by Volume Name* mode) or summarizing the word 'CDIM' with four random digits (*Random* mode) or inputting CD(DVD) Image file name manually (*Manual* mode).

When a new disc is inserted (default value *Unchecked*)

When *Checked* the program creates CD/DVD Image for a newly inserted disc.

Directory for CD/DVD Images (*program directory path* by default)


Assigns the directory on your HDD to store created CD/DVD Images.

Directory for Temporary Storage (default value *Windows Temporary Directory*)

Assigns the directory on your HDD to be used as Temporary Storage for drag-and-drop and Files Open.

Warning. Please do not select **"Directory for Temporary Storage"** as destination folder for **Recover All** and **Recover Selected** operations. When you close CDRoller, the program automatically cleans out this temporary folder, and all recovered files and subfolders will be lost!

A.4.5. Audio Extraction



DAE Method (default value *Dynamic Sync Width*)

By the *Dynamic Sync Width* method the program tries to synchronize new audio data with the previously read block of audio sectors by changing the overlap area between two consecutive read blocks. *Fixed Sync Width* means that a set amount of frames is used for blocks synchronization. Read error detection and lost synchronization control also occurs in both methods. The audio extraction by *Burst Copying* method is the fastest. Burst copy doesn't use any synchronization and error recovering.

Read Command (default value *AUTODETECT*)

If *AUTODETECT* (recommended setting) option has been selected, the program tries itself to find an appropriate read algorithm for user's CD drive.

SCSI READ CD function is the base command recommended by SCSI-3 Standard for reading audio frames. It is supported by all ATAPI drives that have DAE feature, and some SCSI devices.

SCSI READ (10) function may be used for DAE on SCSI drives support SCSI-2 Standard.

Note. The list of audio read commands used by program in *AUTODETECT* mode is not limited by two ones mentioned above. Some known read functions are absent in the selection list because a wrong chosen extraction command may cause problems on some SCSI systems.

Swap Channels (default value *Unchecked*)

When checked, the program itself will exchange left and right channels in the audio samples before writing them into output file. This may be suitable for some CD drives to exchange stereo channels while extraction.

"Big Endian" (default value *Unchecked*)

Motorola "Big Endian" mode is often used on drives from Grundig, IMS, Kodak, Ricoh and some others.

WARNING. Check this option only if the extracted output file seems to consist of noise!

Wave Format (default value *44,100 Hz; 16 Bit; Stereo*)

Indicates a brief description of audio compression format that has been selected.

Select Encoder (default value *Internal WAV*)

Assigns an appropriate encoder from the list of available ones.

File extension (default value *.wav*)


Indicates the extension of output file (.wav, .mp3 or .raw).

Options

Activates an options dialog box to select audio compression format.

High Quality (default value *Unchecked*)

For some audio compression formats, specifying this flag might improve the audio quality or other characteristics.

A.4.6. Disc TestFile System Test group.**Show the details of "import" file** (default value *Checked*)

For multisession discs only. When *Checked*, a report window displays some info whether a file was imported from the prior session ("came from session # ..."), or not.

Include to Disc Test (default value *Checked*)

When *Checked* File System Test will be included to the list of available tests.

Check on the disc (default value *All available sessions*)

If *All available sessions* option has been selected the program checks file systems of all sessions on multisession disc. In case of *Selected session only* the **selected** session is examined.

Note. There is no difference between these two settings for single session disc.

Disc Surface Test group.**Scan ratio Track Bar** (default position *20 to 2000 sectors*)

Sets the current ratio of read sectors to total sectors in the block. For example, "20 to 2000 sectors" setting means that the program reads 20 sectors in the block of 2000 sectors and therefore, then skips

(2000 - 20) sectors before the next reading. This setting is used for Disc Surface Test and also for DAE Quality test.

Include to Disc Test (default value *Unchecked*)

When *Checked* Disc Surface Test is included to the list of available tests. For mixed CDs it means that as Disc Surface Test as DAE Quality test will be included to the list of available tests.

Check on the disc (default value *All available sessions*)

If *All available sessions* option has been selected the program scans disc surface on all sessions. In case of *Selected session only* the selected session is examined on multisession disc.

Note. There is no difference between these two settings for single session disc.

Audio Read Overlap (default and minimum values are 0, maximum value is 7)

Sets the number of overlapping sectors for DAE Quality test. This may be useful to determine the value of overlap for so-called "jitter correction" while reading CD audio data.

Annex B License Agreement

CDRoller - End User License Agreement (EULA).

YOU SHOULD CAREFULLY READ THE FOLLOWING LEGAL AGREEMENT. USE OF THE SOFTWARE PROVIDED WITH THIS AGREEMENT (THE "SOFTWARE") CONSTITUTES YOUR ACCEPTANCE OF THESE TERMS. IF YOU DO NOT AGREE TO THE TERMS OF THIS AGREEMENT, DO NOT INSTALL AND/OR USE THIS SOFTWARE. USER'S USE OF THIS SOFTWARE IS CONDITIONED UPON COMPLIANCE BY USER WITH THE TERMS OF THIS AGREEMENT.

1. LICENSE GRANT.

Digital Atlantic Corp. grants you a license to use one copy of the version of this SOFTWARE on any one hardware product for as many licenses as you purchase. "You" means the company, entity or individual whose funds are used to pay the license fee. "Use" means storing, loading, installing, executing or displaying the SOFTWARE. You may not modify the SOFTWARE or disable any licensing or control features of the SOFTWARE except as an intended part of the SOFTWARE's programming features. When you first obtain a copy of the SOFTWARE, you are granted an evaluation period of not more than 14 days, after which time you must pay for the SOFTWARE according to the terms and prices discussed in the SOFTWARE's documentation, or you must remove the SOFTWARE from your computer. This license is not transferable to another company, entity, or individual.

2. OWNERSHIP.

The SOFTWARE is owned and copyrighted by Digital Atlantic Corp. Your license confers no title or ownership in the SOFTWARE and should not be construed as a sale of any right in the SOFTWARE.

3. COPYRIGHT.

The SOFTWARE is protected by United States copyright law and international treaty provisions. You acknowledge that no title to the intellectual property in the SOFTWARE is transferred to you. You further acknowledge that title and full ownership rights to the SOFTWARE will remain the exclusive property of Digital Atlantic Corp. and you will not acquire any rights to the SOFTWARE except as expressly set forth in this license. You agree that any copies of the SOFTWARE will contain the same proprietary notices which appear on and in the SOFTWARE.

4. UNAUTHORIZED USE.

You may not use, copy, rent, lease, sell, modify, decompile, disassemble, otherwise reverse engineer, or transfer the SOFTWARE except as provided in this agreement. Any such unauthorized use shall result in immediate and automatic termination of this license.

5. DISTRIBUTION.

Permission to distribute the SOFTWARE is not transferable, assignable, saleable, or franchisable. Each entity wishing to distribute the package must independently satisfy the terms of the distribution license. All distribution of SOFTWARE is further restricted with regard to sources which also distribute virus source code and related virus construction/creation materials. The SOFTWARE may not be made available on any site, CD-ROM, or with any package which makes available or contains viruses, virus source code, virus construction programs, or virus creation material.

6. WARRANTY.

THIS SOFTWARE IS PROVIDED ON AN "AS IS" BASIS. DIGITAL ATLANTIC CORP. DISCLAIMS ALL WARRANTIES RELATING TO THIS SOFTWARE, WHETHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. NEITHER DIGITAL ATLANTIC CORP. NOR ANYONE ELSE WHO HAS BEEN INVOLVED IN THE CREATION, PRODUCTION, OR DELIVERY OF THIS SOFTWARE SHALL BE LIABLE FOR ANY INDIRECT, CONSEQUENTIAL, OR INCIDENTAL DAMAGES ARISING OUT OF THE USE OR INABILITY TO USE SUCH SOFTWARE, EVEN IF DIGITAL ATLANTIC CORP. HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES OR

CLAIMS. THE PERSON USING THE SOFTWARE BEARS ALL RISK AS TO THE QUALITY AND PERFORMANCE OF THE SOFTWARE. SOME JURISDICTIONS DO NOT ALLOW LIMITATION OR EXCLUSION OF INCIDENTAL OR CONSEQUENTIAL DAMAGES, SO THE ABOVE LIMITATIONS OR EXCLUSION MAY NOT APPLY TO YOU TO THE EXTENT THAT LIABILITY IS BY LAW INCAPABLE OF EXCLUSION OR RESTRICTION. IN NO EVENT SHALL ANY THEORY OF LIABILITY EXCEED THE LICENSE FEE PAID TO DIGITAL ATLANTIC CORP.

7. SEVERABILITY.

In the event of invalidity of any provision of this license, the parties agree that such invalidity shall not affect the validity of the remaining portions of this license.

8. LIABILITY.

NO LIABILITY FOR CONSEQUENTIAL DAMAGES. IN NO EVENT SHALL DIGITAL ATLANTIC CORP. OR ITS SUPPLIERS BE LIABLE TO YOU FOR ANY CONSEQUENTIAL, SPECIAL, INCIDENTAL OR INDIRECT DAMAGES OF ANY KIND ARISING OUT OF THE DELIVERY, PERFORMANCE OR USE OF THE SOFTWARE, EVEN IF DIGITAL ATLANTIC CORP. HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES. IN NO EVENT WILL DIGITAL ATLANTIC CORP.'S LIABILITY FOR ANY CLAIM, WHETHER IN CONTRACT, TORT OR ANY OTHER THEORY OF LIABILITY, EXCEED THE LICENSE FEE PAID BY YOU, IF ANY.

9. INSPECTION AND TESTING.

You agree and acknowledge that you will thoroughly inspect and test the SOFTWARE for all of your purposes upon commencement of your use. Any suit or other legal action, claim or any arbitration relating in any way to this agreement or software covered by it must be officially filed or officially commenced no later than Three months (90 days) after your first use of the software.

10. ENTIRE AGREEMENT.

This is the entire agreement between you and Digital Atlantic Corp. which supersedes any prior agreement or understanding, whether written or oral, relating to the subject matter of this license.

11. RESERVED RIGHTS. All rights not expressly granted here are reserved to Digital Atlantic Corp.