

Subsections of datasets (T21)

The INTREPID Subsection tool can extract a subset of data from a dataset and save it as a new separate dataset.

For a practical introduction to this tool, see the Guided Tour [Managing INTREPID datasets \(G06\)](#).

It can extract data lying within or outside:

- A rectangular geographic area defined by
 - Corner points or
 - Centroid, size and orientation,
- An existing polygon dataset or a polygon that you trace on the screen.

It can also (in combination with a geographic region if required) extract data

- Selected by a logical expression and/or
- Subsampled from the original dataset.

You can choose whether to leave out or retain but set to *null* the data that is to be excluded from the new dataset.

If the Subsection process removes part of the data from the middle of one or more lines in a line dataset, you can choose whether to convert each split line into two separate lines or to leave them as one line.

The Subsection tool displays the dataset graphically. You can choose the degree of detail (subsampling interval) used in the display of a vector dataset.


You can save a traced polygon as a new polygon dataset for later use if required. In this way the Subsection tool can act as a utility for creating polygon datasets.

The Subsection tool

>> *To use Subsection with the INTREPID graphic user interface*

- 1 Choose Subsection from the File menu in the Project Manager, or use the command **subset.exe**. INTREPID displays the Subsection Main window.
- 2 If you have previously prepared file specifications and parameter settings for Subsection, load the corresponding task specification file using Load Options from the File menu. (See [Specifying input and output files](#) for detailed instructions.) If all of the specifications are correct in this file, go to step 8. If you wish to modify any settings, carry out the following steps as required.

- 3 Specify the dataset from which you wish to extract the Subsection. Use Load Vector Dataset or Load Grid Dataset from the File menu. (See [Specifying input and output files](#) for detailed instructions.) INTREPID displays the dataset in the Subsection Main window.



While preparing for the Subsection process, or afterwards, you can zoom (enlarge an area of the display) and pan (examine different regions while enlarged) (See [Zooming and panning the display](#) for details). For a large dataset that is slow to display you can also determine the display subsampling interval (See [Specifying the display resolution](#) for instructions)

- 4 Specify the output dataset to be created with the results of the process. Use Specify Output from the File menu. (See [Specifying input and output files](#) for detailed instructions.)
- 5 Specify the geographic criteria for extracting the Subsection using options from the Spatial menu (See [Specifying the Subsection criteria](#) for details).
- 6 Specify the conditional criteria for extracting the Subsection using options from the Condition menu. You can use this in conjunction with Spatial criteria if required. (See [Specifying the Subsection criteria](#) for details).
- 7 Specify the options for the process (whether to delete or retain *nulls*, split lines, pass or reject data inside a polygon) using options from the Options menu. (See [Subsection options](#) for more information.)
- 8 When you have made specifications and settings according to your requirements, choose Apply. INTREPID will perform the Subsection process and display the new dataset in the Subsection Main window.
- 9 If you wish to record the specifications for this process in a task specification (`.job`) file in order to repeat a similar task later or for some other reason, use Save Options from the file menu. (See [Specifying input and output files](#) for detailed instructions.)
- 10 If you wish to repeat the process, choose Close Dataset from the File menu, then repeat steps 2–9, varying the parameters and/or data files as required.

11 To exit from Subsection, choose Quit from the File menu.

To view the current set of specifications choose Report from the Window menu. INTREPID displays the Subsection Report window. See [Displaying options and using task specification files](#) for details and an example of a set of specifications.

During the Subsection process, INTREPID displays messages in the Status section of the Command area in the Subsection Main window. These messages indicate INTREPID's current activity.


You can view Help information by choosing options from the Help menu (See [Help](#) below).

You can execute Subsection as a batch task using a task specification (.job) file that you have previously prepared. See [Displaying options and using task specification files](#) for details.

Specifying input and output files

To use Subsection, you will need to specify the vector or grid dataset from which you wish to extract the subsection, and the name of the new subsection dataset.

Choose the options as required from the File menu.



In each case INTREPID displays an Open or Save As dialog box. Use the directory and file selector to locate the file you require. (See "[Specifying input and output files](#)" in [Introduction to INTREPID \(R02\)](#) for information about specifying files).

Vector dataset notes: INTREPID obtains the X and Y data from the dataset aliases. The dataset must have the following aliases identifying appropriate field files.

Alias	Field File
X	X coordinate (geographic location)
Y	Y coordinate (geographic location)

See "[Vector dataset field aliases](#)" in [INTREPID database, file and data structures \(R05\)](#) for more information about aliases.

Load Vector Dataset Use this option to specify a vector dataset from which you wish to create the subsection. INTREPID will open the dataset and display its traverse lines or points in the Subsection Main window.

Load Grid Dataset Use this option to specify a grid dataset from which you wish to be create the subsection. INTREPID will open the dataset and display it in the Subsection Main window.

Specify Output Use this option to specify the name for the output vector or grid

dataset you are creating with the subsection process.

Load Options If you wish to use an existing task specification file to specify the Subsection process, use this option to specify the task specification file required. INTREPID will load the file and use its contents to set all of the parameters for the Subsection process. (See [Displaying options and using task specification files](#) for more information).

Save Options If you wish to save the current Subsection file specifications and parameter settings as an task specification file, use this option to specify the filename and save the file. (See [Displaying options and using task specification files](#) for more information).

The Subsection tool display

Zooming and panning the display

You can enlarge and reduce the display (zoom in and out) and view different parts of it (pan).

>> *To zoom in and out (enlarge/reduce) by steps*

To zoom in (enlarge the display) choose Zoom In from the Command area. Each time you choose this button, INTREPID will enlarge the display by 25%.

To zoom out (reduce the display) choose Zoom Out from the Command area. Each time you choose this button, INTREPID will reduce the display by 25%.


>> *To zoom in on a selected area of the display*

- 1 Ensure that you are not currently tracing a polygon (Check that the Trace a Polygon option in the Spatial menu is turned off—See [Creating polygons on the screen](#) for details).
- 2 Hold down the left mouse button and drag diagonally (corner to corner) across the area that you wish to enlarge. INTREPID will enlarge the selected region to fill the display area of the window.

If you choose Zoom Out, having used this process to zoom in, INTREPID will immediately zoom out to the full dataset display.

To pan the display (view different parts)

When you have zoomed in, the Pan/Zoom indicator in the Command area consists of a small square within a larger square. The large square represents the whole display and the small square the part visible on the screen. When you drag the small square to a different part of the large square INTREPID shows the corresponding part of the display.




If you are viewing the whole display, the small square may occupy the whole of the large square.

Specifying the display resolution

This section applies only to vector datasets. If you are processing a large vector dataset, INTREPID may take some time to display the data. It normally displays every 10th data point (the **display subsampling interval**). To speed up the data display on the screen, decrease the subsampling interval.

To modify the display subsampling interval, choose Display Subsampling from the Options menu. INTREPID displays the Subsampling for Display dialog box.



Specify the subsampling interval you require in the Subsampling Rate text box, then choose OK.


Note: Increasing the value of the Subsampling Rate parameter means increasing the interval—INTREPID displays fewer data points.

INTREPID will redisplay data in the Subsection Main window using the new subsampling interval.

Be careful not to confuse output subsampling with display subsampling. The output subsampling interval affects the data that INTREPID copies to the new dataset. The display subsampling interval affects the way INTREPID displays the dataset in the Subsection tool main window. See [Subsampling for the output dataset](#) for more information about output subsampling.

Subsection process display example

Here is an example of a Subsection line dataset display. The first illustration shows part of the original dataset display with a polygon specified as the subsection criterion. The second illustration shows the new dataset created from the data that was within the polygon.




Specifying the Subsection criteria

There are three ways of specifying the criteria for extracting the subsection. You can use the methods singly or in combination.

- Specifying a geographic region for the subsection using one of the following methods
 - A rectangle defined by its centroid, size and orientation,
 - A rectangle defined by a pair of diagonally opposite corners,
 - A polygon that you trace on the screen,
 - An existing polygon dataset,
- Specifying a condition (a logical expression defining criteria for including values in the output dataset)
- Specifying a subsampling interval for the output dataset.


>> To specify a rectangle or polygon

Choose the corresponding option from the Spatial menu



>> To specify a condition

Choose Expression from the Condition menu.



>> To specify an output subsampling interval

Choose Output Subsampling from the Condition menu.

Rectangles

You can define a rectangular geographic region for the subsection process. It can be defined in terms of centroid, size and orientation or a pair of opposite corners and can have any projection^{1,2}. If it has a different projection from the input dataset, INTREPID will automatically convert it before the subsection process.

Specifying the projection and datum of a rectangle

The Rectangle Dimensions for Clipping dialog box (illustrated below) contains Projection and Datum command buttons, and a display of the current projection and datum of the rectangle. The default projection and datum is that of the input dataset.

>> To specify the projection and datum of a rectangle

In the Rectangle Dimensions for Clipping dialog box choose the appropriate command button. See [INTREPID's supported datums and projections \(R09\)](#) for more information about projections.

Projection Use this to specify the projection of the rectangle. If you choose Projection INTREPID displays the Projections dialog box. Select the projection you require by clicking the name of the projection and choosing OK.


Datum Use this to specify the datum of the rectangle. If you choose Datum INTREPID displays the Datum dialog box. Select the datum you require by clicking the name of the datum and choosing OK.

1.² If the rectangle is geodetic, then it may not strictly be a rectangle. For simplicity we shall still refer to it as such.

Rectangle defined by corners

>> *To specify a rectangle defined by corners.*

- 1 Choose Rectangle from the Spatial menu. INTREPID displays the Rectangle Dimensions for Clipping dialog box.
- 2 Select the Corners option. INTREPID displays the corresponding parameter text boxes.



Specify the parameters then choose OK.

Lower Left Corner: Easting, Northing Use these text boxes to specify the location coordinates of the lower left corner of the rectangle using the rectangle's distance units (See [Specifying the projection and datum of a rectangle](#)).


Upper Right Corner: Easting, Northing Use these text boxes to specify the location coordinates of the upper right corner of the rectangle using the rectangle's distance units (See [Specifying the projection and datum of a rectangle](#)).

Rectangle defined by centroid, size and orientation

>> *To specify a rectangle defined by centroid, size and orientation.*

- 1 Choose Rectangle from the Spatial menu. INTREPID displays the Rectangle Dimensions for Clipping dialog box.

- 2 Select the Centroid Dimensions option. INTREPID displays the corresponding parameter text boxes.



Specify the parameters then choose OK.

Centroid: Easting, Northing Use these text boxes to specify the coordinates of the centroid of the rectangle using the rectangle's distance units (See [Specifying the projection and datum of a rectangle](#)).

Dimensions: X Direction, Y Direction Use these text boxes to specify the dimensions of the rectangle using the rectangle's distance units (See [Specifying the projection and datum of a rectangle](#)).

Rotation Use this text box to specify the orientation of the rectangle. The default value is 0, which orients the Y dimension (see above) in the North/South direction. The rotation is expressed in degrees, positive in the clockwise direction, so that, for example, if Rotation is +45°, the Y dimension will be in the North–Easterly direction.


Existing Polygon Datasets

You can specify an existing polygon dataset to define the region for the subsection.

>> *To use an existing polygon dataset*

- 1 Choose Load Existing Polygon from the Spatial menu. INTREPID displays an Open dialog box.

- 2 Use the directory and file selector to locate the dataset you require. (See [Specifying input and output files](#) for details about specifying files). INTREPID displays the outline of the polygon dataset.



Creating polygons on the screen


You can use the mouse to trace a new polygon directly onto your dataset display for use as the region for the subsection.

You can save this as a new polygon dataset for later use if required. In this manner the Subsection tool can act as a utility for creating polygon datasets.

If you make an error or no longer require the traced polygon, you can erase it from the display.

>> *To trace a polygon on the screen.*

- 1 Choose Trace a Polygon from the Spatial menu. INTREPID will enter polygon trace mode and turn on the Trace a Polygon option in the Spatial menu.
- 2 Click each vertex of the required polygon. You do not need to close the polygon (i.e., you do not need to click the first vertex again at the end). INTREPID will create a closed polygon with the vertices you specify.
- 3 Choose Trace a Polygon from the Spatial menu again. INTREPID will exit from polygon trace mode.



Saving a traced polygon

You can create a polygon dataset defining this region.

>> *To save a traced polygon*

- 1 Choose Save Current Polygon As from the Spatial menu. INTREPID displays a Save As dialog box.
- 2 Use the directory and file selector to specify a name for the new polygon dataset. (See [Specifying input and output files](#) for details about specifying files).

Pass or reject data inside

After you have specified spatial criteria for extracting the subsection data (i.e., the rectangle or polygon), you can specify whether the data within the rectangle or polygon will form the new dataset, or be the data that is excluded from the new dataset.

The default option is to use the data inside the rectangle of polygon for the new dataset.

No matter which way you set this option, INTREPID will still apply the condition and the output subsampling if specified (See [Conditions—using an expression](#) and [Subsampling for the output dataset](#)).

>> *To exclude data within the rectangle or polygon*

Turn on Reject Data Inside in the Spatial menu.

>> *To include data within rectangle or polygon*

You should only need to do this to reverse a previous Reject Data Inside setting.


Turn off Reject Data Inside in the Spatial menu.

Conditions—using an expression

You can use a logical expression as a criterion for extracting the Subsection. You can use this alone or in conjunction with spatial criteria and/or subsampling.

To specify a logical expression for the subsection process

- 1 Choose Expression from the Conditions menu. INTREPID displays the Subsection Condition dialog box.



- 2 Specify any logical expression involving fields in the vector dataset / values in the grid dataset. Use the standard INTREPID expressions notation. (See [INTREPID expressions and functions \(R12\)](#) for a full description of the syntax of expressions.

For example, if you have a field called **LINE_NUMBER** you could specify:

```
LINE_NUMBER > 1200
```

If you are testing grid values in a condition, use the name of the grid itself as the field name in the expression. For a multiband grid add a colon followed by the band number.

Examples:

```
raw_grid < 2016
```

```
K_Th_U_grid:1 > 1723.56
```

Subsampling for the output dataset


Output subsampling works for vector datasets only. If you are creating a subsection of a vector dataset you can reduce the detail in the output dataset by only including some of the data, for example every 10th data point.

The corresponding operation on grid datasets consists essentially of increasing the size of the grid cells. If you wish to perform such processes on grid datasets use the INTREPID Grid Operations tool. See [Grid Operations \(T25\)](#) for further information.

Be careful not to confuse output subsampling with display subsampling. The output subsampling interval affects the data that INTREPID copies to the new dataset. The display subsampling interval affects the way INTREPID displays the dataset in the Subsection tool main window. See [Specifying the display resolution](#) for information about display subsampling.

>> To specify a subsampling interval for an output vector dataset

- 1 Choose Output Subsampling from the Condition menu. INTREPID displays the Dataset Output Subsampling dialog box.



- 2 Specify the subsampling interval (in data points) in the corresponding Subsample Rate text box.

For example, if you specify 5 then INTREPID will copy every 5th data point to the output dataset.

Note: Increasing the value of the Subsample Rate parameter means increasing the interval—INTREPID displays fewer data points.

- 3 Choose OK.


Subsection options

Deleting or retaining *nulls*

You can choose whether you wish INTREPID to omit the excluded data from the new dataset or retain it but set all values to *null*. INTREPID will normally omit the excluded data.

>> *To retain the excluded data but set all of its Z values set to null*

Choose Retain Nulls from the Options menu.



INTREPID will place a check mark against this option.

>> *To omit the excluded data*

You should only need to do this to reverse a previous Retain Nulls setting.

Choose Delete Nulls from the Options menu. INTREPID will place a check mark against this option.

Splitting lines

This section applies only to line datasets. If the Subsection process removes part of the data from the middle of one or more lines in a line dataset, you can choose whether to convert the separated line segments into separate lines or to leave them as a single line.

If you leave the split line as a single line, there may be a large difference in Z values on either side of the gap. This could cause time consuming, unnecessary and irrelevant smoothing activity in several INTREPID tools. If the two line sections become two separate lines, these problems are avoided.

If you split the lines, all lines retain the original line number.

The default option is for INTREPID to leave the data as a single line.

>> *To specify that lines should be split*

Turn on the Split Lines option in the Options menu.

>> *To specify that lines should not be split*


Turn off the Split Lines option in the Options menu.

Apply

When you choose **Apply**, INTREPID performs the subsection operation.

Help

You can use the Help menu to display help text on the topics shown in the menu illustration below.



Exit


>> To exit from Subsection

Choose Quit from the file menu.

Displaying options and using task specification files

Displaying options

To display the current file specifications and parameter settings, choose Report from the Window menu.



INTREPID displays the Subsection Report window containing the task specifications.

Using task specification files

You can store sets of file specifications and parameter settings for Subsection in task specification (**.job**) files. Also, at V5.0, the protobuf option is delivered in the form of task files.

>> To create a task specification file with the Subsection tool

- 1 Specify all files and parameters.
- 2 If possible, execute the task (choose Apply) to ensure that it will work.
- 3 Choose Save Options from the File menu. Specify a task specification file (INTREPID will add the extension **.job**) INTREPID will create the file with the settings current at the time of the Save Options operation.

For full instructions on creating and editing task specification files see [INTREPID task specification \(.job\) files \(R06\)](#).

>> *To use a task specification file in an interactive Subsection session*

Load the task specification (**.job**) file (File menu, Load Options), modify any settings as required, then choose Apply.

>> *To use a task specification file for a batch mode Subsection task*

Type the command **subset.exe** with the switch **-batch** followed by the name (and path if necessary) of the task specification file.

For example, if you had a task specification file called **surv329.job** in the current directory you would use the command

```
subset.exe -batch surv329.job
```

Task specification file notes and example

Here is an example of a Subsection task specification file, using Parmas format.

```
Process Begin
  Name = subsection
  GRID = /disk1/surv/mlevel_grid
  OUT = /disk1/surv/mlevel_A
  Parameters Begin
    Box_Centroid_East = 740000.0
    Box_Centroid_North = 8415000.0
    Box_Width = 2000.0
    Box_Height = 1000.0
    Box_Rotation = 0.0
    Output_Subsampling = 1
    Shrink = Yes
    SplitLines = No
    Exclude = No
    Box_Projection = "TMAMG54"
    Box_Datum = "AGD66"
    Search_Condition = "mlevel_grid>1969"
  Parameters End
Process End
```

A similar job file, this time written using V5.0 protobuf syntax is shown below.

```
# Example task file V5.0 protobuf syntax - subset
# Subsection a line dataset using a bounding polygon.
# Usage: fmanager -batch subsection_line_polygon.task

IntrepidTask {
  Subset {
    IN: "../datasets/ebagoola_S..DIR"; # a line dataset
    CLIP_POLY: "../datasets/eba_polygon..DIR";
    OUT: "../datasets/ebagoola_S_subset..DIR"; # what you want to create
    ReportFile: "subsection.rpt";
    Output_Subsampling: 1;
    RectangleOption: None; # no rectangular clipping
    Shrink: true;
    SplitLines: false;
    Exclude: false; # keep the data inside the box!!
  }
}
```

Notes

- Use **IN** = to specify an input vector dataset

- Use **GRID =** to specify an input grid dataset
- The **Box_Projection** and **Box_Datum** statements *apply only to rectangles*, not to polygon datasets, which have their own projections.
- If you wish to use a traced polygon in a task specification file, you must save it as a polygon dataset, using Save Current Polygon As from the Spatial menu.