

Oracle Insurance Framework Administrator User Manual

Version 3.11

December 2008

Insbridge Framework Administrator (IBFA) User Manual

Part # formerly P01-753-11

December 2008

Copyright © 2008, Oracle. All rights reserved.

Primary Authors: Mary Elizabeth Wiger

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Oracle, JD Edwards, and PeopleSoft are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Contents

FIGURES	5
PREFACE	8
<i>Audience</i>	8
<i>Navigating IBFA</i>	8
<i>System Requirements</i>	8
<i>Notational Conventions</i>	8
<i>Additional Information</i>	9
<i>Manual History</i>	9
CHAPTER 1	10
INSBRIDGE FRAMEWORK ADMINISTRATOR.....	10
CHAPTER 2	11
INTRODUCTION TO THE INSBRIDGE PAGE	11
<i>Configuration File</i>	12
<i>Introduction to Subscribers</i>	14
<i>Introduction to Database Connection</i>	17
CHAPTER 3	21
INTRODUCTION TO THE SOFTRATER PAGE.....	21
<i>SoftRater Test Interface</i>	21
<i>Optional Rate Operators</i>	23
<i>Optional Map Request Operators</i>	25
CHAPTER 4	27
INTRODUCTION TO SOFTRATER ENGINE CONFIGURATION.....	27
<i>Connectors</i>	30
CHAPTER 5	32
SOFTRATER EXPLORER.....	32
<i>Introduction to SoftRater Explorer</i>	32
<i>Explorer Configuration Page</i>	32
<i>Subscriber Configuration Page</i>	34
<i>Introduction to Environments</i>	35
<i>Introduction to Line of Business Management</i>	40
<i>Virtual File Server Management</i>	42
<i>Carriers & Portal Management</i>	48
CHAPTER 6	50
INTRODUCTION TO SOFTRATER PACKAGES	50
<i>SoftRater Packages Page</i>	51
<i>Loading Packages</i>	52
<i>Moving Packages</i>	54
<i>Downloading Packages</i>	56
<i>Unloading Packages</i>	59
<i>Copying Packages</i>	62
<i>Deleting Packages</i>	64
<i>Searching for Packages</i>	67
<i>Viewing Package Details</i>	68

CHAPTER 7	71
SOFTDATA TEST INTERFACE.....	71
CHAPTER 8	73
SERVICES	73
<i>Introduction to the Insbridge Message Service.....</i>	<i>74</i>
<i>Starting & Stopping the Message Service.....</i>	<i>74</i>
<i>Viewing Messages</i>	<i>75</i>
<i>Deleting Messages.....</i>	<i>77</i>
<i>Process Configuration.....</i>	<i>78</i>
<i>Introduction to Insbridge Task Manager.....</i>	<i>80</i>
<i>Starting & Stopping Task Manager</i>	<i>80</i>
CHAPTER 9	81
LOGS.....	81
<i>Error Log.....</i>	<i>81</i>
<i>Database Events</i>	<i>82</i>
<i>Event Log Events</i>	<i>84</i>
<i>Introduction to the Audit Log</i>	<i>86</i>
CHAPTER 10	89
SECURITY	89
<i>Changing the Type of Authentication Used.....</i>	<i>89</i>
<i>Windows Authentication</i>	<i>90</i>
<i>Custom Authentication</i>	<i>91</i>
<i>External API Access.....</i>	<i>92</i>
<i>Changing the Password</i>	<i>93</i>
CHAPTER 11	95
SOFTLIBRARIES.....	95
<i>Adding SoftLibraries</i>	<i>97</i>
<i>Editing SoftLibraries</i>	<i>104</i>
<i>Deleting SoftLibraries</i>	<i>104</i>
CHAPTER 12	106
SUPPORT.....	106
GLOSSARY.....	107
INDEX.....	111

Figures

Figure 1 Insbridge Framework Administrator Main Screen	10
Figure 2 Insbridge Page	12
Figure 3 Insbridge Page Configuration File Path	13
Figure 4 Configuration File New Window	13
Figure 5 Changing Location of Configuration File	14
Figure 6 Adding Subscriber Links.....	15
Figure 7 Adding a New Subscriber.....	15
Figure 8 Subscriber List.....	16
Figure 9 Subscriber List.....	16
Figure 10 Deleting a Subscriber.....	17
Figure 11 Adding Database Link	17
Figure 12 Adding a New Database.....	18
Figure 13 Database List	19
Figure 14 Edit Database Window	20
Figure 15 Confirm Deleting Database	20
Figure 16 SoftRater Test Interface	22
Figure 17 Test Results	23
Figure 18 Optional Rate Operators	23
Figure 19 Custom XML Map Request Operators	25
Figure 20 SoftRater Engine Configuration Page.....	28
Figure 21 Connectors	30
Figure 22 Explorer Configuration Page	33
Figure 23 Carrier Configuration Page	34
Figure 24 Environment Listing Page	35
Figure 25 Adding an Environment.....	36
Figure 26 Environment List.....	37
Figure 27 Edit Environment.....	37
Figure 28 Confirm Delete of Environment.....	37
Figure 29 Configuration Page for Configuring an Environment	38
Figure 30 Configuring an Environment.....	38
Figure 31 Line of Business Management Screen	40
Figure 32 Adding a Line of Business.....	40
Figure 33 Line of Business Management Screen	41
Figure 34 Selecting a Line of Business to Delete.....	42
Figure 35 Virtual File Server Management Screen	42
Figure 36 Virtual File Server Management Window.....	43
Figure 37 Virtual File Server Management Screen	43
Figure 38 Editing Virtual File Server Management.....	44
Figure 39 Editing Virtual File Server Management.....	45
Figure 40 Virtual File Server Management Screen	45
Figure 41 Deleting a Virtual File Server Management	46
Figure 42 Deleting Virtual File Server.....	46
Figure 43 Deleting Virtual Server on Popup.....	47
Figure 44 Confirming Deleting of a Virtual File Server Management.....	47
Figure 45 Carrier & Portal Management Screen	48
Figure 46 Adding a Carrier / Portal.....	48
Figure 47 Carrier / Portal Management Page	49
Figure 48 Editing a Carrier / Portal.....	49
Figure 49 Confirming Deleting a Carrier / Portal	49
Figure 50 SoftRater Packages	50
Figure 51 SoftRater Explorer.....	51
Figure 52 SoftRater Explorer Screen	52

Figure 53 Selecting Packages.....	52
Figure 54 Loading a Package.....	53
Figure 55 Load Packages Results Page.....	54
Figure 56 SoftRater Explorer Screen.....	55
Figure 57 Selecting Packages to Move.....	55
Figure 58 Moving SoftRater Packages.....	56
Figure 59 SoftRater Explorer Screen.....	57
Figure 60 Selecting Packages to Download.....	57
Figure 61 Downloading SoftRater Packages.....	58
Figure 62 Download Package Results.....	59
Figure 63 SoftRater Explorer Screen.....	60
Figure 64 Selecting Packages to Unload.....	60
Figure 65 Unloading SoftRater Packages.....	61
Figure 66 Download Package Results.....	62
Figure 67 SoftRater Explorer Screen.....	63
Figure 68 Selecting Packages to Copy.....	63
Figure 69 Moving SoftRater Packages.....	64
Figure 70 SoftRater Explorer Screen.....	65
Figure 71 Selecting a Package to Delete.....	65
Figure 72 Deleting SoftRater Packages.....	66
Figure 73 Searching for a Package.....	67
Figure 74 Selecting a Package to View Details.....	69
Figure 75 SoftData Test Interface.....	71
Figure 76 Test Results.....	72
Figure 77 Insbridge Services Screen.....	73
Figure 78 Insbridge Services Screen.....	74
Figure 79 Insbridge Services Screen.....	75
Figure 80 Insbridge Message Service.....	76
Figure 81 Batch Message Information.....	76
Figure 82 Insbridge Services Screen.....	77
Figure 83 Insbridge Message Service.....	78
Figure 84 Insbridge Services Screen.....	79
Figure 85 Process Configuration Window.....	79
Figure 86 Insbridge Task Manager.....	80
Figure 87 Insbridge Error Log.....	82
Figure 88 Insbridge Error Log.....	83
Figure 89 Insbridge Database Events.....	83
Figure 90 Emailing an Event.....	84
Figure 91 Insbridge Error Log.....	85
Figure 92 Insbridge Event Log Event.....	85
Figure 93 Emailing an Event.....	86
Figure 94 Audit Log.....	87
Figure 95 Viewing Audit Log Details.....	88
Figure 96 Insbridge Security Page.....	90
Figure 97 SoftRater Explorer.....	91
Figure 98 Packages Tab of SoftRater.....	91
Figure 99 Logging into Framework Administrator.....	92
Figure 100 Allowing External API Access.....	93
Figure 101 Changing your Password.....	94
Figure 102 SoftLibrary Main Page.....	95
Figure 103 SoftLibrary Implementation Information.....	96
Figure 104 SoftLibrary Web Services.....	97
Figure 105 SoftLibrary Screen.....	97
Figure 106 Completed SoftLibrary Screen.....	98
Figure 107 Arguments Screen.....	99
Figure 108 GetHelpText Screen.....	100

Figure 109 RequestXML Screen	101
Figure 110 ResponseXML Screen	101
Figure 111 Ping Screen	102
Figure 112 GetLog Screen	102
Figure 113 Test Screen – Request.....	103
Figure 114 Test Screen – Response.....	103
Figure 115 Completed SoftLibrary.....	104
Figure 116 SoftLibrary Type Search.....	105

Preface

Welcome to the *Oracle Insurance Insbridge Rating and Underwriting Framework Administrator User Manual*. This manual describes the settings and options of Oracle Insurance Insbridge Rating and Underwriting Framework Administrator (IBFA). IBFA is a component within the Oracle Insurance Insbridge Rating and Underwriting (IBRU) System that enables administrators to configure Insbridge applications such as Oracle Insurance Insbridge Rating and Underwriting RateManager (RateManager) and Oracle Insurance Insbridge Rating and Underwriting SoftRater (SoftRater).

Audience

This manual is intended for system administrators who are tasked with setting up and managing Insbridge environments. Users should be familiar with their company's environments and the requirements of the end users.

Navigating IBFA

Navigate through Insbridge Framework Administrator using the top and side bar menus. Your browser's tool bars will not be displayed.

System Requirements

System requirements for server and clients can be found in Oracle Insurance Insbridge Recommended Operating Environments Guide. This guide can be obtained from Oracle Insurance Insbridge Support.

Notational Conventions

This section explains the conventions used in this book:

- Menu selections are shown with arrows. For example, the command to select the **Print** choice from the **File** menu looks as follows:

Select **File** ► **Print**

- File names and path names are shown in **bold**.
- New or emphasized terms are shown in *italics*.

Additional Information

For more information, see these Oracle Insurance resources:

- Oracle Insurance IBRU RateManager User Guide
- Oracle Insurance IBRU PricingManager User Guide
- Oracle Insurance IBRU BatchManager User Guide
- Oracle Insurance IBRU SoftRater User Guide

Manual History

New editions incorporate any updates issued since the previous edition.

Edition	Publication Number	Product Version	Publication Date	Comment
1 st Edition	P01-753-01	V 3.5	November 2005	
2 nd Edition	P01-753-02	V 3.6	June 2006	Update
3 rd Edition	P01-753-03	V 3.7	December 2006	Update Version
4 th Edition	P01-753-04	V 3.8	July 2007	Update Version
5 th Edition	P01-753-05	V 3.8.3	October 2007	Update Version
6 th Edition	P01-753-06	V 3.8.5	November 2007	Update Version
7 th Edition	P01-753-07	V 3.8.7	January 2008	Update Version
8 th Edition	P01-753-08	V 3.8.8	March 2008	Update Version
9 th Edition	P01-753-09	V 3.9	May 2008	Update Version
10 th Edition	P01-753-10	V 3.10	October 2008	Update Version
11 th Edition	P01-753-11	V 3.11	December 2008	Update Version

Insbridge Framework Administrator

The Insbridge Framework Administrator (IBFA) is an administrative tool used to configure RateManager, SoftRater, PricingManager and BatchManager. It provides:

- The ability to configure Insbridge applications. All Insbridge applications utilize one Configuration File.
- Access to SoftRater Explore.
- Access to the SoftRater Test Interface.
- Access to the Error Log and Audit Log.
- The ability to start and stop the Insbridge Message Service, as well as view messages.
- The ability to configure the SoftRater Engine.
- Access to the SoftData Test Interface.
- Manage SoftLibraries.

The IBFA can be accessed by going to <http://<yourserver>/ibfa>, where <yourserver> is the server the IBFA is installed on. This is usually the same server that RateManager is installed on. If you do not know this information, contact your system administrator.




Figure 1 Insbridge Framework Administrator Main Screen

Introduction to the Insbridge Page

The Insbridge page is the starting point of the IBFA. The Insbridge page allows you to:

- View the configuration file and change the location
- Set up subscribers
- Set up database connections

Before you can use RateManager or SoftRater, subscriber and database information must be entered on the Insbridge page. This is generally done at installation time, but may be performed at a later date if necessary.

Navigating to the Insbridge Page

1. Using the menu tree, select **Insbridge**.



2. This will open the Insbridge page.

Configuration File [D:\Program Files\InsBridge\Framework\2.0.0\InsBridge.Xml]

The Framework Administrator Web will configure any Insbridge Framework Configuration file (Insbridge.xml) found on your network. Although all Insbridge Applications may have their own version of this configuration file, we suggest that all apps that reside on the same Framework Server share the same file.

Change Config File location:

Add Subscriber

Please consult with an Insbridge [sales](#) or [support](#) representative before adding/editing subscriber information.

Click on the id of the subscriber in the list to edit.



Add Database Connection

Create or edit database connection. This database connection can be global to the Insbridge Framework or unique to the Subscriber.

Click on the name of the connection to edit.






Figure 2 Insbridge Page

3. From here, you can view the configuration file, enter in subscriber information and enter in database connection information.

Configuration File

All Insbridge applications utilize a configuration file (Insbridge.xml). When you make a change to subscribers, environments, etc. using the Framework Administrator, the configuration file gets updated. The configuration file contains settings for:

- Subscribers
- Carriers/Portals
- Environments
- Database Connections
- Security
- Virtual File Servers
- Internet Proxy

While it is possible for each application to use its own version of the configuration file, Oracle Insurance strongly recommends that all applications residing on the same Framework server use the same file.

Viewing the Configuration File

Complete file information will not be available until you have configured your environments.

1. From the Insbridge page, click the underlined configuration file path, **D:\ProgramFiles\InsBridge\Framework\2.0.2\InsBridge.Xml**.

Configuration File [D:\Program Files\InsBridge\Framework\2.0.0\InsBridge.Xml](#)

The Framework Administrator Web will configure any Insbridge Framework Configuration file (Insbridge.xml) found on your network. Although all Insbridge Applications may have their own version of this configuration file, we suggest that all apps that reside on the same Framework Server share the same file.

Change Config File location:

Figure 3 Insbridge Page Configuration File Path

2. The configuration file will open in a new window.




Figure 4 Configuration File New Window

Choosing a Different Configuration File

The Framework Administrator allows you to choose a different configuration file or change where your current configuration file is stored.

1. If the configuration file does not exist in the new location, you can copy the existing configuration file to the new location.
2. From the Insbridge page, enter the new location of the configuration file in the text box next to **Change Config File location** (be sure to include the file name).

Configuration File [D:\Program Files\InsBridge\Framework\2.0.0\InsBridge.Xml]

The Framework Administrator Web will configure any Insbridge Framework Configuration file (Insbridge.xml) found on your network. Although all Insbridge Applications may have their own version of this configuration file, we suggest that all apps that reside on the same Framework Server share the same file.

Change Config File location:

Figure 5 Changing Location of Configuration File

3. When you are finished, click .
4. You also can click to find the new file. After you have selected the new file, click .
5. The Insbridge page will refresh and the path to the new configuration file will show. All Insbridge applications will now use the new configuration file.

Introduction to Subscribers

A *subscriber* is typically a single carrier however; a subscriber also can be a portal to many different carriers.

There are two types of subscribers:

- **Carriers** – A carrier is a single entity where all users are managed under the same subscriber ID. Multiple carriers can be created. This allows for different groups within the company to have their own subscriber IDs.
- **Portals** – A portal is a collection of different carriers all managed under one subscriber ID. Portals are most often used by general agencies that do not use RateManager but need a way to manage SoftRater packages.

Subscriber Type and Libraries

Subscriber designation determines what templates can be applied in RateManager. If everyone is under the same subscriber, users will not be able to use the Library to share templates within the company. Users will still be able to apply templates from others outside the company.

If users want to use the Library function to share programs within the company, you must create separate carrier subscribers that define groups within the company. For example, if the company has one group that creates programs for selected areas and another group that creates programs for the remaining areas, each can be set up as separate subscribers. By doing this, each group will be able to use the Library to apply templates from each other.

Adding a Subscriber

Oracle Insurance assigns your company's subscriber information. If you do not know the correct subscriber information (type, ID and name), please consult with an Oracle Insurance support representative to obtain the proper information.

Typically, you only need to add a subscriber the first time the RateManager system is installed. The information, (type, ID and name) for adding a new subscriber is assigned by Oracle Insurance.

1. From the Insbridge page, click the **Add Subscriber** link.

Add Subscriber

Please consult with an InsBridge [sales](#) or [support](#) representative before adding/editing subscriber information.



Figure 6 Adding Subscriber Links

2. This will open the **Add Subscriber** window.

Figure 7 Adding a New Subscriber

3. Enter the **Type**, **ID**, **Name** and **Description** for the new subscriber. Oracle Insurance

should have provided this information to your company. When you finish entering the information, click **Save**.

4. The new subscriber will now show in the list of subscribers.

Add Subscriber

Please consult with an Insbridge [sales](#) or [support](#) representative before adding/editing subscriber information.




Figure 8 Subscriber List

5. To configure environments, LOB's and virtual servers for a new carrier, see the SoftRater Configuration Page. To configure environments, carriers/portals, LOB's and virtual servers for a new portal, see the Portal Configuration Page.
6. You can edit a subscriber's description by clicking their ID in the subscriber listing. The type, ID and name of a subscriber cannot be edited.

Editing a Subscriber

The only edit you will be allowed to make to a subscriber is the Description. The description becomes important when entering sublines. Sublines are classifications that fall in between lines of business and program folders. Each line of business will automatically have one default subline placed underneath it. This subline will be named with the subscriber description.

To edit a Subscriber, click on the hyperlinked Subscriber ID number. This will bring up the Edit Subscriber window. Make any changes and click Save to save your changes and return to the previous screen.

Please contact Oracle Insurance Insbridge Support for any other changes.

Deleting a Subscriber

If a subscriber is no longer needed, they can be deleted. Make certain a subscriber is not needed before deleting them, as this action cannot be undone. When a subscriber is deleted, all associated database connections and environment settings are also deleted.

1. From the Insbridge page, click the hyperlinked Subscriber ID number (in Figure 9, you would click 1002).

Add Subscriber

Please consult with an Insbridge [sales](#) or [support](#) representative before adding/editing subscriber information.



Figure 9 Subscriber List

2. This will open the **Edit Subscriber** window.




Figure 10 Deleting a Subscriber

3. Click the **Delete** button. A warning message will be displayed. Click **OK** to remove the Subscriber or **Cancel** to return to the previous screen.

WARNING	Deleting a subscriber also deleted all database connections and environments setup for that subscriber.
----------------	--

Introduction to Database Connection

Databases can be added at any time. Depending upon your database type, some fields may be required. When you go to save, if a field is required and you have not entered any information, you will have to correct the error before the database can be saved.

Adding a Database Connection

1. From the Insbridge page, click the **Add Database Connection** link.

Add Database Connection

Create or edit database connection. This database connection can be global to the Insbridge Framework or unique to the Subscriber.

Figure 11 Adding Database Link

2. This will open the **Database Connection** window.

Connection -- Web Page Dialog

Databases

Connection

Database connections can be global to the Insbridge Framework or unique to the Subscriber.

Subscriber: Global

Name:

Server:

Server Type: SQLServer

Catalog:

Catalog Type: Other

Query Buffer:

Tablespace:

Schema:

User:

Password:

Save Cancel

Figure 12 Adding a New Database

3. Select if this is to be a global database or unique to the **Subscriber**. This information cannot be changed once you have saved it.
4. Enter in a Database **Name**. This information cannot be changed once you have saved it.
5. Enter in the **Server** name. This is the name of the server that houses the database.
6. Select the **DB Server Type**. This is the type of server that houses the database. Currently, RateManager and SoftRater support SQL Server, Oracle and DB2.
7. Enter in the name of the **Catalog** in the database. For DB2 servers, this is the System DSN Name. For Oracle servers, this is the Oracle ODBC driver information.
8. Select the **Catalog Type**. This is the type of catalog in the database. The types available are: RateManager, SoftRater and Other. If you are using a SQL Server, you can choose either RateManager or SoftRater. If you are using an Oracle or DB2 database, you will need to choose Other and enter the remaining information.
9. Enter in a **Query Buffer**. For certain Database Management Systems (DBMS), system batch query optimization is required for performance and/or because of limits on/in the system. This value will control the maximum number of batch query operations that can be submitted to the target DBMS in any one transaction. It is known that for certain DB2

platform versions a value of 31 is required because of a hard software limit.

10. Enter in the name of the **Tablespace** in the database.
11. Enter in the name of the **Schema** that defines the structure of the database.
12. Enter in the **Username** to access the database.
13. Enter in the **Password** to access the database.
14. Click **Save** to save your work.

Editing a Database

You will be allowed to make edits to most fields. The Subscriber and Name fields will not allow for changes. To edit a database, click on the hyperlinked Database Name. This will bring up the Edit Subscriber window. Make any changes and click Save to save your changes and return to the previous screen.

Please contact Insbridge Support for any other changes.

Deleting a Database

If a database is no longer needed, it can be deleted. Make certain the database is not needed before deleting it, as this action cannot be undone.

1. From the Insbridge page, scroll down to the subscriber you need. Click the underlined database you want to delete (in Figure 13, you would click [rm310](#)).

Add Database Connection

Create or edit database connection. This database connection can be global to the Insbridge Framework or unique to the Subscriber.




Figure 13 Database List

2. This will open the **Edit Database** window.




Figure 14 Edit Database Window

3. Click **Delete**, you will be asked to confirm deletion of the database.




Figure 15 Confirm Deleting Database

4. Click **OK** to delete the subscriber or **Cancel** to return to the Edit Database window.

WARNING This action cannot be undone.

Introduction to the SoftRater Page

The SoftRater page is the testing area of SoftRater. The SoftRater Test Interface provides a place for you to test input files against SoftRater Packages (SRP's) that have been loaded throughout your network or that are publicly accessible.

The SoftRater page has four areas:

- **SoftRater Test Interface**
- **Rate Operators**
- **Map Request Operators**
- **Result Information**

Navigating to the SoftRater Page

1. Using the menu tree, click **SoftRater**.



2. This will open the **SoftRater** page.

SoftRater Test Interface

Use the SoftRater Test Interface when you want to:

- Compare rates from different servers
- Verify a package is loaded
- Verify SoftRater is using the correct version of a program
- See how long SoftRater is taking to rate a program

Rating a File Using the SoftRater Test Interface

When rating a file through the SoftRater Test Interface, you have the ability to instruct SoftRater on how to rate the file and how to return the results. These options are divided into two categories:

- Rate Operators
- Map Request Operators

SoftRater Test Interface

This page will test input files against SoftRater Packages (SRPs) that have been loaded throughout your network or that are publicly accessible. Please enter the required information below. Click [here](#) to view the SoftRater for Windows help document.

The screenshot shows the 'REQUEST INFORMATION' section of the SoftRater Test Interface. At the top, there is a blue header bar with the text 'REQUEST INFORMATION'. Below this, there is a 'Server:' label followed by a text input field containing the word 'SERVER' and a red asterisk. To the right of the 'Server' field is a 'Browse...' button. Below the 'Server' field is a label 'Select an XML file or enter text below:' followed by a large, empty text area. To the right of the text area is a 'GetFile' button. At the bottom of the text area are two buttons: 'Clear' and 'ViewXml'.

Figure 16 SoftRater Test Interface

1. On the SoftRater page, enter the name of the server you want to rate against in the **Server** text box.
2. Browse for an XML file to rate or copy and paste an XML file into the large text box. If you browse for an XML file, you can view the XML in the large text box by clicking **GetFile**. This allows you to edit the XML before rating.
3. Scroll down the page and choose any optional operators SoftRater should use when rating the file.
4. When you are ready to rate the file, scroll to the bottom of the page and click **Execute!**.
5. The file will be rated and the results will be shown in the results box.

The following options require you to check a box to enable the item:

Add a root node to the results? (AddRoot): Add the root node when you want to determine how long SoftRater is taking to rate a policy. The root node contains the time rating started and the time rating stopped. It also shows you the number of input files and the number of output files. The root node is always the first line in the results and begins with `<i bdoc>`.

Add company descriptions to the results? (AddHeading): Add the folder pathway when you want to see the name of the path of the folder, program and program version.

Add the program inputs to the results? (AddInputs): Add the program inputs when you want to verify that SoftRater is using the correct input values.

Add descriptions to the result items? (AddResultDesc): Add descriptions to the results when you want to see the name of the variable or input along with the result ID. The variable or input name will be shown after the `d`, while the result ID is shown after the `i`. In the following example output, `VehPri nci pal l yDri ven` is the input name, and `Pri mary Vehi cl e` is the result ID:

```
<m i="Pri mary Vehi cl e" d="VehPri nci pal l yDri ven" v="1" />
```

Include empty items in the results? (AddResultEmpty): By default, SoftRater does not output results that do not have a value. If you would like to see all results, check this box.

Debug Rate? (DebugRate): Check this box if you would like to see the debugged XML along with the results.

The following option requires you to enter specific information into the text box:

SoftRater environment definition override? (EnvRef): If you do not want to rate against the default SoftRater environment, enter the environment that should be rated against in this box.


Optional Map Request Operators

Map request operators enable you to submit custom XML to the SoftRater engine and receive custom XML back from it.

Optional Custom XML MapRequest Operators

If you would like to submit custom XML to the Insbridge Rating Engine, you must supply the rating information below. There are two ways in which you can submit custom XML and receive custom/Insbridge results.

1. Map your custom xml using the Insbridge RateManager. This process will create data processors for you. Note: You must map your inputs and outputs separately to achieve custom-in and custom-out success.
2. Upload your own processors to a RateNode file server for workflow custom-in and custom-out processing.

MAPREQUEST OPERATORS 

Subscriber:	<input type="text"/>
Line Of Business:	<input type="text"/>
Program:	<input type="text"/>
Version:	<input type="text"/>

Input Processor Type?	<input type="text" value="NONE"/> ▼
Input Processor Name:	<input type="text"/>
Output Processor Type?	<input type="text" value="NONE"/> ▼
Output Processor Name:	<input type="text"/>

Add results to custom input?

Figure 19 Custom XML Map Request Operators

The following information is required if you are using a mapping:

Subscriber: Your Company's subscriber ID.

Line of Business: The number for the line of business you are rating. For example, if you are rating a file for the fire line of business, then enter 5.

Program: The program ID you are rating.

Version: The program version you are rating.

The following information is required only if using custom input XML:

Input Processor Type: The type of input mapping to use.

GLOBAL: A mapping that can be used by all programs under a specific line of business. Global mappings are created in RateManager from the **Global Inputs** screen.

LOCAL: A mapping that is specific to a particular program version. Local mappings are created in RateManager from the **Program Listing** screen.

CUSTOM: A mapping that was created outside of RateManager and then imported.

Input Processor Name: The unique identifier that was entered for the mapping.

The following information is required only if you want to receive custom output XML:

Output Processor Type: The type of output mapping to use.

GLOBAL: A mapping that can be used by all programs under a specific line of business. Global mappings are created in RateManager from the **Global Inputs** screen.

LOCAL: A mapping that is specific to a particular program version. Local mappings are created in RateManager from the **Program Listing** screen.

CUSTOM: A mapping that was created outside of RateManager and then imported.

Output Processor Name: The unique identifier that was entered for the mapping.

You can optionally check the following:

Add results to custom input: If you want the original input file to be appended at the beginning of the result file, select this box.

Introduction to SoftRater Engine Configuration

The SoftRater Engine configuration page allows an administrator to configure information specific to the SoftRater Engine. For additional information on caching, see the SoftRater topic Introduction to SoftRater Caching in the SoftRater User Guide.

To Navigate to the SoftRater Engine Configuration Page

1. Using the menu tree, click the plus box (+) next to **SoftRater** to expand it and then click **Engine**.



2. This will open the **SoftRater Engine** configuration page.

SoftRater Engine

Insbridge's SoftRater™ is the engine that executes the rating and underwriting instructions defined within the Insbridge RateManager™.

Engine Type:

WEB RATE THREADS

* A request with multiple rates in one document will force the Webservice to thread the payload. *

Maximum Threads:

STATS

* Return detailed stat information about each transaction rate request. *

Start Time:

Stop Time:

Execution Time:

PROGRAM CACHE SETTINGS

* Cache program information from all of your environments for faster and more efficient rating. *

Enabled:

Category Miss Buffer Purge %:

< back next >

CACHED PROGRAM LISTING

Remove	Sample Company-Sample Program-Version 2 (5.800.3.8)
Environment:	sr_sit
Total Hit Rows:	33
Total Miss Rows:	42
Package Creation Date:	02/18/2007 12:45:51 PM
Cache Enabled Date:	02/18/2007 12:56:45 PM

Figure 20 SoftRater Engine Configuration Page

Engine Type

Drop down listing that allows you to select which configuration information to show.

SoftRater for Windows: Shows configuration information for the SoftRater for Windows engine.

Connectors: SoftRater for Windows has the ability to call-out to external Carriers and Portals to get information.

Connectors may require Professional Services. For more on connectors, please see the section on Connectors below.

Web Rate Threads

The IBFA system administrator can enter in the number of Web Rate Threads. This feature will allow for a rating that goes through web services to specify the maximum number of threads that need to be executed. Threading can be set to any number required. Setting the maximum number of threads will ensure that ratings will be returned in sequential order.

Stats

Stats allows you to choose if statistical information will be included in the return XML. Any combination of the options may be selected. The statistical information is returned in the <stats> node.

Start Time: Timestamp of when rating started. Returned in the <start_time> node.

Stop Time: Timestamp of when rating finished. Returned in the <stop_time> node.

Execution Time: The **Start Time** minus the **Stop Time**. The result is the length of time rating took, in milliseconds (1000 milliseconds = 1 second). Returned in the <running_time> node.

NOTE

Start Time and **Stop Time** are shown in microseconds (10^{-3} seconds), while the execution time is shown in milliseconds (10^{-2} seconds).

Program Cache Settings

Allows you to configure the cache. After making a change, be sure to click . If you want to reset the options to the last saved version, click .

Enabled: A check indicates the cache is enabled. If you uncheck the box and then click , the cache will be disabled and all data (hits and misses) will be purged from the cache.

Category Miss Buffer Purge %: The percentage (1-99, integers only) of misses to be removed from the cache at a time. A setting of 0 will not purge any misses. A setting of -1 will cause no misses to be stored in the cache. Misses will only be purged when the server is inactive.

Cached Program Listing

The Cached Program Listing will be displayed only when program cache settings are enabled. Cached program listing shows programs that have information stored in the cache. If more than five programs have information stored in the cache, use the < back and next > hyperlinks to navigate between the pages.

Remove: Removes the corresponding program's data (hits and misses) from the cache.

Environment: The name of the environment the program was rated in.

Total Hit Rows: Total number of hits stored for the corresponding program.

Total Miss Rows: Total number of misses stored for the corresponding program.

Package Creation Date: Time stamp of when the package was created for the corresponding program.

Cache Enabled Date: Time stamp of when information was first stored in the cache for the corresponding program.

For additional information on caching, see the SoftRater topic Introduction to SoftRater Caching in the SoftRater User Guide.

Connectors

Connectors provide the ability to connect with external services. For example if you wanted to get a rate from an external carrier, you could create a connection that would take a rate request, transform the file if needed, send it to the carrier, and receive a response back. The connector can transform Insbridge XML to a custom format and vice versa. Typically users of connectors are Insurance Agencies that need the ability to do real-time rating with multiple carriers.

SoftRater Engine

Insbridge's SoftRater™ is the engine that executes the rating and underwriting instructions defined within the Insbridge RateManager™.

Engine Type:

SoftRater	
Url:	<input type="text" value="SoftRater.asmx"/>
AInsureRate	
InsBridge DirectConnect AInsureRate Engine. Used for InsBridge Comparative Rating.	
Url:	<input type="text" value="https://AInsureRate.com/H5XMLRequest.asp"/>
User:	<input type="text" value="test"/>
Password:	<input type="password" value="••••••••"/>

Figure 21 Connectors

Editing a Connector

If **Connectors** is selected as the Engine Type, the screen will refresh with a list of available connectors. Connectors cannot be added or deleted from this screen. For each connector a URL, user name and password can be shown. The SoftRater connector cannot be edited (read-only). Connectors will be listed in the same order they are listed in the connector.config file, which is in the Insbridge folder on the server where Insbridge is installed.

Connector information must have at least a URL. If other information such as a user name and password is required, it may be listed. URLs, user names and passwords, or other information

can be edited here. Type in any changes in the text box and click **Save**. Any edits here will be saved to the connectors.config file.

If you have made a mistake or do not want to implement changes, click **Refresh** to return the screen to the original entry.

Adding a Connection

Adding connectors is a multi step process that may require some Professional Services. Adding a new connector requires an IBFA patch, updated connector.config file, and transformation files if needed. In IBFA, a new connector must have a corresponding subscriber added and an environment setup as well.

Customization may be required for the connection. Please contact Oracle Insurance Support representative for more information.

SoftRater Explorer

Introduction to SoftRater Explorer


SoftRater Explorer provides a place for you to configure environments, LOB's, virtual file servers and, if applicable, carriers & portals. Once configured, SoftRater Explorer is used to download, load, unload, move and delete packages to/from your SoftRater environments. For more information about SoftRater Packages (SRP's), see Introduction to SoftRater Packages.

Explorer Configuration Page

The Explorer Configuration page is where you set up email addresses that will appear in the drop downs when you perform a package operation, i.e. load package. This page also is used to set up internet proxy settings.

Navigating to the Explorer Configuration Page

1. Using the menu tree, click the plus box (+) next to **SoftRater** to expand it and then click **Explorer**.



2. This will open the **Explorer Configuration Page**.

Configuration File [D:\PROGRAM FILES\INSBRIDGE\Webs\IBFA\System\SoftRater\Xml\rnx.xml]

Please enter the SoftRater Explorer configuration information below.

Admin Email Address:

Internet Proxy: None
 UserID Password

Intranet Credentials: Use Anonymous
 Domain UserID Password

Figure 22 Explorer Configuration Page

Configuration File: This configuration file (rnx.xml) contains the information entered on the current page (**Explorer Configuration Page**). You can view the file by clicking the underlined path to the file.

Admin Email Address: Email addresses entered here will appear in the drop downs for packaging operations. Separate multiple email addresses with a semicolon (;).

Internet Proxy: If you use an internet proxy, you will need to set up this information in order for packaging operations to succeed. The first text box is for the name of the proxy and the last two are for you to enter a user ID and password.

Intranet Credentials: If anonymous website to website access is denied, even within your own network, this setting will allow you to enter a windows account that the Insbridge application can impersonate. You can select to use anonymous or you can enter in a domain, user ID and password.

NOTE


When you are finished making changes to the email addresses, proxy settings or intranet credentials, click **Save** to update the configuration file.

Subscriber Configuration Page

Once you have added a new subscriber through the Insbridge page, you will need to set up environments and, optionally, lines of business and virtual servers for that carrier.

Navigating to the Subscriber Configuration Page

1. Using the menu tree, click the plus box (+) next to **SoftRater** to expand it and then again next to **Explorer**. Then click the name of the subscriber (in this case, **MaryRM11**).



2. For first time users, this will open the **Configuration Page** for **MaryRM311**.

The screenshot shows the 'Config' page for the carrier 'Mary RM311'. The page is divided into several sections:

- Add Environment**: A section for adding, editing, or removing environments. It contains a table with the header 'NAME - DESCRIPTION' and a message: 'No environments found.'
- Line-of-Business Management**: A section for managing line-of-businesses. It contains a table with the header 'ID - DESCRIPTION' and a message: 'No Lines found.'
- Virtual File Server Management**: A section for managing virtual file servers. It contains a table with the header 'DESCRIPTION - SERVER - TYPE - ENVIRONMENT' and a message: 'No file servers found.'

Figure 23 Carrier Configuration Page

From Carriers, you can set up the following:

- Environments
- Lines of Business
- Virtual Servers

For Portals, you will have one more option:

- Carrier and Portal Management

Carriers and portals are configured and managed in the same way. The difference between the two is the addition of carriers or other portals to any portal subscriber.

If you have not configured any SoftRater environments, the **Packages** tab will be hidden. Before you can manipulate packages, you must add and configure an environment. See Introduction to Environments for more information.

If you already have an environment setup, you will see the **Packages** tab. Click the **Config** tab to enter or edit another environment.

Introduction to Environments

An *environment* is a pointer to a location where SoftRater Packages (SRP's) are stored and loaded. Environments are local to the carrier/portal they are created under. The carriers under a portal will all use the same environment. There is no limit to the number of environments you may have. You must have at least one environment created in order to load packages to SoftRater. Environments have the following options:

- Adding an Environment
- Editing an Environment
- Deleting an Environment
- Configuring an Environment

Adding an Environment

1. To add an Environment, click the **Add Environment** hyperlink on the Configuration Page.

Add Environment

Add, edit, or remove environments from your Explorer configuration.


NAME - DESCRIPTION
 No environments found.

Figure 24 Environment Listing Page

2. This will open the **Add Environments** window.




Figure 25 Adding an Environment

3. Type in a name for your environment and select one of the three predefined types:
 - Development
 - Production
 - Quality Assurance
4. If you want to make the new environment secure, check the box next to **Secure**. A secure environment will be available to users who are logged into the Framework Administrator only. For more information on this, see Introduction to Framework Administrator Security.
5. Once you have entered the information, click **Save** to update the configuration file and return to the Configuration page.
6. After adding your environments, you will need to configure them. See Configuring an Environment for more information.

NOTE

The environment types are for classification purposes only. There is no difference between the three types.

Editing an Environment

All elements of an environment can be edited at any time. Click the underlined environment name. You will be placed on the Environments text box. Make any changes and save.

Deleting an Environment

1. To delete an environment, click the environment's name in the environment listing, in this case, Test Environment.

Add Environment

Add, edit, or remove environments from your Explorer configuration.


NAME - DESCRIPTION
 <u>Test Environment</u> - Quality Assurance

Figure 26 Environment List

- This will open up the **Edit Environments** window.




Figure 27 Edit Environment

- Click **Delete**. You will be asked to confirm deletion of the environment.




Figure 28 Confirm Delete of Environment

- Click **OK** to delete the environment or **Cancel** to return to the **Edit Environment** window.

NOTE

Deleting an environment does not delete any packages stored in that environment. It only removes the reference to the location of the packages from the Framework Administrator.

Configuring an Environment

Once you have added an environment, you will need to configure the environment so that SoftRater knows where to find, store and load packages.

1. Navigate to the configuration page for the appropriate subscriber. Select the subscriber member you need from the menu on the left hand side, in Figure 29, **Mary RM311**.

Carriers will have one member listed. Portals may have many members listed. Every member listed under a portal subscriber will use the same environments. You will not have to set up environments for every carrier or portal that is a member of a portal subscriber.




Figure 29 Configuration Page for Configuring an Environment

2. This will open up the environment configuration page. The environments you previously setup will be listed. If an environment is missing, you must return to the subscriber configuration page and add it.




Figure 30 Configuring an Environment

Here, your environments are broken up into the three types:

- **Development**
- **Quality Assurance**
- **Production**

For each environment, you can set up the following information:

Environment: The name of the environment. Selecting the radio button next to an environment's name will set it up as the default environment.

Package Location: Physical location of where the packages should be stored. Click to run a process to validate the permissions on the directory and certify any packages in the directory. In order for the Framework Administrator to successfully manipulate packages in the location, it must have full control of the directory.

DB Server: The name of the server that houses the database that packages will be loaded to. For DB2 servers, this is the DB2 Registered Alias Name. For Oracle servers, this is the System DSN Name.

DB Server Type: The type of server that houses the database. Currently, RateManager and SoftRater support SQL Server, Oracle and DB2. For information on setting up Oracle and DB2 drivers, see below.

DB Catalog: The name of the catalog in the database. For DB2 servers, this is the System DSN Name. For Oracle servers, this is the Oracle ODBC driver information.

DB Catalog Type: The type of catalog in the database. The types available are: RateManager, SoftRater and Other. If you are using a SQL Server, you can choose either RateManager or SoftRater. If you are using an Oracle or DB2 database, you will need to choose Other and enter the remaining information.

***DB Query Buffer:** For certain Database Management Systems (DBMS), system batch query optimization is required for performance and/or because of limits on/in the system. This value will control the maximum number of batch query operations that can be submitted to the target DBMS in any one transaction. It is known that for certain DB2 platform versions a value of 31 is required because of a hard software limit.

***DB Tablespace:** The name of the table space in the database.

***DB Schema:** The name of the schema that defines the structure of the database.

DB User: Username to access the database.

DB Password: Password to access the database.

Engine Type: The type of Insbridge SoftRater engine that is used. The available options are: Windows, WebSphere, WebLogic or JBoss.

Engine Location: The location of the SoftRater engine. If the engine is local to the Framework Administrator (i.e. located on the same server), leave this field as LOCALHOST. If the engine is located on a different server, enter the name in the box.

Engine EnvDef: This field should remain blank, unless the engine is located on a different server. If the **Engine Location** is set to LOCALHOST, leave this field blank. If the **Engine Location** is not LOCALHOST, this should match the name of the environment on the remote server.

NOTE

* Items marked with an asterisk only need to be entered/edited if you are using an Oracle or DB2 server.

Introduction to Line of Business Management

Adding or deleting a line of business from the Framework Administrator does not add or remove that line of business from RateManager. What it does do is provide you with a way to filter the results shown on the **Packages** page.

Adding a Line of Business

1. From the Configuration Page, click the **Line-of-Business Management** hyperlink.

Line-of-Business Management

Your rating book of businesses are identified by an id and a description. There is no limit to the number of LOB's (line-of-business) that your Explorer can contain.

ID - DESCRIPTION

Figure 31 Line of Business Management Screen

2. This will open the **Line of Business Management** window.




Figure 32 Adding a Line of Business

3. Type the XML ID of the line in the text box next to **ID**. The XML ID is available from RateManager by viewing the **Program Inputs XML**. The XML ID for the line of business will be on the first line, next to LOB=.
4. Type in a name for the line of business next to **Desc**. The name here does not have to match the name used in RateManager.
5. Click .
6. The line of business will be added to the list. Once you have finished adding LOB's, click .
7. The added LOB's will now appear in the search option available for the SoftRater Explorer. For additional information, see Searching for Packages.

Editing a Line of Business

Lines cannot be edited once added. If you have made a mistake, you must delete the line and re-enter. You can enter the Line of Business screen by clicking the Line of Business hyperlink or checking the box in front of any line of business. This will place you on the Lines text box where you can add or delete lines.

Deleting a Line of Business

1. To remove a line of business from the listing, click the **Line-of-Business Management** hyperlink available on the Configuration Page.

NOTE	The portal configuration page will not be displayed until you have created a portal subscriber. If the portal configuration page is not displayed, return to the Insbridge page and add a new subscriber with a type as Portal.
-------------	---

Line-of-Business Management

Your rating book of businesses are identified by an id and a description. There is no limit to the number of LOB's (line-of-business) that your Explorer can contain.

ID - DESCRIPTION
<input type="checkbox"/> 1 - AUTO
<input type="checkbox"/> 2 - HOME
<input type="checkbox"/> 3 - LIFE
<input type="checkbox"/> 4 - FIRE

Figure 33 Line of Business Management Screen

2. This will open the **Line of Business Management** window.




Figure 34 Selecting a Line of Business to Delete

3. Place a checkmark next to all LOB's you would like to delete.
4. Click .
5. The line(s) of business will be deleted from the list. Once you have finished deleting LOB's, click **Save**.

Virtual File Server Management

Virtual file server management allows you to set up servers that are in different locations where packages can be downloaded.

Adding a New Virtual File Server

1. From the Configuration Page, click the **Virtual File Server Management** link.

Virtual File Server Management

There are times when you must download SoftRater packages from different locations. These locations require a domain name of an ip-address of the particular server.

DESCRIPTION - SERVER - TYPE - ENVIRONMENT
 No file servers found.

Figure 35 Virtual File Server Management Screen

2. This will open the **Virtual File Server Management** window.




Figure 36 Virtual File Server Management Window

3. Enter the name of the server and a description. Take care when entering the server name. This field cannot be edited. If you have made a mistake, you must delete and re-enter.
4. Click **Add** to add the server to the list. Enter in as many servers as you need.
5. When you are finished, click **Save** to save your work and return to the previous screen.

Editing a Virtual File Server

Virtual File Servers can have the description and environment changed as needed. The server name and type cannot be edited. If you have made a mistake with the server name, you must delete and re-enter. The server type is set on the SoftRater Engine page.

1. From the Configuration Page, click the **Virtual File Server Management** link.

Virtual File Server Management

There are times when you must download SoftRater packages from different locations. These locations require a domain name of an ip-address of the particular server.



Figure 37 Virtual File Server Management Screen

2. This will open the **Virtual File Server Management** window.




Figure 38 Editing Virtual File Server Management

3. If multiple environments are available from the server, click the virtual file server's underlined description (in this case, **DEFAULT ENVIRONMENT**). You can also place a checkmark next to the server and click **Edit Selected Server**.
4. This will open the **Edit Virtual File Server** window. Clicking a virtual file server's underlined description in the listing of virtual file servers on the configuration page will also open this window.

NOTE

IBFA will attempt to connect to the environment when you edit. If the remote name cannot be resolved or is unable to connect, an error message will be displayed.




Figure 39 Editing Virtual File Server Management

6. Select the appropriate environment from the drop down. You can also edit the description from this page. Click **Save** when you are finished to return to the **Virtual File Server Management** window.
7. When you are finished adding servers, click **Save**.
8. The configuration page will refresh to show the added servers.

Deleting a Virtual File Server

There are two ways to delete a virtual file server:

The first way is from the **Virtual File Server Management** window. Use this method when you want to delete a server with an obvious error, for example a typo in the server name. This method will not try to discover the environment. No warning message will be displayed

1. From the Configuration Page, click the **Virtual File Server Management** link.

Virtual File Server Management

There are times when you must download SoftRater packages from different locations. These locations require a domain name of an ip-address of the particular server.

DESCRIPTION - SERVER - TYPE - ENVIRONMENT
<u>DEFAULT ENVIRONMENT</u> - VIRTUAL SERVER - Windows - Default Environment

Figure 40 Virtual File Server Management Screen

2. This will open the **Virtual File Server Management** window.





Figure 41 Deleting a Virtual File Server Management

3. Place a checkmark next to the server(s) you would like to delete and click  .
4. The server will be removed from the list.
5. When you are finished deleting servers, click **Save**. The configuration page will refresh and the deleted servers will no be displayed.

Deleting a Virtual File Server

The second way to delete a virtual file server is from the **EditVfsServer** popup.

1. From the Configuration Page, click the underlined server name. In the example below, **DEFAULT ENVIRONMENT**.

Virtual File Server Management

There are times when you must download SoftRater packages from different locations. These locations require a domain name of an ip-address of the particular server.

DESCRIPTION - SERVER - TYPE - ENVIRONMENT
<u>DEFAULT ENVIRONMENT</u> - VIRTUAL SERVER - Windows - Default Environment

Figure 42 Deleting Virtual File Server

2. This will open the **EditVfsServer** window.




Figure 43 Deleting Virtual Server on Popup

3. Click **Delete**.
4. You will be asked to confirm deleting the server.




Figure 44 Confirming Deleting of a Virtual File Server Management

5. Click **OK** to delete the selected servers.
6. The configuration page will refresh and the deleted servers will no longer show.

Carriers & Portal Management

If a subscriber is a portal, you can add carriers and/or portals to it. This enables you to manage those carriers/portals from one location. Portals are generally used for SoftRater package management only by general agencies that do not use RateManager. This option will not be displayed if you have set up the subscriber as a carrier type.

Adding a Carrier/Portal

1. From the Portal Configuration Page, click the **Carrier & Portal Management** hyperlink.

Carrier & Portal Management


Carrier Management allows you to configure your Explorer with the Carriers or Portals that you want it to manage. Please consult with your system administrator for all valid Portal and Carrier information.

Click on the id of the carrier or portal in the list to edit.

No Carriers/Portals found.

Figure 45 Carrier & Portal Management Screen

2. This will open the **Add Carrier/Portal** window.



The screenshot shows a dialog box titled "Subscriber -- Web Page Dialog". The main heading is "Clients" with a "close" link. Below the heading is the section "Carrier/Portal" with the instruction "Please enter/update your Insbridge Customer information below." There are three input fields: "ID:", "Name:", and "Desc:". At the bottom right are "Save" and "Cancel" buttons.

Figure 46 Adding a Carrier / Portal

3. Enter the ID, name and a description for the new carrier/portal. Oracle Insurance should have provided the ID and name to you. When you are finished, click **Save**.
4. The carrier/portal will be added to the list. You can now add and configure environments for that carrier/portal.

Deleting a Carrier/Portal

1. To remove a carrier/portal from the listing, click the ID number in the list, in this case **1005**.

Carrier & Portal Management

Carrier Management allows you to configure your Explorer with the Carriers or Portals that you want it to manage. Please consult with your system administrator for all valid Portal and Carrier information.




Figure 47 Carrier / Portal Management Page

2. This will open the **Edit Carrier/Portal** window.




Figure 48 Editing a Carrier / Portal

3. Select **Delete**. You will be asked to confirm deletion of the carrier/portal.




Figure 49 Confirming Deleting a Carrier / Portal

4. Click **OK** to delete the carrier/portal or **Cancel** to return to the **Edit Carrier/Portal** window.

Introduction to SoftRater Packages

A package is a small file that holds all the RateManager logic for a specific program and version. Packages are created in RateManager using the  **Create Package** button.

There are two types of packages. The first is called a *local package*. The local SoftRater package (SRP) exists in the development environment and can be rated against using ScenarioManager. When a local package is created in RateManager, it is automatically loaded to the local SoftRater.

The second type is a full package. Full packages are created the same way as local packages, except that a SoftRater environment is specified when the package is created. The environment specified while creating the package is where the package will initially be stored. The package can then be loaded or moved to a different environment using the SoftRater Explorer. For information on creating packages, see the RateManager topic Introduction to Packaging.





Figure 50 SoftRater Packages

SoftRater Packages Page

Navigating to SoftRater Explorer

1. Using the menu tree, click the plus box (⊕) next to **SoftRater** to expand it and then again next to **Explorer**. Then click the name of the subscriber (in this case, **Mary RM311**).



2. The Explorer will automatically load the list of packages for the default environment. You can use the drop down to select a different environment and click **Get Listing!** to update the list of packages.

If you have not configured any SoftRater environments, the **Packages** tab will be hidden. Before you can manipulate packages, you must add and configure an environment. See Introduction to Environments for more information.




Figure 51 SoftRater Explorer

From here, you have many options. You can:

- Load Packages
- Move Packages
- Download Packages
- Unload Packages
- Copy Packages
- Delete Packages
- Search for Packages
- View Package Details
- Navigate to the Configuration Page

Loading Packages

Loading a package takes the logic stored in the package and places it in the database, so that it can be rated against. Packages can be loaded from any SoftRater environment.

To Load a Package

1. Navigate to the **SoftRater Explorer** for the appropriate subscriber.




Figure 52 SoftRater Explorer Screen

2. The Explorer will automatically load the list of packages for the default environment. You can use the drop down to select a different environment and click **Get Listing!** to update the list of packages.




Figure 53 Selecting Packages

3. Select the package(s) you would like to load and click .
4. This will open the **Load Packages** window where you can select options for loading the package(s).




Figure 54 Loading a Package

Load Options

Sync:

This will load the package while you wait. This option is only available if you are loading one package.

Async:

This will load the packages in the background and, optionally, notify you at the email address you enter when loading is complete. This is the only option available when loading multiple packages.

Email address:

If you want to be notified when the load operation is finished, either select or enter your email address. If you would like to add your email address to the drop down list, see the Explorer Configuration Page.

5. When you have finished choosing your options, click **OK**.
 - If you chose the Sync load option, the package listing should refresh and an icon (📄) will appear next to the loaded package.
 - If you chose the Async load option, you should receive a message that the request was successful.

When the process finishes, if you elected to receive an email, you should receive an email with the results. If you elected not to receive an email, nothing will be sent to you. Refresh the listing and an icon (📧) will appear next to the loaded packages.

If you receive error messages, check your configuration settings and try again.




Figure 55 Load Packages Results Page

NOTE

If you load a package for a program that already has a package loaded, the original package will be unloaded and the new package will be loaded in its place. The old package will remain on disk until deleted and can be reloaded at any time.

Moving Packages

Moving a package works the same as moving a file on your hard drive. The package will be removed from the current environment and moved to the selected environment.

To Move a Package

1. Navigate to the **SoftRater Explorer** for the appropriate subscriber.
2. The Explorer will automatically load the list of packages for the default environment. You can use the drop down to select a different environment and click **Get Listing!** to update the list of packages.




Figure 56 SoftRater Explorer Screen

3. Select the package(s) you would like to move.




Figure 57 Selecting Packages to Move

4. Right click one of the selected packages and choose **Move SRP...** from the popup menu.




Figure 58 Moving SoftRater Packages

5. Select the environment you would like to move the package(s) to and click **OK**. The package(s) will be moved and the package listing will be updated.

Downloading Packages

Downloading a package copies the package from a remote server to your local server. Only packages that are not on your local server can be downloaded. The remote server that you want to download from must be set up as a virtual machine before you can download.

To Download a Package

1. Navigate to **SoftRater Explorer** for the appropriate subscriber.
2. The Explorer will automatically load the list of packages for the default environment.




Figure 59 SoftRater Explorer Screen

- To get a listing of packages that are available for download, select a remote server using the drop down and then click **Get Listing!**. For information on setting up a remote server, see Virtual File Server Management.
- The package listing will refresh and packages that are available for download will have a package icon (📦) next to them.




Figure 60 Selecting Packages to Download

- Select the package(s) you would like to download and click **Download**.




Figure 61 Downloading SoftRater Packages

Download Options

Sync:

This will download the package(s) while you wait.

Async:

This will download the package(s) in the background and, optionally, notify you at the email address you enter when downloading is complete.

Email address:

If you want to be notified when the download operation is finished, either select or enter your email address. If you would like to add your email address to the drop down list, see Explorer Configuration.

- When you have finished choosing your options, click **OK**.
 - If you chose the Sync download option, the package listing should refresh and the downloaded packages will have been removed from the listing.
 - If you chose the Async download option, you should receive a message that the request was successful.

When the process finishes, if you elected to receive an email, you should receive an email with the results. If you elected not to receive an email, nothing will be sent to you. The package listing will be refreshed and the downloaded packages will remain in your listing but without the package icon.

If you receive an error message, check your configuration settings and try again.




Figure 62 Download Package Results

Unloading Packages

Unloading a package removes the logic for that package from the database. The package itself remains on disk until deleted. You do not need to unload a package before loading another package for the same program and version. If you load a package for a program and version that already has a package loaded, the old package will be unloaded before the new package is loaded.

To Unload a Package

1. Navigate to the **SoftRater Explorer** for the appropriate subscriber.




Figure 63 SoftRater Explorer Screen

- The Explorer will automatically load the list of packages for the default environment. You can use the drop down to select a different Environment and click **Get Listing!** to update the list of packages.
- Select the package(s) you would like to unload.




Figure 64 Selecting Packages to Unload

- Right click one of the selected packages and choose **Unload** from the popup menu.




Figure 65 Unloading SoftRater Packages

Unload Options

Sync:

This will unload the package while you wait. This option is only available if you are unloading one package.

Async:

This will unload the packages in the background and, optionally, notify you at the email address you enter when unloading is complete. This is the only option available when unloading multiple packages.

Email address:

If you want to be notified when the unload operation is finished, either select or enter your email address. If you would like to add your email address to the drop down list, see Explorer Configuration.

5. When you have finished choosing your options, click **OK**.
 - If you chose the Sync unload option, the package listing should refresh and the unloaded package will no longer have an icon (📁) next to the name.
 - If you chose the Async unload option, you should receive a message that the request was successful.

When the process finishes, if you elected to receive an email, you should receive an email with the results. If you elected not to receive an email, nothing will be sent to you. Refresh the package listing and the unloaded packages will no longer have an icon (📁) next to their name.

If you receive an error message, check your configuration settings and try again.




Figure 66 Download Package Results

Copying Packages

Copying a package works the same as copying a file on your hard drive. The package will be copied from the current environment and moved to the selected environment.

To Copy a Package

1. Navigate to the **SoftRater Explorer** for the appropriate subscriber.
2. The Explorer will automatically load the list of packages for the default environment. You can use the drop down to select a different environment and click **Get Listing!** to update the list of packages.




Figure 67 SoftRater Explorer Screen

3. Select the package(s) you would like to copy.




Figure 68 Selecting Packages to Copy

4. Right click one of the selected packages and choose **Copy SRP...** from the popup menu.



Figure 69 Moving SoftRater Packages

5. Select the environment you would like to copy the package(s) to and click **OK**. The package(s) will be copied and the package listing will be updated.

Deleting Packages

Deleting a package removes it from disk. Once deleted, a package cannot be reloaded.

To Delete a Package

1. Navigate to the **SoftRater Explorer** for the appropriate subscriber.
2. The Explorer will automatically load the list of packages for the default environment. You can use the drop down to select a different environment and click **Get Listing!** to update the list of packages.





Figure 70 SoftRater Explorer Screen

3. Select the package(s) you would like to delete. You can either click  or you can right click and select Delete from the menu.




Figure 71 Selecting a Package to Delete

4. This will open the **Delete Package** window, where you can specify options for deleting the package(s).




Figure 72 Deleting SoftRater Packages

Delete Options

Sync: This will delete the package(s) while you wait.

Async: This will delete the package(s) in the background and, optionally, notify you at the email address you enter when deleting is complete.

Email address: If you want to be notified when the delete operation is finished, either select or enter your email address. If you would like to add your email address to the drop down list, see Explorer Configuration.

5. When you have finished choosing your options, click **OK**.
 - If you chose the Sync delete option, the package listing should refresh and the deleted packages will have been removed from the listing.
 - If you chose the Async delete option, you should receive a message that the request was successful.

When the process finishes, if you elected to receive an email, you should receive an email with the results. If you elected not to receive an email, nothing will be sent to you. The package listing will be refreshed and the deleted packages will have been removed from the listing.

If you receive an error message, check your configuration settings and try again.

NOTE

If you delete a package that is loaded, the package will remain loaded. However, if you unload a package that has been deleted, you will not be able to reload it or move it to a different environment.

Searching for Packages

To quickly find the package(s) you need, you can use the search option available from the SoftRater Explorer.

To Search for a package

1. Navigate to the **SoftRater Explorer** for the appropriate subscriber.
2. The Explorer will automatically load the list of packages for the default environment.
3. Click the magnifying glass icon (🔍) to expand the search toolbar.




Figure 73 Searching for a Package

Search Options

Remote Listing: Allows you to filter which remote packages will be shown.

- **Global** – Will show all packages located on the virtual server, even if they are for a different subscriber.
- **Subscriber** – Will only show packages located on the virtual server if they are for the current subscriber.
- **Datastore** – Will only show packages located on the virtual server if they are for the current datastore.

Date Filter: Allows you to filter the packages based on when they were created.

- **None** – Will not apply a date filter.
- **Today** – Will only show packages that were created today.
- **This Week** – Will only show packages that were created this week.
- **This Month** – Will only show packages that were created during the current month.
- **Last Month** – Will only show packages that were created in the prior month.
- **Last Year** – Will only show packages that were created in the prior year.

Package Status: Allows you to filter packages based on whether there status.



- **On Disk** – Will only show packages that are currently stored on disk, regardless of whether or not they have been loaded to the database.
- **All** – Will show packages that are on disk and packages that have been loaded to the database, but deleted from disk.

LOB: Allows you to filter the packages based on the line of business. Only LOB's that have been set up through the configuration page will show in this listing. See Adding/Deleting a Line of Business for more information.

Desc: Name of the program the package is for. This option is case sensitive.

Program: The program number the package is for. This option treats the program number as text. Thus, if you search for **1**, this will match programs **1, 13, 21**, etc.

Version: The version number the package is for. This option is also treated as text.

4. Once you have entered your search options, click .
5. If you want to hide the search toolbar, click  again or click [hide](#), located in the upper right corner of the screen.

NOTE

Hiding the search toolbar does not reset the search options to default. The search options will be reset the next time you navigate to SoftRater Explorer.

Viewing Package Details

The package listing shows information about each package including the program name, version, ID, LOB, time stamp and size. Additional details, such as deployment notes, input XML and output XML are also available for packages.

To View Details about a Package

1. Navigate to the **SoftRater Explorer** for the appropriate subscriber.
2. Select the package you would like to see details about.
3. Right click the selected package and choose **Show Details** from the popup menu.




Figure 74 Selecting a Package to View Details

4. A bottom frame will open that has information about the package.

In Figure 74, the details displayed are for a Release. The icon in front of the release indicates that a package has been changed and unloaded since the Release was packaged. When this happens, the updated package will be placed in the list and can be re-packaged..

Details for Viewing

Package details will vary and not all packages may not contain details.

Notes: When a user creates a full package, they have the option of including deployment notes. Any notes included when the package was created will be shown here.

Programs: If more than one program is in the packages, the program details will be listed out.

Insbridge Rating Input XML: Allows you to see what the input XML should look like.

Insbridge Rating Output XML: Allows you to see what the output XML will look like.






Translator Files: Allows you to see samples translator files for use with custom XML. Translator files will only be listed if the user has selected this option when creating a full package.

Local Insbridge Input Translators: Allows you to see the name and the file used for the input translations. Local Insbridge input translators will be listed only if the user has selected this option when creating a full package.

NOTE	The bottom frame will remain open with the selected package until you right click and choose Show Details again.
-------------	---

Package Icons

Some packages/releases on the SoftRater Explorer packages tab will have icons in front to indicate that an action has taken place.

Icon	Description
	A package has been loaded.
	A package contained within this release has been unloaded from the release. Packages are unloaded when an updated version is created. To see which package has been unloaded, highlight the release and right click. Select Show Details. The lower portion of the screen will display the contents of the release. If the package icon is displayed, that package is still included. If the package icon has been removed, that package has been unloaded.
	A release is unlocked and open for updating.
	A package that was created using ESI. This icon will be displayed in front of the package name. ESI packages are not system generated. ESI packages are entered directly into the database. See External API Access within this guide and The ESI User Guide for information on working with ESI.
	A package that is available for download. This icon will be displayed when a package is located on another server and can be downloaded. Once the package is downloaded, the icon will be removed.

SoftData Test Interface

The SoftData Test Interface allows you to test a SoftData request file that is in InsbridgeDataRequest.XML format. You can select the file or you can copy from a source and paste in the text box.

To Test a File Using the SoftData Test Interface

1. Using the menu tree, click **SoftData**.



2. This will open the **SoftData Test Interface** page.

SoftData Test Interface

This page will test SoftData request submittals. Click [here](#) to view the SoftData help document.


A screenshot of the 'SoftData Test Interface' page. At the top, there is a blue header bar with the text 'REQUEST INFORMATION'. Below the header, there is a text input field with the label 'Select an XML file or enter text below:'. To the right of the input field are two buttons: 'Browse...' and 'GetFile'. Below the input field is a large, empty text box with a vertical scrollbar on the right side. At the bottom of the text box are two buttons: 'Clear' and 'ViewXml'.

Figure 75 SoftData Test Interface

3. Browse for an XML file to use or copy and paste an XML file into the large text box. If you browse for an XML file, you can view the XML in the large text box by clicking **GetFile**. This allows you to edit the XML before rating.

NOTE

You cannot use your mouse right click features to cut and paste however, you can use your keyboard controls. Highlight the text you want to cut or copy. Use the Control Key plus the letter key to either "C" copy or "X" cut. Position your cursor where you want your text to be placed. Use the Control Key plus the letter key "V" to paste.

Control + X will cut text.
Control + C will copy text.
Control + A will select all text.
Control + V will paste text.

4. When you are ready to submit the file, click **Execute!**.
5. The file will be submitted and the results will be shown in the results box.

Results

Any results received from the InsBridge SoftData Engine request will be in the text area below.

RESULT INFORMATION
<pre><ibdoc gen_date="9/22/2006 12:09 PM" timespan="0.625016"><dataresults lob="1" env_def="rm_sit"><program parent_id="123" id="69" ver="1"><m i="62" r="1" l="false"><d p="1"><v>1.00</v><q>1</q></d><d p="2"><v>0.98</v><q>2</q></d><d p="3"><v>0.96</v><q>3</q></d><d p="4"><v>0.94</v><q>4</q></d><d p="5"><v>0.92</v><q>5</q></d><d p="6"><v>0.90</v><q>6</q></d><d p="7"><v>0.88</v><q>7</q></d><d p="8"><v>0.86</v><q>8</q></d><d p="9"><v>0.84</v><q>9</q></d><d p="10"><v>0.82</v><q>10</q></d></m><m i="53" r="1" l="false"><d p="1"><v>1.00</v><q>1</q></d><d ...at this time...</m></ibdoc></pre>
<input type="button" value="Clear"/> <input type="button" value="Execute!"/> <input type="button" value="ViewXml"/>

Last Exec Time: Wed Nov 22 10:14:39 CST 2006

Note: Microsoft Internet Explorer 5.5 required

Note: Browser security setting required: Initialize and script ActiveX controls not marked as safe: Set to "Enable" or "Prompt"

Figure 76 Test Results

6. To view the XML file in Internet Explorer, click **ViewXml**.

Services

The Services page allows you to start and stop the **Insbridge Message Service** and **Insbridge Task Manager**. It also allows you to view messages, configure the Message Service and view tasks.

Navigating to the Services Page

- Using the menu tree, select **Services**.



- This will open the **Services** page.

Insbridge Message Service

The Insbridge Message Service is a Message Queue Listener that will route all batched messages to an assembly (process) for execution. These processes may take resources and time to execute. Please consult with you system admin before configuring the number of listeners per process.

Message Process

Batch Rating

If you see this message, you have not requested a listing from the selected spoke client. Clicking View Messages will provide you with a list view of the first in - first out messages that are waiting to execute.

Insbridge Task Manager

The Insbridge Task Manager gives you the ability to execute daily, weekly, hourly, or by the minute.

(This process may take a while to execute)

TASK	LAST RUN-DATE	START-TIME	STATUS

Figure 77 Insbridge Services Screen

- From here you can interact with the Insbridge Message Service.

Introduction to the Insbridge Message Service

The Insbridge Message Service is a message queue listener that routes messages to an assembly for execution.

For example, when a user submits a rate request in BatchManager, that request gets picked up by the Insbridge Message Service and delivered to the batch-rating client. The batch-rating client then rates the file and notifies the user when the results are ready. If the Insbridge Message Service is not started, the request will remain in the queue until it is either deleted or the service is started, at which point the request will be sent.

Starting & Stopping the Message Service

Framework Administrator provides the ability to start and stop the Message Service. When stopped, messages will be sent to the appropriate queue. When the Message Service is started again, the messages will be processed on a first-in, first-out basis.

The Message Service has two buttons to accomplish this task, **Start** and **Stop**. Only one button will be enabled at a time. If the start button is enabled, it means the service is currently stopped. If the stop button is enabled, it means the service has been started. The grayed out button is the current operation status. For example, if the start button is grayed out, the service has been started. If the stop button is grayed out, the service has been stopped.

To Start or Stop the Message Service

1. Navigate to the **Services** page.

Insbridge Message Service

The Insbridge Message Service is a Message Queue Listener that will route all batched messages to an assembly (process) for execution. These processes may take resources and time to execute. Please consult with you system admin before configuring the number of listeners per process.

Message Process

Batch Rating

If you see this message, you have not requested a listing from the selected spoke client. Clicking View Messages will provide you with a list view of the first in - first out messages that are waiting to execute.

Insbridge Task Manager

The Insbridge Task Manager gives you the ability to execute daily, weekly, hourly, or by the minute.

(This process may take a while to execute)

TASK	LAST RUN-DATE	START-TIME	STATUS
------	---------------	------------	--------

Figure 78 Insbridge Services Screen

2. Next to **Insbridge Message Service**, click or .
3. After a few seconds, the buttons will refresh to indicate if the service is started or stopped.
4. If one of the clients is currently performing an operation, you may receive an error message when you attempt to stop the service. Simply click again to stop the service. The client will abort the operation and the service will be stopped.

Viewing Messages

When a message is submitted to the Message Service and cannot be immediately routed to the appropriate client, the message gets placed in a queue. This can happen if the Message Service is stopped or the client is currently working on another request. The Message Service contains six queues. Each queue operates on a first-in, first-out basis.

To View Messages in the Queue

1. Navigate to the **Services** page.

Insbridge Message Service

The Insbridge Message Service is a Message Queue Listener that will route all batched messages to an assembly (process) for execution. These processes may take resources and time to execute. Please consult with you system admin before configuring the number of listeners per process.

Message Process

Batch Rating

If you see this message, you have not requested a listing from the selected spoke client. Clicking View Messages will provide you with a list view of the first in - first out messages that are waiting to execute.

Insbridge Task Manager

The Insbridge Task Manager gives you the ability to execute daily, weekly, hourly, or by the minute.

(This process may take a while to execute)

TASK	LAST RUN-DATE	START-TIME	STATUS

Figure 79 Insbridge Services Screen

2. Select the appropriate client from the drop down.
 - Batch Rating
 - PricingManager
 - SoftRater - Package
 - Broker - Request
 - Broker - Response
 - Administration

3. Click .
4. The listing will refresh and show any messages that are currently in the queue.

Insbridge Message Service

The Insbridge Message Service is a Message Queue Listener that will route all batched messages to an assembly (process) for execution. These processes may take resources and time to execute. Please consult with you system admin before configuring the number of listeners per process.




Figure 80 Insbridge Message Service

5. To view details on a specific message, click the underlined portion (in this case, Scenario Request).
6. Information about the message will open in a separate window.




Figure 81 Batch Message Information

You can copy the contents of the message to the clipboard by clicking  Copy.

Deleting Messages

At times, you may want to prevent messages that are currently in the queue from being submitted to the appropriate client. To do this, you can delete the messages from the queue.

To Delete Messages from the Queue

This will delete all messages from the selected queue.

1. Navigate to the **Services** page.

Insbridge Message Service

The Insbridge Message Service is a Message Queue Listener that will route all batched messages to an assembly (process) for execution. These processes may take resources and time to execute. Please consult with you system admin before configuring the number of listeners per process.

Message Process

Batch Rating

If you see this message, you have not requested a listing from the selected spoke client. Clicking View Messages will provide you with a list view of the first in - first out messages that are waiting to execute.

Insbridge Task Manager

The Insbridge Task Manager gives you the ability to execute daily, weekly, hourly, or by the minute.

(This process may take a while to execute)

TASK	LAST RUN-DATE	START-TIME	STATUS
------	---------------	------------	--------

Figure 82 Insbridge Services Screen

2. Select the appropriate client from the drop down.
 - Batch Rating
 - PricingManager
 - SoftRater - Package
 - Broker - Request
 - Broker - Response
 - Administration
3. Click .
4. The listing will refresh and show any messages that are currently in the queue.

Insbridge Message Service

The Insbridge Message Service is a Message Queue Listener that will route all batched messages to an assembly (process) for execution. These processes may take resources and time to execute. Please consult with you system admin before configuring the number of listeners per process.




Figure 83 Insbridge Message Service

5. Click . All messages will be deleted from the selected queue and the listing will refresh.

Process Configuration

For each client, the Framework Administrator allows you to change how many threads are used. Threading enables a process to finish faster by splitting the process into smaller processes that run quasi-simultaneously. On multiprocessor systems, using multiple threads enables the operating system to assign the threads to different processors.

In addition, the Framework Administrator also enables you to change the administrator email address for each client. When a process fails, an email will be sent to the person who initiated the process, as well as to the administrator email addresses listed for the client of that process.

WARNING	Before changing the number of threads, you should consult with your system administrator. Setting the number too high can result in poor performance or even a system crash. If you are unsure of how many threads to use, set the number to 1. For single processor systems, Insbridge recommends a maximum of 2 threads.
----------------	---

Editing the Process Configuration for a Client

1. Navigate to the **Services** page.

Instridge Message Service

The Instridge Message Service is a Message Queue Listener that will route all batched messages to an assembly (process) for execution. These processes may take resources and time to execute. Please consult with you system admin before configuring the number of listeners per process.

Message Process

Batch Rating

If you see this message, you have not requested a listing from the selected spoke client. Clicking View Messages will provide you with a list view of the first in - first out messages that are waiting to execute.

Instridge Task Manager

The Instridge Task Manager gives you the ability to execute daily, weekly, hourly, or by the minute.

(This process may take a while to execute)

TASK	LAST RUN-DATE	START-TIME	STATUS

Figure 84 Instridge Services Screen

2. Select the appropriate client from the drop down.
 - Batch Rating
 - PricingManager
 - SoftRater - Package
3. Click .
4. This will open the **Process Configuration** window for the selected client.

Process Configuration -- Web Page Dialog

Services

SoftRater Batch Engine

The SoftRater Batch Rating tool allows you to rate hundreds or thousands of policies. See the PricingManager to see how you could utilize this product to make comparisons against batch rated files.

Threads:

Admin Emails:

Figure 85 Process Configuration Window

5. Enter an integer for the number of threads and email addresses separated by semicolons (;).
6. Click **Save** when finished to save your changes and return to the **Services** page.

Introduction to Insbridge Task Manager

The Insbridge Task Manager is a task queue that lists the tasks that are scheduled to be performed as well as the last time the task was run and the status. Tasks listed here are system tasks, for example, clearing out temporary files, and generally are not changed or altered once in place. Tasks are entered when IBFA is set up. To edit or delete a task, you must return to the IBFA setup files. Please contact Insbridge Support for more information.

Starting & Stopping Task Manager

Framework Administrator provides the ability to start and stop Task Manager. When stopped, tasks will not be performed. When Task Manager is started again, the tasks will be processed as scheduled. Tasks that are past due will not be processed. For example, if a temp file cleanup is scheduled nightly and the Task Manager was stopped four days ago, the temp file cleanup will not be run four additional times.

Task Manager has two buttons, **Start** and **Stop**. Only one button will be enabled at a time. If the start button is enabled, task manager is currently stopped. If the stop button is enabled, task manager has been started. The grayed out button is the current operation status.

Insbridge Task Manager

The Insbridge Task Manager gives you the ability to execute daily, weekly, hourly, or by the minute.

(This process may take a while to execute)







TASK	LAST RUN-DATE	START-TIME	STATUS
Project Temp File Cleanup	Jan 16 2009 4:00PM	2:00AM	Ready 
<p> ID: 5 Type: Daily Machine: Weekend: True</p> <p> Path: [FRAMEWORK_PATH]\Insbridge.Net.Fwk.dll</p> <p> Type: Insbridge.Net.Fwk.PrjClean</p> <p> Success Emails: False</p>			

Figure 86 Insbridge Task Manager

Viewing Task Details

To view the currently scheduled tasks, click . The tasks will be listed below. To collapse the task details, click the corresponding up arrow ().

Error Log

The Error Log allows you to view all errors encountered while using RateManager. It also allows you to view errors generated by an Insbridge application. These events are separated into two types.

- **Database Events** are triggered when a user tries to do something they are not allowed to do (such as trying to delete a used variable).
- **Event Log Events** are triggered when an Insbridge application either fails to do what it is supposed to do, or successfully completes an operation.

To Navigate to the Error Log

1. Using the menu tree, click the plus box (+) next to **Logs** to expand it and then click **Error**.



2. This will open the **Error Log**.

Insbridge Database Events

Insbridge saves log information to your client database. This page will show you a listing of those logs.

Database Log Information

Age: Today

If you see this message, you have not requested a log listing from the selected log. Clicking View Logs will provide you with a list view of that particular log.

Insbridge Event Log Events

This will provide you with a listing of event logs that reside in the Windows Event Viewer.

TYPE	DATE	APPLICATION
Age: Today <input type="button" value="View Logs"/>		
If you see this message, you have not requested a log listing of Insbridge events from the event log.		

Figure 87 Insbridge Error Log

3. From here, you can view **Database Events** and **Event Log Events**.

Database Events

Database events are triggered when a user encounters an error while using RateManager.

For example, if a user tries to delete a variable that is still being used, RateManager will display an error message that the variable cannot be deleted, and the error will be logged in the database event log.

To View the Database Event Log

1. Navigate to the **Error Log**.

Insbridge Database Events

Insbridge saves log information to your client database. This page will show you a listing of those logs.

Database Log Information

Age:

If you see this message, you have not requested a log listing from the selected log. Clicking View Logs will provide you with a list view of that particular log.

Insbridge Event Log Events

This will provide you with a listing of event logs that reside in the Windows Event Viewer.

TYPE	DATE	APPLICATION
Age: <input type="button" value="Today"/> <input type="button" value="View Logs"/>		
If you see this message, you have not requested a log listing of Insbridge events from the event log.		

Figure 88 Insbridge Error Log

2. Select the **Age** drop down under **Insbridge Database Events** to select the age limit for the events you want to view. Click when you are finished making your choice.
3. The database log will update to show the events you requested.

Insbridge Database Events

Insbridge saves log information to your client database. This page will show you a listing of those logs.

Database Log Information

Age:








 <u>Program</u>	1/22/2008 10:52:18 AM	Program name not unique for current ...	
Program name not unique for current line and company. Please make your changes and try your request again.			
 <u>SupportServices</u>	1/22/2008 10:32:02 AM	Could not find a part of the path "\...	
 <u>Variables</u>	1/22/2008 09:58:38 PM	The selected Result Variable can ...	

Figure 89 Insbridge Database Events

4. To view details about an event, click the corresponding down arrow (). The details will be displayed in an information box.
5. To email an event, click the underlined portion of the event to open the email form.




Figure 90 Emailing an Event

6. Enter your email address and the address you want to send the error to. You can send the error to multiple addresses by separating them with a semicolon (;). You can also enter a message to give further details about the error. The actual error message cannot be edited. When you are ready to send the message, click .

Event Log Events

When an Insbridge application generates an error, it logs the event in the server's event viewer. Error events occur when an Insbridge application fails to do what it is supposed to. For example, if the Insbridge Message Service fails to start, an error event will be logged.

In addition to error events, information events are also logged in the event viewer. An information event describes the successful completion of an operation by an Insbridge application. For example, when the Insbridge Message Service starts successfully, an information event is logged.

To View the Event Log

1. Navigate to the **Error Log**.

Insbridge Database Events

Insbridge saves log information to your client database. This page will show you a listing of those logs.

Database Log Information

Age: Today

If you see this message, you have not requested a log listing from the selected log. Clicking View Logs will provide you with a list view of that particular log.

Insbridge Event Log Events

This will provide you with a listing of event logs that reside in the Windows Event Viewer.

TYPE	DATE	APPLICATION
Age: Today <input type="button" value="View Logs"/>		
If you see this message, you have not requested a log listing of Insbridge events from the event log.		

Figure 91 Insbridge Error Log

2. Select the **Age** drop down under **Insbridge Event Log Events** to select the age limit for the events you want to view. Click when you are finished making your choice.
3. The event log will update to show the events you requested.

Insbridge Database Events

Insbridge saves log information to your client database. This page will show you a listing of those logs.

Database Log Information

Age: All

0 events found.

Insbridge Event Log Events

This will provide you with a listing of event logs that reside in the Windows Event Viewer.





















TYPE	DATE	APPLICATION
Age: All <input type="button" value="View Logs"/>		
 Error	5/1/2008 10:25:14 AM	InsbridgePublishedException 
 Error	4/30/2008 3:48:55 PM	InsbridgePublishedException 
 Error	4/30/2008 3:48:55 PM	InsbridgePublishedException 
 Error	4/30/2008 2:02:21 PM	InsbridgePublishedException 
 Error	4/29/2008 1:48:20 PM	InsbridgePublishedException 
 Error	4/29/2008 12:50:33 PM	InsbridgePublishedException 
 Error	4/29/2008 12:50:33 PM	InsbridgePublishedException 
 Information	4/29/2008 11:03:30 AM	InsbridgeMessageService 
 Information	4/29/2008 11:03:30 AM	InsbridgeMessageService 
 Information	4/29/2008 11:03:30 AM	InsbridgeMessageService 

Figure 92 Insbridge Event Log Event

4. To view details about an event, click the corresponding down arrow (▼). The details will be displayed in an information box.
5. To email an event, click the underlined portion of the event to open the email form.




Figure 93 Emailing an Event

6. Enter your email address and the address you want to send the error to. You can send the error to multiple addresses by separating them with a semicolon (;). You can also enter a message to give further details about the error. The actual error message cannot be edited. When you are ready to send the message, click .

Introduction to the Audit Log

The Audit Log keeps track of all SoftRater package activity, known as audit events. There are four types of audit events:

- **Download:** An event that records the downloading of a package.
- **Load:** An event that records the loading of a package.
- **Unload:** An event that records the unloading of a package.
- **Delete:** An event that records the deletion of a package.

Viewing the Audit Log

1. Using the menu tree, click the plus box (+) next to **Logs** to expand it and then click **Audit**.



2. This will open the **Audit Log**.

Audit Events

Insbridge audits all SoftRater package activity. This page will show you a listing of these logs.

[\[First Page\]](#) [\[Previous Page\]](#) [\[Next Page\]](#) [\[Last Page\]](#) Page 1 of 1

DESCRIPTION	USER	DATE
Load SoftRater Package Request.		Apr 07 2008 4:04PM
Load SoftRater Package Request.		Apr 07 2008 4:04PM
Move SoftRater Package Request.	SKYWIRE\mgatewood	Mar 23 2008 12:25PM
Load SoftRater Package Request.	SKYWIRE\mgatewood	Mar 23 2008 11:37AM
Load SoftRater Package Request.	SKYWIRE\mgatewood	Mar 23 2008 11:37AM
Load SoftRater Package Request.		Mar 23 2008 11:36AM
Load SoftRater Package Request.		Mar 23 2008 11:36AM
Load SoftRater Package Request.		Mar 04 2008 10:57AM
Unload SoftRater Package Request.		Mar 04 2008 10:57AM
Load SoftRater Package Request.		Mar 04 2008 10:56AM

Figure 94 Audit Log

3. The **Audit Log** shows twenty-five events per page. You can navigate between the pages using the navigational links, First Page, Previous Page, Next page and Last Page located at the top of the page.
4. Click the underlined description to view details about the event.




Figure 95 Viewing Audit Log Details

The security section of the Framework Administrator allows an administrator to set the type of authentication that will be used to certify users and allow them to access to all sections of the Framework Administrator. If a user does not have full access, they will be allowed to see only the **Packages** tab of the SoftRater Explorer. Within the SoftRater Explorer, the user will only be able to manipulate packages that are not located in a secure environment. For more information, see the following sections:

- Changing the Type of Authentication Used
- Securing an Environment - see Adding/Deleting an Environment
- Changing the Password

Changing the Type of Authentication Used

The Framework Administrator allows you to set the type of authentication used. The available options are:

- **None:** All users will have access to all portions of the Framework Administrator.
- **Windows:** Users, and the areas of the Framework Administrator they can access, are validated by IIS. See Windows Authentication for more information.
- **Custom:** Users can log in through an HTML form. Users that are not logged in can only access non-secure environments. See Custom Authentication for more information.

To Change the Type of Authentication

1. Using the menu tree, click **Security**.



2. This will open the **Security** page.

Framework Administration Web Security

To utilize Windows authentication please select the Windows security option and contact your system administrator to update your IIS settings. The Insbridge Custom Forms authentication requires that you enter an admin user and password combination for web access.

- None
- Windows
- Custom
- Allow unauthorized users to view secure environments? (read-only)

External API Access

The Insbridge Framework Administrator has an open API for back-office system automation. To allow an external process to connect to this node, enable and set the access key below.

- Disabled
- Enabled

Figure 96 Insbridge Security Page

3. Select the radio button next to the type of authentication you want to use.
4. Click to save your changes. The next time a user attempts to access the Framework Administrator, the type of authentication you selected will be used to validate their credentials.

Windows Authentication

This option relies on Microsoft Internet Information Services (IIS) to provide authenticated users. All methods supported by IIS are permitted.

When using IIS, the provider module uses the authenticated identity passed in from IIS. IIS authenticates the identity using basic, digest, integrated Windows authentication or some combination of these. You can use impersonation and NTFS ACL permissions to restrict or allow access to protected resources.

For more information on IIS, see the Internet Information Services Home Page.

Custom Authentication

This option collects a user's credentials through a login screen. The user enters a user ID and password and then submits the HTML form. If the application authenticates the request, the system issues a cookie that contains the credentials, key, for reacquiring the identity. Subsequent requests are issued with the cookie in the request headers. The requests are authenticated and authorized by an ASP.NET event handler, using whatever validation method the application specifies. The system also allows the administrator to change or reset the password that is encrypted on disk.

When custom authentication is used, users will initially only see the SoftRater Explorer page.



Figure 97 SoftRater Explorer

If a user wants to navigate to the **Packages** tab of the SoftRater Explorer, they can click the carrier's name (in this case, **Mary RM311**).




Figure 98 Packages Tab of SoftRater

The user only will be allowed to see and manipulate packages that are in non-secure environments.

To have full access to the Framework Administrator, a user must log in. To do this, click [Show FrameworkAdmin Menu](#) located in the upper left corner of the page. A sign-in form will open in the left frame where the user can enter a user ID and password.




Figure 99 Logging into Framework Administrator

User ID, Default Password, Resetting the Password

For security purposes, information regarding the user ID, default password and resetting the password is not included in this help document. For information regarding these, contact a support representative (support-skywire_ww@oracle.com).

External API Access

Oracle Insurance Insbridge Rating and Underwriting Extended Services Interface (ESI) is a library module designed to provide remote services to the Insbridge Rating and Underwriting (IBRU) business services without directly utilizing the system User Interfaces (UI).

ESI allows users to pass information between a user's source policy or business admin system and the RateManager system or the Insbridge Framework Administrator (IBFA) without using either the RateManager or IBFA UI. Information is passed through a custom built interface that resides on a source policy or business admin system on the client side to the ESI web service that resides on the IBRU side. The information is processed and results returned from the ESI web service back to the custom built interface into the client's source policy or business admin system.

ESI is designed to operate on Insbridge version 3.11 and will connect with:

- Oracle Insurance IBRU RateManager Interface
- Oracle Insurance Framework Administrator Interface

To use ESI's IBFA Framework functionality, you need to send down the API key when you do the ESI API call.

When IBFA is installed, a default API key will be generated and saved in IBFA. You can find it in *IBFA* > *Insbridge* > *Security* > *External API Access*.

You can disable ESI's IBFA functionality by setting it to **Disabled**.

For security purpose, you may want to change the key once in a while. To change the key, click on **Generate Key** and then click on **Update**. Every key generated will be unique.

Framework Administration Web Security

To utilize Windows authentication please select the Windows security option and contact your system administrator to update your IIS settings. The Insbridge Custom Forms authentication requires that you enter an admin user and password combination for web access.

- None
- Windows
- Custom
- Allow unauthorized users to view secure environments? (read-only)

External API Access

The Insbridge Framework Administrator has an open API for back-office system automation. To allow an external process to connect to this node, enable and set the access key below.

- Disabled
- Enabled


Figure 100 Allowing External API Access

Changing the Password

You can change the password used for **Custom** authentication at anytime. This password is only utilized when the authentication type has been set to **Custom**. For information on resetting the password, please contact Oracle Insurance Insbridge Support (support-skywire_ww@oracle.com).

To Change the Password

1. Using the menu tree, click the plus box (+) next to **Security** to expand it and then click **Change Password**.



2. This will open the **Change Password** page.

Change 'Custom Security' Admin Password

Insbridge suggests that you use a password that is 6-8 characters long. If you think someone else knows the admin password, please contact your system administrator.

Old Password	<input type="text"/>
New Password	<input type="text"/>
Confirm Password	<input type="text"/>
<input type="button" value="Update"/>	

Figure 101 Changing your Password

3. Enter your current password in the **Old Password** box and enter your new password in the **New Password** and **Confirm Password** boxes. As you type, the text will be shown as asterisks (*) or bullets (•), depending on your browser.
4. When you are finished, click to update your password. The next time a user tries to log in to the Framework Administrator, they will need to use the new password.

SoftLibraries

The SoftLibraries section of the Framework Administrator allows an administrator to add, edit or delete external SoftLibraries. SoftLibraries will be available to all subscribers. SoftLibraries can be created by developers and stored either locally or remotely. Once added into IBFA, these SoftLibraries can be used by callout programs in RateManager. In SoftLibraries you can:

- **Add SoftLibraries**
- **Edit SoftLibraries**
- **Delete SoftLibraries**

SoftLibraries are an advanced topic. This chapter will define the screen features and the functionality. Developing the code that is called will not be discussed here.

Navigating to SoftLibraries

1. Using the menu tree, click **SoftLibraries**.



2. This will open the **SoftLibraries** main page.

Add SoftLibrary

Create or Edit an external library. The library can be an executable, a .NET Library, a Java Library, or a Web Service. Click [here](#) to view the implementation interfaces. You may also submit requests to your SoftLibrary using the [SoftLibrary WebService](#).

NAME	TYPE	STATUS
------	------	--------

Figure 102 SoftLibrary Main Page

The main SoftLibraries page will display any entered SoftLibraries. Other information includes:

Name: The name of the SoftLibrary.




Figure 104 SoftLibrary Web Services

Adding SoftLibraries

1. Click the **Add SoftLibrary** link at the top of the screen. A separate window will be displayed.

Figure 105 SoftLibrary Screen

The SoftLibrary screen will allow you to enter in basic information and to view critical information about the SoftLibrary. There are eight options on the side menu:

Library: The basic SoftLibrary information is entered here.

Arguments: Enter the arguments for the SoftLibrary here.

GetHelpText: This is an information screen. If you want a quick view of the SoftLibrary, this screen contains the basic information.

Request XML: The request XML will be displayed here. This will tell you what requests you are sending out. This is an information only screen.

Response XML: The response XML will be displayed here. This will tell you exactly what you are getting back. This is an information only screen.

Ping: Will ping the server to verify server response.

GetLog: If logging is turned on, this screen will display logs.

Test: Allows you to test the SoftLibrary.

2. The first screen is the Library information screen. Information must be entered here before you can continue.

The screenshot shows a web application window titled "Insbridge SoftLibrary -- Web Page Dialog". The window has a blue header bar with a "close" button in the top right corner. On the left side, there is a vertical sidebar menu with the following items: "Library" (highlighted in light blue), "Arguments", "GetHelpText", "RequestXML", "ResponseXML", "Ping", "GetLog", and "Test". The main content area is a form with the following fields and controls:

- Type:** A dropdown menu set to ".Net Web Service" with a "Search" button to its right.
- Admin Name:** A text input field containing "SoftServices Rating Engine".
- Class Name:** A text input field containing "SoftServices.Rating".
- Endpoint:** A text input field containing "http://oracle/ibfa/connectors/SoftLibraryRating.asmx".
- User:** A text input field containing "admin".
- Password:** A text input field with masked characters (dots).
- Timeout:** A text input field containing "30".
- Logging:** A checked checkbox.
- Status:** A dropdown menu set to "Active".

At the bottom right of the form area, there are three buttons: "Save", "Remove", and "Close".

Figure 106 Completed SoftLibrary Screen

Type: The type of SoftLibrary you want to enter, either .NET Web Service, WebSphere or WebLogic. You can search for a SoftLibrary if necessary. See Searching for a SoftLibrary.

Admin Name: This is the name of the SoftLibrary as it is displayed in RateManager. It is also the name that will be displayed on the main SoftLibraries page. Admin names must be unique.

Class Name: This is the name of the actual SoftLibrary created by the developer from the program where it was created. This information can be obtained from the developer. Class names must be unique.

Endpoint: The location of the Web Service. This information can be obtained from the developer. The endpoint is validated at Save. If this information is incorrect, timeout or other error messages may be thrown on the other screens.

User Name: Only required if the SoftLibrary must use a secure connection.

Password: Only required if the SoftLibrary must use a secure connection.

Timeout: The amount of time the SoftLibrary should wait for a response. Timeout is in milliseconds.

Logging: Check this box if you want logging. Leave it blank for no logging. The default is to have logging take place.

Status: The status of the SoftLibrary. If active is selected, the SoftLibrary will be displayed to RateManager users. If disable is selected, the SoftLibrary will not will be displayed to users. The default status is active.

3. Enter in the **Library** information. Type, Admin Name, Class name and Endpoint are required.
4. Click **Save** to save your entries before you advance to the next screen.
5. Arguments must be entered next. Click the **Arguments** option on the side menu.




Figure 107 Arguments Screen

6. Select available **Arguments** from the drop down menu. The argument name will populate the **Name** field. The current value will populate the **Value** field. If these arguments are correct, click **Save**. If you need to, you can edit both the name field and the value field by typing in what you need.

Adding an Argument

To add an argument, select **--New Argument--** in the Argument drop down list. Enter in a **Name** and a **Value**. Click **Save**. Your argument will be listed below.

Editing an Argument

To edit an argument, select the argument from the Argument drop down list. Edit the **Name** and a **Value**. Click **Save**. Your argument will be listed below with the new values.

Deleting an Argument

If there is an argument that you do not need, you can delete it. Select the argument from the drop down menu and click the **Delete** button. The argument will be removed.

7. If you want to check your SoftLibrary, continue on the **GetHelpText** option on the side menu. The basic information will be listed.




Figure 108 GetHelpText Screen

- The next information screen is the **RequestXML** screen. This screen will display the request XML that is going out.




Figure 109 RequestXML Screen

- The **ResponseXML** screen will tell you exactly what you are getting back.




Figure 110 ResponseXML Screen

10. If you would like to ping the server, click the **Ping** menu option.




Figure 111 Ping Screen

11. To view the logs, click the **GetLog** menu option.




Figure 112 GetLog Screen

- The last menu option is **Test**. Test has three parts. First you must enter in the RequestXML. You can enter in your own XML or you can click the button and have the XML auto populate for you.





Figure 113 Test Screen – Request

- Click the button to execute the XML. The responseXml will be displayed. To view the Arguments sent or to view the RequestXML, click the expand button .




Figure 114 Test Screen – Response

- After you have completed your SoftLibrary, return to the Library screen. If the save button is available, click **Save** to save your entries and then close the window. If the save button is grayed out, you can close the window.

Add SoftLibrary

Create or Edit an external library. The library can be an executable, a .NET Library, a Java Library, or a Web Service. Click [here](#) to view the implementation interfaces. You may also submit requests to your SoftLibrary using the [SoftLibrary Webservice](#).

NAME	TYPE	STATUS	
Southern HIO	.Net Web Service	Active	⌵
cg_SoftLib	.Net Web Service	Active	⌵
Library1 →	WebSphere SoftLibrary	Active	⌵
WebService1	.Net Web Service	Active	⌵
AUTO →	WebSphere SoftLibrary	Active	⌵
Random Number Generator	.Net Web Service	Active	⌵
SoftServices Rating Engine	.Net Web Service	Active	⌵

Figure 115 Completed SoftLibrary

NOTE	<ul style="list-style-type: none"> Windows based SoftLibraries can be copied locally. WebSphere and WebLogic SoftLibraries are remote only. Remote SoftLibraries are indicated by a red arrow → next to the SoftLibrary name.
-------------	--

Editing SoftLibraries

Any SoftLibrary can be edited at any time. Be aware that changes to a SoftLibrary here will affect any programs in RateManager that currently call this SoftLibrary without sending notice to users.

To edit a SoftLibrary, click on the name. The SoftLibrary screen will be displayed. Make your edits and click **Save**.

Deleting SoftLibraries

Any SoftLibrary can be deleted at any time. Be aware that changes to a library here will affect any programs in RateManager that currently call this SoftLibrary without sending notice to users.

To delete a SoftLibrary, click the name. The SoftLibrary screen will be displayed. Click the

Remove button. A warning message will be displayed, click OK to remove the SoftLibrary. Click Cancel to return to the SoftLibrary screen.

Searching for a SoftLibrary

You can search for SoftLibrary types by clicking the search button next to the **Type** option. A separate window will be displayed. Enter in your **Server Name** and select the **Registration** type. Click **Search**. If the server is found, the SoftLibrary type will be listed in the Admin Name field.




Figure 116 SoftLibrary Type Search

If during the installation or configuration of the Insbridge Rating and Underwriting Solution you receive an error or need a question answered, please contact Support at support-skywire_ww@oracle.com or <http://www.oracle.com/skywiresoftware/support.html>.

Address any additional inquiries to:

Oracle Corporation
World Headquarters
500 Oracle Parkway
Redwood Shores, CA 94065
U.S.A.

Worldwide Inquiries:
Phone: +1.650.506.7000
Fax: +1.650.506.7200
oracle.com

Glossary

A	
Administrator:	The person designated by your company who has the authority to create and change groups, usernames, passwords and restrictions.
Algorithm:	A sequence of steps used to perform a calculation.
Assigned Driver:	A driver who has been assigned to a vehicle.
Assigned Vehicle:	A vehicle that has been assigned a driver.
C	
Calculated Variable:	Calculated Variables are used when a result cannot best be derived from simple data mapping in a table. For example, if age is not passed as an input, but is a criteria needed in determining other factors, you would use a Calculated Variable to calculate driver age from the inputs of effective date and driver date of birth. Calculated Variables look at every node (driver, vehicle, location, etc.) independently and create a result for each. Once a calculated variable is created, the result can be used in any other variable.
Callouts	A set of a single or multiple programs and/or SoftLibraries that allows users to call needed operations at a specific time from either inside the system or outside the system.
Category:	A user defined group of information that defines inputs, variables, algorithms and the overall structure of the program.
Criteria:	An input or variable used in a mapped variable to determine which value to return. Any input or variable can be used as a criteria.
D	
Data Type:	The type of data associated with a parameter. RateManager supports three (decimal, integer and string) data types for variables and inputs and a fourth (date) for inputs and result variables only.
Date:	A data type supported for inputs and result variables only. For more information, see Dates in the Contents section.
Decimal:	A data type supported for all types of variables and inputs. Examples of decimal values are 3.1415, 18 and 0.995.
Default Value:	Used by a mapped variable if no match is found based on the criteria.
Dependency:	When copying a variable, algorithm or driver assignment, any element that requires another element to be present or defined will be listed. All dependencies must be resolved.
Driver Assignment:	Driver assignment is an auto insurance specific method of assigning a particular driver to a particular vehicle on a policy, based on certain criteria. Criteria often differ on a carrier basis, and sometimes even on a program level.
Driver Assignment Scenario:	A driver assignment scenario is a list of instructions that define the main sequence of operations to properly define the driver assignment logic for a carrier. A scenario is based upon the same algorithm principle used throughout the RateManager software.

E	
Export:	Exports allow users to export all elements of a program from one database to another database or within the same database. Or to export data in tab-delimited form, from a RateManager table to an outside location.
F	
Flag:	A variable that holds a 1 for true and a 0 for false.
Flag Driver Algorithm:	An algorithm used by a Flag Driver Function to flag drivers based on certain criteria.
Flag Driver Function:	A built-in function used in the main driver assignment that defines the scope of the flagging operation. Most require an association with a predefined Flag Driver Algorithm.
Flag Vehicle Algorithm:	An algorithm used by a Flag Vehicle Function to flag vehicles based on certain criteria.
Flag Vehicle Function:	A built-in function used in the main driver assignment that defines the scope of the flagging operation. Most require an association with a predefined Flag Vehicle Algorithm.
G	
Global:	An input or variable that is available to all programs under a specific subline.
Global Input:	A value that is passed into the rating system.
Global Result:	A value that is passed out of the system after rating.
Group:	A set of users that have the same access rights.
I	
If:	A step type available for use in calculated variables and algorithms. For more information, see If in the contents section.
Import:	Import allows users to bring in programs from an outside location into RateManager. Or to import data in tab-delimited form, into a RateManager table.
Input:	A value that is passed into the rating system.
Integer:	A data type supported for all types of variables and inputs. Examples of integer values are 3, 1859865 and -47.
Interpolation:	An estimated value derived from two known values.
L	
Library:	The Library is where templates are stored and managed.
Linked Variables:	Two or more mapped variables that have been associated with one another because they use the same criteria.
Lock:	A lock will close all associated Variables, Algorithms, Driver Assignments, Sequencing and Result Mappings in a program version from deletions and edits.
M	
Mapped Variable:	A variable that uses other variables and inputs as criteria in determining the appropriate value. See Mapped Variables in the Contents section for more information.

Mask:	A feature that allows the customer to determine how data should be interpreted. See Masking in the Contents section for more information.
N	
Normal Rating Algorithm:	The most common type of algorithm. Examples of what it can be used for are: <ul style="list-style-type: none"> • Determine premiums • Calculate differences in limits being passed into the system vs. limits being rated by the system • Assign tiers
O	
Operator:	A built-in mathematical function used in calculations and comparisons.
P	
Package:	A small file that holds all the RateManager logic for a specific program and version.
Program:	A planned group of procedures executed in a specific order to return a rating. Programs in RateManager typically correspond to rate manuals. Programs can be either created by the users or imported.
Program Date Mask:	Specifies how SoftRater interprets dates being passed into an input file.
Program Folders:	A RateManager file management system that functions in much the same way as Microsoft Windows Explorer. This multi level setup allows for an unlimited number of program folders and subfolders to be placed underneath a subline.
R	
Rank Driver Algorithm:	An algorithm used by a Rank Driver Function to rate drivers based on certain criteria.
Rank Driver Function:	A built-in function used in the main driver assignment that defines the scope and sorting order of the ranking operation. Most require an association with a predefined Rank Driver Algorithm.
Rank Vehicle Algorithm:	An algorithm used by a Rank Vehicle Function to rate vehicles based on certain criteria.
Rank Vehicle Function:	A built-in function used in the main driver assignment that defines the scope and sorting order of the ranking operation. Most require an association with a predefined Rate Vehicle Algorithm.
Reconcile	A comparison feature that compares one program version against another version in the same program and generate a report of the differences.
Restrictions:	Limitations on viewing and editing pages and fields in the system. Restrictions are assigned and changed by the Administrator.
Result Mapping:	A defined set of results, inputs and variables displayed in the output file.
Revision:	A variable specific type of versioning. See Versioning in the Contents section for more information.
S	
Sequence:	The order in which algorithms run. See Sequencing in the Contents section for more information.

SoftLibrary:	A SoftLibrary is a specially developed program that performs a specific task. SoftLibraries may run their own code or call upon other systems to obtain information outside of RateManager, for example, obtaining a credit score
Source:	The source is the creator of a template and will also be the name of the new subline.
String:	A data type supported for all types of variables and inputs. Examples of string values are "2.718", "The quick brown fox jumps over the lazy dog." and "001".
Subline:	Sublines are classifications that fall in between lines of business and program folders. Sublines allow for the separation of programs by source.
T	
Tab-delimited:	A type of text file in which columns are separated by tabs. This is the required format for importing tables into RateManager.
Template:	Templates are exact copies of existing programs within a line of business that can be from within your own user group, any other user group within the company or even from an outside company.
U	
Unassigned Driver:	A driver who has not been assigned to a vehicle.
Unassigned Vehicle:	A vehicle that has not been assigned a driver.
Underwriting Algorithm:	A type of algorithm used to determine if a policy meets the requirements of the company.
Universal:	A collection of programs from all lines of business combined with result group mappings and assigned to execute in sequence that returns a single or multiple results.
V	
Variable:	A name used to represent a value that can change. See Variables in the Contents section for more information.
Version:	One of a sequence of copies of a program, each incorporating new modifications. See Versioning in the Contents section for more information.
W	
Wildcard:	An option available for mapped variables that tells RateManager that one or more rows ignore the value passed in for the criteria. See Variables in the Contents section for more information.
Workflow:	A workflow is a type of program that allows you to call multiple programs from different lines of business together under one universal program.
Working Category:	A classification used to define how elements should run. See Categories in the Contents section for more information.
X	
XML ID:	A number automatically assigned by RateManager to identify inputs and categories.

Index

<	
<i bdoc>.....	24
<hr/>	
A	
Accessing	
Insbridge Applications.....	10
Active	
SoftLibrary Status	99
Add a root node to the results?	24
Add Carrier/Portal.....	48
Add company descriptions to the results?	24
Add Database Connection.....	17
Add descriptions to the result items?.....	24
Add Environment.....	35
Add Results to Custom Inputs	
MapRequest Operators.....	26
Add SoftLibrary Link	96
Add Subscriber	15
Add the program inputs to the results?	24
AddHeading	
Operators	24
Adding	
Arguments.....	100
Carrier/Portal.....	48
Database.....	17
Environment.....	35
Line of Business.....	40
Root Node.....	24
SoftLibraries.....	97
Subscriber	15
Virtual File Server Management	42
AddInputs	
Operators	24
AddResultDesc	
Example	24
Operators	24
AddResultEmpty	
Operators	24
AddRoot	
Operators	24
Admin Email Address	
Explorer Configuration Page.....	33
Admin Name	
SoftLibraries.....	98
Administrator	
Framework Security	89
Age	
Error Logs.....	83, 85
All	
Search Options.....	68
API Key	92
Application Errors	
Error Log	84
Application Failure	
Error Log	81
Arguments	
Adding	100
Deleting	100
Editing	100
SoftLibraries	98
Arguments Screen	99
Async	
Delete Options.....	66
Download Options	58
Load Options	53
Unload Options.....	61
Audit Events.....	86
Delete	86
Download	86
Load	86
Unload	86
Audit Log.....	87
Overview	86
Viewing.....	87
Authentication	
Custom for Framework Administrator ...	91
Windows for Framework Administrator .	90
Authentication Types	
Changing.....	89
Custom	89
Framework Administrator	89
None.....	89
Windows.....	89
<hr/>	
C	
Cache	
Configuring	29
Enabled	29
Misses	29
Cache Enabled Date	
Cached Program Listing.....	30
Time Stamp.....	30
Cached Program Listing	
Cache Enabled Date	30
Environment	29
Package Creation Date	30

Program Cache Settings.....	29	Updating Password	94
Remove.....	29	Custom Input XML	
Total Hit Rows.....	30	MapRequest Operators.....	25
Total Miss Rows.....	30	Custom Output XML	
Carrier & Portal Management.....	48	MapRequest Operators.....	26
Carrier Configuration Page			
Navigating	34		
Carrier/Portal			
Adding	48		
Deleting	49		
Managing	48		
Carriers			
Subscriber Type.....	15		
Category Miss Buffer Purge			
Program Cache Settings.....	29		
Certifying			
Packages in Directory	39		
Change Config File location	14		
Changing			
Administrator Email.....	78		
Authentication Type	89		
Configuration File Location	11, 14		
Password	93		
Threads in Framework Administrator.....	78		
Class Name			
SoftLibraries	99		
Configuration File			
Changing Location	11, 14		
Explorer Configuration Page.....	33		
Overview	12		
Viewing.....	11, 13		
Configuration Page.....	34		
SoftRater Engine.....	27		
SoftRater Explorer	32		
Virtual File Server Management	42, 43		
Configure			
Insbridge Applications.....	10		
Configuring			
Cache.....	29		
Environment.....	38		
Connectors	30		
Adding.....	31		
Editing	30		
Engine Type.....	28		
Cookie			
Custom Authentication.....	91		
Copy SRP... ..	63		
Copying			
Message.....	77		
Package	62		
Custom			
Authentication Types	89		
Mapping	25, 26		
Custom Authentication			
Changing Password.....	93		
Framework Administrator.....	91		

D

Database	
Adding	17
Deleting	19
Editing	19
Database Events	
Error Log	81, 82
Example of Error Log	82
Sending Error Log	84
Viewing Error Log.....	82
Datstore	
Search Options.....	67
Date Filter	
Search Options.....	67
DB Catalog	
DB2	39
Environment	39
Oracle.....	39
DB Catalog Type	
Environment	39
DB Password	
Environment	39
DB Query Buffer	
Environment	39
DB Schema	
Environment	39
DB Server	
Environment	39
DB Server Type	
Environment	39
DB Tablespace	
Environment	39
DB User	
Environment	39
DB2	
Supported Database	39
DB2 Registered Alias Name	
DB Server.....	39
DB2 Servers.....	39
Debug Rate?.....	24
DebugRate	
Operators	24
Default	
API Key	92
Delete	
Audit Events	86
Delete Options	
Async.....	66

Email Address	66	Subscriber	16
Package	66	Virtual File Server Management.....	43
Sync	66	<i>Edition Notice</i>	2
Delete Package	65	Email	
Deleting		Changing Administrator.....	78
Arguments.....	100	Email Address	
Carrier/Portal.....	49	Delete Options.....	66
Database.....	19	Download Options.....	58
Environment.....	36	Load Options	53
Line of Business.....	41	Unload Options.....	61
Message.....	77	Email Addresses	
Package	64	Entering for Packaging Operations	33
SoftLibraries	104	Enabled	
Subscriber	16	Buttons for Message Service	74, 80
Virtual File Server Management	45, 46	Cache.....	29
Deployment Notes		Program Cache Settings.....	29
Package	69	Endpoint	
Desc		SoftLibraries	99
Search Options	68	Engine EnvDef	
Description		Environment	39
Subscriber	15	Engine Location	
Details		Environment	39
Local Insbridge Input Translators.....	70	Engine Type	
Package Notes.....	69	Connectors	28, 30
Package, Insbridge Rating Input XML ...	69	Environment	39
Package, Insbridge Rating Output XML	69	SoftRater Engine Configuration Page ...	28
Translator Files	69	SoftRater for Windows	28
Directory		Environment	
Options for Environment	39	Adding	35
Download		Cached Program Listing.....	29
Audit Events.....	86	Configuring	38
Available for a Package	70	Copying Packages	62
Download Options		DB Catalog	39
Async	58	DB Catalog Type.....	39
Email Address.....	58	DB Password.....	39
Package	58	DB Query Buffer.....	39
Sync	58	DB Schema	39
Downloading		DB Server.....	39
Package	56	DB Server Type.....	39
		DB Tablespace.....	39
		DB User.....	39
		Deleting	36
		Deleting Rules.....	37
		Editing	36
		Engine EnvDef	39
		Engine Location.....	39
		Engine Type	39
		Full Package.....	50
		Moving Packages.....	54
		Name.....	39
		Options	39
		Overview	35
		Package Location.....	39
		Secure	36
		SoftRater Full Packages	50
		Environment Types	36, 39

E

Edit Carrier/Portal	49
Edit Database	19
Edit Environment	37
Edit Selected Server	44
Edit Subscriber	17
Edit Virtual File Server.....	44
Editing	
Arguments.....	100
Database.....	19
Environment.....	36
Line of Business.....	41
Process Configuration.....	78
SoftLibraries	104

EnvRef	
Operators	24
Error Log	81, 82, 84
Database Events	81, 82
Event Log Events	81, 84
Navigating	81
Overview	81
Errors	
Messages, Package	54, 58, 61, 66
ESI	
Overview	92
Packages	70
Event Log Events	
Error Log	81, 84
Example of Error Log	84
Sending Error Log	86
Viewing Error Log	84
Example	
AddResultDesc	24
Error Log of Database Events	82
Error Log of Event Log Events	84
Execution Time	
Stats for SoftRater Engine	29
Explorer	
Configuration Page	32
Navigating to Configuration Page	32
SoftRater	32
Explorer Configuration Page	
Admin Email Address	33
Configuration File	33
Internet Proxy	33
Intranet Credentials	33
External Services	
Connectors	30

F

File	
InsbridgeDataRequest.XML Format	71
Rating on Test	21
Testing Input	21
Testing SoftData Test Interface	71
Framework Administrator	
Authentication Types	89
Changing Password	93
Custom Authentication	91
Full Control of Directory	39
Login Credentials	92
Secure Environments	36
Security Overview	89
SoftLibraries	95
Updating Password	94
Windows Authentication	90
Framework Security	
IIS	90

Microsoft Internet Information Services	90
Full Packages	
SoftRater	50

G

Get File	71
Get Listing!	52, 54, 57, 60, 62, 64, 68
GetHelpText	
SoftLibraries	98
GetHelpText Screen	100
GetLog	
SoftLibraries	98
GetLog Screen	102
Global	
Mapping	25, 26
Search Options	67
Global Inputs	25, 26

I

IBFA	
Accessing	10
Navigating	8
System Configuration	92
Icons	
Packages	70
ID	
Subscriber	15
IIS	
Framework Security	90
Implementation Interfaces	
Required	96
Include empty items in the results?	24
Input	
Testing Files	21
Input Processor Name	
MapRequest Operators	26
Input Processor Type	
MapRequest Operators	25
Insbridge Database Events	
Error Logs	83, 85
Insbridge Framework Administrator	
Overview	10
Insbridge Message Service	75
Overview	74
Insbridge Page	
Navigating	11
Overview	11
Insbridge Rating Input XML	
Package Details	69
Insbridge Rating Output XML	
Package Details	69
Insbridge Task Manager	

Overview	80
Viewing.....	80
InsbridgeDataRequest.XML Format	
Request File	71
Internet Proxy	
Explorer Configuration Page.....	33
Intranet Credentials	
Explorer Configuration Page.....	33

L

Last Month	
Search Options	68
Library	
SoftLibraries	98
Library Information Screen	98
Line of Business	
Adding	40
Deleting	41
Editing	41
MapRequest Operators.....	25
Line-of-Business Management.....	40, 41
Links	
Add SoftLibrary	96
Load	
Audit Events	86
Load Options	
Async	53
Email Address	53
Package	53
Sync	53
Load Packages	53
Loaded	
Deleting a Package	66
Packages	70
Loading	
Package	52
LOB	
Search Options	68
Local	
Mapping	25, 26
Local Insbridge Input Translators	
Package Details	70
Local Package	50
LOCALHOST	
Engine Location	39
Logging	
SoftLibraries	99
Logs	81

M

Managing	
Carrier/Portal.....	48

Mapping	
Custom	25, 26
Global	25, 26
Local.....	25, 26
MapRequest Operators	25
Add Results to Custom Inputs.....	26
Input Process Type	25
Input Processor Name	26
Line of Business	25
Output Processor Name.....	26
Output Processor Type	26
Program.....	25
Subscriber	25
Version	25
Message	
Copying	77
Deleting	77
Overview	75
Viewing.....	75
Message Queue	
Viewing.....	75
Message Service	
Queues.....	75
Stopping & Starting	74
Microsoft Internet Information Services	
Framework Security	90
Misses	
Cache	29
Move SRP.....	55
Moving	
Package	54

N

Name	
Environment	39
SoftLibraries	95
Subscriber	15
Navigating	
Carrier Configuration Page	34
Error Log	81
Explorer Configuration Page	32
IBFA	8
Insbridge Page	11
Services Page	73
SoftRater Engine Configuration Page ..	27
SoftRater Explorer.....	51
None	
Authentication Types.....	89
Search Options.....	68
Notational Conventions.....	8

O

On Disk	
Search Options	68
Operators	
AddHeading	24
AddInputs	24
AddResultDesc	24
AddResultEmpty	24
AddRoot	24
DebugRate	24
EnvRef	24
Optional	21
Optional Map Request	25
Optional Rate	23
Optional Map Request Operators	25
Optional Operators	21
Optional Rate Operators	23
AddHeading	24
AddInputs	24
AddResultDesc	24
AddResultEmpty	24
AddRoot	24
DebugRate	24
EnvRef	24
Options	
Environment	39
MapRequest Operators	25
Rate Operators	23
Oracle	
Supported Database	39
Oracle Insurance Support	106
Oracle ODBC Driver Information	
DB Catalog	39
Oracle Servers	
DB Server	39
Output Processor Name	
MapRequest Operators	26
Output Processor Type	
MapRequest Operators	26
Overview	
Audit Log	86
Configuration File	12
Environment	35
Error Log	81
ESI	92
Framework Administrator Security	89
Framework Administrator SoftLibraries	95
Insbridge Framework Administrator	10
Insbridge Message Service	74
Insbridge Page	11
Insbridge Task Manager	80
Message	75
Package	50
Package Unload	59
Process Configuration	78

Services Page	73
SoftData Test Interface	71
SoftRater Engine Configuration Page ...	27
SoftRater Explorer	32
SoftRater Test Interface	21
Subscriber	14
Threading	78
Virtual File Server Management	42

P

Package	
Async	58
Async Option	53, 61, 66
Available for Download	70
Copy SRP	63
Copying	62
Created with ESI	70
Date Filter	67
Date Filter, Last Month	68
Date Filter, None	68
Date Filter, This Month	68
Delete Options	66
Delete Package	65
Deleting	64
Deleting a Loaded	66
Desc	68
Details, Viewing	68
Download Options	58
Downloading	56
Email Address	58, 61
Email Address Option	53, 66
Environment	35
Error Messages	54, 58, 61, 66
Full	50
Hiding Toolbar	68
Insbridge Rating Input XML Details	69
Insbridge Rating Output XML Details	69
Listing	52, 54, 57, 60, 62, 64, 67, 68
Load Options	53
Loading	52
LOB	68
Local	50
Move SRP	55
Moving	54
Note Details	69
Overview	50
Package Status	68
Package Status, All	68
Package Status, On Disk	68
Program	68
Reloading	54
Remote Listing	67
Remote Listing, Datastore	67
Remote Listing, Global	67

Adding.....	24
Rules	
Deleting Environment.....	37
Deleting Subscriber.....	16
Run Time	
SoftRater.....	24

S

Search	
Hiding Toolbar.....	68
Search Options	
All.....	68
Datastore.....	67
Date Filter.....	67
Desc.....	68
Global.....	67
Last Month.....	68
LOB.....	68
None.....	68
On Disk.....	68
Package.....	67
Package Status.....	68
Program.....	68
Remote Listing.....	67
Subscriber.....	67
This Month.....	68
Version.....	68
Searching	
Package.....	67
SoftLibrary Type.....	105
Secure	
Environment.....	36
Security.....	89
Sending	
Error Log of Database Events.....	84
Error Log of Event Log Events.....	86
Server Setup	
Downloadable Packages.....	42
Services Page	
Navigating.....	73
Overview.....	73
Settings	
Thread.....	78
Show Details	
Packages.....	68
Show Framework Admin Menu.....	91
SoftData Test Interface	
Overview.....	71
Testing.....	71
SoftLibraries.....	95
Adding.....	97
Admin Name.....	98
Arguments.....	98
Class Name.....	99

Deleting.....	104
Displaying in RateManager.....	96
Editing.....	104
Endpoint.....	99
Fields.....	96
GetHelpText.....	98
GetLog.....	98
Implementation Interfaces.....	96
Library.....	98
Logging.....	99
Name.....	95
Password.....	99
Ping.....	98
RequestXML.....	98
ResponseXML.....	98
Searching for Library Type.....	105
Status.....	96, 99
Test.....	98
Timeout.....	99
Type.....	96, 98
User Name.....	99
Using Web Services.....	96
WebSphere.....	104
Windows.....	104
SoftRater	
Determining Run Time.....	24
Package Activity Audit Log.....	86
Supported Databases.....	39
Verifying Input Values.....	24
SoftRater Engine	
Configuration Page.....	27
Engine Type.....	28
Navigating to Configuration Page.....	27
Program Cache Settings.....	29
Stats.....	29
Stats, Execution Time.....	29
Stats, Start Time.....	29
Stats, Stop Time.....	29
Time Stamp.....	29
Web Rate Threads.....	29
SoftRater Environment	
Full Packages.....	50
SoftRater environment definition override?	
.....	24
SoftRater Explorer	
Configuration Page.....	32
Copying a Package.....	62
Deleting Package.....	64
Downloading Package.....	56
Load Packages.....	53
Loading Packages.....	52
Moving a Package.....	54
Navigating.....	51
Overview.....	32
Packages Tab.....	35, 51
Searching for Packages.....	67

Unloading Package	59	Load Options	53
Viewing Package Details	68	Unload Options.....	61
SoftRater for Windows		System Configuration	
Engine Type	28	IBFA	92
SoftRater Packages		System DSN Name	
Environments	35	DB Catalog	39
SoftRater Test Interface		Oracle Servers	39
Overview	21	System Requirements	8
SQL Server			
Supported Database	39		
SRP	21, 50		
Start Button		<hr/>	
Message Services.....	74, 80	<i>T</i>	
Start Time		Task Manager	
Stats for SoftRater Engine	29	Stopping & Starting	80
Starting		Test	
Insbridge Message Service.....	74	SoftLibraries	98
Insbridge Task Manager	80	Test Interface	
Stats		Rating a File	21
SoftRater Engine Configuration Page....	29	Test Screen.....	103
Status		Testing	
SoftLibraries	96, 99	Input Files.....	21
Stop Button		SoftData Request File	71
Message Services.....	74, 80	SoftData Test Interface	71
Stop Time		This Month	
Stats for SoftRater Engine	29	Search Options.....	68
Stopping		Threading	
Insbridge Message Service.....	74	Overview	78
Insbridge Task Manager	80	Threads	
Sublines	16	Changing in Framework Administrator..	78
Subscriber		Setting	29
Adding	15	Settings	78
Assigning Information	15	Time Stamp	
Deleting	16	Cache Enabled Date	30
Deletion Rules.....	16	Package Creation Date	30
Editing	16	SoftRater Engine	29
Information	15	Timeout	
Information for Database	18	SoftLibraries	99
MapRequest Operators.....	25	Toolbar	
Overview	14	Hiding	68
Search Options	67	Total Hit Rows	
Types	14	Cached Program Listing.....	30
Subscriber Type		Total Miss Rows	
Carriers	15	Cached Program Listing.....	30
Portals	14	Translator Files	
Success		Package Details	69
Messages, Package.....	54, 58, 61, 66	Type	
Support	106	SoftLibraries	96, 98
Supported Databases	39	Subscriber	15
RateManager	39	Types	
SoftRater	39	Environment	36, 39
Supported Operations		Framework Administrator Authentication	89
Web Services	96	89
Sync		Input Mapping.....	25, 26
Delete Options	66	Subscriber	14
Download Options.....	58		

U

Unload	
Audit Events	86
Package	54, 60
Unload Options	
Async	61
Email Address	61
Package	61
Sync	61
Unloading	
Package	59
User ID	
Framework Administrator	92
User Name	
SoftLibraries	99
User Violations	
Error Log	81, 82

V

Version	
MapRequest Operators	25
Search Options	68
View XML	
Internet Explorer	23, 72
Viewing	
Audit Log	87
Configuration File	11, 13
Error Log of Database Events	82
Error Log of Event Log Events	84
Insbridge Task Manager	80
Message	75
Message Queue	75

Package Details	68
Virtual File Server Management ..	42, 43, 46, 47
Adding	42
Deleting	45, 46
Edit Virtual File Server	44
Editing	43
Overview	42

W

Web Rate Threads	
SoftRater Engine Configuration Page ...	29
Web Services	
Supported Operations	96
WebSphere	
SoftLibrary	104
Windows	
Authentication Types	89
SoftLibrary	104
Windows Authentication	
Framework Administrator	90

X

XML	
Submitting Custom	25
View Input Details	69
View Output Details	69
XML Files	
Testing a Rating	22
XML ID	41