



Print Audit 6
User Manual



Table of contents

PRINT AUDIT 6 ADMINISTRATION.....3

WELCOME3

GENERAL.....4

Print Audit Licensing4

Changing Your Database.....5

Clearing Pending Jobs.....6

SYSTEM SETTINGS6

Overview6

CLIENT SETTINGS8

Overview8

CUSTOM RULES11

Overview11

Adding, Editing and Deleting Custom Rules.....12

Rule Conditions.....13

Rule Actions15

Rule Groups16

CLIENT CUSTOM FIELDS17

Overview17

Custom Field Types.....18

Adding, Editing and Deleting Custom Fields.....19

Linked Custom Fields20

Adding, Editing and Deleting Custom Field Values21

Importing Custom Field Values23

Custom Field Value Import Formats24

Exporting Custom Field Values28

USER PROFILES29

Overview29

Allowances and Balances30

Setting the Default User Tracking Profile.....31

Adding, Editing and Deleting Tracking Profiles.....31

Resetting User Balances33

Setting the Default User Security Profile.....33

Adding, Editing and Deleting Security Profiles34

USERS.....35

Overview35

Adding and Deleting Users (Advanced).....35

Editing Your Users.....36

Importing Users38

Exporting Users40

PRINTER PROFILES40

Overview40

Setting the Default Printer Profile.....41

Adding, Editing and Deleting Printer Profiles.....41

Printing Limits and Redirection.....43

PRINTERS.....44

Overview44

Adding and Deleting Printers (Advanced).....45

Editing Your Printers.....46



Manual Printer Merging.....46

PRINTER PAPER SIZES:48

Overview48

Adding, Editing and Deleting Paper Sizes.....48

APPLICATION.....50

Overview50

Adding, Editing and Deleting Applications50

Limiting the Number of Tracked Applications51

NETWORK SETTINGS52

Overview52

Changing Your Network Type.....53

Changing How Users Authenticate.....53

Network Login Authentication55

PRINT AUDIT 6 ANALYSIS REPORTING.....56

OVERVIEW.....56

UNDERSTANDING THE ANALYSIS REPORTING TOOL57

GROUPING AND FILTERING IN NORMAL MODE.....58

Analysis Grouping Information58

Using the Printer Grouping and Filtering Tab.....59

Using the User Grouping and Filtering Tab.....61

Saving and Loading Groups62

REPORTS.....63

Creating and Removing Reports.....63

Creating Composite Reports.....64

Report Parameters.....66

Printing and Exporting Reports.....66

Scheduling and Emailing Reports.....67

Report Export Formats68

PRINT AUDIT 6 JOB MANAGER69

WELCOME69

FINDING, VIEWING AND EDITING JOBS70

Searching for Print Jobs70

Changing Your Data View.....71

Editing and Deleting Jobs.....73

JOB REPORTING74

Job Manager Reports.....74

Creating Reports.....75

Printing and Exporting Reports.....77

Scheduling and Emailing Reports.....78

How to Create a Billing Statement79

Job Exporting.....80

Accounting81

ADVANCED.....84

Job Manager and Merged Jobs84

Securing the Job Manager.....84

PRINT AUDIT 6 JOB MERGE WIZARD85

WELCOME86



REQUIREMENTS86

BEFORE YOU BEGIN87

GENERAL USAGE.....88

IMPORTING89

Importing Job Data.....89

Setting up Scheduled Imports.....90

EXPORTING.....93

Exporting Job Data.....93

Setting up Scheduled Exports.....94

PRINT AUDIT 6 DATABASE MAINTENANCE TOOL96

 WELCOME96

 ACCESS MAINTENANCE.....97

Microsoft Access Overview.....97

Changing the Read-Only Password.....99

 SQL SERVER MAINTENANCE101

Microsoft SQL Server Overview101

Creating a New Database.....102

Changing the Print Audit Login Password106

Changing the System Administrator Password.....108

Running a SQL Script110

PRINT AUDIT 6 DATABASE MIGRATION WIZARD113

 OVERVIEW.....113

PRINT AUDIT 6 CLIENT STATUS AND DEPLOYMENT TOOL.....114

 WELCOME114

 USAGE REQUIREMENTS115

 USING THE TOOL116

Querying Client Status.....116

Installing Print Audit 6 to Network Computers117


Removing Print Audit 6 from Network Computers117

Updating the Client Communicator Location.....118

Working With Installation Packages.....118



Print Audit 6 Administration



Welcome

Welcome to the Print Audit 6 Administration tool. You use the Print Audit 6 Administration tool to configure all aspects of Print Audit 6.

The tool consists of several sections; each one focuses on a different aspect of Print Audit 6. You may not need to use all the sections in Print Audit depending on your business needs, but you should familiarize yourself with all of them to fully understand what Print Audit offers.

Please note that you may not have access to all that Print Audit has to offer depending on the type of licensing you purchased.

You can begin using Print Audit immediately with little to no configuration, but we recommend you read the following topics to get an idea of what the product can offer to your organization:

- **Pricing in Print Audit**
- **Custom Rules**
- **Printing Limits and Redirection**
- **Allowances and Balances**



Below are links to topics describing each section of the Administration tool:

- **System Settings** - This section contains information on Administration settings that affect all areas of Print Audit.
- **Client** - This section contains information on how to configure the Print Audit Client and how Print Audit tracks your print jobs.
- **Printers** - This section contains information on how to manage and configure how Print Audit tracks your printers when printing.
- **Users** - This section contains information on how to manage and configure how Print Audit tracks your users when printing.
- **Custom Rules** - This section contains information on how to use our new advanced custom rules feature.
- **Applications (Advanced)** - This section contains information how to manage and configure how Print Audit tracks printing from different applications.
- **Network and Authentication (Advanced)** - This section contains information on advanced network configuration and other advanced topics for more complex networks.

General

Print Audit Licensing

For evaluation purposes you can request a trial license. The trial lasts for 15-days and works on up to 5 computers in your organization. Once your trial ends, you must purchase a license to continue using the software.

To start a trial:

1. When the Administration tool starts and you have no license, the License Activation dialog appears.
2. Click the **Request a trial license** option and click the **Activate** button. The Registration window appears.
3. Please enter information for all of the fields in the Registration window. We use this information so we can support you in your use of the trial.
4. Click the **Submit** button. Print Audit contacts our licensing server and activates your trial.



NOTE: Once you start a trial, you cannot request another one. If you need to extend your trial, or have any questions about the software, please contact Print Audit support.

To purchase a new license:

1. Please contact Print Audit directly, or an authorized Print Audit dealer. They will take your customer information and supply you with a Print Audit license key along with the company name recorded for your purchase.

To activate a license:

1. If the License dialog does not appear when you start the Administration tool, go to the Tools->View/Change License menu item. The Licensing dialog appears.
2. Click the **Activate License** button. The Activation dialog appears.
3. Click the **Activate existing license** option.
4. Enter in your customer information and license key as required.
5. Click the **Activate** button. The Registration window appears.
6. Please enter information for all of the fields in the Registration window. We use this information so we can support you in the use of the software.
7. Click the **Submit** button. Print Audit contacts our license server and activates your key.

If you do not have internet access, or your activation over the internet fails, please contact Print Audit so we can activate your license by other means.

Changing Your Database

If you have several different Print Audit databases you may need to point the Administration tool to one or the other. When you change databases Print Audit asks you for any authentication information before you can use the new database.

If you do not have rights to the new database, or Print Audit encounters some other problem, the Administration tool continues to use your existing database selection.



To change your database:

1. Click the Tools->Set Database menu. A dialog appears asking you to select your new database.
2. Select the new database. For Access databases simply select the new database file. For SQL Server databases please enter the new SQL information.
3. Accept the information. Print Audit attempts to log in to the new database.

Clearing Pending Jobs

Print Audit creates pending jobs when a user either chooses to snooze a job, or when the Print Audit Client sends jobs that were tracked when it was disconnected from the Client Communicator to the database. Only jobs that required pop up information from the user are stored as pending jobs.

In some rare cases, a user could have too many pending jobs to comfortably enter information for. This could happen if their Client was unable to communicate with the Client Communicator for an extended period of time due to a configuration error for example.

If you want to clear pending jobs for all users from the database, you can use the **Clear Pending Jobs** command. Only users who have the rights to edit and delete jobs can clear pending jobs.

To clear pending jobs:

1. Click the **Tools->Clear Pending Jobs** menu. A dialog appears asking you if you are sure you want to clear the pending jobs.
2. Click the **Yes** button to have Print Audit clear all jobs. NOTE: Once jobs are cleared you cannot get them back.

System Settings

Overview

This section of the Administration tool allows you to define settings that affect the overall operation of Print Audit 6. These settings include things such as how many decimal places to use for costs and reporting, as well as the email settings Print Audit should use when sending email.



Listed below are the options you can set in this section.

General Settings

Decimal Places for Costs - You can use from two to four decimal places for costs you assign to printers, users and applications. This setting applies to both data entry and is the default for reporting, however you can choose to override this setting when creating reports.

Percentage Modifier Option - This setting affects how Print Audit handles job cost calculations when multiple cost percentage modifiers are encountered. Click here for more information on job costing in Print Audit 6. The options are as follows:

- **Apply Each** - This option applies each percentage modifier to the cost in the order that it was encountered. For example, if there is a 50% modifier, then another 25%, the final job cost reduced by half, and then by a quarter.
- **Legacy** - This option calculates percentage modifiers the same way as past versions of Print Audit. Provided for backwards compatibility only, we highly recommend you choose one of the other options.
- **Use Highest** - This option uses only the highest modifier encountered. For example, if you had a 50% cost modifier and a 200% cost modifier both applicable for the job, only the 200% modifier is taken into account.
- **Use Lowest** - This option uses only the lowest modifier encountered. For example, if you had a 50% cost modifier and a 200% cost modifier both applicable for the job, only the 50% modifier is taken into account.

Email Notifications

You can configure Print Audit 6 to send email for things like license violations, scheduled reports and in response to certain conditions using custom rules. Before Print Audit 6 can send emails, you must properly set the following options:

SMTP Server - The name or IP address of the SMTP server in your organization to use for sending emails.

SMTP Login - The login to use if your SMTP server requires authentication. If it does not, you can leave this blank.

SMTP Password - The password to use if your SMTP server requires authentication. If it does not, you can leave this blank.



Email Address - Enter the email address of the person you want notified in case of licensing issues. Generally you should enter the email address of the person in your organization responsible for administering Print Audit.

Send Email to Print Audit - Select "Yes" to have Print Audit send an email to our licensing department in case of licensing issues. Print Audit sends no private information, simply your licensing information and the nature of the problem. We use this information to then contact you and help you with your problem.

Select "No" (the default) if you do not want to notify us of licensing issues. If selected, no information is sent to us.

Client Settings

Overview

This section of the Administration tool allows you to set general information about how the Print Audit Client behaves on the desktop. It controls things such as if you want to allow the user to shutdown the Client, whether or not it supports batching and how users have to authenticate before they can print.

Listed below are all the options you can set in this section:

General Settings

This section controls in general how the Client behaves on the Windows desktop.

- **Display Tray Icon** - If set to **Yes** a tray icon displays in the Windows task bar area when the Client is running.
- **Wait for Page Count (Recovery only)** - If set to **Yes**, the Client does not display the Popup window until it has the page count. This can cause a delay before the Popup window appears. If set to **No**, the Client does not display the final job cost or final number of pages on the Popup window. NOTE: If you have Reduction only, this setting gets changed automatically when you add printer limits.
- **Shutdown the Client** - If set to **Yes** the user can shutdown the Client.
- **Enter Comments (Recovery only)** - If set to **Yes** the user can enter comments on the Popup window when it displays.
- **Use Last Entries (Recovery only)** - If set to **Yes** Print Audit automatically populates the Client Popup window with the same entries they used on the last print job.



Client Logo Settings (Recovery Only)

You can choose to set a custom logo to display on the Client popup window when a user prints. The logo must be 474x88 pixels.

Batch Settings (Recovery Only)

This section controls how the Print Audit Client controls batching. Batching is how Print Audit handles multiple print jobs when you want to re-use the same Popup Window entries as a previous job automatically. Please note that these settings have no effect if you configure the Client to not display a popup window when printing.

Batching Type - There are three types of batching.

- **None:** The Client displays a popup on every print.
- **Automatic:** The Client automatically re-uses the same popup window entries for all jobs that you print within the batch timeout from the same program.
- **Manual:** The Client allows you to enter the number of jobs you want to batch on the popup. Print Audit automatically re-uses the popup settings for the number of jobs you indicated or until the time-out expires.

Maximum Batch Size - This displays only for the **Manual** batch type. You enter the maximum number of jobs you want the user to batch here.

Batch Time-out - Use this to enter the number of seconds Print Audit waits before cancelling a batch. This indicates the time-out between jobs, not overall. For example, if you enter 60 seconds for the time-out and set the batch size to twenty jobs, the Client automatically cancels the batch if more than a minute elapses before it detects the start of the second job in the batch.

Authentication

This section controls how Print Audit authenticates users. Print Audit determines who the user is before allowing access to the Print Audit tools and before it allows them to print.

Client Authentication - This controls how the Client determines who the user is. Use the drop-down box to choose an authentication type.



There are three authentication types. They are as follows:

- **Logged in User** - The Client uses the current Windows or Novell login information to identify the user.
- **PIN** - The Client requires the user to enter their Print Audit PIN code to identify the user.
- **PIN and Password** - The Client requires the user to enter their Print Audit PIN and a separate password to identify the user.
- **Network** - The Client requires the user to re-enter their Windows or Novell login information to identify the user. The Client does not store or transmit this information anywhere. Please note that this type of authentication may not work properly on Windows 95, Windows 98 and Windows Millennium depending on your network configuration.

Tools Authentication - This controls how the Print Audit Administration, Job Manager and other tools determine who the user is. Use the drop-down box to choose an authentication type. The authentication options for both Client and Tools are identical.

You can set **Client Authentication** per computer, and choose to report the users as Windows NT, Active Directory or Novell Directory Services. For more information on these advanced settings, please see the Network and Authentication settings section.

Disconnected Jobs

This section allows you to configure how Print Audit deals with print jobs that occur when the Client cannot connect to the Database Communicator.

Disconnected Job Option - This controls exactly what Print Audit does when it detects a print job, but no connection to the Database Communicator. Options are:

- **Track normally** - The jobs are tracked and stored on the local computer. When the Client can connect to the Database Communicator it uploads all of the locally tracked jobs to the database. If the jobs require more information, the Client requests more information from the user.
- **Track silently** - The same as above, except that the user is never asked for further information, the jobs are stored in the database the same as if they were set to "Track with no popup".
- **Ignore Jobs** - Any jobs printed in a disconnected state are not tracked.



- **Disallow jobs** - The Client cancels the job, and displays a message to the user.
- **Ignore old jobs** - Same as Track Normally, except that any jobs older than the specified number of days are ignored.

Disconnected Disallowed Message - This is the message that displays to the user if their job was disallowed due to no connection to the Database Communicator. This is only available if "Disallow jobs" is set for the disconnected job option.

Number of Days Until Old - This is the number of days old the job must be before it is ignored. Only available if "Ignore old jobs" is set for the disconnected job option.

NOTE: It is possible to specify the disconnected job settings per desktop computer.

Custom Rules

Overview

New in Print Audit 6 is the ability for you to create custom rules. These rules can allow you to handle almost any printing control needs within your organization.

Using Custom Rules you can select one or more conditions that trigger one or more actions to take place within the software. For example, you could allow free printing after a certain time of day, send an email to people if jobs of a certain size are printed, display messages to users, etc. You can also define rules that depend on other rules being triggered, so the possibilities are endless.

For most printing needs, such as basic limits and pricing, you can use our User Profiles, Applications or Printer Profiles for your needs, but for complex printing situations and environments Custom Rules may be required. When you define a Custom Rule, the behavior you define in the rule overrides any other settings that you may have made in other areas of the application.

Rules work by evaluating one or more conditions you define, and if those conditions are met the rule triggers one or more actions you define. It is very simple to define rules, but given the combinations of actions and conditions you can create rules to handle very complex situations.



For ease of administering rules, you can create and manage user and printer rule groups. You can define groups for departments for example, and set rules to run only for those departments. These groups are separate from reporting groups you can define in the Job Manager and Analysis Reporting.

You can do the following with Custom Rules section of the Administrator:

- Adding, Editing and Deleting Custom Rules
- Add, Edit and Delete Rule Groups

Adding, Editing and Deleting Custom Rules

You use the Custom Rules section of the Administration tool to add, edit and delete custom rules. Please follow the steps in the sections below.

To add a new custom rule:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.
2. Click on the Custom Rules button on the left hand side of the Administration window. The list of custom rules appears in the right hand side.
3. Double-click on an empty row in the list in the Custom Rules section or click the **New** button on the toolbar. The **Custom Rules** window appears.
4. Enter the rule information as applicable.
5. Click the **Add** button. The custom saves to the database and the window closes.

To edit an existing custom rule:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.
2. Click on the Custom Rules button on the left hand side of the Administration window. The list of custom rules appears in the right hand side.
3. Double-click on the custom rule you want to edit in the list in the Custom Rules section. The **Custom Rules** window appears.



4. Make your changes as appropriate.
5. Click the **Save** button. The **Custom Rules** window closes and you see your changes displayed in the list.

To delete existing custom rule:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.
2. Click on the Custom Rules button on the left hand side of the Administration window. The list of custom rules appears in the right hand side.
3. Click on the custom rule you want to delete. The row appears highlighted.
4. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the rule.
5. Click the **Yes** button on the message box to delete the rule. The list refreshes to show the rule was deleted.

Rule Conditions

You can define a rule with one or more of the following conditions:

- **User** - The user who is printing is or is not a Print Audit user you select.
- **User Profile** - The user who is printing belongs to, or does not belong to the User Profile you select.
- **Printer** - The printer you are printing to is or is not a printer you select.
- **Printer Profile** - The printer you are printing to belongs to, or does not belong to the Printer Profile you select.
- **Computer name** - The name of the computer you are printing from matches fully or partially the computer name you enter.
- **Time of day** - The user is printing the job before or after a defined time, or is being printed between or outside of a range of time.
- **Total page count** - The total page count of the job the user is printing is a certain size, within a certain range, or is greater than or less than a value you enter.
- **Total color page count** - The total number of color pages in the job the user is printing is a certain size, within a certain range, or is greater than or less than a value you enter.



- **Total mono page count** - The total number of black and white pages in the job the user is printing is a certain size, within a certain range, or is greater than or less than a value you enter.
- **Total units in the job** - The total number of units in the job, taking into account Pricing Option, is a certain number, within a certain range or is greater than or less than a value you enter.
- **Total color units in the job** - The total number of color units in the job, taking into account Pricing Option, is a certain number, within a certain range or is greater than or less than a value you enter.
- **Total mono units in the job** - The total number of black and white units in the job, taking into account Pricing Option, is a certain number, within a certain range or is greater than or less than a value you enter.
- **Total job cost** - The total cost of the job, after the user completes the Client Popup, is equal to, less than or greater than or within a range of values you enter.
- **Job duplex setting** - The job the user printed was printed duplex or not.
- **Job n-up setting** - The job the user printed was printed was printed using n-up, with, greater than, less than or within a range of the number you specify.
- **Job origin** - The print job came from, or did not come from a specific environment.
- **Job type** - The type of job is or is not of a specific type (print, plot, etc.)
- **Job was printed to file** - If the job was printed to file or not.
- **Document title** - The title of the document being printed equals, does not equal or partially matches what you enter.
- **Printer group** - The printer the user is printing to does or does not belong to a specific printer rule group.
- **User group** - The user printing does or does not belong to a specific user rule group.
- **Driver color mode** - The color mode we detect from the driver is black and white or color.
- **Application name** - The process name of the application printing is, is not or partially matches the value you enter. The application does not need to be in your Applications list.
- **Job satisfies rule** - The job satisfies or does not satisfy the conditions of another rule you created.
- **Base job cost** - The cost of the job before the Client Popup is shown is, is not, or is within a range of a value you enter.
- **Day of the week** - The job was or was not printed on a selected day.



- **Number of Copies** - The number of copies in the job is, is not, or is within a range of a value you enter.

Rule Actions

You can define a rule with one or more of the following actions:

- **Set track option to** - Set the overall tracking option for the job to the specified value.
- **Set authentication type to** - Set the Client authentication to the selected value.
- **Display message and cancel the job** - Displays a message to the user printing, and cancels the job. You can define the title of the message, as well as the text. You can use message variables in the text to provide a message targeted for the user and situation.
- **Display message and present option to cancel the job** - Displays a message to the user printing, and allows them to decide if they want to cancel the job or not. You can define the title of the message as well as the text. You can use message variables in the text to provide a message targeted for the user and situation.
- **Display message and continue the job** - Displays a message to the user printing, and once they acknowledge, the message continues. You can define the title of the message as well as the text. You can use message variables in the text to provide a message targeted for the user and situation.
- **Send an e-mail message** - Sends an email message. You can define the email address it appears to come from, the list of users who it is to, a subject and text. You can use message variables in the text to provide a message targeted for the user and situation. You can specify multiple addresses in the To and CC fields, separated by a comma.
NOTE: To properly send emails, you must configure the email settings in the System Settings section of the Administrator.
- **Do not deduct job cost from user balance** - The jobs cost will not be deducted from any user balances.
- **Set the cost profile** - You can define detailed pricing for the rule. Please see the Printer Profile Window topic for a description of the pricing fields.
- **Ask for custom fields** - Require the user to enter the custom fields you select on the Client Popup before they can print. If you clear all of the fields, the user does not need to enter any custom fields.



- **Ignore all printing limits** - Ignore any printing limits defined in the User Profile, Application or Printer Profile. However, any limits on cost or pages you setup in other custom rules may still apply.

Rule Groups

Print Audit 6 allows you to create user and printer rule groups. You can use these groups to make administering your rules even easier. For example, you could define rule groups based on department or responsibility, add users to rule groups, and then create rules whose action list requires membership in one or more groups. While similar in implementation, rule groups are not related to the reporting groups you can create in the Job Manager and Analysis Reporting tools.

To add, edit and delete user rule groups:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.
2. Click on the Custom Rules button on the left hand side of the Administration window. The list of custom rules appears in the right hand side.
3. Click the **Groups->Edit User Groups** menu item at the top of the Administration Window. The Edit User Groups window appears.
4. Click **Add** to create a new group, or click an existing group to highlight it and click the **Edit** button. The Edit Group window appears.
5. Add or Remove members from the group, and click the **Save** button on the Edit Group window.
6. Repeat steps 4 and 5 to modify more groups.
7. If you want to delete an existing group, click an existing group to highlight it and click the **Delete** button. A message displays asking if you are sure you want to delete the group. Click **Yes** to continue.
8. Click **Close** on the Edit User Groups window.

To add, edit and delete printer rule groups:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.



2. Click on the Custom Rules button on the left hand side of the Administration window. The list of custom rules appears in the right hand side.
3. Click the **Groups->Edit Printer Groups** menu item at the top of the Administration Window. The Edit Printer Groups window appears.
4. Click **Add** to create a new group, or click an existing group to highlight it and click the **Edit** button. The Edit Group window appears.
5. Add or Remove members from the group, and click the **Save** button on the Edit Group window.
6. Repeat steps 4 and 5 to modify more groups.
7. If you want to delete an existing group, click an existing group to highlight it and click the **Delete** button. A message displays asking if you are sure you want to delete the group. Click **Yes** to continue.
8. Click **Close** on the Edit User Groups window.

Client Custom Fields

Overview

Print Audit 6 allows you to define up to five custom fields the user must enter information for before they can print. Each one of these custom fields can have completely different values and types, allowing you to gather from your users valuable business information for each print job.

For all types of custom fields except for non-validated, your users must enter information on the Client Popup in order to print.

The Client Custom Fields section consists of two to three main grids. The top grid contains a list of all the custom fields you define. The bottom grid contains a list of all the values you enter for a specific field. To see values for a field, click on the field in the top grid to select it. All of the values automatically display in the values grid below. For linked custom field types there are two values grids. The top values grid contains all of the main codes, the bottom values grid contains sub codes for the main code.

You can use this section to do several things. Click on the links below for detailed information:

- Adding, Editing and Deleting Custom Fields
- Adding, Editing and Deleting Custom Field Values
- Importing and Exporting Custom Field Values



- Linked Custom Fields

You can configure Print Audit to display different custom fields depending on user, printer and/or application.

Custom Field Types

When you create a custom field you can choose from one of seven custom field types. The field types you can choose from are as follows:

- **Searchable** - This field type uses a separate popup search window for searching on values from the Client. It keeps track of the last ten used values and supports an unlimited number of values. This field type also supports adding new values from the Print Audit Client.
- **Searchable Drop down** - This field type uses a type-ahead drop down box search so the user does not need to use a separate search window. It keeps track of the last ten used values, but only supports fields that have up to one thousand values. This field type supports adding new values from the Client.
- **Simple Drop down** - This field type is not searchable, a user simply selects an entry from the drop down. It does not keep track of the last ten used values, and only supports fields that have up to one hundred values. It does not support adding new values from the Client. This field works best for a small set of selectable items for a print job, such as added materials needed like binding or shipping.
- **Option** - Not searchable, displays a pair of option buttons for the field. It supports only two values. Used generally for "yes, no" options like Billable and Non-Billable for example.
- **Non-Validated** - This is a free format entry field. No validation is done on what a user enters here.
- **Linked Searchable** - This field acts as two separate fields and allows the user to choose a main code followed by a sub code. The main code is a searchable type field, the sub code is a searchable drop down.
- **Linked Drop down** - This field acts as two separate fields and allows the user to choose a main code followed by a sub code. Both the main code and sub code fields act as searchable drop downs.



Adding, Editing and Deleting Custom Fields

You use the Client Custom Fields section of the Administration tool to add, edit and delete custom fields. You can also change the order in which the custom fields appear on the Client Popup window. Please follow the steps in the sections below.

To add a new custom field:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Double-click on an empty row in the top list in the Client Custom fields section or click in the top list and then click the **New** button on the toolbar. The **Adding New Field** window appears.
3. Enter the name of the field in the **Name** text field. This name depends on your business, but examples are Project, Client, Account, etc. You must enter a unique name for each custom field.
4. Select the type of field from the **Type** drop down.
5. Click the **Save** button. The **Adding New Field** window closes and you should see your new field listed in the top list.

To edit an existing custom field:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Double-click on the field you want to edit in the top list in the Client Custom fields section. The **Editing Field** window appears.
3. Make your changes as appropriate. See the above section to see the fields you can change.
4. Click the **Save** button. The **Editing Field** window closes and you see your changes displayed in the top list.

To change the order of a custom field:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field you want to move in the top list in the Client Custom fields section. The row containing the field is highlighted.



3. Click the Up or the Down arrow buttons on the toolbar at the top of the Administration window to change the order of the custom field.

To delete an existing custom field:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field you want to delete in the top list in the Client Custom fields section. The row containing the field is highlighted.
3. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the field.
4. Click the **Yes** button on the message box to delete the field. The top list refreshes to show the field was deleted.

NOTE: You cannot delete a custom field if it is referenced in a database print job.

Linked Custom Fields

New to Print Audit are linked custom fields. This feature allows you to specify a main and a sub code for a custom field. The main code a user selects determines which sub codes are available for entry.

For example, you could define a linked custom field with "Customer" as the main field, "Project" as the sub field. You could then enter all of your customers into the Customer values list, and for each customer, enter the valid projects. When a user prints, they can first select the Customer and then see a list of only those projects for that customer.

For the most part, using Linked Custom Fields is very simple, and similar to how normal custom fields work in Print Director Print Audit. However, there are some differences. They are as follows:

- You cannot specify cost modifiers or budgets for main codes, only sub codes.
- When importing values for linked custom fields, you must use the proper import format.



- When adding or editing custom field values for linked fields, the process is different.

Adding, Editing and Deleting Custom Field Values

You use the Client Custom Fields section of the Administration tool to add, edit and delete custom values for a field. Please follow the steps in the sections below.

To add a new custom value:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field you want to add values for in the top list. A list of all values for that field appear below.
3. If you are editing a linked custom field type, there are two lists of values. The top list contains the main code values, the bottom list contains the sub code values. Selecting a value in the main code list shows the child codes for that value in the bottom list.
4. Double-click on an empty row in the bottom list in the Client Custom fields section, or click in the bottom list and click the **New** button on the toolbar. The **Adding New Value** window appears.
5. Enter the information for the new value.
6. Click the **Add** button. The value saves to the database and the window sets up to add the next value.
7. Click the **Close** button if you are done adding values. This will close the window and refresh the values. You can also continue steps 4 through 5 to continue adding values.

To add a new custom value from the Popup window:

1. Double-click on the custom field for which you want to add a value on the Client Popup window. A dialog appears asking you for the code and description.
2. Enter the new code and description and click **Add** button. The new value gets added to the database.
3. NOTE: A user can only add codes for the Searchable and Searchable drop down field types. A user must also have permission to add codes from the Popup.



To edit an existing custom value:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field you want to edit values for in the top list. A list of all values for that field appear in the bottom list.
3. If you are editing a linked custom field type, there are two lists of values. The top list contains the main code values, the bottom list contains the sub code values. Selecting a value in the main code list shows the child codes for that value in the bottom list.
4. Double-click on the value you want to edit in the bottom list in the Client Custom fields section. The **Editing Value** window appears.
5. Make your changes as appropriate.
6. Click the **Save** button. The **Editing Value** window closes and you see your changes displayed in the top list.

To edit multiple custom values at once:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field you want to edit values for in the top list. A list of all values for that field appear in the bottom list.
3. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of values you want to edit. NOTE: You cannot edit multiple parent values at the same time if using a linked custom field type. You can edit multiple child values at the same time however.
4. Click the **Edit** button on the toolbar. The **Editing Value** window appears. Please note that not all fields are editable when making changes to multiple values at once.
5. Make your changes as appropriate.
6. Click the **Save** button. The **Editing Value** window closes and you see your changes displayed in the top list.

To delete existing custom values:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field you want to delete values for in the top list. A list of all values for that field appear in the bottom list.



3. If you are editing a linked custom field type, there are two lists of values. The top list contains the main code values, the bottom list contains the sub code values. Selecting a value in the main code list shows the child codes for that value in the bottom list.
4. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of values you want to delete. If you want to delete only one value, you can simply click on it.
5. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the value(s).
6. Click the **Yes** button on the message box to delete the values. The bottom list refreshes to show the values were deleted.

NOTE: You cannot delete a custom field value if it is referenced in a database print job. If you delete a main code in a linked custom field, it deletes all child values.

Importing Custom Field Values

Print Audit allows you to import custom field values from a comma-delimited file on a one time or scheduled basis. This allows you to keep your master list of values in an accounting package or other piece of software and easily synchronize them with the codes in Print Audit. You can also import values from a generic flat file.

To import values into a field:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field for which you want to import values in the top grid. The field row is highlighted.
3. Click the **Import** button on the toolbar at the top of the Administration window. The Import Values window appears.
4. Select the **Import Type** using the drop down on the window **Import Values** window. See Custom Value Import Formats for a description of the different import formats.
5. On the **Import** tab, select the file containing the values you want to import. Please note that this file must be in the format specified by the import format you selected in step 4.



6. Check the **Advanced** tab to ensure settings are appropriate for what you want to do. See the Import Values window help for more information on the **Advanced** tab.
7. Click the **Import** button. Print Audit begins to import the values from the file.
8. Once the import is complete, a message displays indicating whether or not the import was successful. The import window closes and the list refreshes.

To run the import on a scheduled basis:

1. To run scheduled, simply follow the steps 1-6 in the above section. Then:
2. Check the scheduling settings on the **Scheduling** tab on the Import Values window. Ensure the settings reflect the type of schedule you want.
3. Click the **Schedule** button to add the task to the Windows Task Scheduler.

You can schedule a separate import for each custom field you define.

To remove a scheduled import:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field for which you want to cancel the import in the top grid. The field row is highlighted.
3. Click the **Import** button on the toolbar at the top of the Administration window. The **Import Values** window appears.
4. Click the **Remove Schedule** button to remove the task from the Windows Task Scheduler.

OR

Remove the task from the Windows Task Scheduler using its interface.

Custom Field Value Import Formats

The custom value importers require that the file you want to import is in a specific format. Below are the types of importers and their format requirements.



Comma-Delimited (Flat File)

This importer uses a comma-delimited file format. The columns are in the following order:

Code, Description, Cost Modifier, Modifier Type, Use Budget, Budget, Active

- **Code** - The code for the value. Must be unique for the field. This is the only required column.
- **Description** - A user friendly description for the value. If omitted, the Administrator leaves the description of the value blank.
- **Cost Modifier** - The cost modifier. If omitted assumes zero for cost modifier types, 100 for percentage modifier types. This type is used for both b/w and color unit costs if a unit modifier. If you need to specify separate b/w and color modifiers, please use the Print Audit 6 format.
- **Modifier Type** - A number indicating the type of modifier. 0 - Unit cost, 1 - Unit percentage, 2 - Job cost, 3 - Job percentage. If blank, Print Audit assumes unit percentage.
- **Use Budget** - Whether or not this value uses a budget. 0 - Not using a budget, 1 - Using a budget.
- **Budget** - The amount in the budget for this value.
- **Active** - Whether or not the code is currently active. A value of 0 means inactive, 1 means active. If blank, the Administrator assumes active.

Print Audit 4

This importer uses the same format as the Validated Value importing/exporting from Print Audit 4. The format is a comma-delimited file in the following order:

Code, Description, Cost Modifier, Active

- **Code** - The code for the value. Must be unique for the field. This is the only required column.
- **Description** - A user friendly description for the value. If omitted, the Administrator leaves the description of the value blank.
- **Cost Modifier** - A unit percentage modifier. If omitted, the Administrator uses a default of 100. The same modifier is applied for both color and b/w unit percentages.
- **Active** - Whether or not the code is currently active. A value of 0 means inactive, 1 means active. If blank, the Administrator assumes active.



Print Audit 5

This importer uses a comma-delimited file format. The columns are in the following order:

Code, Description, Cost Modifier, Modifier Type, Use Budget, Budget, Active

- **Code** - The code for the value. Must be unique for the field. This is the only required column.
- **Description** - A user friendly description for the value. If omitted, the Administrator leaves the description of the value blank.
- **Cost Modifier** - The cost modifier. If omitted assumes zero for cost modifier types, 100 for percentage modifier types. This modifier type is used for both b/w and color unit costs if it is a unit modifier type.
- **Modifier Type** - A number indicating the type of modifier. 0 - Unit cost, 1 - Unit percentage, 2 - Job cost, 3 - Job percentage. If blank, the Administrator assumes unit percentage.
- **Use Budget** - Whether or not this value uses a budget. 0 - Not using a budget, 1 - Using a budget.
- **Budget** - The amount in the budget for this value.
- **Active** - Whether or not the code is currently active. A value of 0 means inactive, 1 means active. If blank, the Administrator assumes active.

Print Audit 6

This importer uses a comma-delimited file format. The columns are in the following order:

Code, Description, Cost Modifier, Color Cost Modifier, Modifier Type, Use Budget, Budget, Active

- **Code** - The code for the value. Must be unique for the field. This is the only required column.
- **Description** - A user friendly description for the value. If omitted, the Administrator leaves the description of the value blank.
- **Cost Modifier** - The cost modifier for b/w unit costs or percentages if a unit type modifier. If a job type modifier this is the value for the job. If omitted assumes zero for cost modifier types, 100 for percentage modifier types.



- **Color Cost Modifier** - The cost modifier for color costs or percentages. It has no effect for job type modifiers. If omitted, assumes zero for cost modifier types, 100 for percentage modifier types.
- **Modifier Type** - A number indicating the type of modifier. 0 - Unit cost, 1 - Unit percentage, 2 - Job cost, 3 - Job percentage. If blank, the Administrator assumes unit percentage.
- **Use Budget** - Whether or not this value uses a budget. 0 - Not using a budget, 1 - Using a budget.
- **Budget** - The amount in the budget for this value.
- **Active** - Whether or not the code is currently active. A value of 0 means inactive, 1 means active. If blank, the Administrator assumes active.

Print Audit 6 Linked Values

This import format is the only valid format for importing custom values into Linked type custom fields. It is as follows:

Parent Code, Parent Description, Child Code, Child Description, Cost Modifier, Color Cost Modifier, Modifier Type, Use Budget, Budget, Active

- **Parent Code** - The code for the main code in the linked pair. Required.
- **Parent Description** - The description for the main code in the linked pair. If blank, the description is left blank.
- **Child Code** - The child code for the value. Required. The combination of parent code and child code must be unique.
- **Child Description** - A user friendly description for the child value. If omitted, the Administrator leaves the description of the value blank.
- **Cost Modifier** - The cost modifier for b/w unit costs or percentages if a unit type modifier. If a job type modifier this is the value for the job. If omitted assumes zero for cost modifier types, 100 for percentage modifier types.
- **Color Cost Modifier** - The cost modifier for color costs or percentages. It has no effect for job type modifiers. If omitted, assumes zero for cost modifier types, 100 for percentage modifier types.
- **Modifier Type** - A number indicating the type of modifier. 0 - Unit cost, 1 - Unit percentage, 2 - Job cost, 3 - Job percentage. If blank, the Administrator assumes unit percentage.
- **Use Budget** - Whether or not this value uses a budget. 0 - Not using a budget, 1 - Using a budget.
- **Budget** - The amount in the budget for this value.



- **Active** - Whether or not the code is currently active. A value of 0 means inactive, 1 means active. If blank, the Administrator assumes active.

Exporting Custom Field Values

You can export the custom values for a field to a comma-delimited file. You can then use this file for importing into other programs that may need the value list. Print Audit uses two slightly different formats depending on whether you are exporting a linked or a non-linked custom field.

For non-linked custom fields, the format is as follows:

Code, Description, BW Cost Modifier, Color Cost Modifier, Modifier Type, Use Budget, Budget, Active

For linked custom fields, the format is as follows:

Parent Code, Parent Description, Child Code, Child Description, BW Cost Modifier, Color Cost Modifier, Modifier Type, Use Budget, Budget, Active

To export custom field values from a field:

1. Click on the Client Custom Fields button on the left hand side of the Administration window. The Client Custom Fields section appears in the right hand side.
2. Click on the field for which you want to export values in the top grid. The field row is highlighted.
3. Click the **Export** button on the toolbar at the top of the Administration window. A standard Windows dialog appears.
4. Use the dialog to select a file to export the information to and click the **Save** button. The information starts to export.
5. After the export completes a message box appears letting you know how many values were exported.

NOTE: For custom field values that use percentage modifier types, the Color Cost Modifier column is ignored, and the BW Cost Modifier column contains the overall percentage modifier.



User Profiles

Overview

Print Audit allows you to assign tracking and security options to users with user profiles. There are two types of user profiles: Tracking Profiles and Security Profiles. You can assign the same profile to multiple users, allowing you to quickly set up how you want users to behave in Print Audit.

Tracking Profiles control how Print Audit tracks printing from the user. This includes things such as how jobs are tracked, what options they have on the Client Popup Window, if they have custom pricing, printing limits or cost/page allowances.

Security Profiles control what the user can do in the Print Audit tools. For example you can assign the "Administrator" profile to a user to give them full access to configure Print Audit. You can set individual Print Audit policies to control things such as user management, printer management and job exporting.

Print Audit assigns all users to the "Administrator" profile by default. It does this to ensure you do not lock yourself out of the database accidentally when you first install. If you want new users to have other profiles than "Administrator", you can use this section to assign different defaults. You **MUST** have one user at all times as the Print Audit Administrator. Print Audit does try to protect you from removing the last administrator. If you somehow do remove the last Administrator you will not be able to use the Administration tool at all.

Print Audit ships with some standard profiles already defined. You can modify these profiles to suit your business needs, or create new profiles to assign. We recommend you do not modify the Print Audit Administrator security profile.

You can do the following in this section:

- Set the default Tracking Profile
- Add, edit and delete Tracking Profiles
- Define Allowances
- Reset user balances.
- Set the default Security Profile
- Add, edit and delete Security Profiles



Allowances and Balances

Print Audit 6 allows you to set define cost or page balances for users. Whenever a user prints a job, its value is automatically deducted from the user's balance until none is remaining. If the user runs out, they can no longer print. To view an individual user's current balances, you can view the individual user in the Users section of the Administrator.

There are three major pieces that tie into user balances:

Allowances

An allowance is the default balance assigned to a user. You set up allowances on the User Tracking Profile, and whenever a user is assigned to the profile their balances get set to the allowance you define. The types of allowances are as follows:

- **Total Pages** - The total number of pages a user can print before they run out. Counts both b/w and color pages.
- **B/W Pages** - The total number of b/w pages a user can print before they run out. Allows unlimited color printing.
- **Color Pages** - The total number of color pages a user can print before they run out. Allows unlimited b/w printing.
- **B/W and Color Pages** - The total number of b/w and color pages they can print. If either allowance runs out, the user won't be able to print any more pages of that type.
- **Cost** - The total cost of print jobs the user is allowed to print before the allowance runs out.

You can set allowance balances to auto-reset periodically. For example, you could define an allowance of 50 total pages that resets the first of every month. At any point you can manually reset a user's balance.

Additional Balances

In some cases, you may want to have a separate balance for a user that does not reset when their allowance does. For example, in an educational institution a student may purchase extra printing outside of their normal allowance. This balance never automatically resets, although you can choose to manually reset it.



The additional balance is of the same type as the allowance, so it is not possible to have an allowance of total pages and an additional balance of cost for example.

If additional balances are enabled, printing is taken first from any remaining allowance, and then taken from the additional if the allowance runs out.

Overdraft

In some cases, you may want to allow users to be able to still print even if their balance is negative. In this case, you can assign an overdraft amount to the User Profile. For example, if you have a 50 page allowance you could set a 5 page overdraft to give a bit of leeway to your users.

Setting the Default User Tracking Profile

Print Audit uses a Tracking Profile you select as the "default" profile. Print Audit automatically assigns this default profile to users the first time they print.

You can change the default Tracking Profile at any time. When you change the default it only affects new users it does not change existing users in the User list.

To set the default Tracking Profile:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Tracking Profiles Tab in the User Profiles section. A list of all defined Tracking Profiles appears.
3. Use the **Default Profile** drop down box located at the top of the tab to select the new profile to use as the default. Print Audit now assigns the profile you selected to any new users that appear in the Users section

Adding, Editing and Deleting Tracking Profiles

You use the User Profiles section of the Administration tool to add, edit and delete Tracking Profiles. Please follow the steps in the sections below.

To add a new tracking profile:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.



2. Click the Tracking Profiles Tab in the User Profiles section. A list of all defined Tracking Profiles appears.
3. Double-click on an empty row in the Tracking Profiles list, or click the **New** button on the toolbar. The **Tracking Profile** window appears.
4. Enter the information for the new profile. Click here for details on the Tracking Profile window.
5. Click the **Add** button. The value saves to the database and the window sets up to add the next profile.
6. Click the **Close** button if you are done adding profiles. This will close the window and refresh the profiles. You can also continue steps 3 through 4 to continue adding profiles.

To edit an existing tracking profile:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Tracking Profiles Tab in the User Profiles section. A list of all defined Tracking Profiles appears.
3. Double-click on the Profile you want to edit in the profile list. The **Tracking Profile** window appears.
4. Make your changes as appropriate. Click here for details on the Tracking Profile window.
5. Click the **Save** button. The **Tracking Profile** window closes and you see your changes displayed in the list. Please note that if you change the balance information Print Audit asks you if you want to reset your balances. Click here for more information on resetting balances.

To delete existing tracking profiles:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Tracking Profiles Tab in the User Profiles section. A list of all defined Tracking Profiles appears.
3. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of profiles you want to delete. If you want to delete only one profile, you can simply click on it.
4. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the profiles(s).
5. Click the **Yes** button on the message box to delete the profiles. The list refreshes to show the profiles were deleted.



NOTE: You can only delete a profile if no users exist that use it.

Resetting User Balances

You can easily reset the balances for every user in a Tracking Profile. You may want to reset the balances at the start of every month, or using some other criteria that makes sense for your business. Please note that Print Audit automatically asks you if you want to reset user balances when you change the starting balance on the profile window.

You can also setup automatic balance resetting.

To reset user balances:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Tracking Profiles Tab in the User Profiles section. A list of all defined Tracking Profiles appears.
3. Double-click on the Profile you want to reset balances for in the profile list. The **Tracking Profile window** appears.
4. Make sure the allowance values on the **Allowances** tab on the **Tracking Profile** window contains the value you want.
5. Click the **Reset User Balances** button. The **Reset Balances** window appears.
6. Click the option corresponding to the balance option you want.
7. Check the **Set additional balances to zero** box if you want to reset additional balances along with the allowance balances.
8. Click the **Update** button. A message appears asking you to confirm you want to update the balances.
9. Click **Yes** to set the balances of all users that use the profile.

Setting the Default User Security Profile

Print Audit uses a Security Profile you select as the "default" profile. Print Audit automatically assigns this default profile to users the first time they print.

You can change the default Security Profile at any time. When you change the default it only affects new users it does not change existing users in the User list.



To set the default Security Profile:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Security Profiles Tab in the User Profiles section. A list of all defined Security Profiles appears.
3. Use the **Default Profile** drop down box located at the top of the tab to select the new profile to use as the default. Print Audit now assigns the profile you selected to any new users that appear in the Users section.

Adding, Editing and Deleting Security Profiles

You use the User Profiles section of the Administration tool to add, edit and delete Security Profiles. Please follow the steps in the sections below.

To add a new security profile:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Security Profiles Tab in the User Profiles section. A list of all defined Security Profiles appears.
3. Double-click on an empty row in the Security Profiles list, or click the **New** button on the toolbar. The **Security Profile** window appears.
4. Enter the information for the new profile.
5. Click the **Add** button. The value saves to the database and the window sets up to add the next profile.
6. Click the **Close** button if you are done adding profiles. This will close the window and refresh the profiles. You can also continue steps 3 through 4 to continue adding profiles.

To edit an existing security profile:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Security Profiles Tab in the User Profiles section. A list of all defined Security Profiles appears.
3. Double-click on the Profile you want to edit in the profile list. The **Security Profile** window appears. NOTE: We recommend you do not edit the Administrator security profile.
4. Make your changes as appropriate.



5. Click the **Save** button. The **Security Profile** window closes and you see your changes displayed in the list.

To delete existing security profiles:

1. Click on the User Profiles button on the left hand side of the Administration window. The User Profiles section appears in the right hand side.
2. Click the Security Profiles Tab in the User Profiles section. A list of all defined Security Profiles appears.
3. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of profiles you want to delete. If you want to delete only one profile, you can simply click on it.
4. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the profiles(s).
5. Click the **Yes** button on the message box to delete the profiles. The list refreshes to show the profiles were deleted.

NOTE: You can only delete a profile if no users exist that use it.

Users

Overview

Print Audit automatically adds every user it detects to the user list. Over time this list contains every user in your organization that has printed.

You use this list to assign tracking and security profiles, assign users to report groups, set PIN codes and/or passwords as well as check and set user balances.

You can do the following with the users section:

- Editing Users
- Adding and Deleting Users (Advanced)
- Importing and Exporting Users

Adding and Deleting Users (Advanced)

You can use Print Audit to add users to and delete users from the Users list. Print Audit automatically adds users to the list when they print, so you only need to



add/delete users if you have advanced requirements. Note that if you delete a user, it may re-appear as soon as they print.

To add a new user:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Double-click on an empty row in the list or click the **New** button in the toolbar. The **User** window appears.
3. Enter information for the user as applicable.
4. Click the **Add** button. The user saves to the database and the window sets up to add the next user.
5. Click the **Close** button if you are done adding users. This closes the window and refreshes the users. You can also continue steps 3 through 4 to continue adding users.

To delete a user:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Click on the user you want to delete in the user list. The user highlights.
3. Click the **Delete** button on the toolbar at the top of the Administration tool. A message appears asking you to confirm that you want to delete.
4. Click the **Yes** button to continue deleting the user. The user list refreshes to show that Print Audit deleted the user.

NOTE: You can not delete users if they have print jobs in the database.

Editing Your Users

You may need to edit your users for several reasons. You edit users to add/change PIN codes, reset their user balances and assign them to different reporting groups.

You also need to edit users to assign them to different tracking or security profiles.



To edit a user:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Double-click on the user you want to edit. The **User** window appears.
3. Change the information as appropriate.
4. Click the **Save** button. The **User** window closes and you should see changes reflected in the list.

To edit multiple users at once:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of users you want to edit.
3. Click the **Edit** button on the toolbar. The **Update Multiple Users** window appears.
4. Make your changes as appropriate. Please note that you can only change the tracking profile, security profile, balance and reporting group when editing multiple users.
5. Click the **Update** button. The **Update Multiple Users** window closes and you see your changes displayed in the list.

To change/create PIN codes for multiple users at once:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of users whose PIN codes you want to change.
3. Click the **Edit->Generate PIN Codes** menu item. The **Generate PIN Codes** window appears.
4. Enter the length of the PIN code you want to generate.
5. Check the **Numeric only** box if you want to generate numeric only PIN codes.
6. Check the **Overwrite existing** box if you want to overwrite PIN codes if they already exist. If unchecked **Print Audit** creates new PIN codes but does not overwrite existing PIN codes.



7. Click the **Generate** button. Print Audit generates new PIN codes for the users. To see a list of PIN codes for the users you can export the users to a flat file.

NOTE: Resetting a PIN code for the user does not reset their PIN password.

Importing Users

Print Audit allows you to import a user list from a generic comma-delimited format, a Print Audit 4 format flat file, a Print Audit 5 format flat file, a Print Audit 6 format flat file and from a domain. Please note that you can only import Windows users if you run the Administration tool on a Windows NT based computer. You can also schedule user imports to run whenever you like, keeping the users up to date.

IMPORTANT - You do NOT need to import users. Print Audit automatically adds users to the database as they print. Only import users if you want to assign PIN codes to a large number of users at once, set their balances or groups.

When importing users you can adjust several settings that affect how PIN codes, Balances and Groups are set for newly imported users. The options available are dependent on the type of import you are doing.

NOTE: For advanced users the **Network Type** setting in the Network and Authentication Settings section controls which type of domain Print Audit attempts to import from; a Windows NT, Active Directory or Novell NDS domain.

To import users:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Click the **Import** button on the toolbar at the top of the Administration window. The Import Users window appears.
3. Select the **Import Type** using the drop down on the window **Import Users** window. See User Import Types for a description of the different types of user imports.
4. Select the file you want to import for a **Print Audit 4/5** import, or enter the domain you want to import users from for a Domain type import. Please note that the file you choose for a file-based import must be in the correct format.



5. Enter an organizational unit (OU) to limit the import to. This option is only available for Domain type imports, and if your Network Type is Active Directory or Novell NDS.
6. Select the tracking profile, security profile for the import.
7. Select your options for PIN, PIN Password, Balances and Grouping.
8. Click the **Import** button. Print Audit begins to import the users.
9. Once the import is complete, a message displays indicating whether or not the import was successful. The import window closes and the list refreshes.

If you generate PIN codes for users you can export the users to get a list of all assigned PIN codes.

To schedule user imports:

1. Set up the import using the same steps 1-7 above.
2. Click on the **Scheduling** tab.
3. Use the **Run Import** drop down to select how often to run the import. Choices are Daily, Weekly or Monthly.
4. Use the **On** drop down to select the day on which to run the import. This is only effective for Weekly or Monthly schedules.
5. Use the **At** selector to select the time of day at which to run the import. We recommend using a time outside of regular business hours.
6. Click the **Schedule** button. Print Audit creates an entry in the Windows task scheduler that when run imports users using the settings you defined.

To unschedule user imports:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Click the **Import** button on the toolbar at the top of the Administration window. The Import Users window appears.
3. Click the **Unschedule** button. If not enabled, you have no imports scheduled. You can also manually delete the task using the Windows Task Scheduler.



Exporting Users

You can export the Print Audit user list to a comma-delimited file. Print Audit exports all user PIN codes so it is important to make sure you keep track of this file for security purposes.

Print Audit creates a comma-delimited file, with the columns in the following order:

PIN code, Display Name, Unique Name, Network Name, Domain, B/W Allowance Balance, B/W Additional Balance, Color Allowance Balance, Color Additional Balance, Account.

To export users:

1. Click on the Users button on the left hand side of the Administration window. The Users section appears in the right hand side. A list of all users Print Audit has tracked displays in the section.
2. Click the **Export** button on the toolbar at the top of the Administration window. The **Export Users To File** window appears.
3. Type in the file to export to, or use the browse button to select a file.
4. Click the **Export** button on the window to export the users to the selected file.

Printer Profiles

Overview

Print Audit 6 allows you to assign tracking and print cost information to printers through Printer Profiles. For example you use Printer Profiles to set whether Print Audit tracks printing from a printer, if it should track printing in pages, square footage, etc., as well as any printing limits you want to place on your printing device. You only need to create different Printer Profiles if you need to have different tracking or pricing options for different devices. You can set multiple printers to use the same Printer Profile.

New to Print Audit 6 is the ability to determine which custom fields should display on the Popup based on printer, as well as extended job options when printing. Click here for more information on the new options.



Print Audit ships with two profiles already created, one for standard tracking one for ignoring printing. It sets the default profile to the tracking profile.

You can use this section to do the following:

- Set the default Printer Profile
- Add, edit and delete Printer Profiles

Printer Profiles do not take effect until assigned to one or more printers.

Setting the Default Printer Profile

Print Audit uses a Printer Profile you select as the "default" profile. Print Audit automatically assigns this default profile to printers as it adds them to the Printers list.

You can change the default Printer Profile at any time. When you change the default it only affects new printers it does not change printers that already exist in the Printer List.

To set the default Printer Profile:

1. Click on the Printer Profiles button on the left hand side of the Administration window. The Printer Profiles section appears in the right hand side. A list of all existing Printer Profiles displays in the list.
2. Use the **Default Profile** drop down box located just above the Printer Profiles list to select the new profile to use as the default. Print Audit now assigns the profile you selected to any new printers that appear in the Printers section.

Adding, Editing and Deleting Printer Profiles

You use the Printer Profiles section of the Administration tool to add, edit and delete Printer Profiles. Please follow the steps in the sections below.

To add a new printer profile:

1. Click on the Printer Profiles button on the left hand side of the Administration window. The Printer Profiles section appears in the right hand side. A list of all existing Printer Profiles displays in the list.



2. Double-click on an empty row in the Printer Profiles list, or click the **New** button on the toolbar. The **Adding New Printer Profile** window appears.
3. Enter the information for the new profile.
4. Click the **Add** button. The profile saves to the database and the window sets up to add the next profile.
5. Click the **Close** button if you are done adding profiles. This will close the window and refresh the profiles. You can also continue steps 3 through 4 to continue adding profiles.

To edit an existing printer profile:

1. Click on the Printer Profiles button on the left hand side of the Administration window. The Printer Profiles section appears in the right hand side. A list of all existing Printer Profiles displays in the list.
2. Double-click on the Profile you want to edit in the profile list. The **Editing Printer Profile** window appears.
3. Make your changes as appropriate.
4. Click the **Save** button. The **Editing Printer Profile** window closes and you see your changes displayed in the list.

To add a printing limit to a printer profile:

1. Follow the steps above to add a new profile or edit an existing profile.
2. Click the **Printing Limits** tab on the **Printer Profile** window.
3. Click the **Add** button on the **Printer Profile** window. The Printing Limit window appears.
4. Select the type of limit you want.
5. Enter the value you want for the limit.
6. Enter the message you want displayed to the user if they exceed the limit. You can use message variables in the message.
7. Check the **Stop Job** check box if you want Print Audit to stop the job from going to the printer if the job exceeds the limit.
8. Click the **Ok** button to accept the changes to the limit. The window closes and you are back at the **Printer Profile** window.
9. Repeat steps 3 to 8 to add more limits.
10. Click the **Add/Save** button on the **Printer Profile** window to save the changes.



NOTE: When you add a limit Print Audit automatically changes to "wait for page count" mode. This mode causes Print Audit to wait until all pages are spooled before it displays the Popup window or any warnings.

To delete existing printer profiles:

1. Click on the Printer Profiles button on the left hand side of the Administration window. The Printer Profiles section appears in the right hand side. A list of all existing Printer Profiles displays in the list.
2. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of profiles you want to delete.

If you want to delete only one profile, you can simply click on it.

3. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the profiles(s).
4. Click the **Yes** button on the message box to delete the profiles. The list refreshes to show the profiles were deleted.

NOTE: You can only delete a profile if no printers exist that use it.

Printing Limits and Redirection

In Print Audit you can setup multiple limit thresholds for Applications, Printer Profiles or User Track Profiles. You can use these limits to require users to print large jobs to more cost effective printers, limit the amount of color printing they can do to individual printers, limit the number of pages they can print from a website, and so on.

Once a limit is hit, you can define the message that displays to the user, and either make the job cancel and have the user re-print the job to a different printer if needed, or just warn them about their behavior.

Print Audit supports several types of limits. They are as follows:

- **Total pages** - The total number of pages allowed.
- **B/W pages** - The total number of b/w pages allowed.
- **Color pages** - The total number of color pages allowed.
- **Total cost** - The total cost of the job, after the Popup has been completed.
- **Base cost** - The total cost of the job before the Popup displays.



Since it is possible to have limits defined in several different areas of the software, Print Audit processes limits as follows:

1. "Stop" limits are processed before "Warn" limits.
2. Limits are processed in order of Application, User, Printer. So if you have defined a limit for an Application and a similar limit in Printer, the message you entered for the Application limit will display.
3. You can choose, for any individual Application, User Profile or Printer Profile to ignore any defined limits. So for example you could set limits at an Application level, but allow users that belong to a User Profile to print without triggering those limits.

Printers

Overview

Print Audit 6 automatically adds printers to your printers list. Print Audit adds the printer the first time it detects a print job going to the printer. Over time this list contains every printing device in your organization.

You use this list to assign profiles to printers as well as maintain device specific information.

You can do the following with the Printers section:

- Editing your Printers
- Adding and Deleting Printers (Advanced)

One of the most important topics when using Print Audit discusses how the software uses printer matching. The printer matching systems determine how Print Audit determines if the printer someone prints to from the Windows desktop matches one that already exists in the database. The systems are as follows:

- Normal Printer Device Matching
- Automatic Merging (Advanced)
- Manual Merging (Advanced)

The Printer Profiles section and the Printer Paper Sizes section work with the Printers section to determine how jobs are tracked and charged. Click the links to see more information on those sections.



Adding and Deleting Printers (Advanced)

You can use Print Audit to add printers to and delete printers from the Printers list. Print Audit automatically adds printers to the list when printing, so you only need to add/delete printers if you have advanced requirements such as specialized printer matching. Note that if you delete a printer, it may re-appear as soon as someone prints to it.

To add a new printer:

1. Click on the Printers button on the left hand side of the Administration window. The Printers section appears in the right hand side. A list of all printers Print Audit has tracked displays in the section.
2. Double-click on an empty row in the list or click the **New** button in the toolbar. The **Printer** window appears.
3. Enter information for the printer as applicable.
4. Click the **Add** button. The **Adding New Printer** window closes and the new printer adds to the list.

To delete a printer:

1. Click on the Printers button on the left hand side of the Administration window. The Printers section appears in the right hand side. A list of all printers Print Audit has tracked displays in the section.
2. Click on the printer you want to delete in the printer list. The printer highlights.
3. Click the **Delete** button on the toolbar at the top of the Administration tool. A message appears asking you to confirm that you want to delete.
4. Click the **Yes** button to continue deleting the printer. The printer list refreshes to show that Print Audit deleted the printer.

NOTE: You cannot delete printers if they have print jobs in the database.



Editing Your Printers

You may need to edit printers from time to time, mainly to change the Printer Profile assigned to the printer, or to assign the printer to a different reporting group. You can also edit multiple printers at once.

To edit a printer:

1. Click on the Printers button on the left hand side of the Administration window. The Printers section appears in the right hand side. A list of all printers Print Audit has tracked displays in the section.
2. Double-click on the printer you want to edit. The **Editing Printer** window appears.
3. Change the information as appropriate.
4. Click the **Save** button. The **Editing printer** window closes and you should see changes reflected in the list.

To edit multiple printers at once:

1. Click on the Printers button on the left hand side of the Administration window. The Printers section appears in the right hand side. A list of all printers Print Audit has tracked displays in the section.
2. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of printers you want to edit.
3. Click the **Edit** button on the toolbar. The **Update Multiple Printers** window appears.
4. Make your changes as appropriate. Please note that you can only change the tracking profile and reporting group when editing multiple printers.
5. Click the **Update** button. The **Update Multiple Printers** window closes and you see your changes displayed in the list.

Manual Printer Merging

Print Audit supports manual printer merging. This allows you to take any set of print devices listed in the Printers List in the Administrator and merge the devices and all their jobs into one printer device. Print Audit remembers manual merges and automatically merges all future jobs accordingly.

NOTE: This is intended for advanced users only. You should only use manual printer merging if you are sure the printer devices you are merging should be



reporting as only one device. If you merge devices there is no way to separate the job information back to the original printers.

At any point you can "un-merge" a printer to remove all merging information. This does NOT restore the jobs to the separate printers but future print jobs are assigned to the separate devices.

To view merged printers:

1. Click on the Printers button on the left hand side of the Administration window. The Printers section appears in the right hand side. A list of all printers Print Audit has tracked displays in the section.
2. Printers that have other printers merged into them have a "plus" symbol to the left of their name. Click this symbol to expand the printers list to show all printers merged into that device.

To manually merge printers:

1. Click on the Printers button on the left hand side of the Administration window. The Printers section appears in the right hand side. A list of all printers Print Audit has tracked displays in the section.
2. Use CTRL-CLICK or SHIFT-CLICK to select the printers you want to merge. IMPORTANT: The first printer you select is the one Print Audit merges the rest of the printers into. So, for example, if you select printers A, B, C and D in that order, Print Audit merges all of B, C and D's jobs into printer A, and deletes printers B, C and D.
3. Click the **Advanced->Merge Printers** menu. A window appears asking you if you are sure you want to merge these printers.
4. Click the **Yes** button. Print Audit merges the printers and the jobs and refreshes the printer list.

To un-merge a printer:

1. Click on the Printers button on the left hand side of the Administration window. The Printers section appears in the right hand side. A list of all printers Print Audit has tracked displays in the section.
2. Printers that have others merged into them have a "plus" symbol to the left of their name. Click this symbol to expand the printers list to show all printers merged into that device.
3. Click on the merged printer you want to un-merge, and click the **Delete** button on the toolbar. A window appears asking if you are sure you want to delete the merge.



4. Click the **Yes** button. The merged printer now disappears from the list. It will be added as its own separate printer again the next time a user prints to it, but the previously merged jobs will not separate.

NOTE: If the merged printer appears gray in the list, it is an automatically merged device and cannot be deleted.

Printer Paper Sizes:

Overview

Print Audit 6 allows you to charge for print jobs based on the size of paper used to print the job. For example, you could set a cost of \$0.10 per page for Letter sized pages, and \$0.15 for Legal sizes. For very large paper sizes used in plotting of large drawings, you may want to use square footage or square meter tracking instead.

To use paper size costing you need to ensure the paper sizes you use in your day to day business are included on the paper sizes list. You also need to set pricing in a User Profile, Printer Profile or Application to use "per paper size" as the print option and assign that profile to your printers.

Print Audit ships with many of the standard paper sizes, you can add or modify them to suit your needs. You may want to look at each paper size and ensure the cost per page is correct for your business.

You can use this section to do the following:

- Adding, editing and deleting paper sizes

Adding, Editing and Deleting Paper Sizes

You use the Printer Paper Sizes section to add, edit and delete paper sizes. Printer Profiles use these paper sizes if you set the pricing option to "per paper size".

To add a new paper size:

1. Click on the Printer Paper Sizes button on the left hand side of the Administration window. The Printer Paper Sizes section appears in the right hand side.



2. Double-click on an empty row in the bottom list in the Printer Paper Sizes section, or click the **New** button on the toolbar. The **Adding New Paper Size window** appears.
3. Enter the information for the new paper size.
4. Click the **Add** button. The paper size saves to the database and the window sets up to add the next size.
5. Click the **Close** button if you are done adding paper sizes. This will close the window and refresh the sizes. You can also continue steps 3 through 4 to continue adding sizes.

To edit an existing paper size:

1. Click on the Printer Paper Sizes button on the left hand side of the Administration window. The Printer Paper Sizes section appears in the right hand side.
2. Double-click on the paper size you want to edit in the paper size list. The **Paper Size** window appears.
3. Make your changes as appropriate.
4. Click the **Save** button. The **Paper Size** window closes and you see your changes displayed in the top list.

To edit multiple paper sizes at once:

1. Click on the Printer Paper Sizes button on the left hand side of the Administration window. The Printer Paper Sizes section appears in the right hand side.
2. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of paper sizes you want to edit.
3. Click the **Edit** button on the toolbar. The **Update Paper Sizes Cost** window appears.
4. Enter the new costs you want to assign to the paper sizes.
5. Click the **Update** button. The **Update Paper Sizes Cost** window closes and you see your changes displayed in the list.

To delete existing paper sizes:

1. Click on the Printer Paper Sizes button on the left hand side of the Administration window. The Printer Paper Sizes section appears in the right hand side.
2. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of paper sizes you want to delete. If you want to delete only one paper size, you can simply click on it.



3. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the paper size(s).
4. Click the **Yes** button on the message box to delete the paper sizes. The list refreshes to show the paper sizes were deleted.

Application

Overview

Print Audit 6 can determine whether or not to track printing from an application. By default, all applications are watched for print jobs. However you may have instances where you want to track printing from only one application, or you want to track printing from all applications except one. You may also have instances where you do not want users to be able to print information from an application.

New to Print Audit 6, you can now define printing limits, job rules, custom pricing and specify which custom fields are used for the user at an application level.

You DO NOT need to add every application you want to track to this list. Only add applications to the list if you have special tracking needs. Please note that unlike the Users and Printers list, Print Audit does not automatically add every application it detects printing from to the list.

The Applications section in the Administration tool allows you to do the following:

- Add, edit and delete applications
- Limit the number of tracked applications

Adding, Editing and Deleting Applications

You use the Applications section of the Administration tool to add, edit and delete applications. Please follow the steps in the sections below.

To add a new application:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.
2. Click on the Applications button on the left hand side of the Administration window. The list of applications appears in the right hand side.



3. Double-click on an empty row in the list in the Applications section or click the **New** button on the toolbar. The **Applications** window appears.
4. Enter the application information as applicable.
5. Click the **Add** button. The application saves to the database and the window sets up to add the next application.
6. Click the **Close** button if you are done adding applications. This will close the window and refresh the applications. You can also continue steps 4 through 5 to continue adding applications.

To edit an existing application:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.
2. Click on the Applications button on the left hand side of the Administration window. The list of applications appears in the right hand side.
3. Double-click on the application you want to edit in the list in the Applications section. The **Applications** window appears.
4. Make your changes as appropriate.
5. Click the **Save** button. The **Applications** window closes and you see your changes displayed in the list.

To delete existing applications:

1. Click on the **Advanced** header on the left hand side of the Administration window. The list of advanced sections of the Administration tool display.
2. Click on the Applications button on the left hand side of the Administration window. The list of applications appears in the right hand side.
3. Use a combination of CTRL-CLICK and SHIFT-CLICK to select the list of applications you want to delete. If you want to delete only one application, you can simply click on it.
4. Click the **Delete** key on the toolbar at the top of the Administration window. A message appears asking you to confirm you want to delete the application(s).
5. Click the **Yes** button on the message box to delete the applications. The bottom list refreshes to show the applications were deleted.

Limiting the Number of Tracked Applications

Print Audit 6 provides an extremely quick and easy way to have Print Audit limit tracking to only a few applications in your organization. For example, you can set



Print Audit to track printing only from Microsoft Word without having to add every other application to the Applications list.

To limit the number of applications you want tracked:

1. Add the applications you do want tracked to the Applications list and set their tracking options appropriately.
2. Check the **Track only the applications in the list** button. This causes Print Audit to ignore printing from any application not in the Applications list.

Network Settings

Overview

Print Audit 6 allows you to gather network user information from several different types of networks. Print Audit supports Novell NDS networks, Windows NT 4.0 based networks, Active Directory networks and peer to peer Windows networks.

You can also configure Print Audit to require users to authenticate before they can print or use Print Audit tools. You can choose authentication with PIN codes, use existing login information or require the user to re-enter their login information. You can even choose to have a user authenticate differently for printing depending on the computer they are printing from.

Your network settings control how user information appears in Print Audit when users are added and imported.

Please note that we recommend changing these settings only if you are an advanced user with an understanding of networks and how your network is implemented.

You can do the following with this section:

- Change your network type
- Change how users authenticate
- Change the PIN and PIN Password labels
- Set the Disconnected job option per computer
- Change the TCP/IP port the Client listens on



Changing Your Network Type

Print Audit supports several different network types. Your network type controls how Print Audit reports user information as well as how it imports users. Your network type also controls how Print Audit does network authentication.

To change your network type:

1. Click on the **Advanced** header on the left hand side of the Administration window. The left hand list switches to the list of advanced sections.
2. Click on the Network and Authentication button on the left hand side of the Administration window. The section appears with the list of computers that have printed.
3. Use the **Network Type** drop down to select the type of network in your organization.
4. Click the **Save** button on the toolbar at the top of the Administration window to save the changes.

Please note that the network type changes the information of new users as they print, it does not affect existing users. If you change the network type when you have existing users, the next time they print they get added to the list with the new network information and Print Audit treats them as different users. Please be aware that when these new users are added Print Audit uses your default tracking and security profiles. This can end up with a user under one network type having different rights and tracking behavior than the user under the new network type.

For these reasons we highly recommend that you set the network type as early as possible in your Print Audit configuration and only change it if absolutely necessary.

Changing How Users Authenticate

Print Audit allows several different methods of authentication. You can configure Print Audit to require users to authenticate before they can print and authenticate before they can use the Print Audit tools.

You can set Print Audit to require different authentication methods for printing (Client Authentication) and access to the tools (Tools Authentication). For example, you may want Print Audit to use the logged in user for tracking printing but require a PIN code to get into the Print Audit tools.



Please note that the default Client Authentication and Tools Authentication settings are the same as those in the Client Settings section of the Administration tool. We provide them there as well for ease of use.

To change the default client authentication:

1. Click on the **Advanced** header on the left hand side of the Administration window. The left hand list switches to the advanced sections.
2. Click on the Network and Authentication button on the left hand side of the Administration window. The section appears with the list of computers that have printed.
3. Use the **Default client authentication** drop down to select the type of Client Authentication you want to do by default.
4. Click the **Save** button on the toolbar at the top of the Administration window to save the changes. A message appears asking if you want to change all existing computers to use the new default.
5. Click **Yes** to set all computers to the new defaults, or click **No** set the new default, but leave existing computers with their current authentication settings. NOTE: If you leave existing computers to "Network" authentication and you are using the Windows Peer to Peer network setting then the Client uses PIN code authentication instead.

To change the client authentication for a computer:

1. Click on the **Advanced** header on the left hand side of the Administration window. The left hand list switches to the advanced sections.
2. Click on the Network and Authentication button on the left hand side of the Administration window. The section appears with the list of computers that have printed.
3. Double-click on the computer that you want to change authentication for. The **Computer** window appears.
4. Use the Authentication drop down box to select the authentication type.
5. Click the **Save** button on the **Computer** window. The **Computer** window closes and the computer list refreshes to show the changes.

To change the tools authentication:

1. Click on the **Advanced** header on the left hand side of the Administration window. The left hand list switches to the advanced sections.
2. Click on the Network and Authentication button on the left hand side of the Administration window. The section appears with the list of computers that have printed.



3. Use the **Tools authentication** drop down to select the type of Tools Authentication you want.
4. Click the **Save** button on the toolbar at the top of the Administration window to save the changes.

Network Login Authentication

For advanced users Print Audit supports network login authentication. This allows you to have your users enter their Windows or Novell network login information before they print or use the Print Audit tools.


Using this setting on a Windows operating system has the issues that you need to be aware of:

- You cannot use this setting in combination with the "Windows Peer to Peer" Print Audit network type.
- Windows 98, ME computers cannot authenticate with network settings unless they are configured to use user-level sharing. You need to change this in the network settings of your Windows 9x based operating systems.
- If you have NT based computers that are not on the domain they may not be able to successfully authenticate. This is because they authenticate to their local user database and report the domain as the computer name.

For these reasons we recommend you only use this setting if you are running a Novell network or if your Windows network consists of Windows NT/Active Directory based operating systems that connect/authenticate to a domain. If you have a mixed environment we recommend using PIN code security instead.



Print Audit 6 Analysis Reporting



Overview

Welcome to Print Audit Analysis Reporting. You can use this tool to produce pre-prepared reports for your printing volumes and costs. You can use these reports to determine your highest volume printers, distribution of job sizes, percentage of color vs black and white printing, etc. Analysis Reporting also allows you to create Composite Reports. These reports are a combination of several other reports with a title page and table of contents.

This help file consists of several sections. Click the links below for information on each section:

- [Understanding Analysis Reporting](#)
- [Grouping Information](#)



- Creating and Removing Reports
- Creating Composite Reports
- Printing and Exporting Reports
- Scheduling and Emailing Reports

Understanding the Analysis Reporting Tool

You can use the Analysis Reporting tool in two different modes. The normal mode and a "simple" mode. Simple mode in Analysis Reporting supports all of the same reports as the normal mode, but in simple mode you do not have access to complex printer and user grouping.

The Analysis Reporting tool consists of two main areas, the toolbar and the tabbed display area. You use the toolbar to manipulate tabbed information or even create new tabs. The tabs themselves display your printer and user groups along with any created reports. Printer and user groups are not displayed in simple mode.

There are only two tabs visible when you first run the Analysis Reporting tool in normal mode. They are the **Printer Grouping and Filtering** tab and the **User Grouping and Filtering** tab.

The **Printer Grouping and Filtering** tab displays all printers in your database. You use this tab to arrange printers into reporting groups as well as selecting which printers/groups you want to include in your reports. You can also use this tab to enter an estimated cost per page for the printer. Generally, Analysis Reporting uses the actual recorded cost of the print job to calculate total costs when you are doing reports. If you choose, you can use the estimated cost per page you enter to calculate costs. **IMPORTANT:** Actual costs in Print Audit include several things such as unit type, cost modifiers, etc. Estimated cost per page only takes into account the reported page count.

The **User Grouping and Filtering** tab displays all users in your database. You can use this tab to group your users any way that makes sense for your organization. You could group them by last name, or by department, etc.

Once you have your groups defined you can create reports based on your data. After you create a report you can then print it or export it in different formats.



Grouping and Filtering in Normal Mode

Analysis Grouping Information

The Print Audit Reporting Analysis tool allows you to group your printer and user information together. Grouping information has two main purposes:

- Grouping allows you to organize your printers and users in ways that make sense for your organization.
- Grouping allows you to focus on high level reporting issues rather than individual printers.

The last point is the most important. The main function of grouping is to allow you to create groups that you can display on different reports. For example, you may have several printers on one floor of your office. You can combine those printers into a group called "4th floor" and generate reports based only on those printers. You could also create user groups so you can report on printing costs based on internal departments.

These groups are kept separate from reporting groups you can setup using Simple mode and the Job Manager users to give you complete flexibility in how you define groupings for analysis. However you can import your simple groups into the Analysis Reporting tool.

To create a group:

1. Expand the **<INDIVIDUAL>** group or another group you have created to view the contents.
2. Click on one or more items to select them. You can use CTRL-click to select multiple individual items or use SHIFT-click to select a range of items. You can select items from more than one group at once.
3. Click the **Create/Add to Group** button on the tool bar. The **Create/Add to Group** window appears.
4. Select the option to either create a new group or move the selected items to an existing group.
5. Enter your new group name or select the existing group.
6. Click the **OK** button. This moves the selected items to the group you specified.



To import Administrator groups:

1. Click the **Groups->Import Simple Groups** menu item. Print Audit imports the reporting groups from the Administrator and automatically associates your users and printers to those groups. If users or printers exist in multiple groups, they will only be associated with the first group they appear in.

NOTE: This overwrites any other groups you have created.

To delete a group:

1. Click on the group you want to delete. You cannot delete the **<INDIVIDUAL>** group.
2. Click the **Delete Group** button on the toolbar. A message box appears asking if you are sure you want to delete the group.
3. Click **Yes** on the message box. The Analysis tool removes the group and moves any items in that group to the **<INDIVIDUAL>** group.

To rename a group:

1. Click on the group you want to rename. You cannot rename the **<INDIVIDUAL>** group.
2. Click in the column that contains the name of the group. This is the **Printer** column for the **Printer Information** tab, the **Name** column for the **User Information** tab.
3. Type the name of the new group.

Using the Printer Grouping and Filtering Tab

This tab shows all of the printers in the database. You use this tab to decide whether or not printers or groups of printers are included in reports.

To view the contents of a printer group:

1. Click the "plus/minus sign" at the left of the group name to expand/collapse the group. When expanded you can see all of the unique printers included in the group.



To group printers:

1. Expand the **<INDIVIDUAL>** group or another group you have created to view the contents.
2. Click on one or more printers to select them. You can use CTRL-click to select multiple individual printers or use SHIFT-click to select a range of printers. You can select printers from more than one group at once.
3. Click the **Create/Add to Group** button on the tool bar. The **Create/Add to Group** window appears.
4. Select the option to either create a new group or move the selected printers to an existing group.
5. Enter your new group name or select the existing group.
6. Click the **OK** button. This moves the selected printers to the group you specified.

To include/exclude printers and groups from reports:

1. Expand the **<INDIVIDUAL>** group or another group you have created to view the contents.
2. Select the users or groups of printers you want to include/exclude.
3. Click on the **Include** column or hit the SPACEBAR key to toggle the selection.

Printer Grouping and Filtering Tab Columns

- **Include** – This column indicates whether or not you want to include the printer or printer group in any reports.
- **Printer** – This column contains the name of the printer or printer group.
- **Host** – This column contains the host computer for the printer. The host is the computer which controls the printer.
- **Port** – This column contains the port of the printer. For groups this is blank.
- **Est. Cost Per BW Page** - This column contains an estimated black and white cost per page for the individual printer or group. Analysis Reporting uses this estimated cost when you create estimated cost reports.
- **Est. Cost Per Color Page** - This column contains an estimated color cost per page for the individual printer or group. Analysis Reporting uses this estimated cost when you create estimated cost reports.
- **Connection** - How the printer is connected to the computer/network.
- **Model** – The model name of the printer.
- **Color** - Whether or not the printer supports color printing.
- **Duplex** - Whether or not the printer supports duplex printing.



- **Company** - The name of the merged company that owns this printer. Only displays if you have merged data in your database

Using the User Grouping and Filtering Tab

This tab shows all users in the database. You use this tab to decide whether or not users or groups of users are included in reports.

To view the contents of a user group:

1. Click the "plus/minus sign" at the left of the group name to expand/collapse the group. When expanded you can see all of the unique users included in the group.

To group users:

1. Expand the **<INDIVIDUAL>** group or another group you have created to view the contents.
2. Click on one or more users to select them. You can use CTRL-click to select multiple individual users or use SHIFT-click to select a range of users. You can select users from more than one group at once.
3. Click the **Create/Add to Group** button on the tool bar. The **Create/Add to Group** window appears.
4. Select the option to either create a new group or move the selected users to an existing group.
5. Enter your new group name or select the existing group.
6. Click the **OK** button. This moves the selected users to the group you specified.

To include/exclude users and groups from reports:

1. Expand the **<INDIVIDUAL>** group or another group you have created to view the contents.
2. Select the users or groups of users you want to include/exclude.
3. Click on the **Include** column or hit the SPACEBAR key to toggle the selection.



User Grouping and Filtering Tab Columns

- **Include** – This column indicates whether or not you want to include the user or user group in any reports.
- **Name** – This column contains the name of the user or user group.
- **Domain** – This column contains the name of the domain the user belongs to.

Saving and Loading Groups

Once you have setup your groups for your printers and users you can choose to save them to a file so you can share them with others and to make sure you do not have to recreate them all again. You can also setup several different grouping schemes and load in whatever one you need for any given situation.

To save your grouping information:

1. Click the **Save Groups** button. A dialog appears asking you for the file name and path.
2. Use the dialog to choose where you want to save the group information file and choose a name.
3. Click the **Save** button on the dialog to save the groups.

To load your grouping information:

1. Click the **Open Groups** button. A dialog appears asking you for the location of the grouping file you want to load.
2. Use the dialog to find the grouping file you want to load.
3. Click the **Open** button on the dialog to load the groups into memory.

NOTE: Analysis Reporting automatically saves the groups you were working with in the Analysis tool when you close it down. It saves them in a file called "lastused.grp" in your My Documents directory.



Reports

Creating and Removing Reports

The Analysis Reporting tool comes with several different reports for both user and printer reporting which help you to analyze the large amounts of data that Print Audit collects. Each report when it displays has an information cover page. This page is there to remind you of what you chose when you created the report. You can disable this feature at any time.

To create a report:

1. Create any groups you want for printers and users. In normal mode, make sure to include only those groups you want on the report.
2. Click the **Create Report** button on the toolbar. The **Create or Open a Print Audit 6 Report** window appears.
3. Click on the Create a New Report button, or click on a previously saved report.
4. Click the **Ok** button. If you selected a previously saved report, the report displays in a new tab. If you chose to create a new report, the **Create a Report Wizard** appears. The rest of these steps assume you selected to create a new report.
5. Click on the type of the report you want in the reports list. The report highlights and a brief description of the report displays on the right.
6. If running in simple mode, click the **Next** button to select a reporting group for printers and users.
7. Click the **Next** button to select your parameters. The Parameters tab appears.
8. Enter in the report parameters. There are several standard parameters, some reports have custom parameters.
9. Click the **Next** button to enter your report titles. The Titles tab appears.
10. Enter in any title and sub-title you want displayed on the report.
11. Click the **Build** button. The wizard closes and the new report displays in a tab in the main reporting window.

To create and save a report:

1. You can save reports that you build so you can use the same report again and again.
2. Follow steps 1-9 above.



3. Click the **Build and Save** button. A window appears asking you for a name and description you want to give to the report.
4. Enter in the name and description for the report.
5. Click the **Save** button. The window closes and your report appears in a tab in the main reporting window. It is also available to select the next time you create a report.

To remove a report:

1. Click the tab of the report you want to remove from the display.
2. Click the **Remove Report** button on the toolbar. A message box asks you if you are sure you want to remove the report.
3. Click the **Yes** button. Print Audit removes the report.

To enable/disable information cover page:

1. Click the **Reports->Create Cover Page** menu item. If checked, the cover page is printed, if not the cover page is not printed.

Creating Composite Reports

Print Audit allows you to create Composite reports. These are reports that contain several other individual reports along with a title page and table of contents. You can build and save composite reports to quickly generate any combination of reports that meet your business needs. For example you may want to generate Executive Summary, Printer Volumes and User Volumes report for month end reporting. Using Composite reports you can build this once and generate all three reports with one click of the mouse.

To create a Composite report:

1. Create any groups you want for printers and users. Make sure to include only those groups you want on the report.
2. Click the **Create Report** button on the toolbar. The **Create or Open a Single or Composite Report** window appears.
3. Click on the **Create a New Composite Report** button, or click on a previously saved report.
4. Click the **Ok** button. If you selected a previously saved report, the report displays in a new tab. If you chose to create a new report, the **Create a Composite Report Wizard** appears. The rest of these steps assume you selected to create a new report.



5. Enter the general **Report information** on the Report Information tab. This includes the title you want for the report, who prepared it, the date range, etc.
6. Click the **Next** button to go to the **Select Reports** tab.
7. Select the reports you want in the Composite report on the **Select Reports** tab. Print Audit sets a default list of some of the more popular reports. You can add and remove reports to meet your needs. The order that reports appear in the Selected list is the order they will appear in the finished report.
8. If in simple mode, click the **Next** button to go to the **Groups** tab. Select the groups you want to use for the report.
9. Click the **Next** button to go to the **Options** tab.
10. Select the overall report options. These options apply to every individual report within the Composite report.
11. Click the **Build** button. The wizard closes and the new report displays in a tab in the main reporting window.

To create and save a Composite report:

1. You can save Composite reports that you build so you can use the same report again and again.
2. Follow steps 1-10 above.
3. Click the **Build and Save** button. A window appears asking you for a name and description you want to give to the report.
4. Enter in the name and description for the report.
5. Click the **Save** button. The window closes and your report appears in a tab in the main reporting window. It is also available to select the next time you create a report.

To remove a report:

1. Click the tab of the report you want to remove from the display.
2. Click the **Remove Report** button on the toolbar. A message box asks you if you are sure you want to remove the report.
3. Click the **Yes** button. Print Audit removes the report.

To enable/disable information cover page:

1. Click the **Reports->Create Cover Page** menu item. If checked, the cover page is printed, if not the cover page is not printed. This setting affects all reports in the Composite report.



Report Parameters

When you create a report there are several standard options you can select. They are as follows:

Normal Mode Only

- **Filter report data** - If checked Analysis Reporting includes only those groups and individuals that you selected on the grouping tabs. If unchecked Analysis Reporting includes all groups and individuals regardless of your selection.
- **Group report data** - If checked Analysis Reporting uses the groups you selected on the grouping tabs to display information. If unchecked Analysis Reporting does not use the groups and reports each user and printer individually.
- **Use Est. Costs** - Use the estimated costs instead of actual costs on the report. If checked Analysis Reporting uses the estimated cost per page on the Printer Grouping and Filtering tab to calculate costs instead of the costs recorded in the database. If disabled then the selected support does not allow you to use estimated costs.

Both Simple and Normal Mode

- **Sorting** - You can choose to sort some reports in different orders. For example you can sort some reports by descending total page count. If disabled the report does not support custom sorting. NOTE: This parameter option is not available for Composite Reports.
- **Decimal places** - You can enter the number of decimal places to use in costs for the report. Defaults to the number of decimal places configured in the Administrator.

The **Parameters** section contains parameters that are specific to the report you selected. The most common parameter is the date range of the report. You can use the drop-down to select a standard date type or enter a complete custom date for the report.

Printing and Exporting Reports

Once you create the report you want you can choose to print it to your printer or export it to one of our supported formats.



To print a report:

1. Click on the tab of the report you want to print. If you have not created any reports, see Creating and Removing Reports.
2. Click the **Print Report** button on the toolbar. A dialog appears that allows you to select the printer.
3. Select the printer to which you want to print the report.
4. Click the **Print** button. The report will print to your printer.

To export a report:

1. Click on the tab of the report you want to export. If you have not created any reports, see Creating and Removing Reports.
2. Click the **Export Report** button on the toolbar. A dialog appears that allows you to select the export format and the path for the exported file.
3. Use the **Save as type** drop down box to select the type.
4. Use the dialog to select the directory where you want to export the file, and type the name.
5. Click the **Save** button. The analysis tool creates the report in the format you chose.

Scheduling and Emailing Reports

Using Analysis Reporting you can schedule report creation and automatically email a PDF of the report to one or more recipients. **IMPORTANT:** Before Print Audit can email a report, you must properly configure the email settings in the Global Settings section of the Administration tool.

To schedule a report:

1. Create a new or run an previously saved report.
2. Click the **Schedule Report** button on the toolbar. The **Schedule a Report Window** appears.
3. Set how often you want the report to run, and set who you want to email the report to.
4. Click the **Schedule** button. Analysis Reporting creates an entry in the Windows Task Scheduler for the report.



To edit scheduled reports:

1. Click the **View Scheduled Reports** button on the toolbar. The **Scheduled Reports Window** appears.
2. A list of all scheduled reports displays, giving scheduling information and the last time the report was successfully run.
3. Click on the report you want to edit in the list, and click the Edit button. The **Schedule a Report Window** appears.
4. Make your changes, and click the Schedule button. The **Schedule a Report Window** closes.
5. Click the Close button on the **Scheduled Reports Window**.

To delete scheduled reports:

1. Click the **View Scheduled Reports** button on the toolbar. The **Scheduled Reports Window** appears.
2. A list of all scheduled reports displays, giving scheduling information and the last time the report was successfully run.
3. Click on the report you want to delete in the list, and click the **Delete** button. A message appears asking you to confirm that you want to delete the scheduled report. NOTE: Deleting a scheduled report only deletes the scheduling, it does not delete a saved report definition.
4. Click the **Yes** button to delete the scheduled report.
5. Click the **Close** button on the **Scheduled Reports Window**.

Report Export Formats


Analysis Reporting supports several different formats to which you can export your reports. They are as follows:

- **Text File** – This exports the report to a flat text file. Columns are tab-delimited which can be imported into Excel.
- **HTML Page** – This exports the report to an HTML (web page) format you can then put on a website.
- **PDF File** – This exports the report to an Adobe PDF file format to send to others.



- **Raw Data** – This exports the underlying data of the report to a comma-delimited file. NOTE: The information exported may not correspond exactly to what you see in the report. For example, some totals and other calculations may not be in the data. This is due to the fact that some sub totaling and translation take place in the reporting engine.

Print Audit 6 Job Manager



Welcome

Welcome to the Print Audit 6 Job Manager. You use this tool to manage your detailed print job information.

You can search for jobs using several different pieces of search criteria. Once you find the jobs you want you can edit the jobs, build reports based on the job details and export the job information.

You can also use the Job Manager to schedule exports of your job information to a file format that your accounting program can read.



Click on the links below for more information on how to use the Job Manager:

- Searching for jobs
- Changing how you view the data
- Editing and deleting your jobs
- Creating, printing and exporting reports
- Scheduling and Emailing Reports
- Exporting jobs
- Exporting jobs for Accounting

For advanced users:

- Using the Job Manager with merged jobs
- Securing the Job Manager

Finding, Viewing and Editing Jobs

Searching for Print Jobs

One of the first steps in using the Job Manager is to find the job or jobs you want to act on. Print Audit allows you to search for jobs based on a combination of criteria.

We highly recommend that you narrow your search as much as possible. Print Audit can track thousands of print jobs per day depending on the printing volumes in your organization.

You can search for jobs based on the following:

- **Date Printed** - You can specify the date range in which the jobs you want were printed. You can select from one of the standard date ranges, or select **Custom** from the drop-down to enter your own custom date. Print Audit always uses a date range for the search.
- **User who printed** - Use the drop down to select the user you want to search on. You can also type the first few characters of the user name to have Print Audit find all matching users. Click the **Match on Reporting group** option to have Print Audit match on a reporting group you select rather than a user name. Click here for more information on reporting groups. If you leave this blank, Print Audit finds jobs for all users. Please note that you can only select users if you have access to view all print job data.



- **Printer used** - Use the drop down to select the printer you want to search on. You can also type the first few characters of the printer name to have Print Audit find all matching printers. Click the **Match on Reporting group** option to have Print Audit match on a reporting group you select rather than a printer name. Click here for more information on reporting groups. If you leave this blank, Print Audit finds jobs for all printers.
- **Custom Fields (Recovery only)** - If you have defined custom fields to display on the Client Popup window, then you can search on specific custom field values for each custom field you defined.

To search for print jobs:

1. Enter your criteria as described above.
2. Click the **Find Jobs** button on the toolbar. A list of all matching jobs displays in a list below the search criteria.

Once you have a list of jobs, you can do several things. Click the links below for more information:

- Create reports
- Edit jobs
- Export jobs

Changing Your Data View

The Print Audit Job Manager allows you to configure the way you view the columns of information in the job results lists. You can show and hide individual columns, re-arrange the columns and sort on the column information.

Once you get the columns arranged to suit your needs, you can save the configuration and give it a name. You can create multiple configurations this way and easily switch between them.

Please note that you must have searched for and found jobs before you can adjust a view.



To show and hide columns:

1. Right-click on any column header. The **Columns in View** window appears.
2. Check the box to the left of a column name to display the column, or clear the check box to hide the column.
3. Click the **OK** button once you have the arrangement you want. The **Columns in View** window closes and the list updates.

To re-size a column:

1. Move the mouse cursor until it is on the right-hand edge of the column header for the column you want to resize. The cursor changes to resize mode.
2. Click and hold the left mouse button and drag the column edge to the left to make the column smaller or to the right to make it larger.
3. Release the mouse button once column is the size you want. The column resizes to the new size.

To re-size all columns to fit:

1. Click the **Edit->Size Columns To Fit** menu item. Print Audit resizes all displayed columns to fit the data displayed in the columns. Please note that this can take several seconds depending on the number of jobs in the list.

To move a column:

1. Click and hold the left mouse button on the column header of the column you want to move.
2. Move the mouse right to move the column to the right, left to move the column to the left. You should see an outline showing you where the column will end up.
3. Release the mouse button once the column is in the position you want. The column moves to the new position.

To sort on a column:

1. Click on the column header of the column you want to sort. An arrow appears in the column header indicating the sort order. Click again to change the sort order.



To save your data view:

1. Click the **Save Data View** button on the toolbar. A dialog appears asking you to enter the name of the new view.
2. Enter the name you want to call the view.
3. Click the **OK** button on the dialog. The dialog closes and the new view appears in the **Views** drop down in the toolbar. Please note that if you enter the same name as an already existing view Print Audit overwrites the old view.

To select a previously saved data view:

1. Click on the **Views** drop down in the toolbar. A list of all previously saved views appears.
2. Click on the view you want. The results view changes to the new view.

To delete a previously saved data view:

1. Select the data view you want to delete as described in the previous section.
2. Click the **Delete View** button on the toolbar. Print Audit deletes the view and switches to the default view.

Editing and Deleting Jobs

You can use Print Audit 6 to edit existing print jobs. Once you print a job you may want to adjust the job costs, view the detailed job information or delete the jobs.

You can control who has permission to edit and delete jobs.

To edit/view a print job:

1. Search for the job you want to edit.
2. Double-click on the job you want to edit. The **Print Job Window** appears.
3. Make changes to the job if appropriate. Please note that not all fields are editable.
4. Click the **Save** button to exit and save any changes or click the **Cancel** button to close the window.



To delete individual print jobs:

1. Search for the job you want to delete.
2. Click on the job you want to delete. The job highlights.
3. Click the **Delete Current Job** on the toolbar to delete the highlighted job. A dialog appears asking if you are sure you want to delete the job.
4. Click **Yes** to delete the job from the database. The list refreshes to show the results.

To delete an entire list of jobs:

1. Search for the jobs you want to delete.
2. Click the **Edit->Delete All Jobs in List** menu item. A dialog appears asking you to confirm that you want to delete all the jobs in the list.
3. Click **Yes** to delete all the jobs in the list.

Job Reporting

Job Manager Reports

The Print Audit 6 Job Manager allows you to quickly build custom reports based on the jobs in your database. Once you design a report you like you can save the report definition so you can easily create it again. You can also schedule and email your reports to other users.

You can only create reports that deal with the specifics of your print job information. For reports designed for in-depth analysis of your printing information you can use the Print Audit Analysis Reporting tool.

You can use the Job Manager to create three types of reports:

- **Summary Report** - This report allows you to report on total job costs and volumes, including grand totals.
- **Full Report** - This report allows you to report detailed information along with a breakdown of total job costs and volumes, including grand totals.
- **Detail Report** - This report allows you to report detailed print job information in a sorted format but with no totaling.

Once you create the report you want it displays in its own tab in the Job Manager window. You can then print it to a printer or export it to PDF or HTML formats.



After you are done viewing, printing or exporting your report you can click on the **Remove Report** button on the toolbar to close it.

Click the links below for step-by-step instructions on building, printing and exporting reports:

- Creating a Report
- Printing and Exporting Reports
- Scheduling and Emailing Reports
- How to Create a Billing Statement

Creating Reports

Please follow the steps below to quickly create reports based on your print jobs.

To create a Summary report:

1. Search for the jobs you want to include on the report.
2. Click the **Create a new Report** button on the toolbar. **The Build a Report** wizard appears.
3. Click on **Summary (Totals Only)** in the reports list on the left. A description of the report appears on the right.
4. Verify that the number of decimal places you want for the report is correct.
5. Click the **Next** button. The wizard changes to the **Total By** tab.
6. Select the columns to total on. You can select up to three columns to total on. For example, you could select User, Printer and Color to get totals for each user broken down by printer and color.
7. Click the **Next** button. The wizard changes to the **Totals and Breaks** tab.
8. Select the unit type you want to display for the unit totals.
9. Check the **Show job cost totals** to display cost totals on the report, broken down by your **Total By** selection.
10. Check the **Show job count totals** to display the total number of jobs on the report, broken down by your **Total By** selection.
11. Check the **Subtotal** and **Page break** check boxes to set or clear subtotaling and page breaks by level.
12. Click the **Next** button. The wizard changes to the **Titles** tab.
13. Enter in an optional title and sub-title you want displayed at the top of each page in the report. If you want to display the From and To date used in the title when the report prints, you can enter the %from and %to



placeholders in the title. For example: "My report with data from %from to %to".

14. Click the **Build** button to build and display the report. If you want to keep this report definition to re-run later, you can click **Save and Build** to enter a name and description for your new report definition. If you save a report definition it displays in the list of available reports the next time you run the **Build a Report** wizard.

To create a Full report:

1. Search for the jobs you want to include on the report.
2. Click the **Create a new Report** button on the toolbar. The **Build a Report** wizard appears.
3. Click on **Full (Details and Totals)** in the reports list on the left. A description of the report appears on the right.
4. Verify that the number of decimal places you want for the report is correct.
5. Click the **Next** button. The wizard changes to the **Fields** tab.
6. Select up to five fields to display in the report. These fields appear as columns on the finished report.
7. Click the **Next** button. The wizard changes to the **Total By** tab.
8. Select the columns to total on. You can select up to three column to total on. For example, you could select User, Printer and Color to get totals for each user broken down by printer and color.
9. Click the **Next** button. The wizard changes to the **Totals and Breaks** tab.
10. Select the unit type you want to display for the unit totals.
11. Check the **Show job cost totals** to display cost totals on the report, broken down by your **Total By** selection.
12. Check the **Show job count totals** to display the total number of jobs on the report, broken down by your **Total By** selection.
13. Check the **Subtotal** and **Page break** check boxes to set or clear subtotalling and page breaks by level.
14. Click the **Next** button. The wizard changes to the **Titles** tab.
15. Enter in an optional title and sub-title you want displayed at the top of each page in the report. If you want to display the From and To date used in the title when the report prints, you can enter the %from and %to placeholders in the title. For example: "My report with data from %from to %to".
16. Click the **Build** button to build and display the report. If you want to keep this report definition to re-run later, you can click **Save and Build** to enter a name and description for your new report definition. If you save a report definition it displays in the list of available reports the next time you run the **Build a Report** wizard.



To create a Details Only report:

1. Search for the jobs you want to include on the report.
2. Click the **Create a new Report** button on the toolbar. The **Build a Report** wizard appears.
3. Click on **Details Only** in the reports list on the left. A description of the report appears on the right.
4. Verify that the number of decimal places you want for the report is correct.
5. Click the **Next** button. The wizard changes to the **Fields** tab.
6. Select up to five fields to display in the report. These fields appear as columns on the finished report.
7. Click the **Next** button. The wizard changes to the **Sort By** tab.
8. Select the columns to sort. You can select up to three column to sort by. Please note that you must have selected these columns on the **Fields** tab.
9. Click the **Next** button. The wizard changes to the **Titles** tab.
10. Enter in an optional title and sub-title you want displayed at the top of each page in the report. If you want to display the From and To date used in the title when the report prints, you can enter the %from and %to placeholders in the title. For example: "My report with data from %from to %to".
11. Click the **Build** button to build and display the report. If you want to keep this report definition to re-run later, you can click **Save and Build** to enter a name and description for your new report definition. If you save a report definition it displays in the list of available reports the next time you run the **Build a Report** wizard.

Printing and Exporting Reports

Once you create a report you can either print the report or export it to a different file format. Please follow the steps below to print and export your reports.

To print a report:

1. Create the report you want. If already created, click on the tab containing the report you want to print.
2. Click the **Print Report** button on the toolbar. A dialog appears asking you to select your printer.
3. Select the printer and click the **Print** button. The dialog closes and Print Audit sends your report to the printer.



To export a report:

1. Create the report you want. If already created, click on the tab containing the report you want to print.
2. Click the **Export Report** button on the toolbar. A dialog appears asking you to select the export type and the file name.
3. Use the **Save as type** drop down box on the dialog to select the export type. You can select from PDF and HTML formats.
4. Click the **Save** button. Print Audit saves the report to the file you specified.

Scheduling and Emailing Reports

Using the Job Manager you can schedule report creation and automatically email a PDF of the report to one or more recipients. **IMPORTANT:** Before Print Audit can email a report, you must properly configure the email settings in the Global Settings section of the Administration tool.

To schedule a report:

1. Create a new or run a previously saved report. **NOTE:** You cannot schedule reports based on the "All" date range. You must choose a different option.
2. Click the **Schedule Report** button on the toolbar. The **Schedule a Report Window** appears.
3. Set how often you want the report to run, and set who you want to email the report to.
4. Click the **Schedule** button. Analysis Reporting creates an entry in the Windows Task Scheduler for the report.

To edit scheduled reports:

1. Click the **View Scheduled Reports** button on the toolbar. The **Scheduled Reports Window** appears.
2. A list of all scheduled reports displays, giving scheduling information and the last time the report was successfully run.
3. Click on the report you want to edit in the list, and click the Edit button. The **Schedule a Report Window** appears.
4. Make your changes, and click the Schedule button. The **Schedule a Report Window** closes.
5. Click the Close button on the **Scheduled Reports Window**.



To delete scheduled reports:

1. Click the **View Scheduled Reports** button on the toolbar. The **Scheduled Reports Window** appears.
2. A list of all scheduled reports displays, giving scheduling information and the last time the report was successfully run.
3. Click on the report you want to delete in the list, and click the **Delete** button. A message appears asking you to confirm that you want to delete the scheduled report. NOTE: Deleting a scheduled report only deletes the scheduling, it does not delete a saved report definition.
4. Click the **Yes** button to delete the scheduled report.
5. Click the **Close** button on the **Scheduled Reports Window**.

How to Create a Billing Statement

To create a billing statement style report in the Job Manager you first need to search for the jobs you want to bill for, and then generate the report. This example leads you through creating a detailed billing statement for the previous month. The example also assumes that you have a custom field called "Client" that contains codes used that correspond to the client you are billing. See detailed steps below.

1. Open the Print Audit 6 Job Manager.
2. Use the **Date Printed** drop-down box to select a date range for the jobs you want to bill for. For this example select "Last Month" from the drop-down.
3. You can choose to narrow down the report to one specific "Client" or all clients in the database. If you want to narrow down the client select the appropriate one from the **Client drop-down**. Please remember that we are assuming you have a "Client" custom field defined for this example, you can choose to narrow down the search based on any custom field you define.
4. Click the **Find Jobs** button on the toolbar. A list of jobs that match your search criteria appear.
5. Click on the **Create Report** button on the toolbar. The Build a Report wizard appears.
6. Select the level of detail you want in the report. Since we want to produce a detailed billing statement, click the "Full (Details and Totals)" option.
7. Click the **Next** button. The wizard moves to the **Fields** tab.
8. Double-click the fields in the left hand list you want to include on the report. They move to the right hand side. For this example include **Document name, Date Printed, Total Units and Total Cost**.



9. Click the **Next** button. The wizard moves to the **Total By** tab.
10. Use the **1st choice**, **2nd choice** and **3rd choice** drop down boxes to select fields you want to total on. For this example select your "Client" custom field for the first choice and "Color" for your second choice. Leave the third choice blank. This will calculate totals on the report for each client and further break it down by color vs black and white jobs.
11. Click the **Next** button. The wizard moves to the **Totals and Breaks** tab.
12. Use the **Unit Totals** drop down to select "Pages". This will show all totals in pages.
13. Check the **Show job cost totals** box to display a sub-total of job costs for each client.
14. Click the **Next** button. The wizard moves to the **Titles** tab.
15. Enter in an appropriate title and sub-title. For this example a title of "Monthly Billing Statement" may be appropriate.
16. Click the **Build** or the **Build and Save** button. Both will build the report, but **Build and Save** also saves this report definition so that you can re-run the exact report any time you want. Once Print Audit builds the report it appears in a tab in the main Job Manager window.
17. Use the **Print Report** button on the toolbar to print your new report or **Export Report** button to save the report in different formats.

Job Exporting

Exporting Jobs

The Job Manager allows you to export your print jobs to several different formats. You can then use this file in third-party accounting or reporting tools to give you even more job processing options. For example, you could export your jobs to a standard comma-delimited format to allow you to open the jobs in Microsoft Excel for detailed analysis.

When you export jobs you generally need to select an export type and an export configuration. The export type determines how Print Audit will export the jobs. For example, the **Flat File** export type exports your information to a standard text file.

The export configuration determines the format and options of the export type. For example you could create a **Flat File** export that only exports five columns of data in a tab-delimited format.

You can export jobs in one of three ways. Click on the links below for more information:



- Export Current Results - This allows you to choose the export type and configuration you want to use to export all jobs in your current results list.
- Export Current View - This allows you to quickly export all jobs in your current results list to a comma-delimited file that mirrors how you have constructed your current data view.
- Run Accounting - This allows you to choose the export type and configuration you want to use to export all jobs in your database if they have not already been exported for accounting. This export type does not take into account any of your job search criteria.

Print Audit currently supports only **Flat File** exports.

Accounting

Job Type Account Codes

Print Audit 6 allows you to define custom account codes for different job/transaction types. For example you could assign a different accounting code to Print jobs versus Copy jobs.

You can then choose to export these account codes with your other job information to make integration into your accounting data easier.

To setup transaction codes:

1. Click the **Accounting->Edit Job Type Account Codes** menu item. The **Edit Job Type Account Codes window** appears.
2. Click in the Code column for the job type you want to change.
3. Type the new account code in the column.
4. Repeat 2-3 to change codes for all the transaction types.
5. Click the **Save** button. The **Edit Job Type Account Codes** window closes.

Running Accounting Exports

This export type allows you to export any non-accounted jobs to an export type you specify.



To export for accounting:

1. Click the **Accounting->Run Accounting** menu item. The **Export Jobs** window appears.
2. Select the type of export you want to do from the **Export type** drop down box. Currently your options may only include a Flat File Export. New types of exports may be available in the future.
3. Select the configuration you want from the **Configuration** drop down. If you have not defined a custom configuration you only have the **<Default>** configuration.
4. Click the **Export** button to export your information. Depending on your export configuration you may have to select a file name or enter other information. Once done Print Audit exports your jobs for accounting.

You can also have Print Audit run an export on a scheduled basis. You may also need to re-do accounting runs.

Clearing Accounting Runs

In some cases you may need to clear previous accounting runs. For example a file could get lost, or some error could occur with your accounting system that requires you to re-export jobs for accounting. The Job Manager allows you to clear any accounting run.

To clear an accounting run:

1. Click the **Accounting->Accounting Runs** menu item. The **Clear Accounting Runs** window appears.
2. Click on the accounting run you want to clear in the list.
3. Click the **Clear** button. A dialog displays asking you if you are sure you want to clear the run.
4. Click the **Yes** button. Print Audit marks all the jobs in the run as ready to export. The next time you run accounting all jobs that were in the cleared run will export.



Scheduling Accounting Exports

Using the Job Manager you can schedule accounting exports to run daily, weekly or monthly. You can use this functionality to automate the importing of your print job information into an accounting system. Print Audit integrates with the Microsoft Windows Task Scheduler. Advanced users can use the task scheduler directly to further customize how the export runs.

IMPORTANT: Before you can schedule an accounting run you must create a Print Audit user with rights to run accounting and assign them a PIN code..

To schedule an accounting export:

1. Click the **Accounting->Run Accounting** menu item. The **Export Jobs** window appears.
2. Select the type of export you want to do from the **Export type** drop down box. Currently your options may only include a Flat File Export. New types of exports may be available in the future.
3. Select the configuration you want from the **Configuration** drop down. If you have not defined a custom configuration you only have the **<Default>** configuration.
4. Use the **Run Export** drop down to select how often to run the export. Choices are Daily, Weekly or Monthly.
5. Use the **On** drop down to select the day on which to run the export. This is only effective for Weekly or Monthly schedules.
6. Use the **At** selector to select the time of day at which to run the export. We recommend using a time outside of regular business hours.
7. Click the **Schedule** button. The **Accounting Run PIN Code** window appears.
8. Enter the Print Audit PIN code of someone authorized to export all job information.
9. Click the **OK** button. If the PIN code is valid Print Audit stores the settings you entered and creates the task.

To un-schedule an accounting export:

1. Click the **Accounting->Run Accounting** menu item. The **Export Jobs** window appears.
2. Select the type of export you want to do from the **Export type** drop down box. Currently your options may only include a Flat File Export. New types of exports may be available in the future.



3. Select the configuration you want to remove from the **Configuration** drop down.
4. Click the **Unschedule** button to remove the task.

You can also use the Windows Task Scheduler interface directly to remove scheduled runs.

Advanced

Job Manager and Merged Jobs

You can use the Job Manager to view jobs from a merged Print Audit database. Print Audit 6 allows you to merge jobs from multiple companies into one database. For more information on how to merge jobs, please see the documentation on the Print Audit Job Merge Wizard.

If you have jobs from multiple companies in the database you can choose to view any one of the company's data or view all companies at once.

To change the company:

1. Click the **Company** drop down in the toolbar. A list of all available companies appears.
2. Select the company you want to view. The Job Manager clears any existing job results and any reports.
3. Search for the jobs you want for the new selection.

NOTE: When exporting for accounting, Print Audit exports jobs from ALL companies regardless of any company selection in the Job Manager.

Securing the Job Manager

Print Audit allows you to define several different levels of security for the Job Manager. You can also choose to have users enter a PIN code or their network login information before they can use the Job Manager.

Before you can schedule accounting exports you must enter the PIN code of a user who has the rights to run accounting. Print Audit needs this to ensure that your job information is secure as possible. You can choose to enter a PIN code of an existing user or use the Administration tool to create a new user that has run accounting rights.




All security settings in Print Audit are controlled through the Print Audit 5 Administration tool. Please see the topics on Security Profiles and Authentication in the Administration help for more information on security.

Here is a list of the policies you can set in the Security Profile that affect the Job Manager:

- **User can view their own print job data** - A user with this policy can view, export and print only their print job information.
- **User can view all print job data** - A user with this policy can view, export and print all print job information.
- **User can edit existing print jobs** - A user with this policy can edit jobs in the Job Manager.
- **User can run accounting** - A user with this policy can run and clear accounting exports.

If a user does not have any of these policies in their security profile then they cannot use the Print Audit Job Manager.

Print Audit 6 Job Merge Wizard





Welcome

Welcome to the Print Audit 6 Job Merge Wizard. You can use the Job Merge Wizard to merge data from multiple databases into one database. You can report on this data by individual sites that you have merged, or on a global basis.

Job merging is a two step process. First you use the Job Merge Wizard to export the jobs from one database to a file on your computer. Then you can use the Job Merge Wizard to import that file into another database.

This capability is useful for deployments to large organizations with multiple sites. You can export job data from satellite sites, and imported it into a centralized database. This makes centralized reporting possible. The Job Merge Wizard is not meant as a database backup tool, or as a tool to copy databases.

Print Audit supports this database merging through the use of "companies". Each database starts with one and only one "company", the one that corresponds to your organization. As you merge separate sites in you need to assign each to a separate company. This way you can easily keep track of which information came from where, and you do not impact your own data.

Please click the links below for more information on using the Job Merge Wizard:

- General usage
- Before you Begin
- Importing job data
- Scheduling job imports
- Exporting job data
- Scheduling job exports

Requirements

To use the Job Merge Wizard the user must have Print Audit Administration rights. There are additional requirements to setup scheduled imports and scheduled exports:

1. The Windows Scheduling Service must be running. This service is included as part of Windows98 and newer operating systems.
2. You must have administrative privileges on the computer where the Wizard is being run.



3. Before you can schedule job exporting and importing you must create a Print Audit user with Print Audit Administrator rights and assign them a PIN code. You are asked for this PIN code during the final step of the wizard.

Before You Begin

Merge Codes

Print Audit uses *merge codes* to allow you to import data from a large number of databases. The merge codes uniquely identify jobs and custom field values so you can keep track of where the merged data came from. You should decide on your merge codes before using the tool for the first time.

When exporting data from your database you need to enter an export merge code. You can choose any code you find easy to remember. You enter this code as the "Job Merge Code" when exporting data or setting up a scheduled export.

When importing the data (or setting up scheduled imports) you need to create a company that has the same merge code that was used when the data was exported. All the data imported with this merge code will be entered in the database under this company.

When exporting and importing custom field values you can specify a merge code for each field. The merge codes on the import side must match merge codes on the export side for everything to import correctly.

For example:

Suppose you have two offices using Print Audit. Your office is the "head" office. The other office is a "branch" office. You do not want to import custom fields. If you want to merge the branch office data into Print Audit you would need to do the following steps:

1. Choose a merge code for your branch office data. For this example use "branch001".
2. At the branch office, export the data using the Job Merge Wizard. Make sure to use the "branch001" code as the merge code.
3. Send the job file created in step 2 to the head office. You can send the file via email, ftp, WAN or any other way that makes sense for your organization.



4. At the head office, import the data using the Job Merge Wizard. Make sure you create a company with the "branch001" code on the **Merge Codes** tab of the import.
5. Import the data. All of the branch office data is now in the same database as the head office. You can use the Print Audit Job Manager and other tools to view and report on the data.

Performance

We recommend using SQL Server if importing jobs into your database. SQL Server can handle much larger volumes of data than Microsoft Access and can do so much more efficiently.

You can export from Microsoft Access and SQL Server, but if dealing with large volumes of data we highly recommend SQL Server.

If you do not have SQL Server in your organization you can also use Microsoft's SQL Express. Please go to Microsoft's website for more information on SQL Express.

General Usage

The Job Merge Wizard user interface guides you through the process of importing or exporting Print Audit 6 job data. At the top of the window for each step in the wizard is a help note. This note gives you a brief description of the information you need to provide.

Immediately below the help reminder is a list of tabs. This list grows as you use the wizard and contains all the steps that you have already completed along with the current and next steps. At any time you can click on a tab to view its contents and change any of the information. Some changes can cause the list of tabs to change.

Each tab contains information you need to complete before you can proceed to the next step.

Along the bottom of window are four buttons. The back and next buttons move you to the previous and next step in the process, respectively. Once you complete the final step, you use the Finish button to complete the Wizard. At any time, you can click the Cancel button to exit the Wizard without completing it. If cancelled, no data is imported or exported.



Importing

Importing Job Data

To import data, the Wizard guides you through the following 5 steps.

Step 1: Start

Select **Import Jobs Now** and click Next. The wizard moves to the Database tab.

Step 2: Import Into Database

Review the currently selected database. Print Audit imports the jobs into this database. If you want to import data into a different database, click Change Database. Once you are satisfied with your database selection, click Next. The wizard moves to the Import Settings tab.

Step 3: Job Import Settings

Choose **Import Jobs Only** to ignore any custom field values in the import file, or click **Import Jobs and Custom Fields** to import custom field information along with the job information. NOTE: For the custom fields to import correctly the merge codes for the custom fields in the import file **MUST MATCH** the merge codes for your custom fields.

Choose Duplicate records overwrite existing records to overwrite a job in your database if it exists in both the file and the database. **Choose Duplicate records are ignored** if you want to ignore jobs that exist in both the file and the database.

Enter a company name to use for non-imported print jobs. This can simply be your company name, or something like "Head Office". This allows you to easily distinguish between imported jobs and those jobs Print Audit tracked directly to the database. In Step 4 you will set up company names for the data you are importing.

Once you have decided and made the appropriate selections, click Next. The wizard moves to the Merge Codes tab.



Step 4: Merge Codes

You use this tab to add or update the merge codes. The Job Wizard uses merge codes to properly match jobs with companies and to match custom fields.

At minimum you must set up a company and corresponding merge code. Double-click an empty row in the Companies grid, and enter in the name of the company and the merge code. The merge code you enter **MUST MATCH** the merge code used when the jobs you are importing were exported. The company name you enter displays when reporting on the data.

You can create as many companies as you need. Generally you need to create one company for each database you import data from. If you do regular imports of data from two other databases you need to set up two companies, each with a different merge code.

If you choose to import custom field values in the previous step you also need to set up merge codes for the custom fields at this time. Enter in merge codes for custom fields that you want to import data into. These merge codes must match merge codes specified for the custom fields when the data was exported.

Note that unlike job data, imported custom field data becomes a direct part of the database. New custom field values that were imported will show up as options for Print Audit Clients which report directly to this database.

Once you have provided the merge codes, click Next. The wizard moves to the Import From File tab.

Step 5: Import from File

Choose the file you wish to import data from. This file will normally have a .jbs extension. Choose the file and click Finish. Print Audit starts importing your data. Please note that this can take several minutes depending on the amount of data being imported.

Setting up Scheduled Imports

To set up scheduled imports, the wizard guides you through the following 5 steps. Please note that there are additional requirements to set scheduled imports and exports.



Step 1: Start

Select Setup Scheduled Import and click Next. The wizard moves to the Database tab.

Step 2: Import Into Database

Review the currently selected database. Print Audit imports the jobs into this database. If you want to import data into a different database, click Change Database. Once you are satisfied with your database selection, click Next. The wizard moves to the Import Settings tab.

Step 3: Job Import Settings

Choose **Import Jobs Only** to ignore any custom field values in the import file, or click **Import Jobs and Custom Fields** to import custom field information along with the job information. NOTE: For the custom fields to import correctly the merge codes for the custom fields in the import file **MUST MATCH** the merge codes for your custom fields.

Choose **Duplicate records overwrite existing records** to overwrite a job in your database if it exists in both the file and the database. Choose **Duplicate records are ignored** if you want to ignore jobs that exist in both the file and the database.

Enter a company name to use for non-imported print jobs. This can simply be your company name, or something like "Head Office". This allows you to easily distinguish between imported jobs and those jobs Print Audit tracked directly to the database. In Step 4 you will set up company names for the data you are importing.

Once you have decided and made the appropriate selections, click Next. The wizard moves to the Merge Codes tab.

Step 4: Merge Codes

You use this tab to add or update the merge codes. The Job Wizard uses merge codes to properly match jobs with companies and to match custom fields.

At minimum you must set up a company and corresponding merge code. Double-click an empty row in the Companies grid, and enter in the name of the company and the merge code. The merge code you enter **MUST MATCH** the merge code



used when the jobs you are importing were exported. The company name you enter displays when reporting on the data.

You can create as many companies as you need. Generally you need to create one company for each database you import data from. If you do regular imports of data from two other databases you need to set up two companies, each with a different merge code.

If you chose to import custom field values in the previous step you also need to set up merge codes for the custom fields at this time. Enter in merge codes for custom fields that you want to import data into. These merge codes must match merge codes specified for the custom fields when the data was exported.

Note that unlike job data, imported custom field data becomes a direct part of the database. New custom field values that were imported will show up as options for Print Audit Clients which report directly to this database.

Once you have provided the merge codes, click Next. The wizard moves to the Scheduling tab.

Step 5: Job Import Schedule

Set up either a daily, weekly, or monthly import schedule using the controls at the top of the tab. Enter a Print Audit PIN code that has Print Audit Administration privileges. Finally select the directory that contains the files to import.

Every time the schedule executes Print Audit imports all newly exported data files. Files already imported are ignored. The schedule simply controls how often Print Audit checks the directory.

When you are satisfied with your schedule, click the Finish button. At this time Print Audit confirms your PIN code and saves the schedule. If your PIN code is incorrect, you will be prompted to change it.



Exporting

Exporting Job Data

To export data, the Wizard guides you through the following 5 steps.

Step 1: Start

Select **Export Jobs Now** and click Next. The wizard moves to the Database tab.

Step 2: Export From Database

Review the currently selected database. The Wizard exports the jobs from this database. If you want to export data from a different database, click Change Database. Once you are satisfied with your database selection click Next. The wizard moves to the Export Settings tab.

Step 3: Job Export Settings

Click **Export Jobs Only** to export only job data from the database or click **Export Jobs and Custom Fields** to export job and custom field information.

Click **Export New Jobs** to export jobs printed since the last time you exported jobs or click **Export All Jobs in Database** to export all of the jobs.

Once you have made your choices, click Next. The wizard moves to the Merge codes tab.

Step 4: Merge Codes

You use this tab to add or update the merge codes. The Job Wizard uses merge codes to properly match jobs with companies and to match custom fields.

You must specify a merge code for the jobs you export. When these jobs are exported this merge code matches to one entered on the import side.

If you are including custom field values in your export, set up merge codes for the custom fields you wish to export. Double click on the Custom Field Merge Codes grid to the right of the custom field name to enter in a merge code.

If you leave the merge code for a field blank, it will not be exported.



Once you enter the merge codes click Next. The wizard moves to the Export tab.

Step 5: Export to File

Choose a location and name for the file you are going to export to. The file normally has a .jbs extension. Once you have chosen a file, click Finish, and the data will be exported.

Once Print Audit creates the exported file you can move it and copy it like any other file. You can e-mail it to someone, upload it to an FTP site, or copy it to another computer on your network.

Setting up Scheduled Exports

To set up scheduled imports, the wizard guides you through the following 5 steps. Please note that there are additional requirements to set scheduled imports and exports.

Step 1: Start

Select Setup Scheduled Exports and click Next. The wizard moves to the Database tab.

Step 2: Export From Database

Review the currently selected database. The Wizard exports the jobs from this database. If you want to export data from a different database, click Change Database. Once you are satisfied with your database selection click Next. The wizard moves to the Export Settings tab.

Step 3: Job Export Settings

Click **Export Jobs Only** to export only job data from the database or **click Export Jobs and Custom Fields** to export job and custom field information.

Click **Export New Jobs** to export jobs printed since the last time you exported jobs or click **Export All Jobs in Database** to export all of the jobs.

Once you have made your choices, click Next. The wizard moves to the Merge codes tab.



Step 4: Merge Codes

You use this tab to add or update the merge codes. The Job Wizard uses merge codes to properly match jobs with companies and to match custom fields.

You must specify a merge code for the jobs you export. When these jobs are exported this merge code matches to one entered on the import side.

If you are including custom field values in your export, set up merge codes for the custom fields you wish to export. Double click on the Custom Field Merge Codes grid to the right of the custom field name to enter in a merge code.

If you leave the merge code for a field blank, it will not be exported.

Once you enter the merge codes click Next. The wizard moves to the Export tab.

Step 5: Job Export Schedule


Set up either a daily, weekly, or monthly import schedule using the controls at the top of the tab. Enter a Print Audit PIN code that has Print Audit Administration privileges. Finally select the directory that contains the directory to export to.

Every time the schedule executes Print Audit exports the jobs to the directory you specify. The new job file name corresponds to the date and time Print Audit exported the data.

When you are satisfied with your schedule, click the Finish button. At this time Print Audit confirms your PIN code and saves the schedule. If your PIN code is incorrect, you will be prompted to change it



Print Audit 6 Database Maintenance Tool



Welcome

Welcome to the Print Audit 6 Database Maintenance Tool. This tool allows you to perform routine maintenance on your Print Audit database. It leads you through each task in an easy to use wizard style interface so you can quickly perform each task, even if you know nothing about databases.

The tool presents you with different options depending on whether you are using a Microsoft Access or Microsoft SQL Server database as a back-end. You chose which one you wanted to use when you installed Print Audit. The tool automatically detects which version you installed and displays the appropriate screens.

Thank you for using Print Audit.



Access Maintenance

Microsoft Access Overview

Microsoft Access is Print Audit's default database. Print Audit uses a database to store all configuration and print job information.

We highly recommend that you use this tool on a scheduled basis to compact your database. Regularly scheduled compacting of the database greatly reduces the risk of database corruption and other issues. It also decreases the size of your database and speeds up database operations.

The following is a list of the tasks you can accomplish using this tool against a Microsoft Access database.

- Compacting your Print Audit Database
- Changing the Read-Only Database Password

Compacting your Print Audit Database

Compacting your Print Audit database is critical to long-term trouble free operation of Print Audit. Print Audit uses Microsoft Access as its database by default. The benefits of using a Microsoft Access database are that it is free, easy to backup and easy to install. The downside is that it requires periodic maintenance to ensure trouble free operation, and it does not perform well in large environments. You perform this periodic maintenance through compacting.

Compacting does several technical things to your database, but the most important thing from your perspective is that it reduces the size of the database, increases the speed of data access and reduces the chance of database corruption.

Print Audit provides two methods of compacting the database. The first is to use the wizard screens to go through and compact. The second is to compact the database from a DOS command-line. The second method allows you to create a batch file that you can then schedule to automatically compact the database periodically.

To compact the database using the wizard:

1. Start the Print Audit Database Maintenance tool. The tool starts on the **Select Database Task** screen.
2. Click the **Compact your Database** option.



3. Click the **Next** button. The wizard moves to the **Select your Print Audit Database** screen.
4. Enter the Print Audit database you want to compact. The wizard detects what the current database is on this computer. If you want to pick a different database, either type the full path to the database in or select it using the browse button.
5. Click the **Next** button. The wizard moves to the **Ready to Compact** screen and gives you a chance to go back and change things before you compact.
6. Click the **Next** button. The wizard starts to compact your database. When finished, it moves to the **Finished** screen and you are done.

To compact the database from the command line:

1. Ensure that no one is running the Print Audit Administration or Job Manager programs. These “lock” the database. If locked you cannot compact. The Print Audit Client only locks the database if writing a print job so you should not need to shutdown every client.
2. Start an MS-DOS session.
3. Type the full path to the database maintenance tool, followed by a space, /c, another space and the full path to the database you want to compact. If you do not include the path to the database then Print Audit compacts the currently setup database.
4. Press the **Enter** key. Print Audit compacts the database.

For example, if you could type the following (X corresponds to the drive where you placed the database):

```
c:\program files\print audit inc\print audit 6\admin\pa6dbmnt.exe /c  
X:\printaudit.mdb
```

You can use this method of compacting within a batch file that you can schedule to run periodically from any number of scheduling tools.

Select the Database Task

This part of the wizard allows you to select which task you want to perform on your Print Audit database. The options are as follows:

Compact your database – Click this option to compact your Print Audit database. Compacting your database reduces size, increases speed and reduces the risk of corruption. Also choose this option if your database has become corrupted and Print Audit will attempt to repair it.



Change the read-only password – Click this option to change the password for the PAReADonly account. Every Print Audit database has this account with a default password of “password”. If you are concerned about security you should change this password.

Select your Print Audit Database

This part of the wizard allows you to select the Print Audit database on which you want to perform the task you selected. Print Audit automatically chooses the Print Audit database set on this computer. If Print Audit could not find a database, the box is blank.

This screen displays the following information:

- **Database** – Use this box to type in the path to the database on which you want to perform the task. You can also click the Open button to the right of the box to bring up a standard Windows browse dialog so you can search for the database you want.

Click the **Next** button when you are done to move on to the next screen.

Ready to Compact

This part of the wizard allows you to start compacting your database. If you are not sure you want to compact the database you selected on the previous screen, click **Back** to select a different one.

As you compact, the status of the operation displays in the rectangular box.

Click the **Compact** button when you are ready to start the compacting process.

Changing the Read-Only Password

Changing the Read-Only Database Password

For your convenience Print Audit provides a read-only login into your Print Audit database so you can use third party programs to access your data. For example you may need to take the print job data and bring it in to another database in your organization for proper accounting.

Print Audit gives you this functionality through a Microsoft Access database account called “PAReADonly”. When you install a new Print Audit database the



password for this account is “password”. We highly recommend you change this password if you have any concerns about someone using tools other than Print Audit to view your data.

To change the read-only password:

1. Start the Print Audit Database Maintenance tool. The tool starts on the **Select Database Task** screen.
2. Click the **Change the read-only password** option.
3. Click the **Next** button. The wizard moves to the **Select your Print Audit Database** screen.
4. Enter the Print Audit database you want to change. The wizard detects what the current database is on this computer. If you want to pick a different database, either type the full path to the database in or select it using the browse button.
5. Click the **Next** button. The wizard moves to the **Change your Print Audit Read-Only Password** screen.
6. Type in your old password, new password and new password again to confirm. Please note that if this is the first time you are changing the password, the value you should enter in the **Old Password** box is “password”.
7. Click the **Change** button. Print Audit changes the password and moves to the **Finish** screen. Please store the new password in a safe place. If you lose it there is no way to recover it.

Select the Database Task

This part of the wizard allows you to select which task you want to perform on your Print Audit database. The options are as follows:

- Compact your database – Click this option to compact your Print Audit database. Compacting your database reduces size, increases speed and reduces the risk of corruption. Also choose this option if your database has become corrupted and Print Audit will attempt to repair it.
- Change the read-only password – Click this option to change the password for the PAREadOnly account. Every Print Audit database has this account with a default password of “password”. If you are concerned about security you should change this password.



Change your Print Audit Read-Only Password

This part of the wizard allows you to enter your old and new Print Audit read-only passwords. Please remember to store the new password you enter in a safe place. If you lose the new password you will not be able to access the PAREadOnly account for your database.

This screen displays the following information:

- **Old password** – Please enter your existing read-only account password here. If you have never changed the password before, the password is “password”.
- **New password** – Please enter your new password in this box. Do not forget this password.
- **Confirm password** – Please re-enter the password you put in the New password box here. This is just to ensure you entered the password you want.

Click the **Change** button to change the password.

SQL Server Maintenance

Microsoft SQL Server Overview

Print Audit 6 fully supports Microsoft SQL Server as a back-end database. Print Audit uses this database to store configuration information as well as print job information.

This SQL Maintenance tool provides you with simple SQL Server maintenance functionality.

The following is a list of the SQL Server tasks you can accomplish with this tool:

- Creating a Print Audit Database
- Changing the Print Audit Login Password
- Changing the System Administrator Login Password
- Running a SQL Script



Creating a New Database

Creating a Print Audit Database

The main reason to use the Print Audit Database Maintenance tool is to create a new Print Audit database on the SQL Server. The wizard leads you through the steps to creating the database. If you need specific information about each of the wizard screens, click the **Help** button at the bottom left of every wizard screen. Below is a general description of how to use the wizard to create a new Print Audit database.

To create a Print Audit database:

1. Start the Print Audit SQL Server Maintenance tool. The wizard starts on the **Enter SQL Server Login Information** screen.
2. Enter the old SQL Server administration login password and click the **Next** button. The **Select the SQL Server Task** screen appears.
3. Click the **Create a new database** option.
4. Click the **Next** button. The **Enter the Print Audit Database** screen appears.
5. Enter the name of the new Print Audit database name in the text box or you can just use the default.
6. Click the **Next** button. If the Print Audit SQL Server login already exists the **Ready to Create** screen appears, otherwise the **Enter the Print Audit Login Password** screen appears. If the **Ready to Create** screen appears, skip to step 9.
7. Enter the new the Print Audit login password.
8. Click the **Next** button. The **Ready to Create** screen appears.
9. Review the information on the **Ready to Create** screen.
10. Click the **Create** button to start creating the new Print Audit database. The SQL Maintenance tool starts to create the database. This can take a couple of minutes.
11. If Print Audit detects that it is necessary to change the SQL administrator (sa) password, the **Changing the System Administrator Login Password** screen appears. Otherwise you are done.

Enter SQL Server Login Information

This part of the wizard requires you to enter your SQL Server login information. Print Audit uses this information to connect to the SQL Server so it can perform operations on the Print Audit database.



This login must have the appropriate permissions to create and modify databases and logins.

The wizard screen contains the following fields:

- **Server** – Please type the name of the SQL server to which you want to connect. This field defaults to “(local)” which means the SQL Server installed on the computer you are using. If you know the name of another server that you want to install the Print Audit database on, please enter that information here.
- **Login** – Please enter the login name for a SQL Server login that has system administrator privileges. This is typically the “sa” account.
- **Password** – Please enter the password for the SQL Server login you specified above.
- **Use Windows authentication** – Check this box if your SQL Server is setup to allow Windows authentication only. This option disables the **Login** and **Password** boxes and uses your Windows login and password to attempt connection to the database.
- **Network Provider** – You may need to enter an alternative SQL Server network library dll name in this box if you have troubles connecting to the SQL database. If blank, it uses the default network library as defined on the system. The name you enter here must be the name of the dll minus the extension and the path to the dll. So for example if you want to force Print Audit to use SQL Server’s TCP/IP connectivity, you would enter DBMSSOCN or DBNETLIB. NOTE: This is for advanced SQL Server installations only.

Click the **Next** button when you are ready to move to the next step. If Print Audit cannot find the server, or the login and passwords are incorrect, an error message will display. You must enter the proper information before you can continue

Enter the Print Audit Database Name

Use this part of the wizard to enter the name for the Print Audit database. You can name this anything you want or just accept the default.

If a database with the same name already exists on the server the wizard warns you and allows you to choose if you want to overwrite it. If you decide you want to overwrite it all of the old information will be lost.



Please remember the name you enter here, as you may need to enter it into Print Audit when you connect to the database for the first time.

The wizard screen contains the following fields:

- **Database** – Enter the name of the new Print Audit database here. You can also leave the default.

Click the **Next** button to move to the next step of the wizard.

Enter the Print Audit Login Password

This part of the wizard asks you to enter the Print Audit login password. By default the Database Maintenance tool creates a login account called "PrintAudit" on the SQL Server. This is the account that the other products in the Print Audit suite use to connect to your database.

NOTE: You only get this wizard screen while creating a database if the "PrintAudit" login account does not already exist on the server.

The fields on this screen are:

- **Name** – This field displays the login name for the Print Audit login account. You cannot change this value.
- **Password** – This field allows you to enter a password for the Print Audit login account. All Print Audit applications will use this password to connect to your database. You may want to keep this password private if you are worried about users going into the database using means other than Print Audit.

Click the **Next** button to move on to the next part of the installation.

Ready to Create

This part of the wizard provides you with a checkpoint to confirm all of the information you have entered so far. You should write this information down somewhere, as you may need it later to connect to the Print Audit database. If the information on this screen is not correct, you must go back to the previous wizard screens to change it.



This screen displays the following information:

- **Server** – This is the server name that the wizard is going to create the new database on. You entered this server name on the first screen of the wizard. A value of “(local)” means that the wizard will create the database on the SQL server installed on this computer.
- **Database** – This is the name of the database the wizard will create. If “(Overwrite)” is appended to the database name it means that the wizard will replace any existing database with the same name.
- **Login** – This is the name of the Print Audit database login account. This login name cannot be changed. Print Audit will use this login name to connect to the database.
- **Password** – This is the password for the Print Audit login account. A value of “<Password previously set>” for the password means that the Print Audit login account already exists on the SQL Server and will not be changed.

Click the **Create** button to have the Print Audit wizard create the database. Click the **Back** button to go back in the wizard and change any information that is incorrect.

Change the System Administrator Password

This part of the wizard allows you to change the SQL Server “sa” login password. The “sa” account is the main SQL Server account. If you leave it open and unsecured anyone with SQL tools can access and change your server.

NOTE: You only get to this screen while creating a new database if the initial login account was “sa” and the password was blank.

The fields on this screen are:

- **New password** – Enter the new password for the “sa” login. Please record this password somewhere. If you forget the password you will have to reinstall the SQL Server.

Click the **Change** button to change the password.



Finished Using the Wizard

This part of the wizard displays a summary of the task you just accomplished. Congratulations!

Click the **Done** button to exit the wizard.

Changing the Print Audit Login Password

Changing the Print Audit Login Password

You can use the Print Audit Database Maintenance tool to change the Print Audit login password. This is the password that all Print Audit users use to connect to the database.

To change the Print Audit login password:

1. Start the Print Audit Database Maintenance tool. The wizard starts on the **Enter SQL Server Login Information** screen.
2. Enter the SQL Server administration login password and click the **Next** button. The **Select the SQL Server Task** screen appears.
3. Click the **Change the Print Audit User Password** option.
4. Click the **Next** button. The **Change the Print Audit User Password** screen appears.
5. Enter the new password for the Print Audit user login.
6. Click the **Change** button to change the password.

Enter SQL Server Login Information

This part of the wizard requires you to enter your SQL Server login information. Print Audit uses this information to connect to the SQL Server so it can perform operations on the Print Audit database.

This login must have the appropriate permissions to create and modify databases and logins.

The wizard screen contains the following fields:

- **Server** – Please type the name of the SQL server to which you want to connect. This field defaults to “(local)” which means the SQL Server installed on the computer you are using. If you know the name of



another server that you want to install the Print Audit database on, please enter that information here.

- **Login** – Please enter the login name for a SQL Server login that has system administrator privileges. This is typically the “sa” account.
- **Password** – Please enter the password for the SQL Server login you specified above.
- **Use Windows authentication** – Check this box if your SQL Server is setup to allow Windows authentication only. This option disables the **Login** and **Password** boxes and uses your Windows login and password to attempt connection to the database.
- **Network Provider** – You may need to enter an alternative SQL Server network library dll name in this box if you have troubles connecting to the SQL database. If blank, it uses the default network library as defined on the system. The name you enter here must be the name of the dll minus the extension and the path to the dll. So for example if you want to force Print Audit to use SQL Server’s TCP/IP connectivity, you would enter DBMSSOEN or DBNETLIB. NOTE: This is for advanced SQL Server installations only.

Click the **Next** button when you are ready to move to the next step. If Print Audit cannot find the server or the login and passwords are incorrect an error message will display. You must enter the proper information before you can continue.

Change the Print Audit User Password

This part of the wizard allows you to change the Print Audit login password. This is the account that the other products in the Print Audit suite use to connect to your database. You only need to change the password if you have forgotten the old one or if you are concerned about security.

The fields on this screen are:

- **Name** – This field displays the login name for the Print Audit login account. You cannot change this value.
- **New password** – Enter the new password for the Print Audit login account here. Please note that everyone using Print Audit tools will now have to use this new password to get into your database.

Click the Change button to change the password.



Finished Using the Wizard

This part of the wizard displays a summary of the task you just accomplished. Congratulations!
Click the **Done** button to exit the wizard.

Changing the System Administrator Password

Changing the System Administrator Login Password

You can use the Print Audit Database Maintenance tool to change the system administrator login password. This is the password for the SQL Server “sa” account. This is a special account in SQL Server that has full power to change anything on a SQL Server. This password is blank by default when you install SQL Server, so you want to change it as soon as possible.

To change the system administrator login password:

1. Start the Print Audit Database Maintenance tool. The wizard starts on the Enter SQL Server Login Information screen.
2. Enter the old SQL Server administration login password and click the Next button. The Select the SQL Server Task screen appears.
3. Click the Change the system administrator (sa) password option.
4. Click the Next button. The Change the System Administrator Password screen appears.
5. Enter the new password for the system administrator.
6. Click the Change button to change the password.

NOTE: The wizard also allows you to change the system administrator password at the end of the Create Database process.

Enter SQL Server Login Information

This part of the wizard requires you to enter your SQL Server login information. Print Audit uses this information to connect to the SQL Server so it can perform operations on the Print Audit database.

This login must have the appropriate permissions to create and modify databases and logins.



The wizard screen contains the following fields:

- **Server** – Please type the name of the SQL server to which you want to connect. This field defaults to “(local)” which means the SQL Server installed on the computer you are using. If you know the name of another server that you want to install the Print Audit database on, please enter that information here.
- **Login** – Please enter the login name for a SQL Server login that has system administrator privileges. This is typically the “sa” account.
- **Password** – Please enter the password for the SQL Server login you specified above.
- **Use Windows authentication** – Check this box if your SQL Server is setup to allow Windows authentication only. This option disables the **Login** and **Password** boxes and uses your Windows login and password to attempt connection to the database.
- **Network Provider** – You may need to enter an alternative SQL Server network library dll name in this box if you have troubles connecting to the SQL database. If blank, it uses the default network library as defined on the system. The name you enter here must be the name of the dll minus the extension and the path to the dll. So for example if you want to force Print Audit to use SQL Server’s TCP/IP connectivity, you would enter DBMSSOCN or DBNETLIB. NOTE: This is for advanced SQL Server installations only.

Click the **Next** button when you are ready to move to the next step. If Print Audit cannot find the server or the login and passwords are incorrect an error message will display. You must enter the proper information before you can continue.

Change the System Administrator Password

This part of the wizard allows you to change the SQL Server “sa” login password. The “sa” account is the main SQL Server account. If you leave it open and unsecured anyone with SQL tools can access and change your server.

NOTE: You only get to this screen while creating a new database if the initial login account was “sa” and the password was blank.



The fields on this screen are:

- **New password** – Enter the new password for the “sa” login. Please record this password somewhere. If you forget the password you will have to reinstall the SQL Server.

Click the Change button to change the password.

Finished Using the Wizard

This part of the wizard displays a summary of the task you just accomplished. Congratulations!

Click the **Done** button to exit the wizard.

Running a SQL Script

Running a SQL Script

You can use the Print Audit Database Maintenance tool to run any sql script against the Print Audit database. You may need to run scripts to repair accidentally damaged databases, or to perform different database maintenance tasks.

NOTE: Print Audit is not responsible for any damage or loss of data that occurs when running scripts against your database that you have not received directly from Print Audit. You should only use this functionality if Print Audit directs you to, or if you are an advanced SQL user.

To run a sql script:

1. Start the Print Audit Database Maintenance tool. The wizard starts on the **Enter SQL Server Login Information** screen.
2. Enter the SQL Server administration login password and click the **Next** button. The **Select the SQL Server Task** screen appears.
3. Click the **Run a sql script file** option.
4. Click the Next button. The **Enter the Print Audit Database Name** screen appears.
5. Enter the name of the Print Audit database you want to run the script against.
6. Click the **Next** button. The **Select a SQL Script File** screen appears.
7. Type the path to the script file, or click the **Browse** button to open a standard dialog so you can look for the file.



8. Click the **Run** button to run the script. After the script has completed the **Summary** screen appears.

Enter SQL Server Login Information

This part of the wizard requires you to enter your SQL Server login information. Print Audit uses this information to connect to the SQL Server so it can perform operations on the Print Audit database.

This login must have the appropriate permissions to create and modify databases and logins.

The wizard screen contains the following fields:

- **Server** – Please type the name of the SQL server to which you want to connect. This field defaults to “(local)” which means the SQL Server installed on the computer you are using. If you know the name of another server that you want to install the Print Audit database on, please enter that information here.
- **Login** – Please enter the login name for a SQL Server login that has system administrator privileges. This is typically the “sa” account.
- **Password** – Please enter the password for the SQL Server login you specified above.
- **Use Windows authentication** – Check this box if your SQL Server is setup to allow Windows authentication only. This option disables the **Login** and **Password** boxes and uses your Windows login and password to attempt connection to the database.
- **Network Provider** – You may need to enter an alternative SQL Server network library dll name in this box if you have troubles connecting to the SQL database. If blank, it uses the default network library as defined on the system. The name you enter here must be the name of the dll minus the extension and the path to the dll. So for example if you want to force Print Audit to use SQL Server’s TCP/IP connectivity, you would enter DBMSSOEN or DBNETLIB. NOTE: This is for advanced SQL Server installations only.

Click the **Next** button when you are ready to move to the next step. If Print Audit cannot find the server or the login and passwords are incorrect an error message will display. You must enter the proper information before you can continue.



Enter the Print Audit Database Name

Use this part of the wizard to enter the name of the Print Audit database you want to run the script against.

If the database does not exist, Print Audit does not allow you to continue.

The wizard screen contains the following fields:

- **Database** – Enter the name of the Print Audit database here.

Click the **Next** button to move to the next step of the wizard.

Select a SQL Script File

This part of the wizard allows you to select the SQL script file you want to run against the database. Please note that Print Audit is not responsible for any loss of or damage to your Print Audit data when running a script not approved by Print Audit. You should not use this functionality unless Print Audit instructs you to or unless you are an advanced SQL user.

This screen displays the following information:

- **Script** – Type the full path and name of the sql script file you want to run here. You can also click the Browse button to open a standard Windows dialog so you can find the file you want to run.

Click the Run button to run the script.



Print Audit 6 Database Migration Wizard



Overview

Welcome to the Print Audit Database Migration Wizard! This tool allows you to upgrade Print Audit 5 databases to Print Audit 6 databases, as well as migrate Print Audit 6 MSAccess databases to Microsoft's SQL Server.


To migrate your database:

1. Start the Print Audit Database Migration Wizard. The wizard starts on the **Select the Migration Type** screen.
2. Choose the migration type. Click the **Next** button.
3. Depending on the migration type, select either the MSAccess or SQL Server database to migrate from. Click the **Next** button.
4. Depending on the migration type, select either the MSAccess or SQL Server database to migrate to. Click the **Next** button to continue.
5. Select your job migration options. Click the **Next** button to continue.
6. Start migrating the data.



Once the data migration has completed you can click the **Close** button to close the wizard.

Print Audit 6 Client Status and Deployment Tool



Welcome

Welcome to the Print Audit Client Status/Deployment tool. This tool has four main uses:

1. Query computers on a network and retrieve information about Print Audit 6 client installations.
2. Install or upgrade the Print Audit 6 Client on a collection of computers on the network.
3. Un-install the Print Audit 6 Client from a collection of computers on the network.
4. Change the Client Communicator location on a collection of computers on the network.

This tool is not recommended for use with computers running Windows 95, Windows 98, or Windows ME. Windows 2000 or newer is recommended.



Usage Requirements

Minimum Requirements

You must have the Active Directory client extensions installed on a computer to use the Client Status/Deployment tool. The extensions are included with Windows 2000 and newer operating systems. Older operating systems are not supported.

Note that only the computer running the Client Status/Deployment tool needs the Active Directory extensions. Status information and installs can run on computers without the Active Directory extensions.

Requirements for gathering status information from a network

There are no additional software requirements for using the Client Status / Deployment Tool to gather information about Print Audit 6 client installations on the network.

Permissions

To effectively gather status information, you must have the appropriate permissions on the network. The required permissions depend on your network configuration. In general, you need enough permissions to browse computers on the network.

Requirements for pushing the Print Audit 6 client installation to computers on a network

The Client Status / Deployment Tool can only push client installations to (or remotely un-install the Print Audit 6 client from) computers running Windows 2000 or newer operating systems. Depending on how Vista or other operating systems have been secured, remote push installs may not be allowed.

Permissions

In order to install, upgrade, or uninstall Print Audit 6 on network computers, you must meet the following requirements:

1. Target workstations must have Administrative shares enabled.



2. You must have permissions to use the Administrative shares on the target workstations.
3. You must not be running any firewall software that blocks Windows file sharing or remote procedure calls (RPC) on the target computer.

Using the Tool

Querying Client Status

You can use the Client Status / Deployment Tool to query a network and return information about Print Audit installations.

To query a domain:

1. Select **Domain / Open** from the menu, or click the left-most button in the toolbar. The Open Domain dialog appears.
2. Enter in the name of the domain or workgroup you want to query.
3. Enter the name of the OU if you want to restrict the query to a single OU. If you have nested OUs you can separate the OUs with slashes. For example: TopLevelOU/SubOU/InnermostOU.
4. Enter a partial computer name to filter the results by computer name. Print Audit only returns computers that contain the partial name.
5. Click the OK button. Results start displaying immediately but it may take some time to find all computers in your organization.

When you query the network Print Audit returns the computer name and operating system. If the Print Audit Client is installed on a computer the following information also displays:

1. The version of the Print Audit Client.
2. The current Print Audit user (if any).
3. The last time that computer printed.
4. The first time the Print Audit client was ever seen running by the push install / status tool.
5. The most recent time the Print Audit client was seen running.
6. The location of the Client Communicator the Client is connected to. Note that this does not show up for older Clients.

If no information about the Print Audit Client is shown for a computer it is usually caused by one of the following three conditions:



1. The Print Audit client is not installed on that computer.
2. The Print Audit client is installed, but is not currently running (possibly because nobody is logged into that computer).
3. An older version of the Print Audit Client is installed.
4. Firewall software or hardware is blocking the communication to the Print Audit client.

You may save the current status by clicking Domain / Save Report in the menu, or clicking the second button from the left in the toolbar.

Installing Print Audit 6 to Network Computers

You can use the Client Status / Deployment Tool to push the installation or an upgrade of the Print Audit 5 Client to other computers on the network. Whether you are installing or upgrading, the process is the same.

To install Print Audit 5 to the network:

1. Query the network client status.
2. Select the computers on which you want to install or upgrade the Print Audit 5 Client. You can use SHIFT-CLICK and CTRL-CLICK to select more than one computer.
3. Click the **Push->Install to Selected Computers** menu item. The **Select Package to Install** dialog appears.
4. Select or create an installation package.
5. Click the **Install** button. A progress dialog appears showing the installation to the computers.

IMPORTANT: You cannot use this tool to install the Client to Windows 95, 98 or ME computers. If you want to deploy the Client to these operating systems you must use another method such as login scripts.

Removing Print Audit 6 from Network Computers

You can use the Client Status / Deployment Tool to uninstall the Print Audit Client from other computers on the network. This is a very similar process to installing or upgrading the client on network computers.

To uninstall Print Audit from network computers:

1. Query the network client status.



2. Select the computers from which you want to uninstall the Print Audit Client. You can use SHIFT-CLICK and CTRL-CLICK to select more than one computer.
3. Click the **Push->Uninstall from Selected Computers** menu item. The **Select Package to Install** dialog appears.
4. Select the package you want to uninstall.
5. Click the **Uninstall** button. A progress dialog appears showing the installation to the computers.

Updating the Client Communicator Location

You can use the Client Status/Deployment tool to remotely change the location the Print Audit Client uses for the Client Communicator. You may need to do this if you move the Client Communicator after installation of the software.

To update the Client Communicator location:

1. Query the network client status. Select the computers you want to re-configure. You can use SHIFT-CLICK and CTRL-CLICK to select more than one computer.
2. Click the **Push->Change Client Communicator Location** menu item. The **Update Selected Computers** dialog appears.
3. Enter the new location and port number for the Client Communicator.
4. Click the **Update** button. A progress dialog appears showing the update of the computers.

Please note that the Print Audit Clients use the new Communicator location the next time someone prints from that computer.

Working With Installation Packages

Selecting a Package

Click on the package name on the **Select Package** dialog. You need to select a package when installing, upgrading, or uninstalling the Print Audit Client on network computers.



Importing a Package

If you used the Print Audit installer to create a network installation you can import this network installation as a package and use it with this tool to install, upgrade, or uninstall the Print Audit client.

Click the **Import...** button, and browse for the package.ini file for the network installation. This is usually in the same directory as the network installer package that you created using the Print Audit installer. You can also choose the Client only install package which reduces the amount of network traffic for deployment as the client only installer is much smaller than the full installer.

Once you locate the package.ini file, click Open to import the package. You can immediately select this package and use it.

Creating a Package

Generally, you will want to import packages as described above. In some cases, though, you may want to create a new package yourself. To create a new package, click the Add button in the Select Package dialog. The Create New Install Package window will appear. Fill in the settings as described below:

1. **Name** - the name you want to use for this install package.
2. **Description** - a description you want to use for this install package.
3. **Installer** - the Setup (.exe) or Windows Installer (.msi) file you want to push to the clients.
4. **Notify Users when Installation Completes** - Check this box to have a dialog box appear on the computer after the installation finishes. This dialog informs the user that the package successfully installed.
5. **Command Line Parameters** - If the installer requires command line parameters, provide these here. MSI packages automatically get the appropriate command-line parameters for silent installation.

When you are satisfied with the settings, click the OK button to create the installation package. You can immediately select and use this newly-created installation package.

Editing a Package

To edit an existing package, double-click on its name in the list of packages. You can change any of the settings you want. Click OK when you have finished, or Cancel if you do not want to save your changes.



For a description of all the fields, see the description for Creating a Package (above).

Deleting a Package

To delete a previously created installation package select it from the list in the Select Package dialog and click the Delete button.