



LANDWorksCAD for AutoCAD® and Bricscad®

Professional Landscape Design Software

Reference and User Manual



CAD International

www.CAD.com.au – www.CADInternational.com

© 2006 - 2012 - All rights reserved

This page is intentionally blank

Table of Contents

Introduction	7
Welcome	7
About this Manual	8
Disclaimer	9
Overview	10
The LANDWorksCAD Commands	10
The Plant Database	11
Command Details	12
Insert Concept Plant.....	13
Selecting a Concept Plant.....	14
Inserting the Selected Concept Plant	16
Searching for Concept Plants	19
Resetting the Search Criteria	24
Replacing Already Inserted Concept Plants	24
Editing Concept Plants from within LANDWorksCAD	26
Label Concept Plant	34
Text Size	34
Scale Text by the Plot Scale	35
Inserting the Label	35
Insert Existing Plant.....	39
Selecting an Existing Plant	40
Inserting the Selected Existing Plant	41
Replacing Already Inserted Existing Plants	45
Editing Existing Plants from within LANDWorksCAD	46
Label Existing Plant	53
Botanical Name	54
Label Item Using	55
Label Prefix	56
Text Size	56
Trunk Diameter.....	57
Height.....	57
Spread	57
Status 1	57
Status 2.....	57
Comments.....	58
Scale Text by the Plot Scale	58
Inserting the Label	58

Existing Plant Schedule	59
Heading.....	60
Table Size	60
Show Diameter.....	60
Show Height.....	60
Show Spread.....	60
Show Status	60
Show Borders.....	61
Inserting the Schedule	61
Insert Proposed Plant.....	62
Selecting a Proposed Plant.....	63
Inserting the Selected Proposed Plant	65
Searching for Proposed Plants	69
Resetting the Search Criteria	73
Replacing Already Inserted Proposed Plants	73
Editing Proposed Plants from within LANDWorksCAD	75
Label Proposed Plant	83
Number of Plants.....	84
Include Number	85
Label Field Name	85
Terminator Type	86
Terminator Weight.....	87
Terminator Size	87
Text Size	87
Scale Text by the Plot Scale	88
Label with Leader Lines.....	88
Inserting the Label.....	89
Proposed Plant Legend	91
Legend Fields.....	92
Heading.....	92
Group By.....	92
Show Borders.....	93
Show Relative Size.....	94
Show Quantity.....	94
Show Quantity Last	94
Table Size	94
Inserting the Legend.....	95
Plant Display Switching	96
Tally	97
Insert Grid Lines	100
X Spacing.....	101
Y Spacing.....	101
X Extension	101
Y Extension	101
Text Size	101
Circle Text.....	101
Labels Between Grid Lines	101
Inserting the Grid.....	102

Set Heights.....	103
DTM Height.....	104
Text Size.....	105
Scale Text by the Plot Scale.....	105
Set Height.....	105
Show Heights.....	106
Deleting Assigned Heights.....	106
Insert DTM.....	107
Contour Point Spacing.....	108
Mesh Size Control.....	109
DTM Layer.....	111
DTM Colour.....	112
Insert DTM button.....	112
Insert DTM with boundary button.....	114
Modify DTM.....	116
Height Parameter.....	116
Area Parameter.....	117
Insert Batter.....	122
Angle.....	124
Mesh Size.....	124
Inserting the Batter.....	125
Insert Contours.....	126
Spacing.....	127
Highlighting Frequency.....	127
Text Size.....	127
Scale Text by the Plot Scale.....	128
Inserting the Contours.....	128
Adjust Plant Heights.....	130
Figure Height.....	131
Text Size.....	131
Scale Text by the Plot Scale.....	132
Show Heights.....	132
Insert 3D Plants.....	133
Show 2D View.....	134
Show 3D View.....	135
Current Size.....	137
Update Age.....	137
Inserting the Plants.....	138
Insert Sun Light.....	139
Import a .kml or .kmz file.....	140
Import the current location from Google Earth.....	141
Enter the location values.....	142
About.....	144

Appendices145

Appendix 1 – The LANDWorksCAD Plant Database.....	146
Structure	146
Format.....	146
Rows	147
Columns.....	148
Existing Plants worksheet	148
Concept Plants worksheet	149
Plants worksheet	151
Appendix 2 – Editing the Plant Database in Excel	157
Editing Existing Plant Data.....	157
Adding a Plant.....	158
Deleting a Plant.....	159
Re-Arranging/Moving Plants	160
Adding a New Data Item (Column).....	160
Deleting an Existing Data Item (Column).....	161
Re-Arranging/Moving Data Items (Columns)	161
Appendix 3 – Working with the Selection Data.....	162
Displaying the Hidden Selection Data	163
Editing the Existing Selection Data	167
Assigning Selection Data to New Columns.....	171
Removing the Selection Data.....	172
Appendix 4 – Sorting the Plant Database in Excel	174

Introduction

Welcome

Welcome to LANDWorksCAD for AutoCAD® and Bricscad®. This manual will help you design your landscapes “better, faster and funner®”.

LANDWorksCAD is easy-to-use, professional-level software specifically created for landscapers’ needs.

You can use LANDWorksCAD to create sketch plans, concept plans, planting plans, hard works plans, construction details, plant schedules, contour plans and more...

With LANDWorksCAD you can produce three dimensional models of your landscape design, which can be viewed from any position and any angle.

LANDWorksCAD also includes an extensive plant database that is linked to a simple, editable Excel file allowing you to easily set up plants that are specific to you and your area.

We’ve spent hundreds of hours producing this manual to show you how to use the LANDWorksCAD menu, but we know you’ll find ways to use the software we had never thought of so we are looking forward to receiving your thoughts and comments about the software and this manual. If you wish to provide feedback please call +61 2 9973 4499 or send an email to info@cad.com.au

About this Manual

This manual only provides information on the commands in the LANDWorksCAD toolbar and menu, as indicated in the image below, and the associated Excel plant database.

We assume you already have the basics of AutoCAD® and Bricscad® to a certain degree.



Note

The terms “Drawing” and “Model” are interchangeable in this manual.

Even if you’ve been using the software for a while, take the time to read through this manual as you’ll find new ways of doing things and shortcuts you may not have thought of.

Disclaimer

All care has been taken to ensure the accuracy of the information contained in this document, however no warranty expressed or implied is given that this information is either current or accurate and should not be relied on for any purpose.

Copyright© 2006 - 2012 CAD International. All Rights Reserved.


No part of this publication may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording or by any information or storage retrieval system, without express permission in writing from CAD International.

LANDWorksCAD is trademark of CAD Australia Pty Limited trading as CAD International. All other trademarks are the property of their respective owners.

Overview

The LANDWorksCAD Commands

This section provides a quick overview of LANDWorksCAD; the commands in the menu and the database of plants that is supplied.



The Plant Database

LANDWorksCAD is supplied with an extensive plant database allowing you to quickly and easily select the plants you want for your design. You can also edit the plants that are supplied in the database as well as add your own thus allowing you to easily set up plants that are specific to you and your area.

The following points give you some introductory information about the database. For detailed instructions on how to work with it, refer to the Appendices at the end of this manual.

The database:

- is a Microsoft Excel spreadsheet
- has a simple format and contains no formulas
- is called **LandworksPlantDatabase.xls** (it must be called this)
- is stored in
 - C:\Users\Public\LANDWorksCAD folder (on Windows 7 and Vista)
 - C:\Documents and Settings\All Users\LANDWorksCAD folder (Windows XP)(It must reside there)
- can be edited within LANDWorksCAD itself, i.e., you do not need to know anything about Excel
- can also be edited directly in Excel

Command Details

This section explains each command in the LANDWorksCAD menu in detail.

It should be noted that the LANDWorksCAD menu does not necessarily have to appear on the left hand side of the window as shown in previous images. This is the default position only. It can be moved anywhere on the screen and also docked to the edges of the window, just like any standard Windows' window.

Insert Concept Plant




PURPOSE: To select and insert a figure that represents the “concept” of a plant or plants rather than a specific plant, for example, the **figure** might be used to represent general ground cover before any particular ground cover has been decided upon.



[Click to watch Insert Concept Plants in LANDWorksCAD Video on YouTube](#)

The appropriate type of plant can be searched for and plants that have already been inserted can be replaced.


When the command is selected, the following dialog box is displayed.



This command also lets you edit your LANDWorksCAD Excel plant database from within LANDWorksCAD. This is explained at the end of this section. For details on editing your plant database directly in Microsoft Excel, refer to [Appendix 2 – Editing the Plant Database in Excel](#) on page 153.

Selecting a Concept Plant

The “**Selected Items**” area at the top of the dialog box lists the plants defined in the “**Concept Plants**” tab of your LANDWorksCAD Excel plant database. This database is called **LandworksPlantDatabase.xls** and is found in the LANDWorksCAD folder on your computer. Refer to [Appendix 1 – The LANDWorksCAD Plant Database](#) on page 142 for more details on the database.



Index	plan figure name	description	category	shape	heading	label
32	Figures\Plants\RR01.dwg	Desc 1	Tree	Round	Heading 1	Label 1
33	Figures\Plants\RR02.dwg	Desc 2	Tree	Oval	Heading 2	Label 2
34	Figures\Plants\RR03.dwg	Desc 3	Shrub	Round	Evergreen	Label 3
35	Figures\Plants\RR04.dwg	Desc 4	Tall shrub	Spikey	Desert Sh...	Label 4
36	Figures\Plants\RR05.dwg					
37	Figures\Plants\RR06.dwg					
38	Figures\Plants\RR07.dwg					

Buttons: Insert New Plant, Delete Plant, Save Database, Reload Database, ☒ Allow Editing




Note

The buttons just below the selected items area, i.e., “Insert New Plant”, “Delete Plant”, etc. let you edit your plant database from within LANDWorksCAD and are explained later in the section entitled [Edit Concept Plants from Within LANDWorksCAD](#) on page 25.

Scrolling down will show more plants; scrolling sideways will show more data for the plants.

Click once anywhere in the row of data for the plant you want. Preview images of the plant will be displayed in the four, bottom, right hand boxes. Not all of the boxes will necessarily display previews; it depends on what has been defined in your LANDWorksCAD Excel plant database.

The top two previews show the ways the plan view of the plant can be displayed in the drawing. You can switch between these displays whenever you want to after the plant has been inserted – refer to [Plant Display Switching](#) on page 91.



The “**Concept Figure**” preview is of a LANDWorksCAD drawing file, i.e., it must have been drawn in LANDWorksCAD or created in another CAD program and then imported and saved in LANDWorksCAD.

The “**Image**” preview is of a JPG or BMP (bitmap) format file. This could be an actual photograph of the plant or it could be an artistic representation that has been created outside of LANDWorksCAD using image editing software, e.g., PhotoImpact. The JPG format is preferred because file sizes are much smaller.

Having two ways of displaying the plan view of the plant gives you flexibility in how you present your concept drawings and, as stated earlier, you can switch between them whenever you want to.


It is up to you to decide how simple or detailed the plan concept figure is.

Likewise it is up to you to decide if the image display is an actual photograph or a computer generated image.

Both plan displays do not have to be created for every plant, though obviously you must use at least one or nothing will be displayed on the screen.

The plan display to be inserted can be selected by clicking in the white dot above the preview so that a smaller black dot appears within it.

The information explained above also pertains to the Elevation/3D previews; the concept figure is a LANDWorksCAD drawing file and the Image is a JPG or BMP file.



Note


The Elevation/3D figures cannot be inserted using this command. They can be generated automatically via the **Insert 3D Plants** command on page 128 or inserted manually.

Inserting the Selected Concept Plant

Inserting the selected concept plant is a two-step process:

1. Select the diameter of the plant


The diameter of the plant can be selected from the “Diameter” box, as shown below:



If the required diameter is not listed it can simply be typed directly into the box.

The word “Default” means the plant will be inserted at the size it was originally drawn.

2. Insert the plant using the appropriate insertion method



Insert the Plant Using the Appropriate Insertion Method

Once the diameter has been selected, the plant can be inserted into your drawing in three different ways: “1 Point”, “2 Points” or “Scale 2 Points”. These methods are explained below.

Insert Plant by 1 Point



Clicking either of these buttons attaches an image of the plan view of the plant to your crosshair and the plant is inserted where you click your left mouse button.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.

You Tube™ Video

[Click to watch Insert Concept Plants by One Point Video on YouTube](#)

Insert Plant by 2 Points



Clicking either of these buttons attaches an image of the plan figure of the plant to your crosshair, but two mouse clicks are required to insert it. The first mouse click positions the plant figure; the second click defines the orientation of the plant, ie, you can spin it around.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.

You Video

[Click to watch Insert Concept Plants by Two Points Video on YouTube](#)

Insert Plant by Scale 2 Points



Clicking either of these buttons attaches an image of the plan figure of the plant to your crosshair, but two mouse clicks are required to insert it. The first mouse click positions the plant figure; the second click defines the orientation and size, or scale, of the plant, ie, you can spin it around and you can also make it larger or smaller than the original image.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.

This technique ignores the Diameter box.


You Video

[Click to watch Insert Concept Plants by Scale Two Points Video on YouTube](#)



Note

If a plant has not been selected before any of these buttons are clicked, the following dialog box will be displayed, indicating that a plant must be selected from the “Selected Items” list.




Tip

If you want to insert more copies of a plant that you have already inserted you don't have to use this command again, you can simply copy the plants. They will still be recognised as plants from your database.

Searching for Concept Plants

You can search for the plant you want using the **Search Fields** part of the command. You can search on any of the data in the “Concept Plants” sheet of your LANDWorksCAD Excel plant database.



The *Field Name* column lists every column from your database; the *Operator* column controls the range of data you are searching for and the *Value* column provides limits for the search.


The database can be search in two ways, although they are similar.

Method 1




[Click to watch Search Concept Plants \(Double Click\) Video on YouTube](#)


Double-click on the desired Field Name. This activates the “*Compare Field Name Properties*” dialog box as shown below. Here the “*Category*” field was selected.



Select the type of search “*Operator*” from the drop-down list, as shown below. Here “*Equal*” is selected.



Select the desired search “*Value*” from the drop-down list as shown below. Here “*Tree*” is selected. The values in the drop-down list will vary depending on the Field Name selected. The values are extracted from your database.



Click *OK* to finish the process. Your Search Fields area will look as shown below.

Search Fields:

Field Name	Operator	Value
plan figure name		
elev. figure name		
image file name		
elev. image file name		
description		
category	Equal	Tree
shape		

Search Reset

You may repeat the above steps with other Field Names to create multiple search criteria, eg, you might be searching for all trees that have an oval shape.

When you're happy with the search criteria, click the **"Search"** button. The Selected Items area will change and display only the items that match the search criteria. For example, the image below shows only Trees.

Selected Items:

Index	plan figure name	elev. figur...	image file ...	elev. imag...	description	category	shape	h
32	Figures\Plants\RR01.dwg				Desc 1	Tree	Round	h
33	Figures\Plants\RR02.dwg				Desc 2	Tree	Oval	h

The desired plant can now be selected from the filtered list and inserted as described above.

Method 2



[Click to watch Search Concept Plants Video on YouTube](#)

Click once on the desired “*Field Name*”. The Field Name will be highlighted as shown below. Here the “*Category*” field was selected.

Field Name	Operator	Value
plan figure name		
elev. figure name		
image file name		
elev. image file name		
description		
category		
shape		

Search Reset

Click in the green highlighting line under the “*Operator*” heading. A drop down field will appear. Select the type of search “*Operator*” from the drop-down list, as shown below. Here “*Equal*” is selected.

Field Name	Operator	Value
plan figure name		
elev. figure name		
image file name		
elev. image file name		
description		
category	Equal	
shape		

Search Reset

Now click the green highlighting line under the “*Value*” heading. A drop down field will appear. Select the desired search “*Value*” from the drop-down list as shown below. Here “*Palm*” is selected. The values in the drop-down list will vary depending on the Field Name selected. The values are extracted from your database.

Search Fields:

Field Name	Operator	Value
plan figure name		
elev. figure name		
image file name		
elev. image file name		
description		
category	Equal	Tree
shape		

Search Reset

Your Search Fields area will look as shown below.

Search Fields:

Field Name	Operator	Value
plan figure name		
elev. figure name		
image file name		
elev. image file name		
description		
category	Equal	Tree
shape		

Search Reset

You may repeat the above steps with other Field Names to create multiple search criteria, for example, you might be searching for all trees that have an oval shape.

When you're happy with the search criteria, click the **"Search"** button. The Selected Items area will now display only the items matching the search criteria, for example, the image below shows only trees.


Selected Items:

Index	plan figure name	elev. figur...	image file ...	elev. imag...	description	category	shape	h
32	Figures\Plants\RR01.dwg				Desc 1	Tree	Round	H
33	Figures\Plants\RR02.dwg				Desc 2	Tree	Oval	H

The desired plant can now be selected from the filtered list and inserted as described above.

Resetting the Search Criteria


To clear the filtered list of plants and display all the plants in the database again, click the **“Reset”** button and then click the **“Search”** button.



Replacing Already Inserted Concept Plants



[Click to watch Replacing Already Inserted Concept Plants Video on YouTube](#)



The **“Replace”** button lets you replace plants that have already been inserted into the drawing with other plants from the database.

This can be done in either of two ways:

1. You can select the plants to be replaced and then run the command, or
2. You can run the command first and then select the plants to be replaced

The two methods are nearly identical. The main difference is in how you can select the plants to be replaced.

Select the plants to be replaced and then run the command



[Click to watch Replacing Already Inserted Concept Plants Video on YouTube](#)

- Step 1 – Select the plants that have already been inserted into the drawing. You can use any selection technique for this.
- Step 2 – Run the **Insert Concept Plant** command.
- Step 3 – Select the replacement plant from the “Selected Items” list.
- Step 4 – Click the “**Replace**” button.

The selected plants will be replaced.

Run the command first and then select the plants to be replaced



[Click to watch Replacing Already Inserted Concept Plants \(Method 2\) Video on YouTube](#)

- Step 1 – Run the **Insert Concept Plant** command.
- Step 2 – Select the replacement plant from the “Selected Items” list.
- Step 3 – Click the “**Replace**” button.
- Step 4 – Select the plants that have already been inserted into the drawing. You can only select plants one at a time using this method.

The selected plants will be replaced.


Editing Concept Plants from within LANDWorksCAD



[Click to watch Edit Concept Plants Video on YouTube](#)

The buttons and tick box displayed just below the “Selected Items” area let you edit your plant database from within LANDWorksCAD. This means you don’t actually have to know anything about Microsoft Excel to be able to edit your database.

However, your plant database can also be edited directly in Microsoft Excel. Refer to [Appendix 2 – Editing the Plant Database in Excel](#) on page 153 for details.



When the dialog box is displayed, the buttons giving you access to the plant database – “**Insert New Plant**”, “**Delete Plant**” and “**Save Database**” – are “greyed-out”, i.e., they are not accessible. This is to avoid plant data being accidentally edited. The “**Reload Database**” button is available in case the database has been edited in Excel while LANDWorksCAD is open.




Important Note

You can edit the database in Excel while LANDWorksCAD is running, but you cannot and must not edit the database from within LANDWorksCAD while the database is open in Excel.

This is not a limitation of LANDWorksCAD; it is simply how files work in Windows – you cannot work on the same file, at the same time, with two different programs. If the database is open in Excel when you save it from LANDWorksCAD, you will get an error message and LANDWorksCAD will lock up or crash.

To activate the greyed-out buttons and allow editing of your plant database, click the “**Allow Editing**” box, so that a tick is visible. The buttons will then look like this:



You can also edit plants that are already in the database, although there is no specific button for this.


The editing functionality is explained below:

Edit a Concept Plant already in the Database (no button)

To edit the data of a concept plant already in the database simply click on the text and edit it. The row of data will be highlighted in green, except for the specific text to be edited, which will remain white for ease of typing.


You can also press the Tab key to move to the next column.

Some columns provide a list of data to choose from, indicated by a downward pointing triangle. Clicking on the triangle displays the list, as shown below:




When such a list is available you cannot type in something that is not already in the list; you can only select data from the list. You can, however, edit and add to the list by editing the database in Excel. See [Appendix 2 – Editing the Plant Database in Excel](#) on page 153 for details on doing this.

To change the figure or image file for the plant, simply click in the relevant preview box and the following dialog box will be displayed allowing you to browse for the appropriate file.



When you have found the file, select it and click the **Open** button. The file will then be displayed in the preview box.

When you select a plant figure or image using this technique, LANDWorksCAD is editing data to columns you can't see, "behind the scenes". This data is the path and filename of the selected figure/image file. If you cancel the dialog box, the following message will appear:



Click the **Yes** button if you want to completely clear the filename data that was entered, if any. Click the **No** button if you want to retain the filename data that was there, if any.



Note

1. When browsing for figures, the “**Files of type**” section of the dialog box is limited to “**CAD Files *.dwg**” so you will only see LANDWorksCAD type files. Elevation/3D figures have a “-E” at the end of their name for ease of identification.
2. When browsing for image files, the “**Files of type**” section of the dialog box is limited to “**Image Files *.bmp, *.jpg**” so you will only see those types of files. Elevation/3D image files have a “-E” at the end of their name for ease of identification.
3. Selecting the appropriate plant figure/image file is a simple process, but there is one important prerequisite – the figure or image file must exist before it can be selected, i.e., it must have been drawn/created first.



Important Note

When you have finished editing your plants, it is vitally important that you save the changes to the database by clicking the “Save Database” button (see below). If you don’t, you will lose the changes.

Insert New Plant



[Click to watch Insert New Concept Plants in Database Video on YouTube](#)

There are two stages to inserting a new plant:

1. Entering the data, and
2. Selecting the appropriate figures and image files

Entering the data

When the “**Insert New Plant**” button is clicked, a blank row is inserted above the plant that is currently selected in the “Selected Items” list. The relevant data for the new plant can then be typed in.

Selected Items:

Index	description	category	shape	heading	label
32	Desc 1	Tree	Round	Heading 1	Label 1
33	Desc 2	Tree	Oval	Heading 2	Label 2
34	Desc 3	Shrub	Round	Evergreen	Label 3
35	Desc 4	Tall shrub	Spikey	Desert Sh...	Label 4
36	Desc 5				
37					

☒ Allow Editing

To enter the data, click on the blank row, in the column you want to edit and type in the required data. When you select the blank row it will be highlighted in green, but the part of the row in the column you selected will remain white.

You can also press the Tab key to move to the next column.

Some columns provide a list of data to choose from, indicated by a downward pointing triangle. Clicking on the triangle displays the list, as shown below:

Selected Items:

Index	description	category	shape	heading	label
32	Desc 1	Tree	Round	Heading 1	Label 1
33	Desc 2	Tree	Oval	Heading 2	Label 2
34	Desc 3	Shrub	Round	Evergreen	Label 3
35	Desc 4	Tall shrub	Spikey	Desert Sh...	Label 4
36	Desc 5				
37					

☒ Allow Editing

Search Fields:

When such a list is available you cannot type in something that is not already in the list; you can only select data from the list. You can, however, edit and add to the list by editing the database in Excel. Refer to [Appendix 2 – Editing the Plant Database in Excel](#) on page 153 for details on doing this.

Multiple new plants can be inserted by simply clicking the button again and entering the data.

It's up to you to decide how much data you enter. Most columns are not compulsory. Refer to [Appendix 1 – The LANDWorksCAD Plant Database](#) on page 142 for details on the database.

Selecting the appropriate figures and image files

Once the botanical data has been entered, appropriate LANDWorksCAD figures and image files must be selected to represent the plant in the drawing.

To select the plant figure or image file, simply click in the relevant preview box and browse and select the appropriate file, as described in the [Edit a Concept Plan already in the Database \(no button\)](#) section above.

Note that both of the preview boxes do not have to be filled in, but at least one must be, otherwise there will be nothing to see when the plant is inserted.

The Elevation/3D figures and images are not required at all if you are only working in 2D.



Important Note


When you have finished inserting your plants, it is vitally important that you save them to the database by clicking the “Save Database” button. If you don’t, you will lose them.

Delete Plant




[Click to watch Delete Concept Plants from Database Video on YouTube](#)

To delete a plant, select the plant by clicking anywhere in its row and then click the **“Delete Plant”** button.



The following confirmation dialog box will appear (with the appropriate plant name, of course):



Click the **Yes** button to confirm you want to delete the plant from the database. Click the **No** button if you do not want to delete the plant.




Important Note

When you have finished deleting plants, it is vitally important that you save the changes to the database by clicking the **“Save Database”** button. If you don’t, the plants will not be permanently deleted.

Save Database

After you have done any editing, inserting or deleting of plants, you should click the **“Save Database”** button so the changes are stored permanently in the database. If you don’t, the changes will not be remembered by LANDWorksCAD, i.e., plants you thought you added to the database will not be there, plants you thought you deleted will still be there, etc.





Note

You can edit the database in Excel while LANDWorksCAD is running, but you cannot and must not edit the database from within LANDWorksCAD while the database is open in Excel.

This is not a limitation of LANDWorksCAD; it is simply how files work in Windows – you cannot work on the same file, at the same time, with two different programs. If the database is open in Excel when you save it from LANDWorksCAD, you will get an error message and LANDWorksCAD will lock up or crash.

Reload Database

Clicking the “**Reload Database**” button forces LANDWorksCAD to re-read the plant database and show any changes that have occurred since LANDWorksCAD started.



This would be necessary if the database was edited in Excel while LANDWorksCAD was running.

It would also be necessary if you have been editing the plant database from within LANDWorksCAD and have made a few mistakes (it does happen!) and want to start again.

Label Concept Plant




PURPOSE: To label concept plants inserted from the LANDWorksCAD Excel plant database (using the **Insert Concept Plant** command – refer to previous section) for identification on the landscape drawing.



[Click to watch Label Concept Plants Video on YouTube](#)

When the command is selected, the following dialog box is displayed.



Text Size

This box lets you define the size of the label text. Text size is influenced by the next option, **Scale Text by the Plot Scale** and can work in either of the following two ways

1. If the **Scale Text by the Plot Scale** option is ticked, then the text size entered is automatically multiplied by the view's Plot Scale and the text is displayed on the screen at that scaled size.

For example, if a text size of 4mm is entered and the Plot Scale is 100, the text will be displayed on screen at 400mm high.

This technique lets you define the text size based on the height you want it to be when it is printed on paper. If the Plot Scale is changed for some reason, the on-screen text height will automatically adjust, but, providing you print the drawing at the specified Plot Scale, the text will always print at the height specified.

For example, a text height of 4mm and a Plot Scale of 100 produces on-screen text at 400mm high. Printing the drawing at a scale of 1:100 will produce text 4mm high on the paper. Change the Plot Scale to 200 and the on-screen text will become 800mm high, but printing the drawing at a scale of 1:200 will still produce text 4mm high on the paper.

2. If the **Scale Text by the Plot Scale** option is not ticked, then the text size entered is the on-screen height. It is not, in any way, affected by the view's Plot Scale.


For the text to be visible on the screen, the size must be calculated accordingly.

This technique will produce printed text of a different size if the Plot Scale is changed.

For example, if a text height of 400mm is specified and the Plot Scale is 100, the printed text will be 4mm high, but if the Plot Scale is changed to 200, the printed text would be 2mm high.

Scale Text by the Plot Scale

This tick box controls whether the text size entered is automatically multiplied by the view's Plot Scale for on-screen display. Refer to the previous section, **Text Size** for more details.



Inserting the Label

When the **OK** button is clicked, LANDWorksCAD scans the drawing for any concept plants that haven't been labelled. If it finds some, it highlights in grey the last plant inserted and its label is attached to your crosshair letting you position it where it suits you.

The label for the plant is comprised of the text in the "Heading" and "Label" columns of the plant database. These columns are displayed in the "Selected Items" area of the "Insert Concept Plant" dialog box.

When you have placed the label for that concept plant, if there are any others that have not been labelled, the next one is highlighted, its label attached to your crosshair and so on.




Note

1. You do not have to select the plants at any stage
2. The selection of plants is done in reverse order, i.e., the last plant inserted is highlighted first, then the second last plant inserted, etc.
3. If you have the same concept plants inserted at various positions on the drawing, you will only be able to label one group of them using this command. To label the other groups of plants, simply copy the labels.


YouTube™ Video

[Click to watch Label Concept Plants Video on YouTube](#)


The following steps show how the command works.




The command is selected and the text properties set. When the OK button is clicked, the last green plant is highlighted in grey and its label attached to the crosshair, as shown below.



When the first label is inserted, the next concept plant is highlighted (left) and its label is attached to the crosshair, as shown below.



When the second label is inserted, the next concept plant is highlighted (top-right) and its label is attached to the crosshair, as shown below. This would, of course, continue if there were more plants that had not be labelled.



When the last label has been inserted, the command stops.

Insert Existing Plant




PURPOSE: To select and insert a figure to represent the plant(s) in your landscape plan that already exist on-site.



Click to watch Insert Existing Plant (One Point) Video on YouTube

When the command is selected, the following dialog box is displayed.




This command also lets you edit your LANDWorksCAD Excel plant database from within LANDWorksCAD. This is explained at the end of this section. For details on editing your plant database directly in Microsoft Excel, refer to [Appendix 2 – Editing the Plant Database in Excel](#) on page 153.

Selecting an Existing Plant

The “**Selected Items**” area at the top of the dialog box lists the plants defined in the “**Existing Plants**” tab of your LANDWorksCAD Excel plant database.

This database is called **LandworksPlantDatabase.xls** and is found in the LANDWorksCAD folder on your computer. Refer to [Appendix 1 – The LANDWorksCAD Plant Database](#) on page 142 for more details on the database.




Note

The buttons just below the selected items area, i.e., “Insert New Plant”, “Delete Plant”, etc. let you edit your plant database from within LANDWorksCAD and are explained later in the section entitled [Editing Existing Plants from within LANDWorksCAD](#) on page 43.

Scrolling down will show more plants; scrolling sideways will show more data for the plants (if necessary).

Click once anywhere in the row of data for the plant you want. Preview images of the plant will be displayed in the two, bottom, right hand boxes. Both of the boxes will not necessarily display previews; it depends on what has been defined in your LANDWorksCAD Excel plant database.

The two previews show the ways the plan view of the plant can be displayed in the drawing. You can switch between these displays whenever you want to after the plant has been inserted – refer to the [Plant Display Switching](#) command on page 91.



The “**Figure**” preview is of a LANDWorksCAD drawing file, i.e., it must have been drawn in LANDWorksCAD or created in another CAD program and then imported and saved in LANDWorksCAD.

The “**Image**” preview is of a JPG or BMP (bitmap) format file. This could be an actual photograph of the plant or it could be an artistic representation that has been created outside of LANDWorksCAD using image editing software, e.g., PhotoImpact. The JPG format is preferred because file sizes are much smaller.

Having two ways of displaying the plan view of the plant gives you flexibility in how you present your concept drawings and, as stated earlier, you can switch between them whenever you want to.

It is up to you to decide how simple or detailed the plan concept figure is.

Likewise it is up to you to decide if the image display is an actual photograph or a computer generated image.


Both plan displays do not have to be created for every plant, though obviously you must use at least one or nothing will be displayed on the screen.

The plan display to be inserted can be selected by clicking in the white dot above the preview so that a smaller black dot appears within it.

Inserting the Selected Existing Plant


Inserting the selected existing plant is a two-step process:

1. Select the diameter of the plant,
2. Insert the plant using the appropriate insertion method



Select the Diameter of the Plant

The diameter of the plant can be selected from the “Diameter” box, as shown below:



If the required diameter is not listed it can simply be typed directly into the box.

The word “Default” means the plant will be inserted at the size it was originally drawn.

Insert the Plant Using the Appropriate Insertion Method

Once the diameter has been selected, the plant can be inserted into your drawing in three different ways: “1 Point”, “2 Points” or “Scale 2 Points”. These methods are explained below.



Note

If you intend to label the existing plants using the [Label Existing Plant](#) command (page 49), it is not really important which of the following insertion techniques are used because the figure will be automatically re-sized to match the data entered.

Insert Plant by 1 Point



Clicking either of these buttons attaches an image of the plan view of the plant to your crosshair and the plant is inserted where you click your left mouse button.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.



Video

[Click to watch Insert Existing Plant \(One Point\) Video on YouTube](#)

Insert Plant by 2 Points



Clicking either of these buttons attaches an image of the plan figure of the plant to your crosshair, but two mouse clicks are required to insert it. The first mouse click positions the plant figure; the second click defines the orientation of the plant, ie, you can spin it around.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.

You Tube™ Video

[Click to watch Insert Existing Plant \(Two Points\) Video on YouTube](#)

Insert Plant by Scale 2 Points



Clicking either of these buttons attaches an image of the plan figure of the plant to your crosshair, but two mouse clicks are required to insert it. The first mouse click positions the plant figure; the second click defines the orientation and size, or scale, of the plant, ie, you can spin it around and you can also make it larger or smaller than the original image.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.

You Tube™ Video


[Click to watch Insert Existing Plant \(Scale Two Points\) Video on YouTube](#)

This technique ignores the Diameter box.



Note


If a plant has not been selected before any of these buttons are clicked, the following dialog box will be displayed, indicating that a plant must be selected from the “Selected Items” list.



Tip

If you want to insert more copies of a plant that you have already inserted you don't have to use this command again, you can simply copy the plants. They will still be recognised as plants from your database.

Replacing Already Inserted Existing Plants



The **“Replace”** button lets you replace plants that have already been inserted into the drawing with other plants from the database.

This can be done in either of two ways:

1. You can select the plants to be replaced and then run the command, or
2. You can run the command first and then select the plants to be replaced

The two methods are nearly identical. The main difference is in how you can select the plants to be replaced.

Select the plants to be replaced and then run the command

Video

[Click to watch Replace Existing Plants Prior Selection Video on YouTube](#)

- Step 1 – Select the plants that have already been inserted into the drawing. You can use any selection technique for this.
- Step 2 – Run the **Insert Existing Plant** command.
- Step 3 – Select the replacement plant from the “Selected Items” list.
- Step 4 – Click the **“Replace”** button.

The selected plants will be replaced.

Run the command first and then select the plants to be replaced

YouTube™ Video

Click to watch Replace Existing Plants (One by One) Video on YouTube


- Step 1 – Run the **Insert Existing Plant** command.
- Step 2 – Select the replacement plant from the “Selected Items” list.
- Step 3 – Click the “**Replace**” button.
- Step 4 – Select the plants that have already been inserted into the drawing. You can only select plants one at a time using this method.

The selected plants will be replaced.

Editing Existing Plants from within LANDWorksCAD

The buttons and tick box displayed just below the “Selected Items” area let you edit your plant database from within LANDWorksCAD. This means you don’t actually have to know anything about Microsoft Excel to be able to edit your database.

However, your plant database can also be edited directly in Microsoft Excel. Refer to **Appendix 2 – Editing the Plant Database in Excel** on page 153 for details.



When the dialog box is displayed, the buttons giving you access to the plant database – “**Insert New Plant**”, “**Delete Plant**” and “**Save Database**” – are “greyed-out”, ie, they are not accessible. This is to avoid plant data being accidentally edited. The “**Reload Database**” button is available in case the database has been edited in Excel while LANDWorksCAD is open.




Important Note

You can edit the database in Excel while LANDWorksCAD is running, but you cannot and must not edit the database from within LANDWorksCAD while the database is open in Excel.

This is not a limitation of LANDWorksCAD; it is simply how files work in Windows – you cannot work on the same file, at the same time, with two different programs. If the database is open in Excel when you save it from LANDWorksCAD, you will get an error message and LANDWorksCAD will lock up or crash.

To activate the greyed-out buttons and allow editing of your plant database, click the “**Allow Editing**” box, so that a tick is visible. The buttons will then look like this:



You can also edit plants that are already in the database, although there is no specific button for this.

The editing functionality is explained below:

Edit an Existing Plant already in the Database (no button)




Video

[Click to watch Editing Existing Plant Database Video on YouTube](#)

To edit the data of a concept plant already in the database simply click on the text and edit it. The row of data will be highlighted in green, except for the specific text to be edited, which will remain white for ease of typing.


You can also press the Tab key to move to the next column.

To change the figure or image file for the plant, simply click in the relevant preview box and the following dialog box will be displayed allowing you to browse for the appropriate file.



When you have found the file, select it and click the **Open** button. The file will then be displayed in the preview box.

When you select a plant figure or image using this technique, LANDWorksCAD is editing data to columns you can't see, "behind the scenes". This data is the path and filename of the selected figure/image file. If you cancel the dialog box, the following message will appear:



Click the **Yes** button if you want to completely clear the filename data that was entered, if any. Click the **No** button if you want to retain the filename data that was there, if any.



Note

1. When browsing for figures, the “**Files of type**” section of the dialog box is limited to “**CAD Files *.dwg**” so you will only see LANDWorksCAD type files. Elevation/3D figures have a “-E” at the end of their name for ease of identification.
2. When browsing for image files, the “**Files of type**” section of the dialog box is limited to “**Image Files *.bmp, *.jpg**” so you will only see those types of files. Elevation/3D image files have a “-E” at the end of their name for ease of identification.
3. Selecting the appropriate plant figure/image file is a simple process, but there is one important prerequisite – the figure or image file must exist before it can be selected, ie, it must have been drawn/created first.



Important Note

When you have finished editing your plants, it is vitally important that you save the changes to the database by clicking the “**Save Database**” button (see below). If you don’t, you will lose the changes.

Insert New Plant



[Click to watch Insert New Concept Plants in Database Video on YouTube](#)

There are two stages to inserting a new plant:

1. Entering the data, and
2. Selecting the appropriate figures and image files

Entering the data

When the “**Insert New Plant**” button is clicked, a blank row is inserted above the plant that is currently selected in the “Selected Items” list. The relevant data for the new plant can then be typed in.

Selected Items:

Index	plan figure name	image file ...	description	category
32	Figures\Plants\TT01.dwg	Figures\Pl...	Remove	
33	Figures\Plants\TT02.dwg		Retain	
34	Figures\Plants\TT03.dwg			
35	Figures\Plants\TT04.dwg			
36	Figures\Plants\TT05.dwg			
37	Figures\Plants\TT06.dwg			

☒ Allow Editing

To enter the data, click on the blank row, in the column you want to edit and type in the required data. When you select the blank row it will be highlighted in green, but the part of the row in the column you selected will remain white.

You can also press the Tab key to move to the next column.

Multiple new plants can be inserted by simply clicking the button again and entering the data.

It's up to you to decide how much data you enter. Most columns are not compulsory. Refer to [Appendix 1 – The LANDWorksCAD Plant Database](#) on 142 for details on the database.

Selecting the appropriate figures and image files

Once the botanical data has been entered, appropriate LANDWorksCAD figures and image files must be selected to represent the plant in the drawing.

To select the plant figure or image file, simply click in the relevant preview box and browse and select the appropriate file, as described in the [Edit an Existing Plant already in the Database \(no button\)](#) section above.

Note that both of the preview boxes do not have to be filled in, but at least one must be, otherwise there will be nothing to see when the plant is inserted.

The Elevation/3D figures and images are not required at all if you are only working in 2D.



Important Note


When you have finished inserting your plants, it is vitally important that you save them to the database by clicking the **“Save Database”** button (see below). If you don't, you will lose them.

Delete Plant


YouTube™ Video

[Click to watch Delete Concept Plants in Database Video on YouTube](#)

To delete a plant, select the plant by clicking anywhere in its row and then click the **“Delete Plant”** button.



The following confirmation dialog box will appear (with the appropriate plant name, of course):



Click the **Yes** button to confirm you want to delete the plant from the database. Click the **No** button if you do not want to delete the plant.




Important Note

When you have finished deleting plants, it is vitally important that you save the changes to the database by clicking the **“Save Database”** button (see below). If you don't, the plants will not be permanently deleted.

Save Database

After you have done any editing, inserting or deleting of plants, you should click the “**Save Database**” button so the changes are stored permanently in the database. If you don’t, the changes will not be remembered by LANDWorksCAD, i.e., plants you thought you added to the database will not be there, plants you thought you deleted will still be there, etc.




Note

You can edit the database in Excel while LANDWorksCAD is running, but you cannot and must not edit the database from within LANDWorksCAD while the database is open in Excel.

This is not a limitation of LANDWorksCAD; it is simply how files work in Windows – you cannot work on the same file, at the same time, with two different programs. If the database is open in Excel when you save it from LANDWorksCAD, you will get an error message and LANDWorksCAD will lock up or crash.

Reload Database

Clicking the “**Reload Database**” button forces LANDWorksCAD to re-read the plant database and show any changes that have occurred since LANDWorksCAD started.



This would be necessary if the database was edited in Excel while LANDWorksCAD was running.

It would also be necessary if you have been editing the plant database from within LANDWorksCAD and have made a few mistakes (it does happen!) and want to start again.

Label Existing Plant




PURPOSE: To label existing plants inserted from the LANDWorksCAD Excel plant database (using the [Insert Existing Plant](#) command – refer to previous section) for identification on the landscape drawing and for inclusion in a schedule of existing plants.



[Click to watch Label Concept Plants Video on YouTube](#)

The data entered in this command is the data typically collected when the client's property is surveyed.

When the command is selected, the following dialog box is displayed.



The dialog box titled "Label Existing Plant" contains the following fields and controls:

- Botanical Name: A text input field.
- Record item using: A dropdown menu with "botanical name" selected.
- Name used in schedule: A text input field.
- Label Prefix: A text input field containing "T".
- Text Size: A text input field containing "500", followed by a unit label "mm".
- Trunk Diameter: A text input field containing "300".
- Height: A text input field containing "4000".
- Spread: A text input field containing "6000", followed by a "Change spread" checkbox which is checked.
- Status 1: A dropdown menu.
- Status 2: A dropdown menu.
- Comments: A text input field.
- Scale text by the plot scale: An unchecked checkbox.
- Buttons: "OK" and "Cancel" buttons at the bottom.

The "Label Prefix" is used to actually label the plant; the other data will be displayed in the "Existing Plant Schedule" when it is inserted. (Refer to the [Existing Plant Schedule](#) command on page 55)



Note

For an existing plant figure to be included in the **Existing Plant Schedule** it MUST be labelled with this command first.


An example of a label is shown below – the “T1” text.



Botanical Name

This box lets you choose the botanical name of the existing plant you are about to label.


Clicking on the triangle at the end of the box displays a list of the botanical names from your plant database, as shown below:



Label Item

This box lets you choose which data from the database will be used to identify the existing plant in the Existing Plant Schedule.

Clicking on the triangle at the end of the box displays a list of the field names from your plant database, as shown below:



In the example below, the tree being labelled is an *Acacia buxifolia*, but it will be identified in the Existing Plant Schedule with its abbreviation, ie, Ac bu.

Botanical Name	Acacia Buxifolia
Record item using	abbreviation
Name used in schedule	Ac Bu

Name used in schedule

This box displays the actual identifying text that will be displayed in the Existing Plant Schedule, e.g., “Ac bu” in the example above.


Label Prefix

This box lets you enter text that will be displayed as a label for the plant on the drawing. Any amount of text can be entered.

Numbers are automatically appended to the prefix, ensuring the labels are unique.

Typically the prefix would be a code to identify the type of plant, e.g., “T” for tree, “S” for shrub, etc. but it can be anything.

Examples are shown below.



Text Size

This box lets you define the size of the label text. Text size is influenced by the bottom tick box, **Scale Text by the Plot Scale** and can work in either of the following two ways

1. If the **Scale Text by the Plot Scale** option is ticked, then the text size entered is automatically multiplied by the view's Plot Scale and the text is displayed on the screen at that scaled size.

For example, if a text size of 4mm is entered and the Plot Scale is 100, the text will be displayed on screen at 400mm high.

This technique lets you define the text size based on the height you want it to be when it is printed on paper. If the Plot Scale is changed for some reason, the on-screen text height will automatically adjust, but, providing you print the drawing at the specified Plot Scale, the text will always print at the height specified.

For example, a text height of 4mm and a Plot Scale of 100 produces on-screen text at 400mm high. Printing the drawing at a scale of 1:100 will produce text 4mm high on the paper. Change the Plot Scale to 200 and the on-screen text will become 800mm high, but printing the drawing at a scale of 1:200 will still produce text 4mm high on the paper.

2. If the **Scale Text by the Plot Scale** option is not ticked, then the text size entered is the on-screen height. It is not, in any way, affected by the view's Plot Scale.

For the text to be visible on the screen, the size must be calculated accordingly.

This technique will produce printed text of a different size if the Plot Scale is changed.

For example, if a text height of 400mm is specified and the Plot Scale is 100, the printed text will be 4mm high, but if the Plot Scale is changed to 200, the printed text would be 2mm high.

Trunk Diameter

This box lets you enter the actual diameter of the trunk of the plant, in mm, as measured on site.

Height

This box lets you enter the actual height of the plant, in mm, as measured on site.


Spread

This box lets you enter the actual spread, or foliage diameter, of the plant, in mm, as measured on site. The value of the 'Spread' is used to automatically re-size the selected figure to the correct diameter.

Status 1

This box lets you select from four, standard, predefined status notes to be included in the Existing Plant Schedule.

Clicking on the triangle at the end of the box displays the four notes, as shown below. Simply delete the note if you do not want it included in the schedule.



The screenshot shows a form with three rows: 'Status 1', 'Status 2', and 'Comments'. The 'Status 1' row has a text input field followed by a dropdown arrow. The dropdown menu is open, showing four options: 'Almost Dead', 'Infected', 'Remove', and 'Retain'. The 'Status 2' row has a text input field, and the 'Comments' row has a text input field.

Status 2

This box lets you select from four, standard, predefined status notes to be included in the Existing Plant Schedule.

Clicking on the triangle at the end of the box displays the four notes, as shown below. Simply delete the note if you do not want it included in the schedule.

Status 1	Almost Dead
Status 2	
Comments	Almost Dead Infected Remove Retain
Scale text by the plot scale	

Comments

This box lets you type in additional information to be included in the Existing Plant Schedule. The amount of text is not limited by the width of the box.

Scale Text by the Plot Scale


This tick box controls whether the text size entered is automatically multiplied by the view's Plot Scale for on-screen display. Refer to the earlier section, [Text Size](#), for more details.

Inserting the Label


When the **OK** button is clicked, the steps to label the plant are as follows:

1. Select the plant to label.

When the plant is selected, it turns grey and the prefix label and number are attached to your crosshair, as shown below.



2. Position the label and click to insert it.
3. The label is inserted and the figure is re-sized to match the "spread" value entered, as shown below.



4. The command is automatically re-run, letting you label more plants.

Existing Plant Schedule



PURPOSE: To automatically generate a schedule of existing plants based on the criteria entered using the **Label Existing Plant** command.



Click to watch Existing Plant Schedule Video on YouTube



Note

For an existing plant figure to be included in the Existing Plant Schedule it **MUST** be labelled with **Label Existing Plant** command first.

A sample Legend is shown below.

Existing Tree Schedule								
No	Species	Name	Trunk Diam	Height	Spread	Status	Status 2	Comments
T1	Abies Grandis	Ab Gr	300mm	4000mm	1000mm			
T2	Abies Grandis	Ab Gr	300mm	4000mm	1000mm			
T3	Abies Grandis	Ab Gr	300mm	4000mm	1000mm			
Sh4	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			
Sh5	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			
Sh6	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			
Sh7	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			

When the command is selected, the following dialog box is displayed.

Insert Plant Schedule

Heading: Existing Tree Schedule

Table Size: 200 mm

Show:

- ☒ Botanical Name
- ☒ Spread
- ☒ Schedule Name
- ☒ Status
- ☒ Diameter
- ☒ Borders
- ☒ Show Height

OK Cancel

Heading

Text typed in this box will be displayed at the top of the Schedule as a heading. If you do not want a heading leave this box blank

Table Size

This box controls the height, in mm, of each row in the Schedule. It should be adjusted to suit the scale of the drawing you are creating.

A simple “rule of thumb” to determine a suitable size for the table is as follows:

1. Decide how high you want the Legend text to be when printed, e.g., 4mm
2. Add 2mm, to allow a 1mm space above and below the text, → 6mm
3. Multiply that number by the Plot Scale, e.g., a Plot Scale of 200 gives 1200
4. Use this final number as the “Table Size”

Show Diameter

If this box is ticked the **trunk diameter** of the plants, as entered in the **Label Existing Plant** command, will be included in the Schedule.

Show Height

If this box is ticked the **height** of the plants, as entered in the **Label Existing Plant** command, will be included in the Schedule.

Show Spread

If this box is ticked the **spread** of the plants, as entered in the **Label Existing Plant** command, will be included in the Schedule.

Show Status

If this box is ticked the **Status 1**, **Status 2** and **Comments** text, as entered in the **Label Existing Plant** command, will be included in the Schedule.

Show Borders

If this box is ticked, border lines will be generated for the Legend.

With Border Lines

Existing Tree Schedule		
No	Species	Name
T1	Abies Grandis	Ab Gr
T2	Abies Grandis	Ab Gr
T3	Abies Grandis	Ab Gr
Sh4	Schoenoplectus Mucronatus	Sc Mu
Sh5	Schoenoplectus Mucronatus	Sc Mu
Sh6	Schoenoplectus Mucronatus	Sc Mu
Sh7	Schoenoplectus Mucronatus	Sc Mu

Without Border Lines

Existing Tree Schedule		
No	Species	Name
T1	Abies Grandis	Ab Gr
T2	Abies Grandis	Ab Gr
T3	Abies Grandis	Ab Gr
Sh4	Schoenoplectus Mucronatus	Sc Mu
Sh5	Schoenoplectus Mucronatus	Sc Mu
Sh6	Schoenoplectus Mucronatus	Sc Mu
Sh7	Schoenoplectus Mucronatus	Sc Mu

Inserting the Schedule

When the **OK** button is clicked, you are prompted to “Locate the position of the tree schedule”. This is the **top, left** corner of the Schedule. A single click will generate the Schedule.

A sample Schedule is shown below.

Existing Tree Schedule								
No	Species	Name	Trunk Diam	Height	Spread	Status	Status 2	Comments
T1	Abies Grandis	Ab Gr	300mm	4000mm	1000mm			
T2	Abies Grandis	Ab Gr	300mm	4000mm	1000mm			
T3	Abies Grandis	Ab Gr	300mm	4000mm	1000mm			
Sh4	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			
Sh5	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			
Sh6	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			
Sh7	Schoenoplectus Mucronatus	Sc Mu	300mm	4000mm	500mm			



Note

The Schedule does not automatically update if you add or delete plant labels after inserting it. To update the Schedule simply run this command again (it will remember how you set it up last time) and click the top, left corner of it.

You can, of course, click somewhere else if you want to re-position the Schedule.

You do not need to delete the existing Schedule before updating it.

Insert Proposed Plant




PURPOSE: To select and insert a figure to represent the plant(s) you are proposing for a landscape plan.



Click to watch [Insert Proposed Plant \(One Point\) Video on YouTube](#)

The appropriate type of plant can be searched for and already inserted plants can be replaced.

When the command is selected, the following dialog box is displayed.



This command also lets you edit your LANDWorksCAD Excel plant database from within LANDWorksCAD. This is explained at the end of this section. For details on editing your plant database directly in Microsoft Excel, refer to [Appendix 2 – Editing the Plant Database in Excel](#) on page 153.

Selecting a Proposed Plant

The “**Selected Items**” area at the top of the dialog box lists the plants defined in the “**Plants**” tab of your LANDWorksCAD Excel plant database. This database is called **LandworksPlantDatabase.xls** and is found in the LANDWorksCAD folder on your computer. Refer to [Appendix 1 – The LANDWorksCAD Plant Database](#) on page 142 for more details on the database.

Selected Items:						
Index	abbreviation	abbreviati...	botanical name	family	common name	comm
32	Ab x Gr	Abe x Gra	Abelia X Grandiflora	Caprifoliaceae	Glossy Abelia	
33	Ab x Gr Na	Abe x Gra...	Abelia X Grandiflora 'Nana'	Caprifoliaceae	Dwarf Abelia	
34	Ab x Gr Su	Abe x Gra...	Abelia X Grandiflora 'Sunrise'	Caprifoliaceae	Dwarf Pink variegated Abelia	
35	Ab x Gr Va	Abe x Gra...	Abelia X Grandiflora 'Variegata'	Caprifoliaceae	Pink	cream
36	Ab Gr	Abi Gra	Abies Grandis	Pinaceae	Grand Fir	Giant
37	Ab Ma	Abi Ma	Abies Nordmanniana	Pinaceae	Canadian Silver Fir	Nand




Note

The buttons just below the selected items area, i.e., “Insert New Plant”, “Delete Plant”, etc. let you edit your plant database from within LANDWorksCAD and are explained later in the section entitled [Editing Proposed Plants from within LANDWorksCAD](#) on page 70.

Scrolling down will show more plants; scrolling sideways will show more data for the plants.

Click once anywhere in the row of data for the plant you want. Preview images of the plant will be displayed in the six, bottom, right hand boxes. Not all of the boxes will necessarily display previews; it depends on what has been defined in your LANDWorksCAD Excel plant database.

The top row of previews shows three ways the plan view of the plant can be displayed in the drawing. You can switch between these displays whenever you want to after the plant has been inserted – refer to the [Plant Display Switching](#) command on page 91.



The “**Basic Figure**” and “**Detailed Figure**” previews are of LANDWorksCAD drawing files, i.e., they must have been drawn in LANDWorksCAD or created in another CAD program and then imported and saved in LANDWorksCAD.

The “**Image**” preview is of a JPG or BMP (bitmap) format file. This could be an actual photograph of the plant or it could be an artistic representation that has been created outside of LANDWorksCAD using image editing software, e.g., PhotoImpact. The JPG format is preferred because file sizes are much smaller.

Having three ways of displaying the plan view of the plant gives you maximum flexibility in how you present your landscape drawings, e.g., for concept plans, construction plans, presentation plans, etc. and, as stated earlier, you can switch between them whenever you want to.


It is up to you to decide just how “basic” the basic display is or how “detailed” the detailed display is. Either can be as simple or as complex as you wish.

Likewise it is up to you to decide if the image display is an actual photograph or a computer generated image.

All three plan displays do not have to be created for every plant, though obviously you must use at least one or nothing will be displayed on the screen.

The plan display to be inserted can be selected by clicking in the white dot above the preview so that a smaller black dot appears within it.

The information explained above also pertains to the Elevation/3D previews; the Basic and Detailed figures are LANDWorksCAD drawing files and the Image is a JPG or BMP file.




Note

The Elevation/3D figures cannot be inserted using this command. They can be generated automatically via the **Insert 3D Plants** command on page 128 or inserted manually.

Inserting the Selected Proposed Plant


Inserting the selected existing plant is a two-step process:

1. Select the diameter of the plant,
2. Insert the plant using the appropriate insertion method



Select the Diameter of the Plant

The diameter of the plant can be selected from the “Diameter” box, as shown below:



If the required diameter is not listed it can simply be typed directly into the box.

The word “Default” means the plant will be inserted at the size it was originally drawn.

Insert the Plant Using the Appropriate Insertion Method

Once the diameter has been selected, the plant can be inserted into your drawing in three different ways: “1 Point”, “2 Points” or “Scale 2 Points”. These methods are explained below.

Insert Plant by 1 Point



Clicking either of these buttons attaches an image of the plan view of the plant to your crosshair and the plant is inserted where you click your left mouse button.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.



[Click to watch Insert Proposed Plant \(One Point\) Video on YouTube](#)

Insert Plant by 2 Points




Clicking either of these buttons attaches an image of the plan figure of the plant to your crosshair, but two mouse clicks are required to insert it. The first mouse click positions the plant figure; the second click defines the orientation of the plant, ie, you can spin it around.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.



[Click to watch Insert Proposed Plant \(Two Points\) Video on YouTube](#)

Insert Plant by Scale 2 Points



Clicking either of these buttons attaches an image of the plan figure of the plant to your crosshair, but two mouse clicks are required to insert it. The first mouse click positions the plant figure; the second click defines the orientation and size, or scale, of the plant, ie, you can spin it around and you can also make it larger or smaller than the original image.

Note: If inserting the image, a rectangle will be displayed on the crosshair; the image won't actually appear until you click.

You Tube™ Video


[Click to watch Insert Proposed Plant \(Scale Two Points\) Video on YouTube](#)

This technique ignores the Diameter box.



Note

If a plant has not been selected before any of these buttons are clicked, the following dialog box will be displayed, indicating that a plant must be selected from the “Selected Items” list.




Tip

If you want to insert more copies of a plant that you have already inserted you don't have to use this command again, you can simply copy the plants. They will still be recognised as plants from your database.

Searching for Proposed Plants

You can search for the plant you want using the **Search Fields** part of the command. You can search on any of the data in the “Concept Plants” sheet of your LANDWorksCAD Excel plant database.



The "Search Fields" dialog box is shown. It has a table with three columns: "Field Name", "Operator", and "Value". The "Field Name" column lists several options: "plan figure name", "elev. figure name", "3D figure name", "image file name", "detail plan figure name", "detail elev. figure name", and "elev. image file name". Below the table are "Search" and "Reset" buttons.

Field Name	Operator	Value
plan figure name		
elev. figure name		
3D figure name		
image file name		
detail plan figure name		
detail elev. figure name		
elev. image file name		

The *Field Name* column lists every column from your database; the *Operator* column controls the range of data you are searching for and the *Value* column provides limits for the search.


The database can be search in two ways, although they are similar.

Method 1



[Click to watch Searching Proposed Plant \(Method 1\) Video on YouTube](#)


Double-click on the desired Field Name. This activates the “*Compare Field Name Properties*” dialog box as shown below. Here the “*Type*” field was selected.




The "Compare Field Name Properties" dialog box is shown. It has three fields: "Field Name" (containing "type"), "Operator" (a drop-down menu), and "Value" (a drop-down menu). Below the fields are "OK" and "Cancel" buttons.

Field Name	type
Operator	
Value	


Select the type of search “*Operator*” from the drop-down list, as shown below. Here “*Equal*” is selected.



Select the desired search “Value” from the drop-down list as shown below. Here “Palm” is selected. The values in the drop-down list will vary depending on the Field Name selected. The values are extracted from your database.



Click *OK* to finish the process. Your Search Fields area will look as shown below.



You may repeat the above steps with other Field Names to create multiple search criteria, e.g., you might be searching for all trees that have an oval shape.

When you’re happy with the search criteria, click the “**Search**” button. The Selected Items area will change and display only the items that match the search criteria. For example, the image below shows only Trees.

Selected Items:

Index	abbreviation	abbreviati...	botanical name	family	common name	common r...	type	habit
256	Ar Al	Arc Ale	Archontopho...	Palmae	Alexandra Palm	King Palm	Palm	
257	Ar Cu	Arc Cun	Archontopho...	Palmae	Bangalow Palm	Piccabee...	Palm	
424	Bu Ca	But Cap	Butia Capitata		Jelly Palm		Palm	
522	Ca Ac	Car Acu	Carpentaria A...	Palmae	Carpentaria Palm		Palm	
594	Ch Lu	Chr Lut	Chrysalidocar...	Arecaceae	Golden Cane Palm		Palm	
620	Ca Mu	Car Mus	Coccothrinax	Arecaceae	Coconut Palm		Palm	

☐ Allow Editing

The desired plant can now be selected from the filtered list and inserted as described above.

Method 2



[Click to watch Searching Proposed Plant \(Method 2\) Video on YouTube](#)

Click once on the desired “Field Name”. The Field Name will be highlighted as shown below. Here the “Type” field was selected.

Search Fields:

Field Name	Operator	Value
Cultivars		
favourites		
type		
habit		
texture		
maximum width		
maximum height		

Click in the green highlighting line under the “Operator” heading. A drop down field will appear. Select the type of search “Operator” from the drop-down list, as shown below. Here “Equal” is selected.

Search Fields:

Field Name	Operator	Value
Cultivars		
favourites		
type		
habit		
texture		
maximum width		
maximum height		

Search R

Operator dropdown menu:

- Equal
- Not Equal
- Less Than
- Greater Than
- ==
- !=
- <=

Now click the green highlighting line under the “Value” heading. A drop down field will appear. Select the desired search “Value” from the drop-down list as shown below. Here “Palm” is selected. The values in the drop-down list will vary depending on the Field Name selected. The values are extracted from your database.

Search Fields:

Field Name	Operator	Value
Cultivars		
favourites		
type	Equal	Palm
habit		
texture		
maximum width		
maximum height		

Search Reset

Value dropdown menu:

- Wildflower
- Vine
- Vegetable
- Tree
- Shrub
- Succulent
- Perennial
- Palm

Your Search Fields area will look as shown below.

Search Fields:

Field Name	Operator	Value
Cultivars		
favourites		
type	Equal	Palm
habit		
texture		
maximum width		
maximum height		

Search Reset

You may repeat the above steps with other Field Names to create multiple search criteria, for example, you might be searching for all trees that have an oval shape.

When you're happy with the search criteria, click the **"Search"** button. The Selected Items area will now display only the items matching the search criteria, for example, the image below shows only trees.

Selected Items:

Index	abbreviation	abbreviati...	botanical name	family	common name	common r...	type	habit
256	Ar Al	Arc Ale	Archontopho...	Palmae	Alexandria Palm	King Palm	Palm	
257	Ar Cu	Arc Cun	Archontopho...	Palmae	Bangalow Palm	Piccabee	Palm	
424	Bu Ca	But Cap	Butia Capitata		Jelly Palm		Palm	
522	Ca Ac	Car Acu	Carpentaria A...	Palmae	Carpentaria Palm		Palm	
594	Ch Lu	Chr Lut	Chrysalidocar...	Arecaceae	Golden Cane Palm		Palm	
620	Ca Mu	Car Mus	Casuarina Mus...	Arecaceae	Casuarina Palm		Palm	

☐ Allow Editing

The desired plant can now be selected from the filtered list and inserted as described above.

Resetting the Search Criteria

To clear the filtered list of plants and display all the plants in the database again, click the **"Reset"** button and then click the **"Search"** button.




Search Fields:

Field Name	Operator	Value
Cultivars		
favourites		
type		
habit		
texture		
maximum width		
maximum height		

Replacing Already Inserted Proposed Plants

Insert Figure

Diameter Default

The **“Replace”** button lets you replace plants that have already been inserted into the drawing with other plants from the database.

This can be done in either of two ways:

1. You can select the plants to be replaced and then run the command, or
2. You can run the command first and then select the plants to be replaced

The two methods are nearly identical. The main difference is in how you can select the plants to be replaced.

Select the plants to be replaced and then run the command

Video

[Click to watch Replace Proposed Plants \(Prior Selection\) Video on YouTube](#)

- Step 1 – Select the plants that have already been inserted into the drawing. You can use any selection technique for this.
- Step 2 – Run the **Insert Proposed Plant** command.
- Step 3 – Select the replacement plant from the “Selected Items” list.
- Step 4 – Click the **“Replace”** button.

The selected plants will be replaced.

Run the command first and then select the plants to be replaced

Video

[Click to watch Replace Proposed Plants \(One by One\) Video on YouTube](#)


- Step 1 – Run the **Insert Proposed Plant** command.
- Step 2 – Select the replacement plant from the “Selected Items” list.
- Step 3 – Click the **“Replace”** button.
- Step 4 – Select the plants that have already been inserted into the drawing. You can only select plants one at a time using this method.

The selected plants will be replaced.

Editing Proposed Plants from within LANDWorksCAD

The buttons and tick box displayed just below the “Selected Items” area let you edit your plant database from within LANDWorksCAD. This means you don’t actually have to know anything about Microsoft Excel to be able to edit your database.

However, your plant database can also be edited directly in Microsoft Excel. Refer to [Appendix 2 – Editing the Plant Database in Excel](#) on page 153 for details.



When the dialog box is displayed, the buttons giving you access to the plant database – “**Insert New Plant**”, “**Delete Plant**” and “**Save Database**” – are “greyed-out”, i.e., they are not accessible. This is to avoid plant data being accidentally edited. The “**Reload Database**” button is available in case the database has been edited in Excel while LANDWorksCAD is open.




Important Note

You can edit the database in Excel while LANDWorksCAD is running, but you cannot and must not edit the database from within LANDWorksCAD while the database is open in Excel.

This is not a limitation of LANDWorksCAD; it is simply how files work in Windows – you cannot work on the same file, at the same time, with two different programs. If the database is open in Excel when you save it from LANDWorksCAD, you will get an error message and LANDWorksCAD will lock up or crash.

To activate the greyed-out buttons and allow editing of your plant database, click the “**Allow Editing**” box, so that a tick is visible. The buttons will then look like this:



You can also edit plants that are already in the database, although there is no specific button for this.

The editing functionality is explained below:

Edit a Proposed Plant already in the Database (no button)




[Click to watch Editing Proposed Plant Database Video on YouTube](#)

To edit the data of a proposed plant already in the database simply click on the text and edit it. The row of data will be highlighted in green, except for the specific text to be edited, which will remain white for ease of typing.


You can also press the Tab key to move to the next column.

Some columns provide a list of data to choose from, indicated by a downward pointing triangle. Clicking on the triangle displays the list, as shown below:




When such a list is available you cannot type in something that is not already in the list; you can only select data from the list. You can, however, edit and add to the list by editing the database in Excel. See [Appendix 2 – Editing the Plant Database in Excel](#) on page 153 for details on doing this.

To change the figure or image file for the plant, simply click in the relevant preview box and the following dialog box will be displayed allowing you to browse for the appropriate file.



When you have found the file, select it and click the **Open** button. The file will then be displayed in the preview box.

When you select a plant figure or image using this technique, LANDWorksCAD is editing data to columns you can't see, "behind the scenes". This data is the path and filename of the selected figure/image file. If you cancel the dialog box, the following message will appear:



Click the **Yes** button if you want to completely clear the filename data that was entered, if any. Click the **No** button if you want to retain the filename data that was there, if any.



Note

1. When browsing for figures, the "**Files of type**" section of the dialog box is limited to "**CAD Files *.dwg**" so you will only see LANDWorksCAD type files. Elevation/3D figures have a "**-E**" at the end of their name for ease of identification.
2. When browsing for image files, the "**Files of type**" section of the dialog box is limited to "**Image Files *.bmp, *.jpg**" so you will only see those types of files.
3. Elevation/3D image files have a "**-E**" at the end of their name for ease of identification. Selecting the appropriate plant figure/image file is a simple process, but there is one

important prerequisite – the figure or image file must exist before it can be selected, i.e., it must have been drawn/created first.



Important Note

When you have finished editing your plants, it is vitally important that you save the changes to the database by clicking the “**Save Database**”. If you don’t, you will lose the changes.

Insert New Plant



[Click to watch Insert New Proposed Plant \(Database\) Video on YouTube](#)

There are two stages to inserting a new plant:

1. Entering the data, and
2. Selecting the appropriate figures and image files

Entering the data

When the “**Insert New Plant**” button is clicked, a blank row is inserted above the plant that is currently selected in the “Selected Items” list. The relevant data for the new plant can then be typed in.

Index	description	category	shape	heading	label
32	Desc 1	Tree	Round	Heading 1	Label 1
33	Desc 2	Tree	Oval	Heading 2	Label 2
34	Desc 3	Shrub	Round	Evergreen	Label 3
35	Desc 4	Tall shrub	Spikey	Desert Sh...	Label 4
36	Desc 5				
37					
38					

Buttons: **Insert New Plant**, Delete Plant, Save Database, Reload Database, ☒ Allow Editing

To enter the data, click on the blank row, in the column you want to edit and type in the required data. When you select the blank row it will be highlighted in green, but the part of the row in the column you selected will remain white.

You can also press the Tab key to move to the next column.

Some columns provide a list of data to choose from, indicated by a downward pointing triangle. Clicking on the triangle displays the list, as shown below:

Selected Items:

Index	description	category	shape	heading	label
32	Desc 1	Tree	Round	Heading 1	Label 1
33	Desc 2	Tree	Oval	Heading 2	Label 2
34	Desc 3	Shrub	Round	Evergreen	Label 3
35	Desc 4	Tall shrub	Spikey	Desert Sh...	Label 4
36	Desc 5				
37					

Insert New Plant Save Database Reload Database ☒ Allow Editing

Search Fields:

When such a list is available you cannot type in something that is not already in the list; you can only select data from the list. You can, however, edit and add to the list by editing the database in Excel. [Appendix 2 – Editing the Plant Database in Excel](#) on page 153 for details on doing this.

Multiple new plants can be inserted by simply clicking the button again and entering the data.

It's up to you to decide how much data you enter. Most columns are not compulsory. Refer to [Appendix 1 – The LANDWorksCAD Plant Database](#) on page 142 for details on the database.

Selecting the appropriate figures and image files

Once the botanical data has been entered, appropriate LANDWorksCAD figures and image files must be selected to represent the plant in the drawing.

To select the plant figure or image file, simply click in the relevant preview box and browse and select the appropriate file, as described in the [Edit a Proposed Plant already in the Database \(no button\)](#) section above.

Note that both of the preview boxes do not have to be filled in, but at least one must be, otherwise there will be nothing to see when the plant is inserted.

The Elevation/3D figures and images are not required at all if you are only working in 2D.



Important Note


When you have finished inserting your plants, it is vitally important that you save them to the database by clicking the **“Save Database”** button. If you don't, you will lose them.

Delete Plant




[Click to watch Delete Proposed Plant \(Database\) Video on YouTube](#)

To delete a plant, select the plant by clicking anywhere in its row and then click the **“Delete Plant”** button.



The following confirmation dialog box will appear (with the appropriate plant name, of course):



Click the **Yes** button to confirm you want to delete the plant from the database. Click the **No** button if you do not want to delete the plant.




Important Note

When you have finished deleting plants, it is vitally important that you save the changes to the database by clicking the **“Save Database”**. If you don’t, the plants will not be permanently deleted.

Save Database

After you have done any editing, inserting or deleting of plants, you should click the **“Save Database”** button so the changes are stored permanently in the database. If you don’t, the changes will not be remembered by LANDWorksCAD, i.e., plants you thought you added to the database will not be there, plants you thought you deleted will still be there, etc.






Important Note

You can edit the database in Excel while LANDWorksCAD is running, but you cannot and must not edit the database from within LANDWorksCAD while the database is open in Excel.

This is not a limitation of LANDWorksCAD; it is simply how files work in Windows – you cannot work on the same file, at the same time, with two different programs. If the database is open in Excel when you save it from LANDWorksCAD, you will get an error message and LANDWorksCAD will lock up or crash.

Reload Database

Clicking the “**Reload Database**” button forces LANDWorksCAD to re-read the plant database and show any changes that have occurred since LANDWorksCAD started.



This would be necessary if the database was edited in Excel while LANDWorksCAD was running.

It would also be necessary if you have been editing the plant database from within LANDWorksCAD and have made a few mistakes (it does happen!) and want to start again.

Label Proposed Plant



PURPOSE: To label proposed plants inserted from the LANDWorksCAD Excel plant database (using the **Insert Proposed Plant** command – refer to previous section) for identification on the landscape drawing.




[Click to watch Label Proposed Plant Video on YouTube](#)

You can select the plant(s) to be labelled before or after running the command. Refer to the **Number of Plants** section on next page.

When the command is selected, the following dialog box is displayed.

An example of a label is shown below. It shows the botanical name of the plants, how many there are, a leader pointing to one of the plants and a connecting line. Not all these components are compulsory.



Number of Plants

This box displays the number of plants that were selected prior to running the command. If no plants were selected prior to running the command this box displays **1** and you can only label one plant at a time. This box is not editable.




Note


If you select multiple plants prior to running the command, make sure that:

1. You select only plants, and
2. You select the same type of plant


If you select entities other than plants, eg, lines or circles, the following warning box will be displayed. LANDWorksCAD can only label plants.



If you select more than one type of plant, eg, an *Acacia buxifolia* and an *Acacia snodenii* (which can look similar on the screen, depending on the figures used to represent them) the following message box will be displayed. LANDWorksCAD can only label one botanical name at a time.



Include Number




If this box is ticked, the number of selected plants will be included in the label. If the box is not ticked, the number will not be displayed. In the examples shown below, two plants were selected for labelling – the top example had the box ticked, while the bottom example did not.




Label Field Name








This box lets you choose what data from the plant database is used to identify the plants. In the examples and dialog box above the botanical name was used, but any field from your plant database can be used, e.g., abbreviation or common name. Clicking on the triangle at the end of the box displays a list of the fields from your plant database, as shown below:




Terminator Type




This box lets you choose what type of terminator you want on the end of the leader lines (if you use them). Clicking on the triangle at the end of the box displays a list of the terminator types. There are seven to choose from and they are shown below.

Terminator Type	Display
None	 Abies grandis
Arrow	 Abies grandis
Open Arrow	 Abies grandis
Filled Arrow	 Abies grandis
Dot	 Abies grandis
Filled Dot	 Abies grandis
Slash	 Abies grandis

Terminator Weight



Leader lines, if used, are drawn with the current line weight. This box lets you choose an alternate weight, or thickness, of the lines that make up the terminator. Clicking on the triangle at the end of the box displays a list of the available weights; they range from 0 to 3.0mm. There is also a “Default” option, which means the terminator lines are drawn with the same weight as the leader lines. The examples shown below have a current line weight of 0.25mm.



Terminator Size



This box lets you choose the size of the terminator. This is the length of the arrow or slash, or the diameter of the dot.

Text Size



This box lets you define the size of the label text. Text size is influenced by the next option, **Scale Text by the Plot Scale** and can work in either of the following two ways

1. If the **Scale Text by the Plot Scale** option is ticked, then the text size entered is automatically multiplied by the view's Plot Scale and the text is displayed on the screen at that scaled size. For example, if a text size of 4mm is entered and the Plot Scale is 100, the text will be displayed on screen at 400mm high.

This technique lets you define the text size based on the height you want it to be when it is printed on paper. If the Plot Scale is changed for some reason, the on-screen text height will automatically adjust, but, providing you print the drawing at the specified Plot Scale, the text will always print at the height specified.

For example, a text height of 4mm and a Plot Scale of 100 produces on-screen text at 400mm high. Printing the drawing at a scale of 1:100 will produce text 4mm high on the paper. Change the Plot Scale to 200 and the on-screen text will become 800mm high, but printing the drawing at a scale of 1:200 will still produce text 4mm high on the paper.


2. If the **Scale Text by the Plot Scale** option is not ticked, then the text size entered is the on-screen height. It is not, in any way, affected by the view's Plot Scale.

For the text to be visible on the screen, the size must be calculated accordingly.

This technique will produce printed text of a different size if the Plot Scale is changed.


For example, if a text height of 400mm is specified and the Plot Scale is 100, the printed text will be 4mm high, but if the Plot Scale is changed to 200, the printed text would be 2mm high.

Scale Text by the Plot Scale



This tick box controls whether the text size entered is automatically multiplied by the view's Plot Scale for on-screen display. Refer to the previous section, [Text Size](#) for more details.

Label with Leader Lines




This tick box controls whether leader lines are displayed for the label. The left hand example below shows a label with leader lines; the right hand example shows a label without leader lines.



Inserting the Label

When the **OK** button is clicked, you can insert the label. The steps required to do this will vary depending on what options were set in the dialog box.

For example, assume the dialog box was filled in as shown below.



The screenshot shows a dialog box titled "Label Proposed Plant" with a close button (X) in the top right corner. The dialog is divided into two main sections: "Manual Label Options" and "Auto Label Options".

Manual Label Options:

- Number of plants: 3
- Include Number: ☒
- Label field name: botanical name
- Terminator type: Arrow
- Terminator weight: Default
- Terminator size: 200 mm
- Text size: 200 mm
- Scale text by the plot scale: ☐
- Label with leader lines: ☒
- Label button

Auto Label Options:

- Label prefix: Auto Number
- Label suffix: None
- Text size: 300 mm
- Scale text by the plot scale: ☐
- Auto Label button


At the bottom of the dialog are two buttons: "Find Unlabelled" and "Cancel".

The steps required to insert the label would be as follows:

1. Locate the start of the leader (the tip of the terminator)
2. Locate the corner of the leader
3. Locate the end of the leader

The label text is inserted automatically at the end of the leader line.

An example of the resultant label might be as shown below. The ①②③ labels correspond to the three steps above.



The line joining the selected plants is inserted automatically and joins the origin points of the plants. It is inserted with the active colour, layer style and weight.

If the plants had not been selected prior to running the command, you would be prompted to select a single plant before inserting the label

If the “Label with leader lines” option was not ticked, you would only be prompted for the location of the text.

After the label has been inserted, the command remains active, letting you label more plants using the same settings, although only one plant at a time can be labelled.



Tip

Holding down the Shift key while selecting the leader points will constrain the leader lines to be either 0° (horizontal), 45° or 90° (vertical).

To create a purely horizontal (or vertical) leader, hold down the Shift key and simply draw the leader in a straight line.

Proposed Plant Legend




PURPOSE: To automatically generate a Legend of all the proposed plants that have been inserted in the drawing.




[Click to watch Proposed Plant Legend Video on YouTube](#)

A sample Legend is shown below.

Proposed Plants			
	botanical name	common name	Qty
Grass			
	Miscanthus Sinensis 'Variegatus'		6
Perennial			
	Achillea Filipendulina	Fernleaf Yarrow	3
Shrub			
	Acacia Terminalis	Sunshine Wattle	5
Tree			
	Acacia Stricta	Hop Wattle	3
	Acer Negundo KellyS Gold	Golden Box elder	4
	Acer Palmatum 'Dissectum Atropurpureum'	Japanese Maple Threadleaf	8

When the command is selected, the following dialog box is displayed.



Legend Fields

This part of the dialog box lets you select the botanical data that you want displayed in the Legend. Every column that is in the LANDWorksCAD plant database is listed here.

Double-click on a field name to toggle its display status between Yes and No. All field names marked 'Yes' will be included in the Legend.

Heading

Text typed in this box will be displayed at the top of the Legend as a heading. If you do not want a heading leave this box blank.

Group By

The plants in the Legend can be grouped by any of the field names. For example, if the plants were grouped by **Type**, all the *shrubs* would be listed together under a sub-heading of "*Shrub*"; all the *trees* would be listed together under a sub-heading of "*Tree*", etc. Any field name can be used to group the plants.

The example below shows the plants grouped by Type.

Proposed Plants		
	botanical name	con
<input type="checkbox"/>	Grass	
<input checked="" type="checkbox"/>	Miscanthus Sinensis 'Variegatus'	
<input type="checkbox"/>	Perennial	
<input checked="" type="checkbox"/>	Achillea Filipendulina	Fer
<input type="checkbox"/>	Shrub	
<input checked="" type="checkbox"/>	Acacia Terminalis	Su
<input type="checkbox"/>	Tree	
<input checked="" type="checkbox"/>	Acacia Stricta	Hq
<input checked="" type="checkbox"/>	Acer Negundo KellyS Gold	Go
<input checked="" type="checkbox"/>	Acer Palmatum 'Dissectum Atropurpureum'	Ja

Show Borders

If this box is ticked, border lines will be generated for the Legend.

With Border Lines







Proposed Plants	
	botanical name
<input type="checkbox"/>	Grass
<input checked="" type="checkbox"/>	Miscanthus Sinensis 'Variegatus'
<input type="checkbox"/>	Perennial
<input checked="" type="checkbox"/>	Achillea Filipendulina
<input type="checkbox"/>	Shrub
<input checked="" type="checkbox"/>	Acacia Terminalis
<input type="checkbox"/>	Tree
<input checked="" type="checkbox"/>	Acacia Stricta
<input checked="" type="checkbox"/>	Acer Negundo KellyS Gold
<input checked="" type="checkbox"/>	Acer Palmatum 'Dissectum Atropurpureum'

Without Border Lines

Proposed Plants	
	botanical name
<input type="checkbox"/>	Grass
<input checked="" type="checkbox"/>	Miscanthus Sinensis 'Variegatus'
<input type="checkbox"/>	Perennial
<input checked="" type="checkbox"/>	Achillea Filipendulina
<input type="checkbox"/>	Shrub
<input checked="" type="checkbox"/>	Acacia Terminalis
<input type="checkbox"/>	Tree
<input checked="" type="checkbox"/>	Acacia Stricta
<input checked="" type="checkbox"/>	Acer Negundo KellyS Gold
<input checked="" type="checkbox"/>	Acer Palmatum 'Dissectum Atropurpureum'

Show Relative Size

The Legend displays a plan figure for each plant and, by default, automatically scales the figures to fit into the given row height so they are all the same size. If this box is ticked, however, the figures are scaled in size relative to each other.

Not Ticked		Ticked	
	Palm		Palm
	Aral		Aral
	Arcu		Arcu
	Ph ro		Ph ro

Note the difference in size of the “Ph ro”.



Tip

If you insert a Legend with this option ticked and some of the plan figures don't appear, it is most likely because those plants are much smaller on the drawing than the other plants and so are tiny when inserted into the Legend. They are there; they're just so small you can see them.

Show Quantity

If this box is ticked, the second column in the Legend will show the quantity of each plant, ie, LANDWorksCAD will count your plants for you!

Show Quantity Last

If this box is ticked, the quantity figures will be in the last column of the Legend, not the second.

Table Size

This box controls the height, in mm, of each row in the Legend. It should be adjusted to suit the scale of the drawing you are creating.

A simple “rule of thumb” to determine a suitable size for the table is as follows:

1. Decide how high you want the Legend text to be when printed, eg, 4mm
2. Add 2mm, to allow a 1mm space above and below the text, → 6mm
3. Multiply that number by the Plot Scale, eg, a Plot Scale of 200 gives 1200
4. Use this final number as the “Table Size”

Inserting the Legend

When the **OK** button is clicked, you are prompted to “Locate the position of the legend”. This is the **top, left** corner of the Legend. A single click will generate the Legend.

A sample Legend is shown below.

Proposed Plants			
	botanical name	common name	Qty
Grass			
	Miscanthus Sinensis 'Variegatus'		6
Perennial			
	Achillea Filipendulina	Fernleaf Yarrow	3
Shrub			
	Acacia Terminalis	Sunshine Wattle	5
Tree			
	Acacia Stricta	Hop Wattle	3
	Acer Negundo KellyS Gold	Golden Box elder	4
	Acer Palmatum 'Dissectum Atropurpureum'	Japanese Maple Threadleaf	8



Note

The Legend does not automatically update if you add or delete plants after inserting it. To update the Legend simply run this command again (it will remember how you set it up last time) and snap to the top, left corner of it.

You can, of course, click somewhere else if you want to re-position the Legend.

You do not need to delete the existing Legend before updating it.



Note

The Legend is made up of lines and text and can be edited after it has been inserted. Be aware, though, that any edits will be lost if you insert a new Legend.

Plant Display Switching




PURPOSE: To display the plants as basic or detailed figures or bitmap images, regardless of how they were initially inserted.



[Click to watch Plant Display Switching Video on YouTube](#)

All plants in the drawing can be changed automatically or selected plants only can be changed.


When the command is selected, the following dialog box is displayed.



Select the required display type by clicking in the appropriate white dot.

When the OK button is clicked:

- if plants were selected prior to the command being run, then only those plants are changed,
- if no plants were selected prior to running the command, the following confirmation dialog box is displayed:



If the **Yes** button is clicked, all the plants in the drawing are changed.

If the **No** button is clicked, the command is cancelled.



Note

If a drawing contains many plants, changing their display to bitmap images can take a while and subsequent repaints may be slow. It is suggested that plants be displayed as bitmap images only when necessary, e.g., for printing or when presenting to clients.

Tally



PURPOSE: To extract data from the drawing for estimating and quoting. The extracted data is:

- the number of plants
- the lengths of linear entities (lines, arcs, circle and curves)
- areas of planes
- Sub-totals and totals for the above

When the command is selected, the data is written to a temporary file called “quantities.txt”, which is immediately displayed in Notepad.



Note

Quantities.txt is a temporary file. The same name is used every time the command is run and therefore previous data is overwritten. If you want to save the data in quantities.txt you must select **File → Save As** and save the file to another location for later use.

Once saved, being a standard “txt” file, it can be opened in any text editor or even Microsoft Excel or Word.



Tip

Only entities on “named” layers are counted and measured. Entities on layers that have not been named are ignored.

Only entities that are currently visible on screen at the time of running the command are counted and measured. This lets you be selective about what information is extracted, e.g., if only hardscape related layers are turned on, only hardscape data will be extracted.

The data below is an example of the sort of data that is extracted by the Tally command. For ease of reading, the data has been colour coded, as follows:

- Red text is the layer name.
- Black text shows the length of linear entities.
- Blue text shows the areas of planes.
- Green text shows the plants and their quantities.

This colour coding does not occur in the quantities.txt file; all text is black.

Some notes have been added to suggest possible sources of the data.

Decking

2 x 4.000m

Two lengths of deck edging perhaps

1 x 16.000m²

Area of decking

Total length for Decking 8.000m
Total area for Decking 16.000m²

Gardens

1 x 28.447m

Length of garden edging

Acacia sowdenii (Western Myall)	5
Acer rubrum (Red Maple)	5
Anigozanthos manglesii (Mangles Kangaroo Paw)	6
Asplenium nidus (Birds Nest Fern)	4

Total length for Gardens 28.447m
Total plants for Gardens 20

Mulch

1 x 153.201m²

Multiply by the depth and you've got the volume of mulch required

Total area for Mulch 153.201m²

Paving

2 x 6.000m

2 x 1.500m

1 x 9.000m²

Total length for Paving 15.000m
Total area for Paving 9.000m²

Total length 51.447m
Total area 178.201m²
Total plants 20

Insert Grid Lines




PURPOSE: To draw a construction grid on the drawing, with row and column labels.


YouTube **Video**

[Click to watch Insert Grid Lines Video on YouTube](#)

When the command is selected, the following dialog box is displayed.



The image and text below explain the options in this dialog box.



X Spacing

This box lets you define the horizontal distance, in mm, between the vertical lines of the grid.

Y Spacing

This box lets you define the vertical distance, in mm, between the horizontal lines of the grid.

X Extension

This box lets you define how far the horizontal grid lines extend past the first and last vertical grid lines.

Y Extension

This box lets you define how far the vertical grid lines extend past the first and last horizontal grid lines.

Text Size


This box controls the height, in mm, of text used as the row and column labels. It should be adjusted to suit the spacing of the grid lines.

Circle Text

If this option is ticked the text used as row and column labels have a circle drawn around them, as shown in the example above.

Labels Between Grid Lines

If this option is ticked the row and column labels are positioned between the grid lines as shown in the example above. If it is not ticked the labels are placed at the end of the grid lines, as shown below.



Inserting the Grid

When the OK button is clicked you are prompted to locate the **lower left corner** and **upper right corner** of the grid. As you drag your crosshair across the screen the grid is dynamically displayed so you know how it is going to look.

The grid is drawn immediately the upper right corner is selected.

The grid lines and circles are drawn using the current colour, layer, style and weight settings. The text is drawn with the current text settings. It is highly recommended that the grid be put on a separate layer so it can be turned off if necessary.

When inserted, the grid is “grouped”, i.e., selecting any part of the grid automatically selects the entire grid. This makes it easy to work with the grid as if it was a single item. You can “ungroup” the grid if you need to edit it.



Note

This grid is not the same as the standard AutoCAD® grid.

Set Heights



PURPOSE: To assign height values to entities in your drawing, in preparation for generating a 3D Digital Terrain Model (DTM) using the **Insert DTM** command (see page 101).

For an entity to be used when generating a DTM it must have some sort of height. This height can be an actual physical height, i.e., a Z coordinate, or it can be an “assigned” height, i.e., a value assigned by this command.



Note

A height of 0 (zero) is still a valid height.

The entities having heights assigned to them would typically be representing contours, spot heights, boundaries, landforms, etc.

Height values can be assigned to points, lines, arcs, circles and curves.



Note

Assigning a height to an entity does not physically move it to that height.

This command is also used to edit heights that have already been assigned.

If no entities have been selected prior to running the command, you are prompted to select an entity and then the dialog box shown below is displayed.

If an entity or entities have been selected before running the command, the dialog box shown below is displayed immediately.



Note

If you want to assign the same height to multiple entities it is more efficient to select them before running the command. Once the command starts you can only assign a height to one entity at a time.

The text below explains the options in this dialog box.

DTM Height

This box lets you enter the required height value, in mm, that will be assigned to the selected entity or entities.

If the entity or entities have never had heights assigned to them, 0.0 (zero) will be displayed.

If the entity or entities already have a height assigned to them, their height value will be displayed.



Note

If you pre-select multiple entities that have different heights assigned to them, the height of the first entity that had a height assigned to it will be displayed.

Text Size

This box lets you define the size at which the DTM text label will be displayed on the screen when you click the **Show Heights** button (see below). The text size is influenced by the next option, **Scale Text by the Plot Scale** and can work in either of the following two ways

1. If the **Scale Text by the Plot Scale** option is ticked, then the text size entered is automatically multiplied by the view's Plot Scale and the text is displayed on the screen at that scaled size.

For example, if a text size of 4mm is entered and the Plot Scale is 100, the text will be displayed on screen at 400mm high.

This technique lets you define the text size based on the height you want it to be when it is printed on paper. If the Plot Scale is changed for some reason, the on-screen text height will automatically adjust, but, providing you print the drawing at the specified Plot Scale, the text will always print at the height specified.

For example, a text height of 4mm and a Plot Scale of 100 produces on-screen text at 400mm high. Printing the drawing at a scale of 1:100 will produce text 4mm high on the paper. Change the Plot Scale to 200 and the on-screen text will become 800mm high, but printing the drawing at a scale of 1:200 will still produce text 4mm high on the paper.

2. If the **Scale Text by the Plot Scale** option is not ticked, then the text size entered is the on-screen height. It is not, in any way, affected by the view's Plot Scale.

For the text to be visible on the screen, the size must be calculated accordingly.

This technique will produce printed text of a different size if the Plot Scale is changed.

For example, if a text height of 400mm is specified and the Plot Scale is 100, the printed text will be 4mm high, but if the Plot Scale is changed to 200, the printed text would be 2mm high.

Scale Text by the Plot Scale

This tick box controls whether the text size entered is automatically multiplied by the view's Plot Scale for on-screen display. Refer to the previous section, **Text Size** for more details.

Set Height


When this button is clicked, the height value entered is assigned to the selected entity or entities. There is no visual indication of this, although the height values can be displayed with the "Show Heights" button (see below).

After a height has been assigned you are prompted to select another entity to assign a height to.

Show Heights

When this button is clicked the height values (DTM text labels) are displayed next to each entity, at the text size specified, as shown below

When the height values are displayed, this button changes to “**Hide Heights**” letting you hide them if you don’t need to see them any more.



Deleting Assigned Heights

The height values are attached to the entities as attributes. To completely delete the attribute, and hence the assigned height, select the entity or entities you wish to change the height, then run the **Set Heights** command and type 0 as value.



A screenshot of a software dialog box titled "Set DTM Height Data". The dialog has a light blue header bar with a close button (X) in the top right corner. It is divided into two main sections: "DTM Data" on the left and "DTM Text Label" on the right. In the "DTM Data" section, there is a label "DTM Height" followed by a text input field containing the number "0". In the "DTM Text Label" section, there is a label "Text size" followed by a text input field containing "300" and the unit "mm". Below this, there is a checkbox labeled "Scale text by the plot scale" which is currently unchecked. At the bottom of the dialog, there are three buttons: "Set Height" (highlighted with a blue border), "Show Heights", and "Cancel".

Insert DTM



PURPOSE: To generate 3D Digital Terrain Model (DTM) based on the actual and assigned heights of the selected entities.

A DTM is basically a rectangular set of triangles draped over the selected entities. Examples are shown below.



If a selected entity has not been assigned a height value using the **Set Heights** command (see previous section), the 'Insert DTM' process uses the height at which the entity was inserted, ie, its physical Z height. This is typically zero in 2D drawings so it is important that all the selected entities have first had their real life heights assigned.




Note

If an entity has an actual, physical height and an assigned height, the assigned height is used by this command.

The entities to be used in the creation of the DTM must be selected before the command is run.

When the command is selected, the following dialog box is displayed.



The text below explains the options in this dialog box.

Contour Point Spacing

When generating a DTM, each selected linear entity (line, arc, circle and curve) has temporary “contour points” defined along it. This box lets you define the spacing between these contour points.

The spacing is in millimetres.

Smaller spacing generates more contour points and produces a more accurate DTM shape.

However, smaller spacing also increase the amount of time it takes to generate the DTM.

As a rule of thumb, a contour point spacing of **500** is a good value for a DTM of an “average” block of land. If the DTM covers a larger area of land, it could be increased.



Tip

If in doubt, use a larger value as it will generate the DTM more quickly and make it easier for you to determine the appropriate value.


Mesh Size Control

Mesh Size Control allows you to control the total number of triangles (elements) used to generate the DTM. This box lets you define how many triangles you want to use.

Total Number of Elements

Total Number of Elements refers as the number of triangles (elements) that will display when drawing the DTM.

Make sure Total number of elements radio button is selected,



A higher number will give a more accurate DTM shape, but the DTM will take longer to generate.

As a rule of thumb, a mesh size of **2000** is a good starting value for a DTM of an “average” block of land. If the DTM covers a larger area of land, it could be increased.





Tip

If in doubt, use a smaller value as it will generate the DTM more quickly and make it easier for you to determine the appropriate value.

Element Size


Element Size refers to the horizontal size of the triangle (element). This value is approximate.



DTM Layer

This box lets you select the layer on which you want the DTM generated.

The layer can be selected from a list by clicking on the triangle at the end of the box (drop down list), as shown below.




The listed layers are named layers and correspond to the standard LANDWorksCAD numbered layers as follows.

Name	Number	Name	Number
DTM 1	501	DTM 11	511
DTM 2	502	DTM 12	512
DTM 3	503	DTM 13	513
DTM 4	504	DTM 14	514
DTM 5	505	DTM 15	515
DTM 6	506	DTM 16	516
DTM 7	507	DTM 17	517
DTM 8	508	DTM 18	518
DTM 9	509	DTM 19	519
DTM 10	510	DTM 20	520


DTM Colour

This box lets you select the colour with which you want to display the DTM.

The colour number can be typed directly into the box or it can be selected from a palette by clicking on the “Select Colour” button, as shown below.



Insert DTM button




Clicking this button generates the DTM based on the options entered into the dialog box. No further user input is required.




Note

If the Contour Point Spacing is small and/or the Mesh Size is large, it may take a few minutes to generate the DTM.


A sample isometric view of a DTM is shown below. The entities used to generate the DTM can still be seen.



The picture below shows four views of the DTM – Top, ISO, Front and Right.




Insert DTM with boundary button




Clicking this button also generates a DTM, but you are prompted for two corners to define a rectangular boundary that limits the size of the DTM.


In the image below, a rectangle has been drawn to show the proposed boundary.



Clicking on any two diagonally opposite corner points would generate the DTM shown below.



The isometric view below shows the full effect of the boundary on the DTM. Compare it to the full DTM in the previous section.



Modify DTM



PURPOSE: To allow modification of an existing DTM by a simple push/pull drag method.

The DTM is modified by effectively dragging a cone shape slowly across it, although the cone shape is not actually visible. The cone can push the DTM down, like digging a hole or trench, or pull the DTM up, like building a mound of dirt.




Note

This command has only recently been released and is still undergoing intensive development. As such it is not yet fully functional. It was released with the intent of obtaining feedback from users. It will change in both format and function as it is developed.

Any comments and/or suggestions about this command are welcome. Please send them to support@cad.com.au.

The following notes explain how the command works at the time of writing this manual.

When the command is selected, the following dialog box is displayed.



The text below explains the options in this dialog box.

Height Parameter

This box lets you set the height or depth of the cone. Simply type in the value required.

If the number is positive, the cone pulls the DTM up; if the number is negative, the cone pushes the DTM down.

Area Parameter

This box lets you define the size of the area that is affected by the cone. Simply type in the value required.


Larger numbers will have a wider effect. It is like the base diameter of the cone.

When you click the **OK** button you are prompted to “Click and drag to modify the surface”.



Hold down the left mouse button and drag your crosshair across the DTM to “modify” it.

The following images demonstrate how the command works.



The first image below shows a small, flat DTM that is 10m wide by 7m high. It is flat only to demonstrate more clearly how this command works. The command will work on any DTM.



Setting the height parameter to 50, the area parameter to 1200 and dragging the crosshair slowly from point A to point B, gives the result shown below.




Setting the height parameter to -50, the area parameter to 1200 and dragging the crosshair slowly from point A to point B, gives the result shown below.




The speed at which the crosshair is dragged across the DTM will affect the result. Slower speeds will result in a more continuous modification.

For the images shown above the crosshair was dragged across the DTM fairly slowly. As a comparison, for the image below the crosshair was dragged across the DTM fairly quickly.



Extremely slow drag speeds can be used to exaggerate the modification. In the image below, the crosshair was dragged very slowly from C to D.



Insert Batter




PURPOSE: To produce battered banks within an existing DTM.

The batter may represent the sides of a road, a driveway, a building slab, a swimming pool excavation, etc.


The batter can be created above and/or below the DTM.

The images below show before and after the blue “road” was put through the DTM and the batter created by this command.




The image below shows two more examples, one with hidden lines removed, the other shaded, of the use of this command: a path twisting its way up a gentle slope and a pool excavation. Virtually

any shape can be constructed using the “Insert Batter” command; it’s just up to you to work out what you want.



To insert a batter, a ruled surface that represents the landscaping feature (road, driveway, slab, pool, etc.) must first be inserted in the correct position.

Then the command is selected, the following dialog box is displayed.




The text below explains the options in this dialog box.

Angle

This box lets you define the angle of the batter. The angle is measured from horizontal at the ruled surface.

The image below shows two examples of how the batter angle is measured: one with the ruled surface above ground level, the other with the ruled surface below ground level.



Mesh Size

Mesh Size is the number of triangles used within the DTM to generate the selected surface. This box lets you define how many triangles you want to use.

A higher number will give a more accurate DTM shape, but the DTM will take longer to generate.

As a rule of thumb, a mesh size of **500** is a good starting value for a selected ruled surface.



Tip

If in doubt, use a smaller value as it will generate the DTM more quickly and make it easier for you to determine the appropriate value.

Inserting the Batter

As mentioned previously, you need to have drawn a surface crossing the DTM in order for the command to work.

When you click the **OK** button you are prompted to “Locate the surface to batter”. Select the ruled surface and the battering will be created. No further user input is required.



Note

Depending on the complexities of the DTM and the ruled surface it may take a few minutes to generate the batter – please be patient

The batter is created with the current colour, style and weight, but it generated on the same layer as the DTM.

The entire batter process can be reversed with a single Undo command.


Limitation: A current limitation of this command is that the ruled surface should not extend beyond the edges of the DTM.

Insert Contours




PURPOSE: To generate and insert contours based on the DTM. The contours are labelled with their heights.

An example of contours is shown below.



This command slices horizontally through the DTM at multiples of the specified height and generates the corresponding contours. The contours are curve entities and they are drawn at a Z height of zero so they can be used as simple 2D drawing elements.

When the command is selected, the following dialog box is displayed.



The text below explains the options in this dialog box.

Spacing

This box lets you define how far apart the contours are spaced. The value entered is the lowest contour height; subsequent contours are generated at multiples of that value. For example, if “250” is entered, contours are generated at 250, 500, 750, 1000 and so on.

The spacing is measured in millimetres.

Highlighting Frequency

By default, contours are drawn in the current colour. This box lets you define how often the colour is changed to the next colour number, for ease of identifying the contours. The dialog box above shows that every fourth contour line would be drawn in the next colour. For example, if the current colour was 5 (magenta), the first three contours would be drawn in that colour, the fourth contour would be drawn in colour 6 (brown), the next three contours would be drawn in colour 5 again, the eighth contour would be drawn in colour 6 again, and so on.



Note

Contours are also drawn in the current layer, style and weight, but only the colour changes as a highlight.



Tip

If you want all contours drawn in the same colour set the Highlighting Frequency to a high value; higher than the expected number of contours, e.g., 100.

Text Size

This box lets you define the size at which the text showing the contour heights will be displayed on the screen. The contour heights are displayed near the ends of the contours, where possible.

The text size is influenced by the next option, **Scale Text by the Plot Scale** and can work in either of the following two ways

1. If the **Scale Text by the Plot Scale** option is ticked, then the text size entered is automatically multiplied by the view's Plot Scale and the text is displayed on the screen at that scaled size.

For example, if a text size of 4mm is entered and the Plot Scale is 100, the text will be displayed on screen at 400mm high.

This technique lets you define the text size based on the height you want it to be when it is printed on paper. If the Plot Scale is changed for some reason, the on-screen text height will automatically adjust, but, providing you print the drawing at the specified Plot Scale, the text will always print at the height specified.

For example, a text height of 4mm and a Plot Scale of 100 produces on-screen text at 400mm high. Printing the drawing at a scale of 1:100 will produce text 4mm high on the paper. Change the Plot Scale to 200 and the on-screen text will become 800mm high, but printing the drawing at a scale of 1:200 will still produce text 4mm high on the paper.

2. If the **Scale Text by the Plot Scale** option is not ticked, then the text size entered is the on-screen height. It is not, in any way, affected by the view's Plot Scale.

For the text to be visible on the screen, the size must be calculated accordingly.

This technique will produce printed text of a different size if the Plot Scale is changed.

For example, if a text height of 400mm is specified and the Plot Scale is 100, the printed text will be 4mm high, but if the Plot Scale is changed to 200, the printed text would be 2mm high.

Scale Text by the Plot Scale

This tick box controls whether the text size entered is automatically multiplied by the view's Plot Scale for on-screen display. Refer to the previous section, **Text Size** for more details.

Inserting the Contours



When the **OK** button is clicked the contours are automatically generated; there is no further user input required.



Note

A DTM must already exist for this command to work.

The first image below shows the contours generated from the DTM below it.



Adjust Plant Heights



PURPOSE: To assign an “adjustment height” to plant. This height will be used to raise or lower the plant relative to the DTM when the **Insert 3D Plants** command (page 128) is run.

Normally the **Insert 3D Plants** command inserts the plants exactly on the actual DTM, but this command lets you over-ride that.


This is to facilitate a tree sitting in a pot or raised above the ground on a wall, etc. The idea is to give you flexibility for each plant/figure.

Visual examples of the effect of this command are shown in the next section, **Insert 3D Plants**, on page 128.



Note

A plant, or plants, must be selected before running the command. If this is not done, the following dialog box will appear.



When the command is selected, the following dialog box is displayed.



The text below explains the options in this dialog box.

Figure Height

This box lets you set the height of the plant, relative to its location on the DTM. The height is in millimetres.

A positive number will raise the plant above the DTM; a negative number will lower the plant into the DTM.

Text Size

This box lets you define the size at which the text showing the plant heights will be displayed on the screen. The heights are displayed next to the plants.

The text size is influenced by the next option, **Scale Text by the Plot Scale** and can work in either of the following two ways

1. If the **Scale Text by the Plot Scale** option is ticked, then the text size entered is automatically multiplied by the view's Plot Scale and the text is displayed on the screen at that scaled size.

For example, if a text size of 4mm is entered and the Plot Scale is 100, the text will be displayed on screen at 400mm high.

This technique lets you define the text size based on the height you want it to be when it is printed on paper. If the Plot Scale is changed for some reason, the on-screen text height will automatically adjust, but, providing you print the drawing at the specified Plot Scale, the text will always print at the height specified.

For example, a text height of 4mm and a Plot Scale of 100 produces on-screen text at 400mm high. Printing the drawing at a scale of 1:100 will produce text 4mm high on the paper. Change the Plot Scale to 200 and the on-screen text will become 800mm high, but printing the drawing at a scale of 1:200 will still produce text 4mm high on the paper.

2. If the **Scale Text by the Plot Scale** option is not ticked, then the text size entered is the on-screen height. It is not, in any way, affected by the view's Plot Scale.

For the text to be visible on the screen, the size must be calculated accordingly.

This technique will produce printed text of a different size if the Plot Scale is changed.

For example, if a text height of 400mm is specified and the Plot Scale is 100, the printed text will be 4mm high, but if the Plot Scale is changed to 200, the printed text would be 2mm high.

Scale Text by the Plot Scale


This tick box controls whether the text size entered is automatically multiplied by the view's Plot Scale for on-screen display. Refer to the previous section, [Text Size](#) for more details.

When the **OK** button is clicked, the height value entered is assigned to the selected plant or plants. There is no visual indication of this; the plants are simply being preparing for the [Insert 3D Plants](#) command. The height values can be displayed with the [Show Heights](#) button (see below).

Show Heights

When this button is clicked the height values are displayed next to each entity, at the text size specified, as shown below. The bottom plant has not has an adjustment height assigned to it.

When the height values are displayed, this button changes to **Hide Heights** letting you hide them if you don't need to see them any more.



Insert 3D Plants



PURPOSE: To place the plants onto the actual DTM based on their position on the landscape plan.


The 2D plan figures of the plants can be simply moved up onto the DTM or the elevation/3D figures of the plants, as defined in the plant database, can be inserted, replacing the 2D figures.

You can switch between the 2D and 3D figures at any stage.

The command finds the inserted plant figures, looks directly above (or below) them to find their corresponding locations on the DTM and then moves the 2D figures or inserts the elevation/3D figures as directed.

The figures can be inserted at their current size or updated for a particular age, based on information in the database, i.e., maximum height, maximum width and maturity.

When the command is selected, the following dialog box is displayed.




The text below explains the options in this dialog box.


Show 2D View

This option tells LANDWorksCAD to display the 2D plan figures of the plants on the DTM.

The image below shows plants (red) that have been inserted normally into a plan. As you can see, they are all below the DTM.




The plants in the image below have been processed by the **Insert 3D Plants** command with the **“Show 2D View”** option selected. You can see that the plants have been moved up on to the DTM. This is most obvious in the Front and Right views (the bottom two). Some plants have had their heights adjusted relative to the DTM with the **Adjust Plant Heights** command (see the previous section).




Show 3D View

This option tells LANDWorksCAD to display the elevation/3D figures of the plants on the DTM.

The image below shows plants (red) that have been inserted normally into a plan. As you can see, they are all below the DTM.



The plants in the image below have been processed by the **Insert 3D Plants** command with the **“Show 3D View”** option selected. You can see that the plants have been moved up on to the DTM. This is most obvious in the Front and Right views (the bottom two). Some plants have had their heights adjusted relative to the DTM with the **Adjust Plant Heights** command (see the previous section).



The type of elevation/3D figure inserted by this option is controlled by the data in the database. Column C in the database, headed “*elev. figure name*”, contains the file names of the elevation/3D figures to be used.



Note









Appendix 1 – The LANDWorksCAD Plant Database contains more information on this.

The figures can be, as described, either a flat elevation representation of the plant or a full 3D model.

If the figures are drawn as flat elevations, they will appear as shown in the image above. Note how the plants are shown as simple, straight lines in the Top view (top, right window).


However, column K in the database, “*number of 2d figures*”, can be used to make them look more 3D-like. The value in column K is the number of copies of the elevation figure that will be used. The default is one. Each copy is rotated evenly, thereby creating a 3D effect from a 2D drawing.

The table below shows plan and isometric views of a tree with varying number of 2d figures.

No. of 2d figures	1	2	3	4
Plan view				
Isometric view				

If the figures are drawn as full 3D models, they will display appropriately in all views. There is definitely no need to have multiple copies, so column K, “*number of 2d figures*”, should be set to one.

The image below shows an example of a simple 3D plant, in four different views – Top, ISO, Front and Right.



Tip


Another way of achieving a more 3D-like effect, without the overhead of multiple elevation figures or a full 3D model, is to use a single, flat elevation figure, but have it automatically “oriented to the view”. This technique means it will always be displayed parallel to the screen no matter what view you are in or what rotation is applied to the view and thus it will look like a full plant; it will never turn on its side. This effect can be achieved by turning on the “Orient to View” setting in the Figure Options (select Figure → Options from the menu).

Current Size

This option tells LANDWorksCAD to insert the plant figures at their current size, i.e., at the size they were drawn.

Update Age

This option lets you control the size of the plants, based on their age. When this option is selected the “Age” box below it is activated, as shown below, letting you select the age at which you want to display the plants. Click on the down arrow at the end of the box to display a list of ages to select from. You can also type in the age.



The resultant size of the plant is determined by the “Update Age” selected (above) and the plant’s maximum width, maximum height and maturity from the plant database.

The plant’s size is calculated as follows:

$$\text{Age height} = \text{maximum height} * \text{age} / \text{maturity}$$


$$\text{Age width} = \text{maximum width} * \text{age} / \text{maturity}$$

Obviously the maximum height, maximum width and maturity data must exist in the database before the “Update Age” option can work.

Inserting the Plants

When the **OK** button is clicked, one of two things will happen:

1. If plants were selected before the command was run they will be processed as per the settings.
2. If no plants were selected before the command was run, the following dialog box will be displayed.



Click “Yes” to process all plants as per the settings or click “No” to cancel the command. You can then select only the plants that are to be processed and run the command again.

Insert Sun Light



PURPOSE: To insert a light source in your model that represents the Sun.

When modelling in 3D, this light source can be used to generate shadows in a raytraced view.

A sample 3D, raytraced view, with shadows, is shown below.




When the command is selected, it invokes the Geographic Location dialog box:

Geographic location embeds location specific references expressed as real-world coordinates (X, Y and Z) in your drawing.


The geographic marker is a visual representation of the location information and is created at the specified point on the drawing.

Geographic location information can be included in either of the following ways:


- Import a KML or KMZ file with the appropriate location information
- Import a location from Google Earth
- Use the Geographic Location dialog box
- When you insert location information, the drawing contains the following data:
 - North direction — a vector that defines the direction of the North pole from the XY plane
 - Up direction — a vector that is always constrained 90 degrees to the XY plane
 - Geographic location data



Import a .kml or .kmz file

1. Click Render tab ► Sun & Location panel ► Set Location. 
2. Click Import a KML or KMZ File.
3. Navigate to the location of the KML or KMZ file. Click Open.

If your KML or KMZ file references multiple locations, only the first location is used. In such cases, click Close when the Multiple Locations Found dialog box is displayed.




4. Click or enter a point or value for the location in the World Coordinate System (WCS) X, Y, Z format.
5. Click to specify the north direction.


A geographic marker (visual representation of the location information) is inserted at the specified location.

The geographic marker displays differently in 2D and 3D views.

Import the current location from Google Earth

1. Click Render tab ► Sun & Location panel ► Set Location. 
2. Click Import the current location from Google Earth.
The Import from Google Earth task dialog box is displayed.

Note: Google Earth must be installed in your computer to use this feature.



3. Click Continue.
4. Click or enter a point / value for the location in the World Coordinate System (WCS) X, Y, Z format.
5. Click to specify the north direction.

The geographic marker is created at the specified point on the drawing.

The geographic marker displays differently in 2D and 3D views.

Enter the location values

1. Click Render tab ➤ Sun & Location panel ➤ Set Location.



Geographic Location

Latitude & Longitude

Decimal Lat/Long Use Map...

Latitude: 37.795 North

Longitude: 122.394 West

Time Zone: (GMT+10:00) Canberra, Melbourne, Sydney

Coordinates and elevation

X: 0 Y: 0 Z: 0

Elevation: 0

North direction

Angle: 0

Up direction: +Z

Custom direction: (X, Y, Z) = (0, 0, 1)

OK Cancel Help

2. Click Enter the Location Values.
3. (Optional) Select the latitude and longitude format.

You can enter the latitude, longitude, and time zone values manually, or click the Use Map button (steps 4 through 8) to select the values visually.

4. (Optional) Click Use Map.

5. In the Region drop-down list, select the applicable region.
6. In the Nearest City drop-down list, select the nearest city that represents the time zone.
Click OK.

The Time Zone value is updated automatically based on the Nearest City selected.

7. Click Accept Updated Time Zone, if correct. To select a different time zone, click Return to the Previous Dialog Box.

The latitude, longitude, direction, and time zone values are automatically populated based on the values selected in the location picker dialog box.


8. Click Pick Point to specify the X, Y, and Z coordinates. Values can also be entered at the Command prompt.
9. Use the Up or Down arrows to specify the elevation.
10. Click Pick Point, or drag the compass needle icon, to specify the angle.

The north direction angle is calculated when you select a point with reference to the geographic location.


11. Specify the Up direction, if necessary
12. Click OK.

The geographic marker displays differently in 2D and 3D views.

2D



3D




About



PURPOSE: To show the **version number** and **release date** of your LANDWorksCAD software.

When the command is selected, a dialog box similar to the following is displayed:



If a CAD International support person asks you what version of LANDWorksCAD you are using, this is where you find it. When reporting your version it is important to also include the date.

Appendices

The following appendices provide information about the LANDWorksCAD database that is useful to know, but not essential for day to day use of the software.

Appendix 1 – The LANDWorksCAD Plant Database

Structure

The LANDWorksCAD database of plants is a Microsoft Excel spread sheet file called **LANDWorksPlantDatabase.xls**. It must be called this name and it must be stored in the LANDWorksCAD folder on your computer's hard disk.

The LANDWorksCAD plant database contains three worksheets:

- one for existing plants
- one for concept plants
- one for plants

The **Existing Plants** worksheet lets you set up simple figures to represent the plants that already exist in your projects.

The **Concept Plants** worksheet lets you set up simple figures to use when creating a concept plan for your clients.

The **Plants** worksheet is where you store all the plant information related to existing & proposed plants. The information is used for labelling the existing and proposed plants as well as creating schedules & legends. Concept plants are labelled differently.



Note

The word “plant” is used to mean plants and trees.

Format

The format of the worksheets is quite simple:

- Each row in the database contains data that relates to a single plant only, e.g., row 32 contains data for the plant called “Abies grandis”.
Exceptions to this “rule” are explained below.
- Each column contains a particular type of data for each plant, e.g., column N contains the botanical name of each plant.



Note

Excel functionality used within the database is noted where appropriate, but is not necessarily explained fully in this document. For more information consult the Excel Help files or [contact us](#).

Rows

The format of the rows is identical for each worksheet and is as follows:

- | | |
|--------------------|--|
| Row 1 | – is used for section headings, e.g., “CAD Data”, “Names”, “General Appearance”, “Leaves”, etc. |
| Rows 2-27 | – are used to provide selection data for row 32 and higher numbered rows, where required. |
| Row 28 | – is used to repeat the section headings from Row 1. This is done to make it easier to identify where you are in the spreadsheet when freezing rows (Excel functionality). |
| Row 29 | – is used for specific data headings, e.g., “plan figure name”, “Botanical Name”, “Habit”, etc. |
| Rows 30, 31 | – are not used, but do not delete them. |
| Rows 32 and higher | – contain the plant data. |

Rows 1-27, 30 and 31 are initially hidden in the supplied database. This is to prevent users from accidentally, or intentionally, editing the data contained in these rows before they really know what the data is for. These rows can, however, be displayed without affecting the functionality of the database in any way. For instructions on displaying these hidden rows refer to [Appendix 3 – Working with the Selection Data](#) on page 158.

Some row constraints of the database you should be aware of are:

1. You must not add or delete rows within rows 1-31.
2. The plant data must start in row 32 and continue in higher numbered rows, i.e., rows 33, 34, 35 99, 100, 101 ... 1000, 1001, etc.
3. There must be no blank rows in the plant data, i.e., row 32 and higher numbered rows. A blank row is taken to be the end of the plant list.

Some row freedoms of the database you should be aware of are:

1. In the plant data area of the worksheets, i.e., row 32 & higher numbered rows, you can add as many rows as you need, delete rows, move rows, virtually anything you want.
2. You can add to and/or edit the selection data contained in rows 2-27. This is explained in [Appendix 3 – Working with the Selection Data](#) on page 158.
3. The data headings in row 29 (columns L-BX only) can be edited to suit your needs. The words can be changed completely; they can be changed to be all capitals, etc.

Columns

The format of the columns is similar, but not identical, for each worksheet.

Existing Plants worksheet

The Existing Plants worksheet contains 5 columns of data, as shown below.

	A	B	C	D	E
28	Actual Data	CAD Data			Information
29	1/6/2012	plan figure name	image file name	description	category
32		Figures\Plants\TT01.dwg	Figures\Plants\TT01.jpg	Remove	
33		Figures\Plants\TT02.dwg	Figures\Plants\TT01.jpg	Retain	

The use of the columns is explained below.

Column A – is not used at present. You should not remove it, but can use it for notes, comments, etc.

CAD Data

Column B – **Plan Figure Name** – defines the CAD drawing file that will be used to represent the existing plant when displaying the plants normally in plan view.

Column C – **Image File Name** – defines the image file (bmp or jpg format) that will be used to represent the existing plant when displaying the plants for presentation purposes in plan view.

Information

Column D – **Description** – describes the plant. The description for each plant must be unique.

Column E – **Category** – defines the category of your existing plant.

If you click in a cell a small box will appear showing the column heading and a short description of what the data in the cell is used for. An example is shown below.

	A	B	C	D	E
28	Actual Data	CAD Data			Information
29	1/6/2012	plan figure name	image file name	description	category
32		Figures\Plants\TT01.dwg	Figures\Plants\TT01.jpg	Remove	
33		Figures\Plants\TT02.dwg	Figures\Plants\TT01.jpg	Retain	
34		CAD Plan Figure Name Enter the path and name of the cad file you wish to use to represent the plan figure of the concept plant, eg, Landscape- Symbols\Plants\%001.cad			
35					
36					
37					
38					
39					
40					
41					

Some column constraints of this worksheet you should be aware of are:

1. You must not add, delete or move columns within columns A-C.
2. You must not edit in any way the headings in row 29 for columns A-C.
3. The plant data must exist in columns D and E.

Some column freedoms of this worksheet you should be aware of are:

1. In the plant data area of the worksheet, i.e., columns D and E, you can add columns, delete columns and move columns.
2. Data in the columns can be sorted in any order you require, e.g., it can be sorted by plan figure name, by description, etc. [Appendix 4 – Sorting the Plant Database in Excel](#) on page 170 explains how to do this.

Concept Plants worksheet

The Concept Plants worksheet contains 10 columns of data, as shown below.

	A	B	C	D	E
28	Actual Data	CAD Data			
29	1/6/2012	plan figure name	elev. figure name	image file name	elev. image file name
32		Figures\Plants\RR01.dwg			
33		Figures\Plants\RR02.dwg			
34		Figures\Plants\RR03.dwg			
35		Figures\Plants\RR04.dwg			
36		Figures\Plants\RR05.dwg	Figures\Plants-E\BE023-E.dwg	Figures\Plants\WM005.jpg	Figures\Plants-E\MM034-E.jpg

	F	G	H	I	J
28	Concept Information				
29	description	category	shape	heading	label
32	Desc 1	Tree	Round	Heading 1	Label 1
33	Desc 2	Tree	Oval	Heading 2	Label 2
34	Desc 3	Shrub	Round	Evergreen	Label 3
35	Desc 4	Tall shrub	Spikey	Desert Shrub	Label 4

The use of the columns is explained below.

Column A – is not used at present. You should not remove it, but can use it for notes, comments, etc.

CAD Data

Column B – **Plan Figure Name** – defines the CAD drawing file that will be used to represent the concept plant when displaying the plants normally in plan view.

Column C – **Elev. Figure Name** – defines the CAD drawing file that will be used to represent the concept plant when displaying the plants normally in a non-plan, i.e., 3D, views.

Column D – **Image File Name** – defines the image file (bmp or jpg format) that will be used to represent the concept plant when displaying the plants for presentation purposes in plan view.

Column E – **Elev. Image File Name** – defines the image file (bmp or jpg format) that will be used to represent the concept plant when displaying the plants for presentation purposes in non-plan, i.e., 3D, views.

Concept Information

Column F – **Description** – describes the plant. The description for each plant must be unique.

Column G – **Category** – defines the category of the concept plant. Select from a list.

Column H – **Shape** – defines the general shape of the concept plant. Select from a list.

Column I – **Heading** – defines a heading that can be semi-automatically added to the drawing, with the label (see below), to identify your plant.

Column J – **Label** – defines a label that can be semi-automatically added to the drawing, with the heading (see above), to identify your plant.

If you click in a cell a small box will appear showing the column heading and a short description of what the data in the cell is used for. An example is shown below.

F	G	H	I
Concept Information			
description	category	shape	heading
Desc 1	Tree	Round	Heading 1
Desc 2	Description Enter the description for the concept plant. The description must be unique.	Oval	Heading 2
Desc 3		Round	Evergreen
Desc 4		Spikey	Desert Shrub

Some column constraints of the database you should be aware of are:

1. You must not add, delete or move columns within columns A-E.
2. You must not edit in any way the headings in row 29 for columns A-E.
3. The plant data must start in column F and continue in higher lettered columns, i.e., columns G, H, etc.

Some column freedoms of the database you should be aware of are:

1. In the plant data area of the worksheet, i.e., columns E and higher, you can add columns, delete columns and move columns.
2. Data in the columns can be sorted in any order you require, e.g., it can be sorted by Description, by Category, etc. [Appendix 4 – Sorting the Plant Database in Excel](#) on page 170 explains how to do this.

Plants worksheet

The Plants worksheet contains 76 columns of data, some of which are shown below.

	L	M	N	O	P	Q
28	Names					
29	abbreviation	abbreviation-2	botanical name	family	common name	common name 2
32	Ab x Gr	Abe x Gra	Abelia X Grandiflora	Caprifoliaceae	Glossy Abelia	
33	Ab x Gr Na	Abe x Gra Nan	Abelia X Grandiflora 'Nana'	Caprifoliaceae	Dwarf Abelia	
34	Ab x Gr Su	Abe x Gra Sun	Abelia X Grandiflora 'Sunrise'	Caprifoliaceae	Dwarf Pink variegated Abelia	
35	Ab x Gr Va	Abe x Gra Var	Abelia X Grandiflora 'Variegata'	Caprifoliaceae	Pink	cream variegated Abelia
36	Ab Gr	Abi Gra	Abies Grandis	Pinaceae	Grand Fir	Giant Fir

The use of the columns is explained below.

Column A – is not used at present. You should not remove it, but can use it for notes, comments, etc.

CAD Data

Column B – **Plan Figure Name** – defines the basic 2D CAD drawing file that will be used to represent the proposed plant when displaying the plants normally in plan view.

Column C – **Elev. Figure Name** – defines the basic 2D CAD drawing file that will be used to represent the proposed plant when displaying the plants normally in a non-plan, i.e., 3D, view.

Column D – **3D Figure Name** – is no longer used, but the column must not be deleted.

Column E – **Image File Name** – defines the image file (bmp or jpg) that will be used to represent the proposed plant when displaying the plants for presentation purposes in plan view.

Column F – **Detail Plan Figure Name** – defines the more detailed 2D CAD drawing file that will be used to represent the proposed plant when displaying the plants normally in plan view.

Column G – **Detail Elev. Figure Name** – defines the more detailed 2D CAD drawing file that will be used to represent the proposed plant when displaying the plants normally in a non-plan, i.e., 3D, views.

Column H – **Elev. Image File Name** – defines the image file (bmp or jpg) that will be used to represent the proposed plant when displaying the plants for presentation purposes in non-plan, i.e., 3D, views.

Column I – **Line Type** – is not used at present. You should not remove it because it is reserved for future development.

- Column J – **Hatch Pattern** – is not used at present. You should not remove it because it is reserved for future development.
- Column K – **Number of 2d Figures** – defines the number of 2D elevation figures you want to be used to generate a more 3D looking plant. The section called **Show 3D View** on page 130 explains how this data is used.

Names

- Column L – **Abbreviation** – defines the abbreviated name of the plant. This can be any format.
- Column M – **Abbreviation-2** – defines a second abbreviated name of the plant, if required. This can be any format.
- Column N – **Botanical name** – defines the Botanical name of the plant. The botanical name must be unique.
- Column O – **Family** – defines the Family the plant belongs to.
- Column P – **Common Name** – defines the Common Name of the plant.
- Column Q – **Common Name 2** – defines the secondary Common Name of the plant, if there is one.
- Column R – **Cultivars** – defines the Cultivars of the plant.

Favourites

- Column S – **Favourites** – defines if the plant is one your favourites. Select Yes or No from a list.

Type

- Column T – **Type** – defines the type of plant. Select from a list.

General Appearance

- Column U – **Habit** – defines the growth habit of the plant. Select from a list.
- Column V – **Texture** – defines the overall texture of the plant. Select from a list.
- Column W – **Maximum Width** – defines the maximum width the plant will grow to if planted in your region in typical conditions. Measured in millimetres (mm).
- Column X – **Maximum Height** – defines the maximum height the plant will grow to if planted in your region in typical conditions. Measured in millimetres (mm).

Column Y – **Maturity Age** – defines the age, in years, when the plant will typically be mature.

Column Z – **Density** – defines the density of the plant. Select from a list.

Column AA – **Roots** – defines the root structure of the plant. Select from a list.

Column AB – **Seasonal** – defines the seasonal nature of the plant. Select from a list.

Leaves

Column AC – **Leaf Size** – defines the leaf size of the plant. Select from a list.

Column AD – **Leaf Character** – defines the leaf character of the plant. Select from a list.

Column AE – **Leaf Colour** – defines the leaf colour of the plant. Select from a list.

Column AF – **Autumn/Fall Leaf Colour** – defines the leaf colour of the plant in Autumn/Fall.
Select from a list.

Flower

Column AG – **Flowers Season** – defines the dominant flowering season of the plant. Select from a list.

Column AH – **Flower Type** – defines the type of flower of the plant. Select from a list.

Column AI – **Months of Bloom** – defines the typical month(s) of bloom of the plant. Select from a list.

Column AJ – **Flower Colour** – defines the typical flower colour of the plant. Select from a list.

Fruit

Column AK – **Fruit Type** – defines the type of fruit of the plant. Select from a list.

Column AL – **Fruit Size** – defines the size of the fruit of the plant. Select from a list.

Column AM – **Fruit Season** – defines the typical fruiting season of the plant. Select from a list.

Column AN – **Edible** – defines the edibility of the fruit of the plant. Select from a list.

Column AO – **Fruit Colour** – defines the colour of the fruit of the plant. Select from a list.

Bark

- Column AP – **Bark Colour** – defines the colour of the bark of the plant. Select from a list.
- Column AQ – **Bark Texture** – defines the texture of the bark of the plant. Select from a list.
- Column AR – **Bark Shedding** – defines if the bark of the plant sheds or not. Select from a list.

Region

- Column AS – **Global Origin** – defines the global origin of the plant. Select from a list.
- Column AT – **Bioclimatic Zone** – defines the bioclimatic zone of the plant. Select from a list.
- Column AU – **Zone Number** – defines the zone number of the plant. Select from a list.
- Column AV – **Climate Group** – defines the climate group of the plant. Select from a list.

Typical Style

- Column AW – **Style** – defines the style of the plant. Select from a list.
- Column AX – **Interest** – defines the seasonal interest of the plant. Select from a list.
- Column AY – **Design Accent** – defines the design accent of the plant. Select from a list.

Uses

- Column AZ – **Location Uses** – defines the typical location where the plant is used. Select from a list.
- Column BA – **Special Uses** – defines any special uses for the plant. Select from a list.
- Column BB – **Attracts** – defines what the plant attracts. Select from a list.

Position

- Column BC – **Sun** – defines the type of sun/shade the plant likes. Select from a list.
- Column BD – **Tolerances** – defines what the plant is tolerant to. Select from a list.
- Column BE – **Soil Type** – defines the preferred soil type for the plant. Select from a list.

- Column BF – **Soil pH** – defines the preferred soil pH for the plant. Select from a list.
- Column BG – **Soil Condition** – defines the preferred soil condition for the plant. Select from a list.
- Column BH – **Hydrozone** – defines the preferred hydrozone for the plant. Select from a list.

Maintenance

- Column BI – **Maintenance Rating** – defines the maintenance rating for the plant. Select from a list.
- Column BJ – **Water** – defines the water requirements of the plant. Select from a list.
- Column BK – **Pruning** – defines how often the plant should be pruned. Select from a list.
- Column BL – **Fertilization** – defines the type of fertilizer required for the plant. Select from a list.
- Column BM – **Integrated Pest Management** – defines the type of pest management required for the plant.
- Column BN – **Watering Option 1** – defines how often the plant should be watered. Select from a list.
- Column BO – **Watering Option 2** – defines additional information on how the plant should be watered.

Problems

- Column BP – **Susceptibilities** – defines any susceptibilities the plant has. Select from a list.
- Column BQ – **Adverse Factors** – defines any adverse factors relating to the plant. Select from a list.

Miscellaneous

- Column BR – **Description Text** – describes the plant with information not included in the other columns.
- Column BS – **Description 2** – additional or alternative text to describe the plant.
- Column BT – **Nursery ID 1** – defines the nursery ID or code used to identify the plant.
- Column BU – **Container Size** – defines the container size for the plant. Select from a list.

Costing

Column BV – **Price 1** – defines the main price of the plant.

Column BW – **Price 2** – defines an alternative price of the plant.

Column BX – **Price 3** – defines a second alternative price of the plant.

If you click in a cell a small box will appear showing the column heading and a short description of what the data in the cell is used for. An example is shown below.

Botanical Name	
Abies grandis	
Acacia baileyana	
Acacia buxifolia	
Acacia decurrens	
Acacia sowdenii	
Acacia spetabilis	
Acer rubrum	

Botanical Name
Enter the botanical name for the plant.
It must be unique.

Some column constraints of the database you should be aware of are:

1. You must not add, delete or move columns within columns A-K.
2. You must not edit in any way the headings in row 29 for columns A-K.
3. The plant data must start in column L and continue in higher lettered columns, ie, columns M, N, O, etc.

Some column freedoms of the database you should be aware of are:

1. In the plant data area of the worksheet, i.e., columns L and higher, you can add columns, delete columns and move columns.
2. Data in the columns can be sorted in any order you require, e.g., it can be sorted by botanical name, by type, etc. [Appendix 4 – Sorting the Plant Database in Excel](#) on page 170 explains how to do this.

Appendix 2 – Editing the Plant Database in Excel

The plant database can be edited from within LANDWorksCAD or directly in Microsoft Excel. This appendix explains how to edit the database directly in Excel.

The explanations apply to the concept, existing and proposed plants.

The explanations assume basic knowledge of Excel.

Editing Existing Plant Data

Editing the database is as simple as opening it in Excel and entering the appropriate data. Each row pertains to a particular plant. Save the file and the next time you open LANDWorksCAD or reload the database the new data will be available.

For the plant data, i.e., columns L–BX, simply type in the relevant data or select it from the available drop down lists.

For the CAD data, i.e., columns B–H, you must type in the path and file name of the figure/image to be used to represent the plants.

If the file is saved in a folder below the LANDWorksCAD folder, the path can start with the folder directly below the LANDWorksCAD folder, e.g., “Figures\Plants\ ...”

If the file is not saved in a folder below the LANDWorksCAD folder, the path must start from the root folder, e.g., “C:\Acme Landscaping\Plant Library\ ...”

Note: The file name must include its extension, i.e., “.dwg”, etc.

Adding a Plant

To add a new plant, simply insert a new row and enter the appropriate data.



Tip

To insert a new row in Excel, right click in any of the row numbers on the left side of the screen then select **Insert** as shown below.

	L	M	N
28	Names		
29	abbreviation	abbreviation-2	botanical name
32	Ab x Gr	Abe x Gra	Abelia X Grandiflora
33	Ab x Gr Na	Abe x Gra Nan	Abelia X Grandiflora 'Nana'
34	Ab x Gr Su	Abe x Gra Sun	Abelia X Grandiflora 'Sunrise'
35	Ab x Gr Va	Abe x Gra Var	Abelia X Grandiflora 'Variegata'
36	Ab Gr	Abi Gra	
37	Ab No	Abi Nor	Abies Nordmanniana
38	Ab Pi	Abi Pin	Abies Pindrow
39	Ab St Th	Abu Str Tho	Abutilon Striatum 'Thompson'
40	Ac Ad	Aca Adu	Acacia Adunca
41	Ac Ba	Aca Bai	Acacia Baileyana
42	Ac Bi	Aca Bin	Acacia Binervata
43	Ac Bo	Aca Bo	Acacia Boormanii
44	Ac Bu	Aca Bux	Acacia Buxifolia
45	Ac By	Aca Byn	Acacia Bynoeana
46	Ac Ca	Aca Car	Acacia Cardiophylla
47	Ac Co	Aca Cog	Acacia Cognata
48	Ac Co	Aca Coven	Acacia Covenyi
49	Ac Cu	Aca Cul	Acacia Cultriformis
50	Ac De	Aca Dea	Acacia Dealbata
51	Ac De	Aca Dea	Acacia Deanei
52	Ac De	Aca Dec	Acacia Decora
53	Ac De	Aca Dec	Acacia Decurrens
54	Ac El	Aca Ela	Acacia Elata
55	Ac El	Aca Elo	Acacia Elongata
56	Ac Fa	Aca Fal	Acacia Falcata
57	Ac Fa	Aca Fal	Acacia Falciformis
58	Ac Fi	Aca Fim	Acacia Fimbriata
59	Ac Fi	Aca Fim	Acacia Fimbriata

Right click, select Insert

37	Ab No	Abi Nor	Abies Nordmanniana
38	Ab Pi	Abi Pin	Abies Pindrow
39	Ab St Th	Abu Str Tho	Abutilon Striatum 'Thompson'
40	Ac Ad	Aca Adu	Acacia Adunca
41			


Deleting a Plant

To delete an existing plant, simply delete the row.



Tip

To insert a new row in Excel, right click in any of the row numbers on the left side of the screen then select **Insert** as shown below.



Right click, select Delete

Re-Arranging/Moving Plants

Any rows from 32 on can be re-arranged or moved to suit your requirements.



Tip

When re-arranging/moving plants ensure the entire row is selected, not just the visible cells.

The basic steps to move a plant are: 1) insert a new row where you want to move the plant and 2) cut and paste the existing row to the new position. For more details, please refer to the Excel Help system.


Adding a New Data Item (Column)

To add a new item of data for the plants, simply insert a new column, give it a heading in row 29 and then enter the appropriate data for each plant.



Tip

To insert a new column in Excel, right click in any of the column names then select **Insert**.




Deleting an Existing Data Item (Column)

To delete an existing data item, simply delete the column.



Tip

To delete a new column in Excel, right click in any of the column names then select **Delete**.



Right click, select Delete

Re-Arranging/Moving Data Items (Columns)

Any data items (columns), except those in the CAD data section (columns A – K) can be re-arranged or moved to suit your requirements.



Tip

When re-arranging/moving data items ensure the entire column is selected, not just the visible cells.

The basic steps to move a column are: 1) insert a new column where you want to move the data item and 2) cut and paste the existing column to the new position. For more details, please refer to the Excel Help system.

Appendix 3 – Working with the Selection Data

When working on your LANDWorksCAD plant database many columns let you select from a drop-down list of data. An example of this is shown below.

S	T	
Favourites	Type	Ge
favourites	type	
	Shrub	
	Palm	
	Perennial	
	Succulent	
	Shrub	
	Tree	
	Vegetable	
	Vine	
	Wildflower	
	Shrub	

This list is also used when searching for plants in the **Insert Plant** commands in LANDWorksCAD, as shown below.

Search Fields:

Field Name	Operator	Value
Cultivars		
favourites		
type	Equal	Wildflower
habit		Vine
texture		Vegetable
maximum width		Tree
maximum height		Shrub
		Succulent
		Perennial
		Palm

Search Reset

This appendix explains how to work with these lists of selection data.



Note


Everything in this appendix is specific to Excel. The selection data lists cannot be edited in LANDWorksCAD.

Displaying the Hidden Selection Data

The selection data is contained in rows 2-27. Rows 1-27, 30 and 31 are initially hidden in the supplied database. This is to prevent users from accidentally, or intentionally, editing the data contained in these rows before they really know what the data is for. These rows can, however, be displayed without affecting the functionality of the database in any way.


To display these hidden rows, do the following:

1. Open the LandworksPlantDatabase.xls file.
2. Select all rows by clicking on the “**Select All**” button as shown below:



	L	M	N	O
28	Names			
29	abbreviation	abbreviation-2	botanical name	family
32	Ab x Gr	Abe x Gra	Abelia X Grandiflora	Caprifoliaceae
33	Ab x Gr Na	Abe X Gra Nan	Abelia X Grandiflora 'Nana'	Caprifoliaceae
34	Ab x Gr Su	Abe x Gr	Abelia X Grandiflora 'Nana'	Caprifoliaceae
35	Ab x Gr Va	Abe x Gr	Abelia X Grandiflora 'Nana'	Caprifoliaceae
36	Ab Gr	Abi Gra	Abies Nordmanniana	Pinaceae
37	Ab No	Abi Nor	Abies Nordmanniana	Pinaceae
38	Ab Pi	Abi Pin	Abies Pindrow	Pinaceae
39	Ab St Th	Abu Str Tho	Abutilon Striatum 'Thompson'	Malvaceae
40	Ac Ad	Aca Adu	Acacia Adunca	Fabaceae-Mimosac

3. The entire worksheet will be highlighted – all cells will have a grey background.
4. Select from **Home** tab > Cells > Format > Hide & Unhide > **Unhide Rows**



5. Rows 1-31 will be displayed (you may have to scroll up to see them)

1	L	M	N	O	P	Q	R	S	T
2	Names							Favourites	Type
3								Yes	Annual
4								No	Aquatic
5									Bamboo
6									Biennial
7									Broadleaf evergreen
8									Bulb
9									Bulb & Corms
10									Cacti & Succulent
11									Cacti
12									Conifer
13									Fern
14									Grass
15									Ground cover
16									Herb
17									Palm
18									Perennial
19									Succulent
20									Shrub
21									Tree
22									Vegetable
23									Vine
24									Wildflower
25									
26									
27									
28	Names							Favourites	Type
29	abbreviation	abbreviation-2	botanical name	family	common name	common name 2	Cultivars	favourites	type
30									
31									
32	Ab x Gr	Abe x Gra	Abelia X Grandiflora	Caprifoliaceae	Glossy Abelia				Shrub

6. To remove the highlighting click in any cell.

	L	M	N	O	P	Q	R	S	T
1	names							Favourites	Type
2								Yes	Annual
3								no	Aquatic
4									Bamboo
5									Biennial
6									Broadleaf evergreen
7									Bulb
8									Bulb & Corms
9									Cacti & Succulent
10									Orchid
11									Conifer
12									Fern
13									Grass
14									Ground cover
15									Herb
16									Palm
17									Perennial
18									Succulent
19									Shrub
20									Trees
21									Vegetable
22									Vine
23									Wildflower
24									
25									
26									
27									
28	Names							Favourites	Type
29	abbreviation	abbreviation-2	botanical name	family	common name	common name 2	Cultivars	favourites	type
30									
31									
32	Ab x Gr	Abe x Gra	Abelia X Grandiflora	Caprifoliaceae	Glossy Abelia				Shrub



Note

Saving the database with these rows displayed has no effect on the functionality of the database.

The formatting of these rows is white text with a grey background, but this is for identification only; the colours can be changed to suit you.

As an example of how this selection data works, scroll across to the **Type** column (T), click in the cell in row **32** and then click on the small “down arrow” that appears to the right of the cell, as shown below. The selection data in the list that appears is obtained from rows 2-21 in that column. This is the way it works for all columns; the data is obtained from within rows 2-27 of the column selected.

	S	T	U
1	Favourites	Type	General Appearance
2	Yes	Annual	Arching
3	No	Aquatic	Broad
4		Bamboo	Clinging
5		Biennial	Columnar
6		Broadleaf evergreen	Horizontal
7		Bulb	Irregular
8		Cactus	Mound
9		Conifer	Prostrate
10		Fern	Pyramidal
11		Grass	Round
12		Ground cover	Twining
13		Herb	Upright
14		Palm	Vase
15		Perennial	Weeping
16		Succulent	
17		Shrub	
18		Tree	
19		Vegetable	
20		Vine	
21		Wildflower	
22			
23			
24			
25			
26			
27			
28	Favourites	Type	General Appearance
29	favourites	type	habit
30			
31			
32		Conifer	
33		Conifer	
34		Fern	
35		Grass	
36		Ground cover	
37		Herb	
38		Palm	
39		Perennial	
40		Succulent	
41		Fern	

Editing the Existing Selection Data

Changing the Data

You can change the selection data by editing the existing text in the cells and/or adding new data to the empty cells. To do this, simply click in the cell and type in what you want.

LANDWorksCAD does not sort the data in any way, so if you want it listed alphabetically you must do it yourself by re-arranging the cells.

When you have finished editing your selection data, the edited data is immediately available in the drop-down lists within Excel.



Note

The drop-down lists in LANDWorksCAD will not be updated until you have saved your database and then either restarted LANDWorksCAD or reloaded the database.

When you have finished editing your selection data you don't have to hide the rows again. They can be left unhidden and LANDWorksCAD will still read the data correctly.



Important Note

1. The data can only reside in rows 2-27 and these row numbers are fixed
2. You **MUST NOT** insert more rows above row 28, the section headings. If you do, the “**Insert Plant**” commands in LANDWorksCAD will not work properly. For now, this means you are limited to a maximum of 26 items in any list, although this may change in the future.

After editing the selection data, don't forget to save your database.

Expanding the Data

If you have not expanded the selection data, i.e., you have only edited the existing text and/or re-arranged the existing cells, then you can save your database and the new selection data will work fine in LANDWorksCAD. However, if you have expanded the selection data by entering text in the empty cells, the selection data range must be updated to include these new cells. The following example explains how to do this.

This example uses the **Type** column (**T**), but the concept applies equally to all columns that have selection data lists.

In this example, two new entries have been added to the Type list: “Climber/Creeper” and “Fruit Tree”.


The standard selection data for column T is shown on the left below and includes rows 2 – 21. The new selection data is shown on the right and includes rows 2 –23. It includes the two new entries and the data has been re-arranged alphabetically.

	T		T
1	Type	1	Type
2	Annual	2	Annual
3	Aquatic	3	Aquatic
4	Bamboo	4	Bamboo
5	Biennial	5	Biennial
6	Broadleaf evergreen	6	Broadleaf evergreen
7	Bulb	7	Bulb
8	Cactus	8	Cactus
9	Conifer	9	Climber/Creeper
10	Fern	10	Conifer
11	Grass	11	Fern
12	Ground cover	12	Fruit Tree
13	Herb	13	Grass
14	Palm	14	Ground cover
15	Perennial	15	Herb
16	Succulent	16	Palm
17	Shrub	17	Perennial
18	Tree	18	Succulent
19	Vegetable	19	Shrub
20	Vine	20	Tree
21	Wildflower	21	Vegetable
22		22	Vine
23		23	Wildflower
24		24	
25		25	
26		26	
27		27	


New Data

The following steps were used to update the selection data range for this example:

1. Click in the cell in row 32 for column T.
2. Select from the **Data** tab > Data Validation > **Data Validation...**



3. Select the **Settings** tab on the “Data Validation” dialog box that appears, as shown below.




4. The “**Allow**” box is set to allow a “list” to be selected from.
5. The “**Source**” box, as indicated above, shows the cells that contain the list, ie, the selection data. In this example this is cells T2 – T21. (Ignore the \$ signs; they are inserted automatically by Excel)
6. Click on the “**Cell Selector**” as shown above.
7. The “Data Validation” dialog box will be reduced in size and the existing selection data highlighted. as shown below.




Note


The “existing” selection data range may alter from the original depending on how you edited the data.




8. Highlight the new selection data by dragging your cursor over the cells until the flashing highlight rectangle includes the new data, as shown below. The cell numbers in the reduced Data Validation dialog box will adjust accordingly.



- Click on the “Cell Selector” again, as shown below. This will enlarge the “Data Validation” dialog box again.



- Tick the box indicated below to ensure this new selection data applies to all the other cells in the column. The other cells in column T are highlighted.



- Click OK to finish.

All cells in column T now list the two new entries in their selection data list.

Assigning Selection Data to New Columns

If you add a new column to your database, either of two things will happen to the selection data for that column:

- There will be no selection data, ie, rows 2–27 for that column will be empty, so the selection data list will be empty, or
- The new column will have inherited the selection data from an adjacent column so the selection data list will be incorrect because it is pointing to the wrong column.

In both cases, the correct data will have to be entered into the cells and then the selection data lists updated to look at it, using the same technique described in the previous section, [Expanding the Data](#).



Note


The instructions in this section do not cover every function of Data Validation within Excel. For more details refer to the Excel Help system or [contact us](#).

Removing the Selection Data

There may be cases where you do not want the data for a particular column to be restricted to a pre-defined list; you want to be able to enter any data into the cells. To do this you must remove the “list” restriction of Excel’s Data Validation function that is used by LANDWorksCAD.


This is done as follows:

1. Select the cells you want to unrestrict. This may be a small selection of cells or the entire column.
2. Select from the **Data** tab > Data Validation > **Data Validation...**



3. Depending on the cells selected, you may get a message that some of the cells do not have Data Validation settings & you'll be asked if you want to extend the settings to these cells - click **“Yes”**.

4. In the "Settings" tab, the "Allow" field will show the word "List". Change this to read "Any value" & then click **OK**.



5. You can now enter any text you want.
6. Save the database & restart LANDWorksCAD or reload the database for this new setting to be available.

Appendix 4 – Sorting the Plant Database in Excel

The plant database supplied with LANDWorksCAD has the plants sorted alphabetically by their Botanical name, but this can be changed; the plants can be sorted by any column you want.

However, the database can only be sorted in Excel; it cannot be sorted in LANDWorksCAD. LANDWorksCAD simply displays the plants in whatever order they are in Excel.

The secret to sorting the plant database is to NOT select the entire spreadsheet, as is normally done when sorting a spreadsheet. This is because rows 1–31 should not be included in any sorting; they must remain where they are for the spreadsheet to work correctly with LANDWorksCAD.

The steps to sorting the database are as follows:

1. Determine by what column you want the data sorted and note the column letter, e.g., to sort by **Botanical Name** it is column **N**, to sort by **Type** it is column **T**, etc.
2. Scroll up until you can see row 32. Your screen should look something like the image below.

	K	L	M	N	O
28		Names			
29	number of 2d figures	abbreviation	abbreviation-2	botanical name	family
32	1	Ab gr		Abies grandis	
33	1	Ac ba		Acacia baileyana	Fabaceae, sub fam. Mimosoide;
34	1	Ac bu		Acacia buxifolia	Fabaceae, sub fam. Mimosoide;
35	1	Ac de		Acacia decurrens	Fabaceae, sub fam. Mimosoide;
36	1	Ac sa		Acacia sowdenii	
37	1	Ac sp		Acacia spetabilis	
38	1	Ac re		Acer rubrum	
39	1	Ac he		Actinotus helianthi	Apiaceae
40	1	Ad ra		Adiantum hispidulum	Adiantaceae
41	1	Ae pa		Aesculus pavia	
42	1	Ag pr		Agapanthus procox	
43	1	Al to		Allocasuarina torulosa	Casuarinaceae
44	1	Al gl		Alnus glutinosa	
45	1	Am gr		Amelanchia grandiflora	
46	1	An co		Angophora costata	
47	1	An ma		Anigozanthos manglesii	Haemodoraceae

3. Click on row 32's identifying number. This will highlight row 32 as shown below.



	K	L	M	N	O
28		Names			
29	number of 2d figures	abbreviation	abbreviation-2	botanical name	family
32	1	Ab gr		Abies grandis	
33	1	Ac ba		Acacia baileyana	Fabaceae, sub fam. Mimosoide;
34	1	Ac bu		Acacia buxifolia	Fabaceae, sub fam. Mimosoide;
35	1	Ac de		Acacia decurrens	Fabaceae, sub fam. Mimosoide;
36	1	Ac sa		Acacia sowdenii	
37	1	Ac sp		Acacia spetabilis	
38	1	Ac re		Acer rubrum	
39	1	Ac he		Actinotus helianthi	Apiaceae
40	1	Ad ra		Adiantum hispidulum	Adiantaceae
41	1	Ae pa		Aesculus pavia	
42	1	Ag pr		Agapanthus procox	
43	1	Al to		Allocasuarina torulosa	Casuarinaceae
44	1	Al gl		Alnus glutinosa	
45	1	Am gr		Amelanchia grandiflora	
46	1	An co		Angophora costata	
47	1	An ma		Anigozanthos manglesii	Haemodoraceae

4. Scroll down the screen until you can see the last row of plant data.
5. Hold down the **Shift** key and click the last row's identifying number.

6. This will highlight all the rows from 32 to the last row of data, as shown below. Here the last row of data is 266.

	K	L	M	N	O
28	Names				
29	number of 2d figures	abbreviation	abbreviation-2	botanical name	family
254	1	To bo		Toxus boccata	
255	1	Tr sp		Tricocereus spachianus	
256	1	Tr pu		Tricocereus purpur	
257	1	Tr co		Tristania conferta	
258	1	Tr co		Tristania conferto	
259	1	Ts he		Tsuga heterophylla	
260	1	Ts si		Tsuga sieboldii	
261	1	Ul pr		Ulmus procera	Ulmaceae
262	1	Ul sa		Ulmus sarniensis	
263	1	Vi he		Viola hederacea	
264	1	Wis fl		Wisteria florabunda	
265	1	Wo bi		Wodyetia bifurcata	
266	1	Xa au		Xanthorrhoea australis	
267					
268					
269					

7. Select **Data > Sort & Filter > Sort**. The following dialog box will be displayed.



- Click in the first "Sort by" field and select the column you want to sort the data by, eg, column N = Botanical Name, column T = Type, etc.
- Make sure the "Ascending" option is selected, as shown above. So the data is sorted from A to Z.
- Make sure the "My data has headers" option is not selected.
- Click the **OK** button.
- The plants will now be sorted in alphabetical order by the column you selected. You may have to scroll back up to see the results.
- Save your database. The next time you start LANDWorksCAD or reload the database the plants will be listed in this order.

14. If you add more plants to the database it's best to insert them so the plants remain in alphabetical order. If they get mixed up again, simply repeat the steps listed here to re-sort them.



Note

The dialog box shown above gives you the ability to sort the data by several columns; however this functionality is not covered in this manual.