

RAW Image Processing, Viewing and Editing Software

Digital Photo Professional

Ver. 3.8

Instruction Manual

- Content of this Instruction Manual
 - DPP is used for Digital Photo Professional.
 - In this manual, the windows used in the examples are from Windows XP.
 - ▶ indicates the selection procedure of the menu. Example: [File] menu ▶ [Exit].
 - Square brackets are used to indicate items such as menu names, button names and window names that appear on the computer screen.
 - Text inside < > indicates a key on the keyboard.
 - ** indicates a reference page. Click to move to the relevant page.
 - ? : Marks helpful information when a problem arises.
 - $\frac{1}{2}$: Marks tips for using the software skillfully.
 - (!) : Marks information that should be read before use.
 - Tarks additional information you may find helpful.

- Switching Between Pages
 - Click on arrows on the bottom right of the screen.
 - I next page
 - : previous page
 - I return to a page you had previously displayed
 - Click on the chapter headings on the right side of the screen to switch to the contents page of that chapter. Also, click the item you want to read about on the table of contents to move to the relevant page.
- Help and Shortcut Keys
 - For information about using DPP, refer to Help from the [Help] menu.
 - Refer to the [Troubleshooting] ▶ [Shortcut Key List] in the Help for a list of shortcut keys which are helpful for quick operation.



Introduction

Windows

READ CAREFULLY BEFORE USING!

CANON SOFTWARE LICENSE AGREEMENT

IMPORTANT - READ THIS AGREEMENT BEFORE USING THE SOFTWARE ON THE CD-ROM IN THIS BOX. BY USING THE SOFTWARE, YOU AGREE TO BE BOUND BY THE TERMS OF THIS AGREEMENT.

This is a license agreement (the [Agreement]) between you and Canon Inc. ([Canon]).

IF YOU DO NOT AGREE TO THE TERMS AND CONDITIONS OF THIS AGREEMENT, DO NOT USE THE SOFTWARE PROGRAM ON THE CD-ROM AND THE USER MANUAL IN THIS BOX (COLLECTIVELY, THE [SOFTWARE]) AND RETURN THE SOFTWARE WITHIN 30 DAYS FROM THE DATE OF PURCHASE TO YOUR POINT OF PURCHASE FOR A REFUND.

In consideration of the right to use the SOFTWARE, you agree to abide by the terms and conditions of this Agreement.

 LICENSE: Canon grants you the non-exclusive right to use the SOFTWARE only on a single computer. You may physically transfer the SOFTWARE from one computer to another provided that the SOFTWARE is used on only one computer at a time. You shall not install or use the SOFTWARE on a network, multiple CPU, multiple site arrangement, or any other hardware configuration where the SOFTWARE is accessible to more than one CPU or to more than one user.

YOU SHALL NOT ASSIGN, SUBLICENSE, RENT, LEASE, LOAN, CONVEY OR OTHERWISE USE, TRANSFER, COPY, TRANSLATE, CONVERT TO ANOTHER PROGRAMMING LANGUAGE, ALTER, MODIFY, DECOMPILE OR DISASSEMBLE THE SOFTWARE, IN WHOLE OR IN PART, EXCEPT AS EXPRESSLY PROVIDED IN THIS AGREEMENT.

- 2. BACK-UP COPY: You may make one copy of the SOFTWARE solely for back-up purposes, or copy the SOFTWARE onto the permanent storage device (e.g. a hard disk) of your computer and retain the original for back-up purposes. Any other copying of the SOFTWARE is a violation of this Agreement. You must reproduce and include the copyright notice on the back-up copy.
- SUPPORT AND UPDATES: Canon is not responsible for providing maintenance or support for use of the SOFTWARE. No updates, fixes or support will be made available for the SOFTWARE.
- 4. LIMITED WARRANTY AND LIMITATION OF LIABILITY: It is your responsibility to choose, maintain and match the hardware and software components of your computer system. Thus Canon does not guarantee uninterrupted service or correction of errors or that the functions or performance of the SOFTWARE will meet your requirements. THE SOFTWARE IS LICENSED ON AN [AS IS] BASIS AND WITHOUT WARRANTY OF ANY KIND. The CD-ROM storing the SOFTWARE is warranted only against defective material under normal use for a period of ninety (90) days after purchase from an authorized Canon dealer as evidenced by your sales receipt. Your sole remedy for a defective CD-ROM shall be replacement of the same without charge when returned by you at your expense to your point of purchase and proven to be defective upon inspection. The replacement CD-ROM will be warranted for the remainder of the original ninety (90) day warranty period of the defective CD-ROM. The limited warranty does not apply if the failure of the CD-ROM resulted from accident, abuse or misapplication of the SOFTWARE and shall not extend to anyone other than the original user of the SOFTWARE.

EXCEPT AS SPECIFICALLY SET FORTH IN THIS PARAGRAPH 4, CANON, CANON'S SUBSIDIARIES, DISTRIBUTORS AND DEALERS DISCLAIM ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE, WITH RESPECT TO THE SOFTWARE.

NEITHER CANON NOR ANY OF CANON'S SUBSIDIARIES, DISTRIBUTORS OR DEALERS IS LIABLE FOR ANY DAMAGES HOWSOEVER CAUSED, INCLUDING WITHOUT LIMITATION, DIRECT, CONSEQUENTIAL OR INCIDENTAL LOSS OR DAMAGE INCLUDING LOSS OF PROFITS, EXPENSE OR INCONVENIENCE HOWSOEVER CAUSED OR ARISING OUT OF THE SOFTWARE OR THE USE THEREOF.

NEITHER CANON, NOR ANY OF CANON'S SUBSIDIARIES, DISTRIBUTORS OR DEALERS SHALL HAVE ANY OBLIGATION TO INDEMNIFY YOU AGAINST ANY CLAIM OR SUIT BROUGHT BY A THIRD PARTY ALLEGING THAT THE SOFTWARE OR THE USE THEREOF INFRINGES ANY INTELLECTUAL PROPERTY OF SUCH THIRD PARTY.

- 5. TERM: This Agreement is effective upon your using the SOFTWARE and remains in effect until expiration of all copyright interests in the SOFTWARE unless earlier terminated. You may terminate this Agreement by destroying the SOFTWARE. This Agreement will also terminate without notice to you if you fail to comply with any of the terms of this Agreement and you must then promptly return the SOFTWARE. In addition, Canon may enforce its other legal rights.
- 6. U.S. GOVERNMENT RESTRICTED RIGHTS NOTICE: The SOFTWARE is provided with restricted rights. Use, duplication or disclosure is subject to restrictions as set forth in either subparagraph (c) (1) (ii) of the Rights in Technical Data and Computer software clause at DFARs 252.227-7013 or subparagraph (c) (1) and (2) of the Commercial Computer Software Restricted Rights Clause at FAR 52.227-19, as applicable.
- 7. SEVERABILITY: In the event that any provision of this Agreement is declared or found to be illegal by any court or tribunal of competent jurisdiction, such provision shall be null and void with respect to the jurisdiction of that court or tribunal and all the remaining provisions of this Agreement shall remain in full force and effect.
- 8. CONTROLLING LAW: The terms of this Agreement as it relates to purchases of the Software in the United States of America shall be governed and construed in all respects in accordance with the laws and regulations of the State of New York, without reference to choice of law principles. The terms of this Agreement as it relates to purchases of the Software in Canada shall be governed by the laws of the province of Ontario.
- 9. OWNERSHIP: All rights, including but not limited to copyrights and trade secret rights, to the SOFTWARE belong to Canon, its affiliated corporations and third party licensors. Your use of the SOFTWARE is subject to the United States, Canada and other applicable copyright and trademark laws and nothing in this Agreement constitutes a waiver of the rights of Canon, its affiliated corporations and third party licensors under such laws. Nothing contained in Paragraph 1 shall be construed to give Canon any ownership rights in any images, graphics or textual material that you save in connection with the Software.
- 10.ACKNOWLEDGEMENT: BY USING THE SOFTWARE, YOU ACKNOWLEDGE THAT YOU HAVE READ THIS AGREEMENT, UNDERSTOOD IT, AND AGREE TO BE BOUND BY ITS TERMS AND CONDITIONS. YOU ALSO AGREE THAT THIS AGREEMENT IS THE COMPLETE AND EXCLUSIVE STATEMENT OF AGREEMENT BETWEEN YOU AND CANON CONCERNING THE SUBJECT MATTER HEREOF AND SUPERSEDES ALL PROPOSALS OR PRIOR AGREEMENTS, VERBAL OR WRITTEN, AND ANY OTHER COMMUNICATIONS BETWEEN THE PARTIES RELATING TO THE SUBJECT MATTER HEREOF. NO AMENDMENT TO THIS AGREEMENT SHALL BE EFFECTIVE UNLESS SIGNED BY A DULY AUTHORIZED OFFICER OF CANON.

Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference



Introduction

Digital Photo Professional (hereinafter, "DPP") is a high-performance RAW image processing, viewing and editing software for EOS DIGITAL cameras. It is often thought that RAW images are difficult to handle compared with ordinary JPEG images, but using DPP, you can perform advanced edits and print RAW images with ease.

RAW Images and Their Features

What is a RAW Image?

A RAW image is image data that has recorded output data of imaging sensor. Because image processing does not occur inside the camera when a photo is taken and the photo has been recorded in the special form of "RAW image data + Image processing conditions information at the time of shooting", special software is needed to view or edit the image.

* "RAW" means "in a natural condition" or "not processed or refined".

What is RAW Development?


If described in terms of film, the concept of a RAW image is a shot image not yet developed (latent image).

With film, the image appears for the first time when it is developed. And as for RAW images too, you cannot view it as an image on your computer unless you perform subsequent image signal processing. Therefore, even though it is digital, this processing is called "development" and with EOS DIGITAL is performed using DPP. With DPP, you can view, edit and print RAW images without having to be particularly conscious of the development processing.

What Advantages Does a RAW Image Have?

RAW images are recorded in the format "RAW image data + Image processing conditions information at the time of shooting". When you open an image in DPP, the image is instantly developed and you can view the image as an image to which image processing conditions at the time of shooting have been applied.

Even if you perform various adjustments to the image you have opened (it undergoes automatic development processing each time), only the image processing conditions (development conditions) change and the "original image data itself" remains unaffected. Consequently, image deterioration is not a problem and it is the perfect image data for users who want to get creative with their images after they have been shot. In DPP, the "Image processing conditions information" that can be adjusted is called a "Recipe".



Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editina JPEG/TIFF Images Reference Index

Main Features of DPP

Following are the main tasks you can perform with images you have downloaded to your computer.

View and organize RAW images

Real-time adjustment of a RAW image

- Various image adjustments while maintaining the original image
- Freely apply a Picture Style
- View your image before and after adjustment in the same window
- Trimming and adjusting the angle of an image
- Change image size
- **Correction of lens aberration**
- Automatic/manual dust erasure processing
- Convert from a RAW image to a JPEG or **TIFF** image and save
 - Process large numbers of RAW images in batches
 - Transfer the image to image editing software

Print a RAW image

View and organize JPEG and TIFF images

Real-time adjustment of JPEG and TIFF images

Various image adjustments while maintaining the original image

Print JPEG and TIFF images

- Color management compatibility
 - CMYK simulation for commercial printing

System Requirements

OS	Windows 7 ^{*1} , Windows Vista ^{*2} Windows XP Professional/Home Edition ^{*3}	
Computer	PC with one of the above OS preinstalled * Upgraded machines not supported	Contents a a Glance
CPU	1.3GHz Pentium or higher*4	
RAM	Minimum 1GB	Basic
Display	Screen resolution: 1024 × 768 pixels or more Color quality : Medium (16 bit) or more	Operation

- *1 Compatible with 32-bit/64-bit systems for all versions except Starter Edition
- *2 Compatible with 32-bit/64-bit systems for all versions except Starter Edition (Also compatible with Service Pack 1)
- *3 Compatible with Service Pack 2/Service Pack 3
- *4 Core2 Duo or higher is recommended

Supported Images

This software supports the following image types.

	Image type	Extension
RAW images	RAW images ^{*1} shot with EOS DIGITAL cameras, excluding EOS DCS1 and EOS DCS3 RAW images ^{*2} shot with PowerShot cameras	.CR2 .TIF .CRW
JPEG images	Exif 2.2 or 2.21-compatible JPEG images	.JPG, .JPEG
TIFF images	Exif-compatible TIFF images	.TIF, .TIFF



Introduction

Processing Large Numbers of Images

Image type	Extension	
nages ^{*1} shot with EOS DIGITAL as, excluding EOS DCS1 and EOS DCS3 nages ^{*2} shot with PowerShot cameras	.CR2 .TIF .CRW	
2 or 2.21-compatible JPEG images	.JPG, .JPEG	



Compatible with RAW images shot with EOS D6000 or EOS D2000 that have been converted to RAW images using the CR2 Converter and have the ".CR2" extension.

For information on CR2 Converter, refer to Canon's web site.

- *2 Only models where Digital Photo Professional is listed in the "Data Type" item in the "Specifications" section near the end of the Camera User Guide.
 - Use the dedicated CameraWindow application to download images from a PowerShot camera to a computer. See the Software Starter Guide for details.
 - Lens aberration correction can only be used with some camera and lens models.
 - Automatic dust erasure processing and other EOS DIGITAL specific functions cannot be used.
 - RAW images shot with the PowerShot Pro1 are also supported, but they cannot be edited with the DPP RAW image adjustment function.

Contents at a Glance

Downloading Images to Your Computer

 Download images by connecting your camera and computer 	→ p.7
Download images using a card reader	→ p.9

Viewing and Checking RAW Images

 Quickly enlarge parts of an image 	→ p.11
 Sort images (check marks) 	→ p.17, p.18
 Display an image shot simultaneously as a RAW image and JPEG image as a single image 	→ p.20
 Display the images in the thumbnail list display at high resolution 	→ p.21

• Check shooting information such as the shooting date \rightarrow p.10, p.21

Editing RAW Images (Adjusting)

 Adjust brightness/darkness Use automatic adjustment Change the Picture Style 	 → p.12, p.24 → p.30 → p.24
 Sharpen the modulation and contrast of colors (contrast) 	→ p.27
Make skin tone look healthier (color tone)	→ p.27
 Make the image colors more vivid (color saturation) 	→ p.27
 Make an image sharp (sharpness) 	→ p.29
 Adjust an image to make color tone more natural (white balance) 	→ p.25
 Change an image to black-and-white or sepia tones (monochrome) 	→ p.28
 Trim an image and adjust the angle of an image 	→ p.35
 Specify an aspect ratio that matches the size of the paper on which an image is to be printed 	→ p.35

Erase dust shot with the image	→ p.64, p.66
 Erase unwanted parts of an image 	→ p.68
Auto correct RAW images with the Auto Lighting Optimized in	mizer
 Adjust brightness of shadows/highlights 	→ p.54
 Reduce image noise 	→ p.59
 Correct lens aberration 	→ p.60
 Use a Picture Style file 	→ p.56
Edit efficiently	→ p.31
 Edit an image while comparing the image before after adjustment 	and → p.50
 Synchronize multiple images 	→ p.51
 Display an area beyond the set range as a warnin indicator (Highlight/Shadow warning) 	ng → p.52
 Restore an adjusted image to its condition at the of shooting 	time → p.40
Printing	
 Print well on a Canon printer 	→ p.40, p.71, p.72
 Faithfully reproduce the color of the subject when printing 	→ p.40, p.71, p.72
 Print with the shooting information 	→ p.69
 Print a thumbnail list of images 	→ p.70
 Approximate the color seen on screen with your printing results 	→ p.77
Conversion of Images	
 Convert a RAW image to a JPEG image 	→ p.39, p.83
 Edit in Photoshop 	→ p.68, p.84
Perform batch processing	→ p.83
 Edit (adjust) a JPEG image 	→ p.87

Contents at a Glance Basic Operation Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images


Editing JPEG/TIFF Images

Reference





1 Basic Operation



The basic operational flow – from how to download to your computer images shot with a camera to checking, editing, saving and printing a downloaded RAW image – is explained here.

Starting up DPP 6
Main Window Display6
Downloading an Image to Your Computer
Downloading Images Using Your Card Reader
Viewing an Image 10
View Images as Thumbnails in the Main Window 10
Changing the Size of Thumbnail Images 10
Enlarge and View an Image in the Edit Window 11
Enlarging and Viewing a Specific Area 11
Adjusting an Image 12
About the Tool Palette 12
About Recipes 12
Saving an Image 13
Saving 13
Printing an Image 14
Printing 14
Exiting DPP 14



Introduction

Contents at

a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing


Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Starting up DPP

Double-click the desktop icon.



→ DPP starts up and the main window ([Folder] window) appears.



Main window ([Folder] window)




Main Window Display


In the main window, you can use tabs to select either the [Folder] window or the [Collection] window. The [Folder] window displays the images in folders on your computer, while the [Collection] window (p.33) displays images selected randomly by the user from one or more folders and gathered together.

Unless noted otherwise, the [Folder] window will be described as the main window from this point on.

[Folder] window



[Collection] window



	Introduction
	Contents at a Glance
,	Basic Operation
-	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

Downloading an Image to Your Computer

Connect the camera and computer with the cable provided and download the images saved on the memory card inserted in the camera. For downloading images, start up the camera software "EOS Utility" from DPP and use.

Select the save destination for the images.

- Select the save destination in the folder area on the left of the main window.
- When creating a folder, refer to p.47.



Start up EOS Utility.

Select the [Tools] menu ▶ [Start EOS Utility].

Tools

Start EOS Utility	Alt+O
Transfer to Photoshop	Alt+P
Start Quick check tool	Alt+Q
Start Trimming/Angle Adjustment tool	Alt+C
Start Stamp tool	Alt+S
Start Rename tool	Alt+R
Sync folder with EOS Utility	
Preferences	Ctrl+K


EOS Utility




Connect your camera and computer and turn the camera on.

 Connect the camera and your computer with the interface cable provided with the camera and turn the camera on.

 For detailed instructions on connecting your camera and computer, refer to the "EOS Utility Instruction Manual" (PDF electronic manual).



→ The capture window for EOS Utility appears.




→ EOS Utility starts up.

Click the [Main Window] button.




→ The main window for EOS Utility appears.

Complete Complete



- → Downloading of images begins.
- \rightarrow The downloaded images are saved in the folder selected in step
 - 1 and are displayed in the main window of DPP.
- The downloaded images are sorted by date into folders and saved.



Reference

Index



Downloading Images Using Your Card Reader

You can also download images to the computer using a third-party card reader.

Load the memory card into the card reader.

Open [My Computer] ▶ [EOS_DIGITAL] and drag the [DCIM] folder to the [Desktop].



→ The [DCIM] folder is downloaded to your computer.

• All images are saved in folder units inside the [DCIM] folder.

Display the images downloaded to your computer.
 In the [DCIM] folder copied to your desktop, select the folder



- Images in the folder are displayed in the main window of DPI
- Checking before downloading images By selecting the memory card folder directly in DPP, the images in

folder are displayed in DPP and you can check the shot images.

- Copying to your computer may take time when there is a large number of shot images saved in the memory card.
 - For details on the [DCIM] folder structure and the file names of shot images, refer to "Folder Structure and File Names in the Memory Card" in the "EOS Utility Instruction Manual" (PDF electronic manual).

er.	Introduction
er	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
PP.	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
the	Index

Viewing an Image

Images downloaded to your computer are displayed as a thumbnails list in the main window. You can double-click an image to open the edit window and display the image at large size.

View Images as Thumbnails in the Main Window

Main window

Rotate selected image



Click to select the image

Display thumbnails of all the images inside the folder selected in the folder area on the left

Images displayed with the [Images displayed with the [Images displayed with the [Images displayed back in DPP. Please use "ZoomBrowser EX", which is compatible with EOS DIGITAL movie files.

 When aspect ratio information is attached to the shot image with the EOS-1D Mark IV, EOS-1Ds Mark III, EOS-1D Mark III or EOS 7D, the image is displayed as a trimmed image (p.35, p.95).

• For a list of main window functions, refer to p.107.


Changing the Size of Thumbnail Images

You can change the size of the thumbnail images displayed in the main window and display them with shooting information attached.

Select the [View] menu ▶ desired item.

Edit in Edit image window View collections	Ctrl+Righ Alt+G	nt Arrow
Tool palette • Tab • Folders • Toolbar	Ctrl+T	
Large thumbnail Medium thumbnail Small thumbnail Thumbnail with information	Ctrl+1 Ctrl+2 Ctrl+3 Ctrl+4	

→ The display changes to the selected item.



Enlarge and View an Image in the Edit Window

Double-click

Tool palette



→ The edit window appears.

Edit window

 \equiv



- → It may take time for the image to redraw itself.
- Click the [X] in the upper right of the edit window to close the edit window.
- By selecting the [View] menu ▶ [AF Point] in the edit window, you can display the AF points selected in the camera at the time of shooting. However, AF points are not displayed for images which have had their image size changed and then been converted and saved (p.39, p.116).
- For a list of edit window functions, refer to p.110.

Enlarging and Viewing a Specific Area

Double-click the area you want to enlarge.



Double-click

Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editina JPEG/TIFF Images Reference Index

Introduction

- The area you double-clicked is enlarged to 100% (actual pixel size). If you wait for a while, it changes to a clearer display.
- Double-click again to revert to the full view.
- To change the display position, drag on the image or drag the enlargement display position of the tool palette.

Tool palette enlargement display position



 Change the enlargement display position by dragging

$\stackrel{}{\sim}$ To display an image in an enlargement ratio other than 100%


Select the [View] menu ▶ [200% view] or [50% view].

You can change the enlargement ratio when you double-click (p.75).

Adjusting an Image

You can perform a variety of image adjustments, such as adjusting the brightness or changing the Picture Style of an image using the tool palette of the edit window. You can easily restore an image to its original settings with the [] button even if you have made the wrong adjustment. Try out the various adjustments.

As an example, the procedure to adjust the brightness of an image is explained here.



Reverts the image to the original settings

About the Tool Palette

You can adjust images with the tool palette by switching between the [RAW], [RGB] and [NR/Lens/ALO] tab sheets according to your editing requirements.

Because adjustment made with the tool palette (it undergoes automatic development processing each time) only changes the image processing conditions, the "original image data itself" remains unaffected. Therefore, there are no problems with image deterioration that arise with editing and you can readjust your images any number of times. See Chapter 2 onwards for more detailed information on the various functions of the tool palette.

About Recipes

In DPP, all the adjustment contents (image processing conditions information) made with the tool palette is saved to an image as data called a "Recipe" (p.80).



Introduction

The image brightness changes in real time according to the amount of adjustments.

The tool palette does not display 2

Select the [View] menu ▶ [Tool palette].

Saving an Image

If you perform the save operation described here, you can save all the adjustment contents (recipe) made with the tool palette to the RAW image.

Select the [File] menu ▶ [Save].

Fi	le	
C	Save	Ctrl+S
	Save As	Ctrl+Shift+S
	Convert and save	Ctrl+D
	Print	Ctrl+P
	Print with detailed setting	Ctrl+Alt+P
	Contact Sheet Prints	Ctrl+Shift+P
	Plug-in printing	•
	Info	Ctrl+I
	Close	Ctrl+W

→ Your adjustment contents (recipe) are saved to the image.

Saving

With DPP, you can perform the following types of saving according to your requirements. For detailed information on each saving method, refer to Chapter 2 onwards.

• Save (p.38)

Add adjustment contents (recipe) made with the tool palette to a RAW image and save.

Save as (p.38)

Add adjustment contents (recipe) made with the tool palette to a RAW image and save as a separate RAW image. The original RAW image remains unaffected.

Add thumbnail to image and save* (p.21)

Create a new thumbnail image for the main window and save to each image.

The quality of images in the main window improves and images redraw themselves more quickly.

Convert and save (p.39)


Convert adjusted RAW image to a JPEG or TIFF image and save. The original RAW image remains unaffected.

Batch process (p.83)

Convert in batches adjusted multiple RAW images to JPEG or TIFF images and save.

The original RAW images remain unaffected.

* Option available in the main window.





Printing an Image

You can print images with a printer. As an example, the procedure to print one image on one sheet of paper is described here.

Select the [File] menu ▶ [Print]	
Ctrl+S	
Ctrl+Shift+S	
Ctrl+D	
Ctrl+P	
Ctrl+Alt+P	
Ctrl+Shift+P	
+	
Ctrl+I	
Ctrl+W	

→ The printer's print settings dialog box appears.

Print.

- Specify the optimum settings for photograph printing in the printer's print settings dialog box and click the [OK] button.
- → Printing begins.

Printing

With DPP, you can perform the following types of printing according to your requirements. For detailed information on each printing method, refer to Chapter 2 onwards.

- Print one image (p.46)
- Print using a Canon inkjet printer (p.40, p.43)
- Print with a high-end Canon printer (p.71)
- Print with shooting information (p.69)
- Printing a thumbnail list (contact sheet printing) (p.70)


Exiting DPP

In the main window, select the [File] menu ▶ [Exit].

Op	pen in Edit window	Ctrl+0
Op	pen in Edit window (enlarged)	
Sa	ave	Ctrl+S
Sa	ave As	Ctrl+Shift+S
Ac	dd thumbnail to image and save	Ctrl+Shift+T
Co	privert and save	Ctrl+D
Ba	atch process	Ctrl+B
Cr	reate new folder	
Pr	int	Ctrl+P
Pr	int with detailed setting	Ctrl+Alt+P
Co	ontact Sheet Prints	Ctrl+Shift+P
Plu	ug-in printing	+
Ac	dd to collection	Ctrl+G
Re	emove from collection	Ctrl+Shift+G
C	ear collection	
De	elete	Del
In	fo	Ctrl+I
E>	kit.	Alt+F4

DPP exits.

adjusted.



14

2 Advanced Operation

A more advanced operation – from efficiently checking images, to various ways of editing an image, printing a RAW image using a Canon printer and sorting images – is explained here.

Efficiently Checking/Sorting Images	16
Sorting Images	17
Sorting Images in the Main Window	18
Arranging Images in the Main Window	18
Arranging by Type	18
Arranging Freely	19
Displaying a RAW Image and JPEG Image as a Singl	le
Image	20
Improving the Quality of an Image in the Main Window	21
Checking Image Information	21
Editing an Image	23
About the RAW Tool Palette	
Editing with the Tool Palette in the Main Window	23
Adjusting Brightness	24
Changing a Picture Style	24
Picture Style File	25
Adjusting Color Tone by Changing White Balance	25
Adjusting Color Tone Using Click White Balance	26
Adjusting Contrast	27
Changing Color Tone and Color Saturation	27
Adjusting Monochrome	28
Adjusting Sharpness	29
Automatically Adjusting Brightness and Color (Tone	
Curve Assist)	30

Editing Efficiently 31	
Editing in the Edit Image Window	Contents at
Changing the Thumbnail Display Position to a Horizontal	a Glance
Position	
Gathering and Editing Images in the Collection Window 33	Basic Operation
Trimming and Adjusting the Angle of an Image 35	
Applying Adjustment Contents to Other Images 38	Advanced
Saving Editing Results 38	Operat ion
Saving Editing Contents to a RAW Image	Advanced
Saving as a JPEG or TIFF Image	Image Editing and Printing
Re-Editing an Image 40	
Printing an Image 40	Processing Large Numbers
Printing Photographs with Canon Inkjet Printers	of Images
Compatible with Easy-PhotoPrint EX 40	Editing
Printing Photographs with Canon Inkjet Printers	JPEG/TIFF
Compatible with Easy-PhotoPrint	Images
Printing Photographs with a Printer other than Canon	
Inkjet Printers 46	Reference
Organizing Images 46	
Deleting an Unwanted Image 46	Index
Creating a Folder for Saving Images 47	
Moving Images 47	
Moving Images in Folders 48	
Registering Frequent-Use Folders (Bookmark	
Registering Frequent-Use Folders (Bookmark Registration)	

Efficiently Checking/Sorting Images

You can enlarge images displayed as thumbnails in the main window and efficiently check each image. You can attach check marks and sort images into three groups.

Display the quick check window.


Select the [Tools] menu ▶ [Start Quick check tool].

Tools		
Star	t EOS Utility	Alt+0
Tra	nsfer to Photoshop	Alt+P
Star	rt Quick check tool	Alt+Q
Star	't Trimming/Angle Adjustment tool	Alt+C
Star	rt Stamp tool	Alt+S
Star	't Rename tool	Alt+R
Syn	c folder with EOS Utility	
Pref	erences	Ctrl+K

 \rightarrow The quick check window appears.


Click the [Next] or [Previous] button to switch between images to be checked.

Quick check window



• All the images displayed in the main window can be checked in the quick check window.

Double-click the area you want to enlarge.




Double-click

→ The area you double-clicked is enlarged to 50% view.

are not displayed for images which have had their image size changed and then been converted and saved (p.39, p.116).

- To change the display position, drag on the image.
- Double-click again to revert to the full view.
- To exit, click the [OK] button.



$\overline{\mathbb{W}}^{\mathbb{H}}$ Convenient functions of the quick check window

To check only selected images

You can use the quick check window to check only selected images by selecting the desired images from those displayed in the main window and then performing step 1.

Switch between images using the keyboard

You can also switch between images by pressing the < \rightarrow > or < \leftarrow > key.

Switch between screens using the keyboard

You can also switch between full screen display/normal screen display by pressing the <Alt> + <Enter> keys.

Operate using the menu

Each operation can also be performed with the menu which appears when you right-click with the mouse on an image.


- The enlargement ratio when an image is enlarged is half (50%) of the 100% (actual pixel size).
 - You can change the enlargement ratio to 100%, when an image is enlarged (p.75).
 - For a list of quick check window functions, refer to p.114.

Sorting Images

You can sort images by attaching three types of check marks for each subject or theme.

Attach check marks for sorting.

Check mark



The selected check mark appears in the upper left of the window.

Click the [Clear] button to remove the check marks.



Sorting Images in the Main Window

You can sort images by attaching three types of check marks in the main window.

In the main window, select the images you want to sort and attach a check mark for sorting.



- The selected check mark appears in the upper left of the image frame.
- Click the [Clear check] button to remove the check marks.

Arranging Images in the Main Window

You can arrange images in the order of the types of check marks you have attached to images, or in the order of date and time at which the images were shot. You can also freely arrange images by moving them individually.

Arranging by Type

Thumbnail with information Ctrl+4

Sort

Select the [View] menu ▶ [Sort] ▶ desired item. Ctrl+Right Arrow Edit in Edit image window View collections Alt+G Ctrl+T Tool palette 🖌 Tab Folders ✓ Toolbar Ctrl+1 Large thumbnail Ctrl+2 Medium thumbnail Small thumbnail Ctrl+3

The images are arranged in the order according to the selected item.

File name


RAW priority

Check mark1

Check mark2

Check mark3

Shooting Date/Time



Introduction



Click on desired images while holding down the <Ctrl> key. To select multiple consecutive images, click on the first image, and then click on the last image while holding down the <Shift> key.

Sort item	Description	
Check mark1 - Check mark3	Images with check marks take priority and are sorted in number order.	
Shooting Date/Time	Images are sorted by shooting date and time from the earliest.	
File name	Images are sorted by file name in alphanumeric order (0 to $9 \rightarrow A$ to Z).	
RAW priority	Images are sorted in the following order: RAW images \rightarrow JPEG images \rightarrow TIFF images.	


Check mark order

When you assign check marks 1 to 3, the images are sorted as follows: 1 selected: $1 \rightarrow 2 \rightarrow 3$

- 2 selected: $2 \rightarrow 1 \rightarrow 3$
- 3 selected: $3 \rightarrow 2 \rightarrow 1$

Arranging Freely

Drag and drop the image to the desired location.



- The image moves to the desired location.
- You can also select multiple images (p.18) and move them.
- The order of rearranged images is maintained until you exit DPP or select another folder in the folder area.
- Select the [View] menu > [Sort] > [File name] to revert to the order before the images were rearranged.

Maintaining the order of rearranged images


You can maintain the order of rearranged images even if you exit DPP or select another folder in the folder area.

Maintain order without changing image file names You can use the [View settings] tab sheet in the [Prefer

You can use the [View settings] tab sheet in the [Preferences] to maintain the order of images without changing the image file names (p.75).

Maintain order and change image file names

You can use the rename function to maintain the order of images and change the image file names all at once in the order they were rearranged (p.85).



Displaying a RAW Image and JPEG Image as a Single Image

You can display and handle a RAW image and JPEG image shot simultaneously as a single image. In particular, you can halve the number of images displayed in the main window and you can streamline the checking of a large number of images shot simultaneously.

Select the [Tools] menu ▶ [Preferences].

Select the [View settings] tab sheet and checkmark [Display only CR2 images for CR2 and JPEG files of the same name].

eferences			
General settings	View settings	Tool palette	Color management
Grid pitch			
64 Pixels(8-256)		
/ Image selection status			
Images opened in Edit wi	ndow remain selected in main	window	
Magnification in Edit window —			
• Fit to window	◯ 50%	◯100%	0 200%
RAW and JPEG	050%	⊙ 100%	0 200%
	for CR2 and JPEG files of the :	same name	
Sort order in main window			
Retain sort order			
Highlight/shadow Alert			
Highlight 255	(192-255)		
Shadow 0	(0-64)		
Quick check tool display			
	100% (moiré reduction off))	
			OK Cancel

The main window display updates and the simultaneously shot RAW image and JPEG image are displayed as a single image with the [R+J] mark (p.109).

? RAW images with the extension ".CR2" can be displayed as a single image

Images that can be displayed as a single image are images shot with a camera that shoots RAW images with the extension ".CR2" and JPEG images simultaneously. Images that have been simultaneously shot with a camera that shoots RAW images with the extension ".CRW" or ".TIF" cannot be displayed as a single image.

When a single image is displayed	Advanced
Image displayed	Operation
The RAW image is displayed in all windows.	Advanced
Edited image The content which has been adjusted with any of DPP's functions (the	Image Editing and Printing
tool palette etc.) will be applied to the RAW image only.	
However, if you have used the following functions, the adjustments will be applied to both the RAW image and the JPEG image.	Processing Large Numbers
Deleting an image (p.46)	of Images
Moving or copying an image (p.47) Charlemantes (p.47)	
 Checkmarks (p.17, p.18) Rotating an image (p.107, p.114, p.115) 	Editing JPEG/TIFF
 Attaching a thumbnail to an image and saving (p.21) 	Images
Images added to the [Collection] window	
When you add a RAW image and JPEG image displayed as a single image to the [Collection] window, the single image is marked with the	Reference
[R+J] mark. However, because the RAW and JPEG images are	
actually added individually, the number of images shown on the [Collection] tab sheet increases by 2 (p.108).	Index
In step 2, if you uncheck [Display only CR2 images for CR2 and	
JPEG files of the same name], the RAW image and JPEG image are displayed as separate images.	

Introduction

Contents at

a Glance

Basic

Operation

Improving the Quality of an Image in the Main Window

Create a new thumbnail image for the main window and save to each image.

The quality of images in the main window improves and images redraw themselves more quickly.

With all the images selected, select the [File] menu ► [Add thumbnail to image and save].

jile		
0	pen in Edit window	Ctrl+O
0	pen in Edit window (enlarged)	
Sa	аve	Ctrl+S
Sa	ave As	Ctrl+Shift+S
A	dd thumbnail to image and save	Ctrl+Shift+T
C	onvert and save	Ctrl+D
Ba	atch process	Ctrl+B
C	reate new folder	
Pr	int	Ctrl+P
Pr	int with detailed setting	Ctrl+Alt+P
C	ontact Sheet Prints	Ctrl+Shift+P
Pİ	ug-in printing	•
A	dd to collection	Ctrl+G
R	emove from collection	Ctrl+Shift+G
C	ear collection	
Dr	elete	Del

$\frac{1}{2}$ The extent of the improvement in quality

The quality is improved for any JPEG or TIFF image. While the image quality improves regardless of the thumbnail size (p.10), selecting [Large thumbnail], with its larger display size, shows the improvement more clearly than [Medium thumbnail] and [Small thumbnail].


• A large number of images may take some time to add.


• You can specify a presetting for JPEG images to improve the quality of all main window thumbnails (p.73, p.74).

Checking Image Information

- Select the image for which you want to check the image information.
- Select the [File] menu ▶ [Info].

File		
0	pen in Edit window	Ctrl+0
0	pen in Edit window (enlarged)	
Sa	аvе	Ctrl+S
Sa	ave As	Ctrl+Shift+S
A	dd thumbnail to image and save	Ctrl+Shift+T
G	onvert and save	Ctrl+D
Ba	atch process	Ctrl+B
C	reate new folder	
Pr	rint	Ctrl+P
Pt	rint with detailed setting	Ctrl+Alt+P
G	ontact Sheet Prints	Ctrl+Shift+P
Pl	ug-in printing	•
A	dd to collection	Ctrl+G
R	emove from collection	Ctrl+Shift+G
C	lear collection	
D	elete	Del
Ιr	ifo	Ctrl+I
E	×it	Alt+F4







Select a tab sheet and check information.

[Shooting Information] tab sheet

ooting Information Metadata		Shooting Information Met
Item	Value	Description
File Name	IMG 9699.CR2	
Camera Model	Canon EOS XXX	TD a sum out THE 1
Firmware	Firmware Version XXXX	[Document Title]
Shooting Date/Time	X00X/X0X/X0XX00000X	>000000000
Jwner's Name		
Shooting Mode	Shutter-Priority AE	[Author]
[v[Shutter Speed]	1/200	>00000000(
Av(Aperture Value)	2.8	
Metering Mode	Evaluative Metering	[Author Title]
Exposure Compensation	0	200000000
SO Speed	400	
Auto ISO Speed	OFF	[Description]
Lens	EF-S17-55mm f/2.8 IS USM	200000000
Focal Length	55.0mm	,00000000
mage Size	XXX xXXX	[Description Writer]
mage Quality	BAW	x0000000X
Flash	Off	2000000
FE lock	OFF	fl (auguranda)
White Balance Mode	Auto	[Keywords]
AF Mode	One-Shot AF	X0000000K
Picture Style	Standard	
Sharpness	3	[Copyright Status]
Contrast	0	Public domain
Saturation	0	
Color tone	0	[Copyright Notice]
Color Space	sRGB	X0000000(
Long exposure noise reducti		
High ISO speed noise reduc		[Copyright info URL]
Highlight tone priority	0:Disable	X0000000X
Auto Lighting Optimizer	0:Standard	
Peripheral illumination corre	Enable	
File Size	XXXXKB	
Dust Delete Data	No	
Drive Mode	Single shooting	
Live View Shooting	OFF	
Date/Time(UTC)	011	
_atitude		
Longitude		
Altitude		
Geographic coordinate syst		
Camera Body No.	XXXXXXXXXX	
Comment	///////////////////////////////////////	
Johnment		
	ose	

[Metadata] tab sheet

Shooting information is displayed in the [Shooting Information] tab sheet, while IPTC* information appended to the image in Photoshop CS3 or later after shooting is displayed in the [Metadata] tab sheet. IPTC* information provides additional comments on images, such as captions, credits and the shooting location. The information is sorted into 5 different categories and can be viewed by selecting [Description], [IPTC Contact], [IPTC Image], [IPTC Content] or [IPTC Status] from the list box in the [Metadata] tab sheet.

 International Press Telecommunications Council (IPTC) The contents of the [Shooting Information] tab sheet will vary depending on the camera model.



Convenient uses in the main window

Switching displays

÷

If a different image is selected in the main window when the image information window is displayed, the image information for that image will be displayed.

Difference with the [Thumbnail with information]

Detailed shooting information for each image is displayed in the image information window. However, if you want to only check the main shooting information, you can check it for each image in [View] menu (Thumbnail with information) (p.10).

Introduction

Contents at

a Glance

Basic

Operation

Advanced

Operation

Advanced **Image Editing**

and Printing

Processing

Large Numbers of Images

> Editing JPEG/TIFF Images


Reference

Editing an Image

This section explains how to adjust an image using the tool palette in the edit window.

You can easily restore an image to its original condition with the [button even if you have made the wrong adjustment. Try out the various adjustments.

How to make adjustments using the [RAW] tool palette functions, and how to adjust automatically with the [RGB] tool palette are explained in this section.



- The image changes in real time according to adjustments performed with the tool palette.
- To revert to the condition before the last operation performed on the tool palette, select [Undo] in the [Edit] menu or press <Ctrl> + <Z> keys.
- You can rotate an image in the [Adjustment] menu.

- You can adjust an image while comparing the image before and after adjustment (p.50).
- You can synchronize multiple images and edit while comparing them (p.51).
- Refer to p.110 for a list of edit window functions, and p.111 for a list of tool palette functions.

About the RAW Tool Palette


You can adjust images with the tool palette by switching between the [RAW], [RGB] and [NR/Lens/ALO] tab sheets according to your editing requirements.

Adjustments similar to those that can be performed with the functions of your camera can be performed using the functions of the [RAW] tool palette. When the camera settings were incorrect during shooting, or when the shooting result is not what you visualized, you can get closer to what you envisaged with the [RAW] tool palette which is similar to the camera.

All functions other than [RGB] tool palette automatic adjustment, and each function of the [NR/Lens/ALO] tool palette are explained in Chapter 3.


Editing with the Tool Palette in the Main Window

By clicking the [Tool] button (p.107) in the toolbar on the main window, the same tool palette that appears in the edit window is displayed and you can edit images.



Adjusting Brightness

The brightness of an image can be adjusted. Move the slider to the right to make the image brighter and to the left to make the image darker.



Drag the slider left or right

Changing a Picture Style

If the image you shot is different to what you visualized, you can change Contents at the Picture Style to get closer to what you envisaged. a Glance Even if you have saved the image (p.38) with [Monochrome] (p.28) selected, you can still change to another Picture Style at any point by simply selecting a Picture Style other than [Monochrome]. Operation Reverts the image to t Picture Style the original settings Standard Browse. Advanced Select Operation Advanced **Image Editing** and Printing Processina -10.0 -8.0 -6.0 -4.0 -2.0 0.0 2.0 4.0 Large Numbers Contrast: (0) of Images Highlight:(0) Shadow:(0) Linear JPEG/TIFF Color tone:(0) Color saturation:(0) Sharpness:(0) Reference

Even if the RAW image is from a camera that does not have Picture Style settings, you can still set a Picture Style as long as

• You can retain the [Color tone], [Color saturation], [Contrast] and

[Sharpness] settings, even if you change the Picture Style (p.76).

the RAW image is compatible with DPP (p.3).

Introduction

Basic

Editing

Images

Index

The adjustment range is -2.0 to +2.0 (in 0.01-stop increments when entering a value).


Picture Style	Description
Standard	The image looks vivid. Ordinarily, this setting is suitable for most images.
Portrait	For nice skin tones. Effective for close-ups of women and children. By changing the [Color tone], you can adjust the skin tone (p.27).
Landscape	For vivid blues and greens. Effective for making images of landscapes impressive.
Neutral	For natural colors and subdued images. Effective for base images which are to undergo adjustment.
Faithful	When the subject is photographed under a color temperature of 5200K, the color is adjusted colorimetrically to match the subject's color. Effective for base images which are to undergo adjustment.
Monochrome	For black and white images. You can also adjust with [Filter effect] or [Toning effect] (p.28).
(Picture Style file registered in the camera)	Displayed when selecting an image shot with the Picture Style file registered in the camera. In the list, the name of the Picture Style file is displayed in ().
[Picture Style file applied in DPP]	The name of the Picture Style file applied in DPP is displayed in [].

Picture Style File

A Picture Style file is an extended function file of Picture Style. Refer to p.56 for how to use Picture Style files.

Adjusting Color Tone by Changing White Balance

If the color tone of the photographed image does not appear natural, change the white balance to make it appear natural. You can make the color tone natural by setting the light source at the time of shooting an image of, for example, pale-colored flowers.



Introduction

Contents at

a Glance

Adjusting Color Tone Using Click White Balance

You can adjust white balance using a selected part of an image as the standard for white to make the image appear natural. Using click white balance is effective when using it in parts of an image where white color tone has changed under the influence of a light source.



Click on a point that is to be the standard for white.



Click The coordinates of the cursor position and the RGB values (8-bit conversion)

Reverts the image to the original settings

- The color of the image is adjusted with the point you selected as the standard for white.
- If you click on another point in the image, the white balance is adjusted again.
- To finish click white balance, right-click with the mouse or click the [] button again.



Introduction

Contents at

a Glance


? When there are no white areas in your image

When there are no white areas in your image, you can adjust the white balance by clicking on a grey point of the image in step 2. This has the same adjustment result as selecting a white point.

The image is adjusted based on the average value of 5 × 5 pixel range from the clicked point.

Adjusting Contrast

Modulation and degree of contrast can be adjusted. Move the slider to the right to make contrast stronger and to the left to make contrast weaker.



Display the value of the setting


Elinear] - A function for advanced adjustment

Use [Linear] when you will be adjusting separately using image editing software that has advanced editing functions. Note that when [Linear] is checkmarked, the image will become dim.

The Auto Lighting Optimizer (p.58) will not function when [Linear] is checkmarked.

Changing Color Tone and Color Saturation

Skin tone and overall color saturation can be adjusted. If Picture Style (p.24) is set to [Monochrome], [Color tone] and [Color saturation] switch to [Filter effect] and [Toning effect] (p.28).




Introduction

Contents at

a Glance

Adjusting Monochrome

When the Picture Style (p.24) is set to [Monochrome], you can create monochrome photographs with effects similar to filtering and with the look of a single-color photograph.



Display the values of the settings


• Filter effect: Creates an image where the white of clouds and the green of trees are emphasized in the same monochrome photograph.

Į	Contents at	
Filter	Example of effect	a Glance
None	Ordinary monochrome image without filter effect.	
Yellow	Blue sky is reproduced more naturally and white clouds emerge clearly.	Basic Operation
Orange	Blue sky becomes somewhat darker. The brightness of the setting sun increases further.	Advanced Operation
Red	Blue sky becomes quite dark. Autumn leaves become clear and bright.	
Green	Human skin tones and lips become softer. The green leaves of trees become clear and bright.	Advanced Image Editing and Printing
Toning effect: You can create a monochrome photograph to which a single color has been added. You can choose from [None], [Sepia], [Blue], [Purple]		Processing Large Numbers of Images
	nd [Green].	Editing JPEG/TIFF Images
		Reference
		Index



Adjusting Sharpness

You can make the overall atmosphere of an image harder or softer. Move the slider to the right to make an image harder and to the left to make an image softer.



Sharpness is unnatural

Adjust sharpness with the window view set to [100% view], [50% view] or [200% view]. If the view is set to [Fit to window] (full view), the sharpness may seem unnatural.

The adjustment range is 0 to 10 (in 1-stop increments).




Automatically Adjusting Brightness and Color (Tone Curve Assist)

In order to make the image a desirable standard image, automatically adjust the image tone curve (p.122). You can select the degree of automatic adjustment from "Standard" and "High".

Click on the [RGB] tab sheet and click the desired automatic adjustment button.


- Standard: Standard automatic adjustment. Suitable for most images.
- **High:** Use when the effect achieved in standard automatic adjustment is not strong enough.



Images not suitable for automatic adjustment (tone curve assist)

The result of automatic adjustment (tone curve assist) may not be as expected with the following images:

- · Images which have been shot with the proper exposure
- Images where the brightness is unbalanced
- Images which are too dark
- Images which have extreme backlighting
- If you click the [25] button, the tone curve as well as the [Hue] and [Saturation] revert to the default settings. Take care when adjusting the [Hue] and [Saturation] individually (p.91).



Introduction

→ The tone curve changes as adjusted.

Editing Efficiently

Editing in the Edit Image Window

The thumbnail display and the edit window are combined and images can be edited efficiently while quickly switching between images to be edited. Images to be edited are selected beforehand in the main window.


In the main window, select the images you want to edit.



→ The main window switches to the edit image window.

Edit the image.


Change the size Edit image window



Select the image to be edited The selected image is displayed as an enlargement in the middle of the window

- → It may take time for the image to redraw itself.
- The same tool palette as in the edit window is displayed and you can edit the image.
- To revert to the condition before the last operation performed on the tool palette, select [Undo] in the [Edit] menu or press <Ctrl> + <Z> keys.
- By selecting the [View] menu ▶ [AF Point] in the edit window or edit image window, you can display the AF points selected in the camera at the time of shooting. However, AF points are not displayed for images which have had their image size changed and then been converted and saved (p.39, p.116).

-	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
/ou	Reference
on > +	Index
edit	\sim




- The area you double-clicked is enlarged to 100% (actual pixel size).
- To change the display position, drag on the image or drag the enlargement display position (p.111) of the tool palette.
- Double-click again to revert to the full view ([Fit to window]).
- To return to the main window, click the [Main window] button on the toolbar.

To display an image in an enlargement ratio other than 100%


Click the [50% view] or [200% view] on the toolbar.

- You can change the way the tool palette is displayed (p.76).
 - You can change the enlargement ratio when you double-click (p.75).
 - With the edit image window, you can only select images from one folder. To gather images from several folders for editing, refer to "Gathering and Editing Images in the Collection Window" (p.33).
 - For a list of edit image window functions, refer to p.115.



Changing the Thumbnail Display Position to a Horizontal Position

Select the [View] menu ▶ [Change thumbnail position].



 If you select [Change thumbnail position] again, the thumbnail display reverts to the vertical position.

Gathering and Editing Images in the Collection Window

You can gather any randomly selected images together in the [Collection] window for viewing, comparison and editing. You can gather images from several folders as well as from only one folder, allowing you to work with them efficiently.

Select images from the [Folder] window in the main window, and select the [File] menu ▶ [Add to collection].

Open in Edit window	Ctrl+O
)pen in Edit window (enlarged)	
Save	Ctrl+S
Save As	Ctrl+Shift+S
Add thumbnail to image and save	Ctrl+Shift+T
Convert and save	Ctrl+D
Batch process	Ctrl+B
Create new folder	
Print	Ctrl+P
Print with detailed setting	Ctrl+Alt+P
Contact Sheet Prints	Ctrl+Shift+P
Plug-in printing	•
Add to collection	Ctrl+G
Remove from collection	Ctrl+Shift+G
lear collection	




- The selected images are added to the [Collection] window and the number of selected images is shown on the [Collection] tab sheet.
- When you add RAW and JPEG images displayed as a single image (p.20), the number of images shown on the [Collection] tab sheet increases by 2.
- You can select several images and add them to the [Collection] window.
- You can also add images to the [Collection] window by selecting images, right-clicking with your mouse, and selecting [Add to collection] from the menu that appears.
- You can add up to 1,000 images to the [Collection] window.

Select the [Collection] tab sheet.



→ The selected images are displayed in the [Collection] window.

Check displayed images in the [Collection] window.



Edit the images.

- You can now edit the images displayed in the [Collection] window.
- Images displayed in the [Collection] window are retained in the [Collection] window even after exiting DPP.



Removing randomly selected images

Select the images to be removed in the [Collection] window and then select [Remove from collection] in the [File] menu. (You can also remove images from the [Collection] window by selecting the images, right-

clicking with the mouse, and selecting [Remove from collection] from the menu that appears.)

Note that even if you remove an image from the [Collection] window, the original image remains unaffected.

Removing all images

Select [Clear collection] in the [File] menu. (You can also remove all images from the [Collection] window by selecting one image, rightclicking with the mouse, and selecting [Clear collection] from the menu that appears.)

Note that even if you remove all images from the [Collection] window, the original images remain unaffected.

Modifications to the image are applied to the original image

Modifications made to images added to the [Collection] window are all applied to the original image.

- You can arrange images displayed in the [Collection] window the same way as in the [Folder] window (p.18, p.19). You can maintain the order of rearranged images even after exiting DPP by checkmarking [Retain sort order] on the [View settings] tab sheet in the [Preferences] (p.75).
 - You cannot use the following functions in the [Collection] window.
 - Starting of EOS Utility (p.7), or synchronizing of folders with EOS Utility
 - Batch change the file name of images (p.85)

Advanced Operation

Introduction

Contents at

a Glance

Basic

Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference



Trimming and Adjusting the Angle of an Image

You can trim only the part of an image you need, or change the composition of an image where an image shot horizontally becomes vertical. You can also adjust the angle of an image before trimming. When aspect ratio information is attached to an image shot with the EOS-1D Mark IV, EOS-1Ds Mark III, EOS-1D Mark III or EOS 7D, the trimming range based on the aspect ratio information is displayed.

Select the image to be trimmed.

Open the trimming/angle adjustment window.


 Select the [Tools] menu > [Start Trimming/Angle Adjustment tool].

Tools

Start EOS Utility		Alt+0
Transfer to Photoshop		Alt+P
Start Ouick check tool		Alt+O
Start Trimming/Angle Adjustment tool		Alt+C
Start Stamp tool		Alt+S
Start Rename tool		Alt+R
Sync folder with EOS Utility		
Preferences		Ctrl+K

- → The trimming/angle adjustment window appears.
- → Editing can be done once the trimming/angle adjustment window has reached a clear display.

Adjust the angle of the image as needed. Trimming/angle adjustment window



Drag* (0.01-degree increments; adjustment range: -45 to +45 degrees)

Use the mouse (click $\blacktriangle/ \bigtriangledown$) to adjust the angle or directly enter the adjustment angle^{*} (0.01-degree increments; adjustable range: -45 to +45 degrees)

- * You cannot adjust the angle of images that exceed 6666 x 4444 pixels in size.
- If you click [Center on Screen], you can display the trimming range in the center of the window.
- When correcting lens aberrations, it is recommended to perform [Lens aberration correction] before adjusting the angle of the image.
- If you click the [OK] button after adjusting only the angle of the image, the image will be trimmed at the largest possible trimming range.

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing


Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference



Select a ratio and drag the trimming range. Cancel Reset Select a trimming Height 1051 ratio 1010 Rotate left Rotate right Drag the



- The trimming range can be moved by dragging.
- You can enlarge or reduce the size of the trimming range by dragging the four corners of the trimming range.
- List of aspect ratios (width : height)


Free
1:1
3:2
2:3
4:3
3:4
5:4
4:5
A Size Landscape
A Size Portrait
Letter Landscape
Letter Portrait
Custom
[Free] You can trim a

You can trim an image to any size, regardless of the [Free]: selectable ratio.

[Custom]: You can trim an image at the specified ratio.

Click the [OK] button to return to the main window.

- → The trimming range frame is displayed in the trimmed image (p.109).
- → When the trimmed image is displayed in an edit window or the edit image window, it is displayed in its trimmed form.



Introduction

About trimmed images

 The trimmed range can be reverted to its original condition at any time

A trimmed image is displayed or printed as a trimmed image. However, since the image is not actually trimmed, you can always revert to the original image by clicking the [Reset] button in the trimming/angle adjustment window or performing the "Re-Editing an Image" procedure (p.40).

Display of the trimmed image in each window

- Main window: The frame showing the trimming range is displayed on the image (p.109).
- Edit window: The image is displayed in its trimmed condition.
- Edit image window: The thumbnail image is the same as the main window display, and the enlarged image is the same as the edit window display.

Printing a trimmed image

You can print as a trimmed image by printing it in DPP.

• The image becomes a trimmed image when converted and saved The trimmed RAW image actually becomes a trimmed image when converted to a JPEG or TIFF image and saved (p.39).

Images that have aspect ratio set will be displayed as trimmed images

When aspect ratio information is attached to an image shot with EOS-1D Mark IV, EOS-1Ds Mark III, EOS-1D Mark III or EOS 7D, the set trimming range based on the aspect ratio information is displayed. However, since the image is not actually trimmed, you can change the trimming range or revert to the condition before trimming. When reverting to the condition before trimming is performed based on the aspect ratio information at the time of shooting, click the [Reset] button. Also, if you want to cancel all the trimming range, click the [Clear] button (p.117).

Convenient functions of the trimming/angle adjustment window

Switch between screens using the keyboard

You can also switch between full screen display/normal screen display by pressing the <Alt> + <Enter> keys or the <F11> key.

Operate using the menu

Each operation can also be performed with the menu which appears when you right-click with the mouse on the image.

Apply the trimmed range to another image

You can apply the trimmed range to another image by clicking the [Copy] button to copy the trimmed range, displaying another image and then clicking the [Paste] button.

To batch apply a copied trimming range to multiple images, select the trimmed image and the multiple images to which you want to apply the trimmed range in the main window, and display the trimming/ angle adjustment window. With the trimmed image displayed, click the [Copy] button and then click the [Apply All] button. This will apply the trimming range to all the images selected when the trimming/ angle adjustment window is displayed.

To select multiple images in the main window, click the images while holding down the <Ctrl> key. To select multiple consecutive images, click on the first image, and then click on the last image while holding down the <Shift> key.

For images shot with ISO speed range expansion set, noticeable noise may make it difficult to view image details in the trimming/ angle adjustment window, so using this function is not recommended.

For a list of the trimming/angle adjustment window functions, refer to p.117.

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



Applying Adjustment Contents to Other Images –

You can copy the image adjustment contents (recipe) adjusted with the tool palette and apply it to other images.

You can efficiently adjust multiple images by adjusting one image and applying the results of this to multiple images shot in similar shooting environment.

Select the adjusted image and then select the [Edit] menu > [Copy recipe to clipboard].

→ The recipe is copied.

Select the image to which the recipe is to be applied and then select the [Edit] menu > [Paste recipe].


 \rightarrow The recipe is applied to the image.

Saving Editing Results

Saving Editing Contents to a RAW Image

All the contents (recipe) adjusted with the tool palette as well as the trimmed (p.35) range information can be saved to a RAW image or to a separate RAW image.

The adjustments made with the tool palette (p.53 to p.63) and the dust erase processing explained in Chapter 3 (p.64 to p.68) can also be saved in a RAW image.



Select the [File] menu ▶ desired item.

Eile	
Open in Edit window	Ctrl+0
Open in Edit window (enlarged)	
Save	Ctrl+S
Save As	Ctrl+Shift+S
Add thumbnail to image and save	Ctrl+Shift+T
Convert and save	Ctrl+D
Batch process	Ctrl+B
Create new folder	
Print	Ctrl+P
Print with detailed setting	Ctrl+Alt+P
Contact Sheet Prints	Ctrl+Shift+P
Plug-in printing	+
Add to collection	Ctrl+G
Remove from collection	Ctrl+Shift+G
Clear collection	
Delete	Del
Info	Ctrl+I
Exit	Alt+F4

Your adjustments are saved to the image.



Introduction



The recipe (p.80) can be saved as a separate file from the image and loaded and applied to another image (p.81).

Saving as a JPEG or TIFF Image

To view, edit and print a RAW image with software other than DPP, convert to a more versatile JPEG or TIFF image and save. The image is saved as a separate image, so the RAW image remains unaffected.

Select the image to be converted.


Select the [File] menu ▶ [Convert and save].

File		
O	pen in Edit window	Ctrl+O
Op	pen in Edit window (enlarged)	
Sa	ave	Ctrl+S
Sa	ave As	Ctrl+Shift+S
Ac	dd thumbnail to image and save	Ctrl+Shift+T
Co	privert and save	Ctrl+D
Ba	atch process	Ctrl+B
Cr	reate new folder	
Pr	int	Ctrl+P
Pr	int with detailed setting	Ctrl+Alt+P
Co	ontact Sheet Prints	Ctrl+Shift+P
Plu	ug-in printing	•
Ac	dd to collection	Ctrl+G
Re	emove from collection	Ctrl+Shift+G
C	ear collection	
De	elete	Del
In	fo	Ctrl+I
E>	cit	Alt+F4

→ The [Convert and save] window appears.

Specify the necessary settings, and then click the [Save] button.

 By default, the image is converted and saved to a JPEG image with the highest image quality, without changing the image size. Change the settings according to your requirements.



Re-Editing an Image

Only the image processing conditions are changed in images adjusted with the tool palette (p.23 to p.30), so the "original image data itself" remains unaffected.

Also, the trimming range information of a trimmed image (p.35) is simply saved to the image.

For this reason, you can undo any adjustments saved (p.38) to the image, trimming information, and revert to the condition when last saved, or when the image was shot.

Select the image that is to be re-edited.

Select the [Adjustment] menu > desired item.

 A dia re 	stment
- Aujus	suneni

Hajasemene	
Rotate Left	Ctrl+L
Rotate Right	Ctrl+R
Add check mark1	Alt+1
Add check mark2	Alt+2
Add check mark3	Alt+3
Remove check mark	Alt+Z
Apply Dust Delete Data	
Work color space	•
Tone Curve Assist - Standard Tone Curve Assist - High	
Revert to last saved settings Revert to shot settings	Ctrl+Alt+Z Ctrl+Shift+Z

→ The image reverts to the conditions of the selected item.

Printing an Image

This section explains how to print high-resolution photographs easily with Canon inkjet printers compatible with the Canon printing software, Easy-PhotoPrint EX or Easy-PhotoPrint. It also explains how to print photographs using other printers.

Proceed to the page for the printer you are using.

- Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint EX (Same page)
- Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint (p.43)
- Printing Photographs with a Printer other than Canon Inkjet Printers (p.46)

Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint EX

You can perform the following types of photograph printing with Canon inkjet printers compatible with Easy-PhotoPrint EX (hereinafter, "EPP EX") :

- Simple printing of RAW images
- Printing with faithful colors

To perform this printing, it is necessary to first install EPP EX version 1.1 or later on your computer.

Introduction

Select the image to be printed.


Start up EPP EX.

Select the [File] menu ▶ [Plug-in printing] ▶ [Print with Easy-PhotoPrint EX].

Eile

Open in Edit window	Ctrl+O	
Open in Edit window (enlarged)		
Save	Ctrl+S	
Save As	Ctrl+Shift+S	
Add thumbnail to image and save	Ctrl+Shift+T	
Convert and save	Ctrl+D	
Batch process	Ctrl+B	
Create new folder		
Print	Ctrl+P	
Print with detailed setting	Ctrl+Alt+P	
Contact Sheet Prints	Ctrl+Shift+P	
Plug-in printing	•	Print with Easy-PhotoPrint EX
Add to collection	Ctrl+G	
Remove from collection	Ctrl+Shift+G	


→ EPP EX starts up.





In the EPP EX window, select the [File] menu >

In [Print Quality], select [Quality Priority], click the [Option] button, and then in the dialog box that appears, checkmark [Print with the best quality when you select [Quality Priority]].



Click and checkmark [Print with the best quality when you select [Quality Priority]]

Select the [Advanced] tab, checkmark [Enable ICC profile], and then click the [OK] button.


→ The [Preferences] window closes.

Contents at a Glance Basic Operation Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images Editina JPEG/TIFF Images Reference Index

Introduction




→ The [Preferences] window appears.





Click

Select the paper type, and then click the [Layout/ Print] button.



Introduction

Additional information

Print up to 1000 images at a time

You can print up to 1000 images selected in DPP at a time. When printing more than 1000 images, divide the printing into several jobs.

The printed image's color is not what you expected

In the EPP EX window, select [Preferences] in the [File] menu and then click the [Advanced] tab in the [Preferences] window to display the [Advanced] tab sheet.

In the [Advanced] tab sheet, select [Enable ICC profile] in [Color correction for printing] and try printing using the [Perceptual] setting (p.123).

Advantages of printing with EPP EX

Printing with faithful colors

When the color space (p.123) is set to sRGB or Adobe RGB (p.68, p.77), this color space is automatically transmitted from DPP to EPP EX, allowing you to print with faithful colors.

When the color space is set to Apple RGB or ColorMatch RGB, the image is printed with an sRGB color space, and when set to Wide Gamut RGB, with an Adobe RGB color space.

Printing with a wide color reproduction

When the color space setting (p.68, p.77) is set to Adobe RGB and the image is printed with a Canon inkjet printer, the color reproduction range is wider, and green and blue in particular are reproduced vividly.

DPP is also compatible for printing with Easy-PhotoPrint Pro (p.71).

Printing Photographs with Canon Inkjet Printers Compatible with Easy-PhotoPrint

You can perform the following types of photograph printing with Canon inkjet printers compatible with Easy-PhotoPrint (hereinafter, "EPP"):

- Simple printing of RAW images
- High quality printing using the color reproduction range of Adobe RGB and a Canon inkjet printer

To perform this printing, it is necessary to first install EPP version 3.5 or later on your computer. When using an Easy-PhotoPrint EX-compatible inkjet printer, it is recommended that you print using Easy-PhotoPrint EX (p.40).

Select the image to be printed.

Start up EPP.

 Select the [File] menu > [Plug-in printing] > [Print with Easy-PhotoPrint].

File

Open in Edit window	Ctrl+0	
Open in Edit window (enlarged)		_
Save	Ctrl+S	-
Save As	Ctrl+Shift+S	
Add thumbnail to image and save	Ctrl+Shift+T	
Convert and save	Ctrl+D	
Batch process	Ctrl+B	
Create new folder		·
Print	Ctrl+P	
Print with detailed setting	Ctrl+Alt+P	
Contact Sheet Prints	Ctrl+Shift+P	
Plug-in printing	•	Print with Easy-PhotoPrint Ctrl+
Add to collection	Ctrl+G	
Remove from collection	Ctrl+Shift+G	
Clear collection		

→ EPP starts up.

Contents at a Glance

Introduction

a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index

In the EPP window, select the [File] menu > [Preferences].

File	
Pr	eferences
E>	cit

→ The [Preferences] window appears.


In [Print Quality], select [Quality Priority].

Preferences		×
Print Advanced		
Spool print job page by page Number of copies : Printing Order : Amount of extension of borderless printing : Print Quality :	1 Copies By Date Default Quality Priority	— Select Qualit Priorit
	Defaults	
	OK Cancel Help	J

Select the [Advanced] tab sheet and check that the EPP image compensation function is disabled.

• If not disabled, the operation of the EPP image compensation function may prevent images being printed with faithful color reproduction.

mage	Dptimize images automatically	– If checked,	
	Apply Rotate/Trimming to the same images in the same manner	click to	
	When landscape images are rotated depending on the selected layout :	remove the	
	Rotate Left Do no Distance	check mark	
	O Rotate Right		
Layout	Always trim when you select the layout with the margins		
	Set margins to the minimum when you select the layout with the margins		
	Print filename when you select the index in layout		
	Preview all layouts of A4 and Letter		
Image Selection	Select images from multiple folders		
selection		 Click to 	
		close the	
	Defaults	window	
	Derauks	WINGOW	
	OK Cancel Help		
		1	



Introduction

Contents at

a Glance

Advanced Operation


Advanced age Editing nd Printing

rocessing rge Numbers of Images


Editing **JPEG/TIFF** Images

Check that the image compensation function is disabled, select the paper type and then click [Next].

If checked, click to remove the check marks



Specify the layout, and then click [Print].



Click to print

2 Additional information

Print up to 1000 images at a time

You can print up to 1000 images selected in DPP at a time. When printing more than 1000 images, divide the printing into several jobs.


The printed image's color is not what you expected Change the [Rendering intents when using Easy-PhotoPrint] (p.77) to

[Perceptual] (p.123) and print.

Printing with a wide color reproduction

When the color space (p.68, p.77) is set to Adobe RGB and the image is printed with Canon inkjet printer, the color reproduction area widens, and green and blue in particular are reproduced vividly. When the color space is set to Apple RGB or ColorMatch RGB, the image is printed with an sRGB color space, and when set to Wide Gamut RGB, with an Adobe RGB color space.

DPP is also compatible for printing with Easy-PhotoPrint Pro (p.71).



Introduction

Select the layout

→ Printing begins.

Printing Photographs with a Printer other than Canon Inkjet Printers

You can print one image on one sheet of paper.

Select the image to be printed.

Select the [File] menu ▶ [Print].

	Fi	la
	_	IC,

Open in Edit window Open in Edit window (enlarged)	Ctrl+O
Open in Edit window (enlarged)	
Save	Ctrl+S
Save As	Ctrl+Shift+S
Add thumbnail to image and save	Ctrl+Shift+T
Convert and save	Ctrl+D
Batch process	Ctrl+B
Create new folder	
Print	Ctrl+P
Print with detailed setting	Ctrl+Alt+P
Contact Sheet Prints	Ctrl+Shift+P
Plug-in printing	•
Add to collection	Ctrl+G
Remove from collection	Ctrl+Shift+G
Clear collection	
Delete	Del
Info	Ctrl+I
Exit	Alt+F4

→ The [Print] dialog box appears.

Set to photograph printing and print.

 Specify the optimum settings for photograph printing in the printer's print settings dialog box and click the [OK] button.
 Printing bogins

→ Printing begins.

Organizing Images


This section explains how to delete unwanted images, create folders for saving images, move or copy images, etc., and organize your images.

Deleting an Unwanted Image

Be aware that you cannot recover deleted images.

Select an unwanted ima	ge in the main window.
------------------------	------------------------

Open in Edit window	Ctrl+0
Open in Edit window (enlarged)	
Save	Ctrl+S
Save As	Ctrl+Shift+S
Add thumbnail to image and save	Ctrl+Shift+T
Convert and save	Ctrl+D
Batch process	Ctrl+B
Ireate new folder	
Print	Ctrl+P
Print with detailed setting	Ctrl+Alt+P
Contact Sheet Prints	Ctrl+Shift+P
Plug-in printing	
Add to collection	Ctrl+G
Remove from collection	Ctrl+Shift+G
Clear collection	
Delete	Del
info	Ctrl+I
Exit	Alt+F4



Introduction

→ The [Confirm File Delete] dialog box appears.

Click the [Yes] button.

- → The image is moved to the [Recycle Bin] and is deleted from DPP.
- The images are deleted completely from your computer when the [Empty Recycle Bin] operation is performed on the [Recycle Bin] on the desktop.

Creating a Folder for Saving Images

You can create a folder for sorting images.

In the folder area, select the location where the new folder is to be created.



Select the [File] menu ▶ [Create new folder].

<u>F</u> ile			
0	pen in Edit window	Ctrl+0	
0	pen in Edit window (enlarged)		
Sa	Save Ctrl+S		
Sa	ave As	Ctrl+Shift+S	
A	dd thumbnail to image and save	Ctrl+Shift+T	
C	onvert and save	Ctrl+D	
Ba	atch process	Ctrl+B	
G	reate new folder		
Pr	int	Ctrl+P	
Pr	int with detailed setting	Ctrl+Alt+P	
C	ontact Sheet Prints	Ctrl+Shift+P	
Pİ	ug-in printing	•	
A	dd to collection	Ctrl+G	
R	emove from collection	Ctrl+Shift+G	
C	ear collection		

→ The [Create new folder] dialog box appears.

Enter a folder name and click the [OK] button.

→ The new folder is created in the folder selected in step 1.

Moving Images

date or themes.

Folder

🖕 📋 My Documents Hy Music

🖃 🚞 Photo

🚡 🏹 My Network Places 🗄 🦳 Trave

- 🦳 🗙 😐 🧔 My Computer

🞯 Desktop

You can move or copy images to a separate folder and sort by shooting Contents at a Glance Drag the image to be moved or copied. Basic • To move: Drag the image and release when the image is in the Operation destination folder. • To copy: Drag the image while holding down the <Ctrl> key and release when the image is in the destination folder. Advanced Operation Digital Photo Professional - FC: Documents and Settings\canonWy Docume File Edit View Bookmark Adjustment Tools Window Help Advanced **Image Editing** Collection (0) and Printing Processing Large Numbers of Images Editina JPEG/TIFF → The images are moved or copied to the destination folder. Images Reference Index

Introduction

Moving Images in Folders

You can move or copy folders that contain images, and sort the images by folders.

Drag the folder to be moved or copied.

- **To move:** Drag the folder and release when the folder is in the destination folder.
- **To copy:** Drag the folder while holding down the <Ctrl> key and release when the folder is in the destination folder.



→ The folders are moved or copied to the destination folder.

Registering Frequent-Use Folders (Bookmark Registration)

You can register frequently used folders in bookmarks. Registered folders appear by clicking the [Bookmark] menu.

	onal - [C:\Documents and Settings\canon\My Adjustment Tools <u>Wi</u> ndow <u>H</u> elp	Documen
Edit image window Folder View	Tool Select al Clear al	
Desktop My Documents My Music My Pictures My Pictures My Nickures My Nickures My Nickures My Collegate My Nickure Places Travel		Select

Select the [Bookmark] menu ▶ [Add].


- The folder selected in step 1 is registered in the [Bookmark] menu.
- Select a registered folder from the [Bookmark] menu to display images in the selected folder in the main window.

Organizing Bookmarks

You can change a folder name or delete a folder registered in [Bookmark].

Select the [Bookmark] menu ▶ [Organize].

The [Sort bookmarks] window appears and you can change folder names or delete folders.



3 **Advanced Image Editing and Printing**

Various preferences including advanced image adjustment, automatic dust erasure processing, various printing functions for printing out work, and color management are explained here, geared to the user who is competent in the handling of third-party image editing software.

Adjusting While Comparing with the Original Image	50
Changing How the Window is Split	50
Adjusting by Comparing Multiple Images	51
Displaying an Area Beyond the Set Range as a	
Warning Indicator (Highlight/Shadow Warning)	52
Performing Advanced Editing	53
Adjusting White Balance with Color Temperature	53
Tuning White Balance with Color Wheel	53
Adjusting Dynamic Range	
Adjusting Brightness of Shadows/Highlights	
Tone Curve Adjustment	55
Example of a Tone Curve Operation	
Using a Picture Style File	
About the RGB Tool Palette	57
Using the Auto Lighting Optimizer	58
Reducing Noise	59
Correcting Lens Aberration	60
Compatible Cameras	60
Compatible Lenses	60
Making Corrections	
About Shooting Distance Information Slider	63
Correcting Multiple Images at a Time	63

Performing Automatic Dust Erasure Processing 64	
Compatible Cameras	Contents at a Glance
Manually Erasing Dust (Repair Function)	Basic Operation
Transferring a RAW Image to Photoshop 68	Advanced
Setting Work Color Space 68	Operation
Printing with Shooting Information	Advanced
Printing a Thumbnail List (Contact Sheet Printing) 70	Image Editing and Printing
Printing RAW Images on a High-End Canon Printer 71	
Printing with a High-End Canon Inkjet Printer	Processing Large Numbers
Printing with a Large-Format Canon Printer	of Images
Specifying Preferences	Editing
General Settings73	JPEG/TIFF Images
View Settings75	
Tool Palette	Reference
5	

Introduction


Index

S

Adjusting While Comparing with the Original Image

You can display before and after versions of an adjusted image in the same window and adjust while checking the adjustment results.


In the edit window, select the [View] menu ▶ [Before/ after comparison].



- → The image divides into a left and right window.
- The window on the right shows the image after editing.

Change the image display.

 Select the [View] menu ▶ [Change up/down/left/right] ▶ [Up/ down].




- → The layout of the two images changes to top and bottom.
- The bottom window shows the image after editing.

Changing How the Window is Split

You can change the display of the image to a single image split in two.

In the edit window, select the [View] menu ▶ [Display mode] ▶ [Split single image].





- One image is divided and displayed on the left and right or top and bottom.
- To switch between top and bottom, and left and right, perform the same operation as step 2 on the left page.



Introduction

Contents at

a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing

Reference

Index



Images can also be displayed in the edit image window by the same operation.

Adjusting by Comparing Multiple Images

You can synchronize the display position of multiple edit windows and adjust images while comparing them with each other.

In the edit window, display the multiple images to be compared.


Align the images.

- Select the [Window] menu > [Arrange vertically] or [Arrange horizontally].
- → The edit windows are aligned.

Select the [Window] menu > [Synchronize].

Enlarge the image.


Enlarge and display any of the edit windows.



The other edit windows will also be displayed in the same position/enlargement ratio.

Move the display position.

- If you move the enlargement display position in one of the edit windows, the enlargement display position will also change in the other edit windows.
- To cancel synchronization, select the [Window] menu
 [Synchronize] again.



Introduction

Synchronization only applies to the enlargement display position and the enlargement ratio. Adjustments to the images are not synchronized.

Displaying an Area Beyond the Set Range as a Warning Indicator (Highlight/Shadow Warning)

You can set up a warning indicator in both the highlighted part and the shaded part, which is effective for checking the light and dark areas and preventing excessive adjustment of an image. Where the area on the image has exceeded that set range, you can display the highlighted part in red and the shaded part in blue.

Select the [Tools] menu ▶ [Preferences].

Select the [View settings] tab sheet.


ind pitch 64 Pixels(8-256) mage selection status Images opened in Edit window remain selected in main window agnification in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in Edit window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main window Images opened in main win	General settings	View settings	Tool palette	Color management
nage selection status Images opened in Edit window remain selected in main window agnification in Edit window Images opened in Edit window <	rid pitch			
nage selection status Images opened in Edit window remain selected in main window agnification in Edit window Images opened in Edit window <	64 Pixels(8-25)	6)		
Images opened in Edit window remain selected in main window agnification in Edit window Images opened in Edit window <td></td> <td>·</td> <td></td> <td></td>		·		
agnification in Edit window Image: Fit to window Image: Fit to window agnification when the Edit/Edit image window is double-clicked Image: Sonow Image:	nage selection status			
 Fit to window 50% 100% 200% agnification when the Edit/Edit image window is double-clicked 50% 100% 200% AW and JPEG Stopping only CR2 images for CR2 and JPEG files of the same name art order in main window Retain sort order aphlight/shadow Alert Highlight 255 192-255) Shadow 0 -64) 	Images opened in Edit w	vindow remain selected in main	window	
 Fit to window 50% 100% 200% agnification when the Edit/Edit image window is double-clicked 50% 100% 200% AW and JPEG Stopping only CR2 images for CR2 and JPEG files of the same name art order in main window Retain sort order aphlight/shadow Alert Highlight 255 192-255) Shadow 0 -64) 	agnification in Edit window			
agnification when the Edit/Edit image window is double-clicked 50% 100% 200% AW and JPEG Pipisplay only CR2 images for CR2 and JPEG files of the same name art order in main window Retain sort order Highlight 255 192-255) Shadow 0 0 -64) Uick check tool display		0.50%	0100%	0200%
O 50% O 100% O 200% AW and JPEG Image: Display only CR2 images for CR2 and JPEG Files of the same name and order in main window Check in sort order Highlight 192-255) Shadow 0 -64) uick check tool display	0	0.00	0	0
AW and JPEG	agnification when the Edit/Ed	dit image window is double-click	ed	
		0 50%	100%	0200%
ort order in main window Retain sort order ighlight/shadow Alert Highlight 255 192-255) Shadow 0 0-6-64) uick check tool display	AW and JPEG			
cht order in main window cht order in main window cht order cht of t/shadow Alert Highlight 255 192-255) Shadow 0 0-0-64) uick check tool display				
Retain sort order ighlight/shadow Alert Highlight 255 192-255) Shadow 0 0-64)	Display only CR2 images	for CR2 and 1PEG files of the	ame name	
lighlight/shadow Alert Highlight 255 192-255) Shadow 0 0-0-64)	Display only CR2 images	for CR2 and JPEG files of the :	ame name	
Highlight/shadow Alert Highlight 255 Shadow 0 9-64) uick check tool display		for CR2 and JPEG files of the :	ame name	
Highlight 255 192-255) Shadow 0 0-6-64) uick check tool display	ort order in main window	for CR2 and JPEG files of the :	ame name	
Shadow 0 0-64)	ort order in main window	for CR2 and JPEG files of the :	ame name	
Shadow 0 0-64)	ort order in main window	for CR2 and JPEG files of the :	ame name	
uick check tool display	ort order in main window Retain sort order Ighlight/shadow Alert		ame name	
	ort order in main window Retain sort order Ighlight/shadow Alert Highlight 255	192-255)	ame name	
	ort order in main window Retain sort order Ighlight/shadow Alert Highlight 255	192-255)	ame name	
	ort order in main window Retain sort order ighlight/shadow Alert Highlight 255 Shadow 0	192-255)	ame name	
	ort order in main window PREtain sort order Ighlight/shadow Alert Highlight 255 Shadow 0 uick check tool display	192-255) D-64)		
	ort order in main window PREtain sort order Ighlight/shadow Alert Highlight 255 Shadow 0 uick check tool display	192-255) D-64)		



Display the edit window.

Select the [View] menu ▶ [Highlight]. Similarly, select [Shadow].

On the opened image, if there is an area that exceeds the value entered in step 3, the highlighted part of that area is displayed in red and the shaded part is displayed in blue.



Introduction

You can also display the warning with the same operation in the edit image window.

Enter the warning value for [Highlight] and [Shadow].

Performing Advanced Editing

This section explains how to use the advanced adjustment function on the tool palette in the edit window.


Adjustments made using the high-level functions of the [RAW] and [RGB] tool palettes, as well as the functions of the [NR/Lens/ALO] tool palette are explained in this section.

Adjusting White Balance with Color Temperature

White balance can be adjusted by setting a numerical value for color temperature.

Select [Color temperature] from the [White balance adjustment] list box.

Set the color temperature.




Tuning White Balance with Color Wheel

White balance can be tuned by moving a cursor in the color direction shown in the color wheel.

In the [RAW] tool palette, click the [Tune] button.

Tune by dragging a point.



 You can also fine-tune your adjustment by directly entering the adjustment values.

- To register adjustment results as personal white balance (p.82), select a setting other than [Shot settings] from the [White balance adjustment] list box, and then tune with the color wheel. You cannot register the adjustment results as personal white balance when you have selected [Shot settings] from the list box and have done any tuning.
- The adjustment range of color tone is 0 to 359 (1 unit in numerical value input), and the adjustment range of color saturation is 0 to 255 (1 unit in numerical value input).

Introduction

Contents at

a Glance

Basic

Operation

Advanced Operation

Advanced Image Editing

and Printing

Processing

Large Numbers

of Images

Editina

JPEG/TIFF


Images

Reference

Index

Adjusting Dynamic Range

Dynamic range (width of gradation expression) from dark points to bright points in an image can be adjusted.



Move to the left or right Input shadow points

• The horizontal axis shows the input level and the vertical axis shows the output level.

Adjusting Brightness of Shadows/Highlights

You can adjust the brightness of shadows and highlights in an image. By adjusting shadows and highlights in an image with a restricted brightness, you can reduce the effects of clipping in shadows and highlights.

Picture Style		Basic Operation
Standard V Browse		
		Advanced Operation
		Advanced Image Editing and Printing
-10.0 -8.0 -6.0 -4.0 -2.0 0.0 2.0 4.0 Contrast: (0) Highlight: (0) Shadow: (0)	Drag the sliders left or right	Processing Large Numbers of Images
Color tone:(0)		Editing JPEG/TIFF Images
Sharpness:(0)		



Reference

Index

Introduction

Contents at

a Glance


Deale

Tone Curve Adjustment

You can adjust the brightness, contrast and color of a specific area by changing the tone curve (p.122).


In the tool palette, select the [RGB] tab sheet.

Select the tone curve mode and interpolation method.



Right-click with the mouse inside the graph to display the menu

Make adjustments.




- The histogram display changes according to adjustment. You can also fix the histogram display to the display before any adjustments (p.76).
 - The tone curve mode and interpolation method for a tone curve can also be changed in [Preferences] (p.76).

Introduction

Example of a Tone Curve Operation

Makes medium tones brighter

Makes medium tones darker



Makes tones harder

Makes tones softer



Using a Picture Style File

A Picture Style file is an extended function file of a Picture Style. With DPP, you can apply to RAW images Picture Style files that you have downloaded from Canon's web site effective for various scenes or Picture Style files created with "Picture Style Editor". When using a Picture Style file, save it to your computer beforehand.

- Display the image to which the Picture Style file is to be applied in the edit window (p.11).
- Select the [RAW] tab sheet in the tool palette, and click the [Browse] button.

Standard	Browse

→ The [Open] dialog box appears.

- Select a Picture Style file saved on your computer, and click the [Open] button.
 - → The Picture Style file you selected is applied to an image.
 - To apply a different Picture Style file, follow the procedure from step 2 again.
- Introduction Contents at a Glance Basic Operation Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images Editina JPEG/TIFF Images Reference Index
- The Picture Style files that you can apply to the camera are files with the ".PF2" extension only. Furthermore, you cannot apply Picture Style files with the extension ".PSE" to an image; however if such a file is registered in the camera and the image is shot, the image will display correctly.

About the RGB Tool Palette


You can adjust images with the tool palette by switching between the [RAW], [RGB] and [NR/Lens/ALO] tab sheets according to your editing requirements.

The [RGB] tool palette functions are the same as ordinary image editing software, such as tone curve adjustment that is explained here, with which you can adjust RAW images.

However, because the adjustment width of the functions in the [RGB] tool palette is wider than the [RAW] tool palette, the image color may be saturated, or the image quality may deteriorate if you adjust too much. Therefore we recommend for functions other than tone curve adjustment (p.55) and automatic adjustment (p.30), that you adjust images using the same functions available in the [RAW] tool palette. Refer to Chapter 5 for explanations on functions of the [RGB] tool palette other than tone curve adjustment.

Using the tool palette

We recommend that as a general principle you edit RAW images using the [RAW] tool palette. However, where the adjustment width with the [RAW] tool palette is not wide enough and you wish to use the special functions in the [RGB] tool palette, we recommend that you adjust your images at the necessary lowest limit with the [RGB] tool palette after having completed basic adjustment with the [RAW] tool palette. Use the adjustment function of the [NR/Lens/ALO] tool palette (p.112) when applying the Auto Lighting Optimizer (p.58), reducing noise (p.59) or correcting aberration (p.60) after you have made any required adjustments with the [RAW] and [RGB] tool palettes.



Using the Auto Lighting Optimizer

If the shooting result is dark or the contrast is low, you can use the Auto Lighting Optimizer function to auto-correct the brightness and contrast, and obtain a more pleasant image.

You can also change the settings of the image shot with the camera's Auto Lighting Optimizer function.

This function is compatible only with RAW images shot with EOS-1D Mark IV, EOS 5D Mark II, EOS 7D, EOS 50D, EOS REBEL T2i/550D and EOS REBEL T1i/500D.

* ALO stands for Auto Lighting Optimizer.

Select the [NR/Lens/ALO] tab sheet from the tool
palette in the edit window or edit image window.

RAW RGB NR/Lens/ALO	
Auto Lighting Optimizer	
Low Standard	Strong
Noise reduction	Apply
	IR Preview
RAW	
Luminance noise reduction:(7)	
0	20
Chrominance noise reduction:(9)	
0	20
TIFF/JPEG	
Luminance noise reduction:(0)	
0 0	
Chrominance noise reduction:(0)	
0.0	
	le W
Lens aberration correction	Tune
Peripheral illumination	OFF
Distortion	OFF
Chromatic aberration	OFF
Color blur	OFF

Introduction Checkmark the checkbox. RAW RGB NR/Lens/ALO Contents at Auto Lighting Optimizer Checkmark a Glance Standard Strong Low Basic • For images shot with the camera's Auto Lighting Optimizer Operation function, the checkbox is already checked. Change the settings according to your preferences. Advanced Operation RAW RGB NR/Lens/ALO Auto Lighting Optimizer Advanced \checkmark Select from three levels: Image Editing Low. Standard Strong and Printing Low/Standard/Strong → Auto correction is applied to the image to match the settings. Processing • For images shot with the camera's Auto Lighting Optimizer Large Numbers of Images function, the settings at the time of shooting are applied as the default values. Editina To cancel the Auto Lighting Optimizer, remove the check mark JPEG/TIFF from the checkbox. Images Reference Index When [Highlight tone priority] is set to [Enable] in EOS 7D and EOS REBEL T2i/550D Custom Functions, the Auto Lighting Optimizer function cannot be set.


Reducing Noise

You can reduce noise that arises in RAW images shot at night or with a high ISO speed.

NR is an abbreviation for "noise reduction".


Select the [NR/Lens/ALO] tab sheet from the tool palette in the edit window or edit image window.

Click the [NR Preview] button.



→ The [NR Preview] window appears.

Adjust an image.



NR check window

- You can set a noise reduction level from within a range of 0 to 20. The larger the setting, the larger the noise reduction effect.
- The noise reduction effect can be checked when an image is displayed at 100% in the NR check window.
- You can change the display position of the NR check window by dragging the enlargement display position in the navigator window.

Click the [Apply] button.

→ Noise reduction is applied to the image and the image is redisplayed.

The noise reduction function does not work

Noise reduction cannot be applied when [Viewing and saving RAW images] (p.73) is set to [High speed] in the [Preferences] window. Select [High quality] to reduce noise.

To set the same noise reduction level for several images

After selecting multiple images in the main window, you can set the same noise reduction level for the images without displaying the [NR Preview] window, by adjusting the noise reduction level in the [NR/Lens/ ALO] tool palette (p.112) using the [Luminance noise reduction] and [Chrominance noise reduction] sliders, and then clicking the [Apply] button.

- You can set the default noise reduction beforehand, using [Default noise reduction settings] in the [Tool palette] tab sheet in the [Preferences] (p.76).
 - When [Apply camera settings] is selected, you can pre-set a noise reduction level that suits the camera settings beforehand as the default.
 - When [Set as defaults] is selected, you can pre-set a preferred default setting for the noise reduction level beforehand. This is particularly useful for applying noise reduction to all the images in a folder at once, such as batch noise reduction for images with high ISO speeds.

However, for images with recipes attached, the noise level recorded in the recipe will be applied.

- If [Luminance noise reduction] has been set, resolution may be reduced along with reduction of noise.
- If [Chrominance noise reduction] has been set, color bleeding may occur along with reduction of noise.
- For a list of [NR Preview] window functions, refer to p.113.

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



Correcting Lens Aberration

You can easily make corrections to drops in peripheral illumination, distortions in the subject, and color blur which occur by the physical characteristics of the lens or slightly remaining aberration.

Please note that you can only correct RAW images which have been taken with the compatible cameras and lenses listed below. JPEG or TIFF images cannot be corrected.

Compatible Cameras

EOS-1Ds Mark III	EOS-1D Mark III
EOS-1Ds Mark II	EOS-1D Mark II
EOS-1D	EOS 5D Mark II
EOS 7D	EOS 50D
EOS 30D*2	EOS REBEL T2i/550D
EOS DIGITAL REBEL XSi/450D	EOS DIGITAL REBEL XTi/400D DIGITAL
—	
	EOS-1Ds Mark II EOS-1D EOS 7D EOS 30D*2 EOS DIGITAL REBEL

*1 Requires firmware version 1.1.1

*2 Requires firmware version 1.0.6

Compatible Lenses

Ultra wide and wide lenses		
EF 14mm f/2.8L USM	EF 14mm f/2.8L II USM* ³	
EF 20mm f/2.8 USM	EF 24mm f/1.4L USM	
EF 24mm f/1.4L II USM*3	EF 24mm f/2.8	
EF 28mm f/1.8 USM	EF 28mm f/2.8	
EF 35mm f/1.4L USM	EF 35mm f/2	
Standard and medium telephoto lenses		
EF 50mm f/1.2L USM* ⁴	EF 50mm f/1.4 USM	

EF 50mm f/1.8	EF 50mm f/1.8 II
EF 85mm f/1.2L USM	EF 85mm f/1.2L II USM*5
EF 85mm f/1.8 USM	EF 100mm f/2 USM

Telephoto lenses		
EF 135mm f/2L USM	EF 135mm f/2.8 (with Softfocus mechanism)	
EF 200mm f/2L IS USM*3	EF 200mm f/2.8L USM	
EF 200mm f/2.8L II USM	EF 300mm f/2.8L IS USM	
EF 300mm f/4L IS USM	EF 400mm f/2.8L IS USM	
EF 400mm f/5.6L USM	EF 400mm f/4 DO IS USM	
EF 500mm f/4L IS USM	EF 600mm f/4L IS USM	
EF 800mm f/5.6L IS USM*3		

Introduction
Contents at a Glance
Basic Operation
Advanced Operation
Advanced Image Editing and Printing
Processing Large Numbers of Images
Editing JPEG/TIFF Images
Reference
Index

Zoom	lenses
EF 16-35mm f/2.8L USM	EF 16-35mm f/2.8L II USM* ³
EF 17-35mm f/2.8L USM	EF 17-40mm f/4L USM
EF 20-35mm f/3.5-4.5 USM	EF 24-70mm f/2.8L USM
EF 24-85mm f/3.5-4.5 USM	EF 24-105mm f/4L IS USM
EF 28-70mm f/2.8L USM	EF 28-90mm f/4-5.6 USM
EF 28-90mm f/4-5.6 II USM	EF 28-90mm f/4-5.6
EF 28-90mm f/4-5.6 II	EF 28-90mm f/4-5.6 III
EF 28-105mm f/3.5-4.5 USM	EF 28-105mm f/3.5-4.5 II USM
EF 28-105mm f/4-5.6 USM	EF 28-105mm f/4-5.6
EF 28-135mm f/3.5-5.6 IS USM	EF 28-200mm f/3.5-5.6
EF 28-200mm f/3.5-5.6 USM	EF 28-300mm f/3.5-5.6L IS USM
EF 55-200mm f/4.5-5.6 II USM	EF 55-200mm f/4-5.6 USM
EF 70-200mm f/2.8L USM	EF 70-200mm f/2.8L IS USM
EF 70-200mm f/2.8L IS II USM*3	EF 70-200mm f/4L USM
EF 70-200mm f/4L IS USM*4	EF 70-300mm f/4-5.6 IS USM
EF 70-300mm f/4.5-5.6 DO IS USM	EF 75-300mm f/4-5.6 II* ³
EF 75-300mm f/4-5.6 III* ³	EF 75-300mm f/4-5.6 USM
EF 75-300mm f/4-5.6 II USM	EF 75-300mm f/4-5.6 III USM
EF 90-300mm f/4.5-5.6	EF 90-300mm f/4.5-5.6 USM
EF 100-300mm f/4.5-5.6 USM	EF 100-400mm f/4.5-5.6L IS USM

Iviacro	o lenses	
EF 50mm f/2.5 Compact Macro*3	EF 100mm f/2.8 Macro USM	
EF 100mm f/2.8L Macro IS USM*	³ EF 180mm f/3.5L Macro USM	Contents a a Glance
MP-E 65mm f/2.8 1-5x Macro Photo* ³		Basic
EF-S	lenses	Operation
EF-S 60mm f/2.8 Macro USM	EF-S 10-22mm f/3.5-4.5 USM	Advanced
EF-S 15-85mm f/3.5-5.6 IS*3	EF-S 17-55mm f/2.8 IS USM	Operation
EF-S 17-85mm f/4-5.6 IS USM	EF-S 18-55mm f/3.5-5.6	
EF-S 18-55mm f/3.5-5.6 II	EF-S 18-55mm f/3.5-5.6 USM	Advanced Image Editi
EF-S 18-55mm f/3.5-5.6 II USM	EF-S 18-55mm f/3.5-5.6 IS* ³	and Printin
EF-S 18-135mm f/3.5-5.6 IS* ³	EF-S 18-200mm f/3.5-5.6 IS* ³	Processin
EF-S 55-250mm f/4-5.6 IS* ³		Large Number of Images
	y to images shot with a combination	Editing
of lenses *3 *4 *5 and EOS 5D or E	EOS 30D with the firmware versions to EOS 5D. 1.1.0 or earlier, EOS 30D with	Images
of lenses *3 *4 *5 and EOS 5D or E below. * You cannot attach an EF-S lens *3 EOS 5D with firmware version firmware version 1.0.5 or earlie *4 EOS 5D with firmware version	EOS 30D with the firmware versions to EOS 5D. 1.1.0 or earlier, EOS 30D with er 1.1.0 or earlier, EOS 30D with	JPEG/TIFI Images
of lenses *3 *4 *5 and EOS 5D or E below. * You cannot attach an EF-S lens *3 EOS 5D with firmware version firmware version 1.0.5 or earlie	EOS 30D with the firmware versions to EOS 5D. 1.1.0 or earlier, EOS 30D with er 1.1.0 or earlier, EOS 30D with er 1.0.5 or earlier, EOS 30D with	JPEG/TIFI
 of lenses *3 *4 *5 and EOS 5D or E below. * You cannot attach an EF-S lens *3 EOS 5D with firmware version firmware version 1.0.5 or earlie *4 EOS 5D with firmware version firmware version 1.0.4 or earlie *5 EOS 5D with firmware version 1.0.4 or earlie *5 EOS 5D with firmware version 1.0.4 or earlie *0 You can also correct RAW ima even when the extender is attached the extender is attached to compact Macro fitted with Life The aberration correction function 	EOS 30D with the firmware versions to EOS 5D. 1.1.0 or earlier, EOS 30D with er 1.1.0 or earlier, EOS 30D with er 1.0.5 or earlier, EOS 30D with er ages taken with the compatible lens ached. ages shot with EF 50mm f/2.5 e Size Converter EF. ction is not available for images shot lens other than those given under	JPEG/TIF Images Reference

61

Introduction

Making Corrections

You can make corrections to any of the four aberrations as below, either one at a time or simultaneously.

- Peripheral illumination
- Distortions
- Chromatic aberration (color fringing which occurs in the periphery of an image)
- Color blur (blue or red color blur which sometimes occurs at the edge of the highlighted area of an image)


In the tool palette, select the [NR/Lens/ALO] tab sheet.

Click the [Tune] button.

RAW RGB NR/Lens/ALO	
Auto Lighting Optimizer	
Low Standard	Strong
Noise reduction	Apply
RAW	IR Preview
Luminance noise reduction:(7)	
0	
Chrominance noise reduction:(9)	
o (~]	20
TIFF/JPEG	
Luminance noise reduction:(0)	
o 0	20
Chrominance noise reduction:(0)	
0 0	20
Lens aberration correction	Tune
Peripheral illumination	OFF
Distortion	OFF
Chromatic aberration	OFF
Color blur	OFF

→ The [Lens aberration correction] window appears.

Checkmark the items to be corrected.



- → The image is corrected and redisplayed.
- Check the results of corrections to peripheral illumination or distortions in the full view.
- Check the results of corrections to chromatic aberration and colo blur by clicking the area on the image you want to check. In the top right of the window, the area is displayed at 200% in the enlargement display section (p.118).
- You can lessen the degree of correction by moving the slider to the left for the item you want to correct.
- You can respectively correct red chromatic aberration with the [R] slider of the [Chromatic aberration] or blue chromatic aberration with the [B] slider.

Click the [OK] button.

- The [Lens aberration correction] window closes and the result of the corrections is applied to the image in the edit window and the image is redisplayed.
- The result of the settings of the [Lens aberration correction] window is also displayed in the tool palette.
- → In the main window, the [) mark is displayed on the image to indicate the lens aberration corrections (p.109).

	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
olor ne	Editing JPEG/TIFF Images
to [R]	Reference
on	Index
t of the	00

About Shooting Distance Information Slider

When correcting RAW images shot with the cameras in the table below, if shooting distance information has been saved to the image, the slider is set automatically according to this shooting distance information.

However, if no shooting distance information is saved to the image, the slider is set automatically to the right end at infinity position and a [<!>] appears above the slider.

If the image's shooting distance is not infinite, you can minutely adjust the distance by operating the slider while looking at the screen.

EOS-1D Mark IV	EOS-1Ds Mark III	EOS-1D Mark III
EOS 5D Mark II	EOS 7D	EOS 50D
EOS 40D	EOS REBEL T2i/550D	EOS REBEL T1i/500D
EOS DIGITAL REBEL XSi/450D	. EOS DIGITAL REBEL XS/1000D	·

• When correcting RAW images shot with the cameras in the table below, it is set automatically to the right end at infinity position. You can then minutely adjust the distance by operating the slider while looking at the screen if the shooting distance is not infinite.

EOS-1D Mark II N	EOS-1Ds Mark II	EOS-1D Mark II
EOS-1Ds	EOS-1D	EOS 5D
EOS 30D	EOS DIGITAL REBE XTi/400D DIGITAL	:L

 For RAW images shot with MP-E 65mm f/2.8 1-5x Macro Photo or EF 50mm f/2.5 Compact Macro with Life Size Converter EF, the slider indicator changes to [Magnification factor].

 [Shooting distance information] slider is applied to all the correction items with check marks.

Correcting Multiple Images at a Time

Select multiple images to correct in the main window. Display tool palette by clicking the [Tool] button (p.107) in the toolbar. If you perform correction procedures (p.62) when tool palette is displayed, you can apply the same corrections to all the images selected in the main window.

Also, you can apply same corrections by copying the recipe of the corrected image and pasting it onto the multiple images (p.38).

? Additional information

Some noise appeared in the periphery of an image after correcting [Peripheral illumination]

You can reduce the noise by using luminance and/or chromatic noise reduction of the noise reduction function (p.59). However, if you had applied high amount of [Peripheral illumination] correction to the images that have been shot at night or with a high ISO speed, the noise might not be reduced.

 The image appears with less resolution after correcting [Distortion]

You can make the image similar to the one before correction by applying more sharpness with the sharpness adjusting function (p.29).

The colors of the image became weaker after correcting [Color blur]

You can make the image similar to the one before correction by adjusting the color tone (p.27) and/or the color saturation (p.91) to make the color deeper.

The result of [Color blur] correction cannot be detected

[Color blur] correction is effective for correcting blue or red color blur which occurs at the edge of the highlighted area of an image. If conditions do not match, correction cannot be made.

The periphery of the image may be truncated when [Distortion] correction is made.

For a list of the [Lens aberration correction] window functions, refer to p.118.

Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



63

Performing Automatic Dust Erasure Processing


The Dust Delete Data that is appended to images shot with the camera that can attach this data, can be used to automatically erase dust spots.

Compatible Cameras

EOS-1D Mark IV	EOS-1Ds Mark III	EOS-1D Mark III
EOS 5D Mark II	EOS 7D	EOS 50D
EOS 40D	EOS REBEL T2i/550D	EOS REBEL T1i/500D
EOS DIGITAL REBEL XSi/450D	EOS DIGITAL REBEL XTi/400D DIGITAL	

In the main window, select an image appended with Dust Delete Data.

Select the [Tools] menu ▶ [Start Stamp tool]. → The copy stamp window appears. When the image has redrawn itself, click the [Apply Dust Delete Data] button.



→ Dust spots are erased in a single operation.

Click the [OK] button to return to the main window.

The [] mark (p.109) is displayed on an image from which due spots have been erased.

ply	Introduction
	Contents at a Glance
ow. dust	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

Additional information

 The dust-erased image can be reverted to its original condition at any time

A dust-erased image is displayed or printed as a dust-erased image. However, since the dust on the image is not actually erased, you can always revert to the original image by clicking the [Undo] button in the copy stamp window or performing the "Re-Editing an Image" procedure (p.40).

Check dust erasure in the copy stamp window

Check dust erasure in the copy stamp window. Images before dust erasure are displayed in other windows and you will be unable to check them.

Printing dust-erased images

You can print as a dust-erased image by printing it in DPP.

• The [Apply Dust Delete Data] button cannot be clicked

Even with an image that has Dust Delete Data attached to it in the camera, if there is no dust to remove by DPP from the image, the [Apply Dust Delete Data] button will be disabled.

To erase dust spots that cannot be erased with the automatic dust erasure processing

In automatic dust erasure processing, dust spots are erased based on information relating to dust saved in the Dust Delete Data. However, there may be cases where you will not be able to erase dust spots depending on the type of dust. If this occurs, erase those dust spots using the repair function (p.66) or the copy stamp function (p.68).

The image becomes a dust-erased image when converted and saved

The dust-erased RAW image actually becomes a dust-erased image when converted to a JPEG or TIFF image and saved (p.39).

\in Useful functions of the copy stamp window

Checking the dust erased spots

After step 3, you can display and check in detail the erased dust spots one by one by pressing the <Shift> + <F> keys. (Press the <Shift> + keys to return to the previous dust spot.)

Canceling a specified erased dust spot only

After step 3, you can press the <Shift> + <F> keys or the <Shift> + keys to display the erased dust spot, and then press the <Shift> + keys to cancel only the erased dust spot displayed.

 Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the <Alt> + <Enter> keys.

Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

For a list of the copy stamp window functions, refer to p.119.

Automatic Dust Erasure Processing in the Main Window

In the main window, you can also automatically erase dust spots in multiple images appended with Dust Delete Data.

Select multiple images appended with Dust Delete Data, and then select the [Adjustment] menu ▶ [Apply Dust Delete Data].

Dust spots in all the selected images are erased in a single operation.

Operation Advanced

Image Editing and Printing

Processing Large Numbers of Images

> Editing JPEG/TIFF Images

Reference

Index



Contents at

a Glance

Basic


Operation

Advanced

Manually Erasing Dust (Repair Function)

You can erase dust spots in an image by selecting them one by one.

- In the main window, select the image you want to erase dust spots.
- Select the [Tools] menu ▶ [Start Stamp tool].
- ➡ The copy stamp window appears.
- When the image has redrawn itself, double-click the point from where dust is to be erased.




- → The display changes to 100% view.
- The display position can be changed by dragging.

Click the button that matches the dust spot to be erased.

- When you move the cursor over the image, the dust erasure range appears as [O].

Place the dust spot to be erased within the $[\bigcirc]$ an click.



- → The dust spot within the [O] is erased.
- Click on another part of the image to continue erasing dust spots in the image.
- To erase dust in another part of the image, either right-click with the mouse, or click the button clicked in step 4 again to cancel dus erasure processing and perform the operation again from step 3.
- When the dust spot cannot be erased, [S] is displayed.

Click the [OK] button to return to the main window.

→ The [] mark (p.109) is displayed on an image from which dust spots have been erased.

Ind	Introduction
	Contents at a Glance
	Basic Operation
<	Advanced Operation
	Advanced Image Editing and Printing
spots	Processing Large Numbers of Images
with el dust ep 3.	Editing JPEG/TIFF Images
ow. n dust	Reference
	Index

Additional information

- Click several times when dust spots are not erased completely Where unwanted dust spots are not erased even after performing step 5 once, they may be erased completely when you click several times.
- Mainly spots of dust can be erased with the repair function Spots of dust can be erased with the repair function. You may be unable to erase lines of dust. In this case, use the copy stamp function (p.68).
- The dust-erased image can be reverted to its original condition at any time

A dust-erased image is displayed or printed as a dust-erased image. However, since the dust on the image is not actually erased, you can always revert to the original image by clicking the [Undo] button in the copy stamp window or performing the "Re-Editing an Image" procedure (p.40).

Check dust erasure in the copy stamp window

Check dust erasure in the copy stamp window. Images before dust erasure are displayed in other windows and you will be unable to check them.

Printing dust-erased images

You can print as a dust-erased image by printing it in DPP.

 The image becomes a dust-erased image when converted and saved

The dust-erased RAW image actually becomes a dust-erased image when converted to a JPEG or TIFF image and saved (p.39).

Useful functions of the copy stamp window

Checking the dust erased spots

After step 5, you can display and check in detail the erased dust spots one by one by pressing the <Shift> + <F> keys. (Press the <Shift> + keys to return to the previous dust spot.)

Canceling a specified erased dust spot only

After step 5, you can press the <Shift> + <F> keys or the <Shift> + keys to display the erased dust spot, and then press the <Shift> + keys to cancel only the erased dust spot displayed.

 Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the <Alt> + <Enter> keys.

Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

To apply dust erasure to the same place in several other images, you can efficiently erase dust spots by clicking the images while holding down the <Ctrl> key in the main window, or, by selecting multiple images by clicking the first image and then clicking the last image while holding down the <Shift> key, and then displaying the copy stamp window.

For images shot with ISO speed range expansion set, noticeable noise may make it difficult to view dust spots in the copy stamp window, so using this function is not recommended.

For a list of the copy stamp window functions, refer to p.119.

Advanced Operation Advanced Image Editing and Printing

Introduction

Contents at

a Glance

Basic Operation

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



67

Erasing Unwanted Parts of an Image (Copy Stamp Function)

You can correct an image by pasting a section copied from another part of the image to an unwanted part of the image.

Follow steps 1 to 3 in "Manually Erasing Dust (Repair Function)" (p.66).

Specify the section to be copied.

- Click on the section that is to be the copy source while holding down the <Alt> key.
- To change the section that is to be the copy source, perform the operation above again.
- To fix the position of the copy source, checkmark [Fix Copy Source position].

Correct the image.

- Click or drag on the section you want to correct on the image. [+] in the window indicates the copy source and [O] indicates the copy destination.
- The copied image is pasted in the position to which it was dragged.
- For [Pen type], you can select from [Brush] (the pasted image's borders simulate a brush) and [Pencil] (the pasted image's borders are sharp).

Click the [OK] button to return to the main window.

 \rightarrow The [] mark (p.109) is displayed on a corrected image.

Transferring a RAW Image to Photoshop

A RAW image can be converted to a TIFF image (16bit) and transferred to Photoshop.

Select the [Tools] menu ▶ [Transfer to Photoshop].

→ Photoshop starts up and the transferred image is displayed.

A single image can be transferred at a time

Only one image can be transferred at a time. To send multiple images at a time, refer to p.84.

- Compatible versions of Photoshop are 7.0 or later.
- Transferred images are automatically converted to TIFF images (16bit) to which an ICC profile (p.122) is added. The ICC profile contains information about [Preferences] (p.77) or work color space set for each image as described below and the appropriate color information is relayed to Photoshop.
- When you exit Photoshop, only the original RAW image remains, and the transferred image will disappear. Saving the transferred image as a separate image in Photoshop is highly recommended.

Setting Work Color Space

A different work color space (p.123) from the default settings (p.77) can be set for each image.

Select the [Adjustment] menu > [Work color space] > color space to be set.

A color space set individually does not change even when the default setting is changed

If you set an image with a color space different to the default setting and then subsequently change the default color space setting (p.77), this default setting will not be applied and the individually set color space will remain.

-¥

The color space of a RAW image can be changed freely as many times as required

Since only the image processing conditions information changes, the color space of a RAW image can be changed at any time.

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference


Index



Printing with Shooting Information

You can freely lay out one image on one sheet of paper and print together with titles and shooting information, etc.


- Select one image to be printed.
- Select the [File] menu > [Print with detailed setting].
- Specify the required settings for printing, and then click the [Print] button.



Switches the settings tab sheet

÷

To maintain the settings The settings of each tab sheet in step 3 are memorized when the [Apply] button is clicked (excluding the contents of the [Text] tab sheet). The settings can be applied to another image when printing. You can set printer profiles (p.77). If CMYK simulation has been set, the image is printed in the set colors (p.77).




Introduction

- The image can be moved by dragging.
- Drag the four corners of the image to change the size.
- For the shooting information, click [1] on the [Text] tab sheet and select the necessary items in the window that is displayed.


Printing a Thumbnail List (Contact Sheet Printing)

You can print rows of multiple images on one sheet of paper.

- Select images to be printed in a thumbnail list.
- Select the [File] menu ▶ [Contact Sheet Prints].
- Specify the required settings for printing, and then click the [Print] button.



Switches the settings tab sheet



Print preview

Index

Printing RAW Images on a High-End Canon Printer

Printing with a High-End Canon Inkjet Printer

For high-end Canon inkjet printers that are compatible with the printing software Easy-PhotoPrint Pro, you can print with DPP by a simple operation that has the following features:

- Simple printing of RAW images
- Printing in faithful colors
- High quality printing using a wide color space of Adobe RGB, etc. and the wide color reproduction range of a high-end Canon inkjet printer

To print with DPP, first install Easy-PhotoPrint Pro version 1.3 or later on your computer.

Select the [File] menu ▶ [Plug-in printing] ▶ [Print with Easy-PhotoPrint Pro].

→ Easy-PhotoPrint Pro starts up.

Match on-screen image colors and printing result colors.

 Select [Custom] in [Print Quality], click the [Set] button, and in the window that appears, drag the slider to [1] at the right end, and then click the [OK] button to close the window.

Next, click the [Color Adjustment] button to display the [Color Adjustment] window and display the [Color Management] tab sheet. Set [Color Mode] to [Enable ICC Profile] and [Printer Profile] to [Auto], and then click the [OK] button to close the [Color Adjustment] window.

Specify any other required settings for printing, and then print.

Additional information

Print up to 1000 images at a time

You can print up to 1000 images selected in DPP at a time. When printing more than 1000 images, divide the printing into several jobs.

- Function set in DPP that is not applied to printing Specified CMYK simulation (p.77) is not applied.
- The printed image's color is not what you expected In the Easy-PhotoPrint Pro window, click the [Color Adjustment] button to display the [Color Management] tab sheet, set [Rendering Intent] to [Perceptual] (p.123), and try printing.

Advantages of printing with Easy-PhotoPrint Pro

Printing with faithful colors

When a color space is set (p.68, p.77), it is automatically transmitted from DPP to Easy-PhotoPrint Pro, allowing you to print with faithful colors.

Printing with a wide color reproduction

When the color space setting (p.68, p.77) is set to a color space wider than sRGB (such as Adobe RGB), the image is printed with a wider color gamut than an image that has an sRGB color space, with green and blue in particular being reproduced vividly.

	Introduction
S.	Contents at a Glance
	Basic Operation
	Advanced Operation
ed	Advanced Image Editing and Printing
	Processing Large Numbers of Images
er en	Editing JPEG/TIFF Images
	Reference
	Index
	00

Printing with a Large-Format Canon Printer

You can use DPP to print with the DPP-compatible Canon large-format imagePROGRAF printer. To print with DPP, first install imagePROGRAF Print Plug-In for Digital Photo Professional on your computer.

Select the [File] menu ▶ [Plug-in printing] ▶ Plug-In for the printer you use.

→ The Plug-In starts up.

Specify the required settings for photograph printing, and then print.

Additional information

A single image can be printed at a time

You can print a single image selected in DPP at a time. When printing multiple images, perform printing for each image individually.


• Functions set in DPP that are not applied to printing Specified output resolution (p.73) and CMYK simulation (p.77) are not applied. Advantages of printing with imagePROGRAF Print Plug-In

Printing with faithful colors

When a color space is set (p.68, p.77), it is automatically transmitted from DPP to the Plug-In, allowing you to print with faithful colors.

Printing with a wide color reproduction

When the color space setting (p.68, p.77) is set to a color space wider than sRGB (such as Adobe RGB), the color reproduction range of the imagePROGRAF printer is fully utilized and the image is printed with a wider color gamut than an image that has an sRGB color space, with green and blue in particular being reproduced vividly.



Specifying Preferences

You can change the various functions of DPP in the [Preferences] window. Check the contents of each window and set.

Also, depending on the item, a detailed explanation may be available, so refer to each window.

Select the [Tools] menu ▶ [Preferences].

→ The [Preferences] window appears.

Select the tab sheet, specify the settings, and then click the [OK] button.

erences			
General settings	View settings	Tool palette	Color management
Startup folder			
 Last displayed fold 	er		
🔘 Specified folder			
Browse	C:\Documents and :	Settings\canon\My Docume	nts\My Pictures
Save recipe			
 Display message v 	when adding file		
Add to file automatic			
Viewing and saving RAV	/ images		
📀 High quality (recorr	nmended)	View/save RAW images a	at high quality NR tool palette can be used
View images a reduction off)	t high speed (moiré	Morre is reduced and the	NR tool palette can be used
O High speed			
Originopood			
JPEG image quality			
🔲 Remove block nois	e and mosquito nois	e	
🔲 Display thumbnails	s at high quality		
Default value of output re	solution		
350 dpi(1-6	0000)		
At EOS Utility startup			
Edit image window	enabled at EOS Utili	ty startup	
			OK Cancel

General Settings

You can specify the folder that opens when DPP is started up, image quality of displayed and saved RAW images, etc.

ferences					
General settings	View settings	Tool palette	Color management		Basic
Startup folder				3	Operation
 Last displayed fol 	der				
🔘 Specified folder					
Browse	CADocuments and Setti	ngs\canon\My Documents\	My Pictures		Advanced
					Operation
Save recipe					operation
💿 Display message	when adding file				
🔾 Add to file automa	tically				Advanced
					Image Editing
Viewing and saving RA		ew/save RAW images at hi	ah aualitu		Image Editing and Printing
 High quality (record) Wiew images 	M	piré is reduced and the NR			
reduction off)	at high speed (moiré				
🔘 High speed					Processing
					Large Numbers
JPEG image quality	ise and mosquito noise				of Images
Display thumbnail					
	is at nigh quanty				Editing
- Default value of output r	resolution			_	JPEG/TIFF
250					Images
dpi(1-	60000)				
At EOS Utility startup					
Edit image window	w enabled at EOS Utility st	artup			Reference
					Reference
			OK Cancel		Index



Introduction

Contents at

a Glance

Introduction Contents at a Glance Basic Operation Advanced Operation Advanced Image Editing and **Printing** Processing Large Numbers of Images Editing JPEG/TIFF Images

Reference

Index

• Viewing and saving RAW images

You can select from two types of image quality for displaying/saving RAW images: high image quality with false color reduction processing and noise reduction function (p.59) used, or high speed without false color processing and noise reduction function used.

[High quality]

- False color reduction processing is automatically applied, and the image can be displayed/saved as a false color reduced-high quality image. Furthermore, you can use the noise reduction function (p.59) to reduce the luminance noise and chrominance noise.
- Because the effects of the false color reduction processing and noise reduction function are difficult to see in the [50% view] or [Fit to window] display of the edit window and edit image window, use [100% view] or [200% view] to check.
- We recommend that you normally set [High quality] for a balance between image quality and display speed.

[View images at high speed (moiré reduction off)] of [High quality]

- If you checkmark [View images at high speed (moiré reduction off)], when the image is displayed in the edit window or the edit image window, false color reduction processing is not applied. However, you can use the noise reduction function.
- As the setting is the same as [High quality] other than for image display, the image undergoes false color reduction processing when it is saved.

[High speed]

- Since false color reduction processing is not applied, the display speed of a RAW image in the edit window or the edit image window, and the time it takes to save a RAW image is shorter than with [High quality].
- You cannot use the noise reduction function (p.59).
- Depending on the image, it may be displayed/saved with false color or noise being noticeable.

For images shot with ISO speed range expansion set, the difference in image quality between [High quality] and [High speed] becomes remarkable. To check the image quality of images shot with ISO speed range expansion, make sure to set [High quality] and check the images in the edit window or edit image window.

JPEG image quality

[Remove block noise and mosquito noise]

 You can improve the quality of a JPEG image by reducing the noise particular to JPEG images.

This setting is also effective when RAW images are converted to JPEG images and saved (p.39, p.83) and for JPEG images that have been saved with a different name.

[Display thumbnails at high quality]

 You can have the thumbnails for JPEG images automatically displayed at high quality. If you checkmark [Display thumbnails at high quality], all subsequent JPEG image thumbnails imported into DPP will be displayed at high quality.

? The extent of the improvement in noise reduction

The higher the JPEG image's compression rate, the more noise is reduced. When the compression rate is low, the effect of noise reduction is negligible.

Default value of output resolution

You can set the resolution for RAW images converted and saved as JPEG or TIFF images (p.39, p.83).

View Settings

You can specify settings relating to the display.

srid pitch 64 Pixels(8-256) mage selection status ✓ Images opened in Edit window Asgnification in Edit window ① Fit to window Asgnification when the Edit/Edit ima tAW and JPEG C Display only CR2 images for C iort order in main window	0 50%	0100%	0 200%
age selection status Images opened in Edit window agnification in Edit window Fit to window agnification when the Edit/Edit ima AW and JPEG Display only CR2 images for C ort order in main window	○ 50% age window is double-click	O 100%	
age selection status Images opened in Edit window Iagnification in Edit window Iagnification when the Edit/Edit ima AW and JPEG Image Display only CR2 images for C ort order in main window	○ 50% age window is double-click	O 100%	
Images opened in Edit window Iagnification in Edit window Fit to window Iagnification when the Edit/Edit ima AW and JPEG Display only CR2 images for C ort order in main window	○ 50% age window is double-click	O 100%	
Iagnification in Edit window	○ 50% age window is double-click	O 100%	
Fit to window lagnification when the Edit/Edit ima AW and JPEG Display only CR2 images for C ort order in main window	age window is double-click	ed	
Fit to window agnification when the Edit/Edit ima AW and JPEG Display only CR2 images for C ort order in main window	age window is double-click	ed	
AW and JPEG Display only CR2 images for C ort order in main window			0 200%
AW and JPEG Display only CR2 images for C ort order in main window			0 200%
Display only CR2 images for C	0 50%	100%	0 200%
Display only CR2 images for C			
Display only CR2 images for C			
ort order in main window			
	R2 and JPEG files of the ·	same name	
Retain sort order			
ighlight/shadow Alert			
Highlight 255	(192-255)		
Shadow 0			
	(0-64)		
uick check tool display			
⊙ 50%	00% (moiré reduction off))	

Sort order in main window


You can set the order of images which have been rearranged in the main window to be maintained or not maintained (p.19).

If you checkmark the checkbox, the order of the rearranged images is maintained even if you exit DPP or select another folder in the folder area.

If you remove the check mark, the order of the rearranged images is not maintained and reverts to the previous order when you exit DPP or select another folder in the folder area.

Highlight/shadow warning

Highlighted/shaded areas that exceed the set range can be displayed on the image as warning indicators (p.52).



Tool Palette

You can specify settings for the tool palette.

General settings View settings	Tool palette	Color managemer
Default settings of RGB tool palette		
Tone curve mode	Tone curve interpolation meth	od
💽 RGB R G B	💽 Curve	
🔵 Luminance R G B	🔘 Straight	
Histogram display		
O Before adjustment		
 After adjustment 		
Tool palette display in Edit Image Window		
 Docking display 		
◯ Floating display		
Same for Main window and Edit window		
Default noise reduction settings		
 Apply camera settings 		
🔿 Set as defaults		
RAW luminance noise reduction: (0)	o 0	20
RAW chrominance noise reduction: (0)	0 0	20
TIFF/JPEG luminance noise reduction: (0)	0 0	20
	0 0	20
TIFF/JPEG chrominance noise reduction: (0)		

Default settings of RGB tool palette

You cannot apply changes to the settings until you re-open the folder.

Changes are not applied to the edited image

Even if the default setting is changed, the new default setting is not applied to edited (i.e., adjusted using the tool palette, trimmed, dusterased) images. Change each one individually.

Modified Picture Style settings

You can select whether the [Color tone], [Color saturation], [Contrast] and [Sharpness] settings will be changed or retained, when you change the Picture Style.

- If you checkmark the checkbox, the [Color tone], [Color saturation], [Contrast] and [Sharpness] settings will be changed to match the camera's preset settings, when you change the Picture Style.
- If you remove the check mark, the [Color tone], [Color saturation], [Contrast] and [Sharpness] settings will be retained, even if you change the Picture Style.

Default noise reduction settings

You can set a default beforehand for the noise reduction level. RAW Images

- When [Apply camera settings] is selected, you can pre-set a noise reduction level that suits the camera settings beforehand as the default.
- When [Set as defaults] is selected, you can pre-set a preferred default setting for the noise reduction level beforehand.
 JPEG/TIFF Images

• You can set a desired default noise reduction level beforehand. For images not having a recipe attached, the default set here for noise reduction level is applied. However, if you want to apply settings to images in the opened folder, you need to re-open the folder after making settings here. For images with a recipe attached, the noise level recorded in the recipe remains as it is and the default for noise reduction level set here is not applied.

Advantages of setting a noise reduction default

In instances where the same level of noise occurs in several images, such as images shot with high ISO speed, setting an appropriate default noise reduction setting enables you to apply a batch noise reduction default to all the images displayed in DPP (excluding images with a recipe attached). This eliminates the need to apply noise reduction to each individual image. And, since you always shoot with the same conditions, it is also useful when you want to set the same noise reduction level for all shot images. Introduction

Contents at a Glance

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



Color Management

You can specify settings relating to color management, such as settings for work color space, conditions for color matching, etc.

General settings	View settings	Tool palette	Color management
)efault settings of Work (color space		
💿 sRGB		🔿 Apple RGB	
🔿 Adobe RGB		🔘 ColorMatch RGB	
◯ Wide Gamut RGB			
olor matching settings -			
For display			
💿 sRGB			
◯ Use the OS setting	js		
🔘 Moniter profile			
Browse			
Printing profile		Rendering	intents
None		V O Perce	eptual
		 Relat 	tive Colorimetric
CMYK simulation profil	le	Rendering	intents
None		V Perce	eptual
			tive Colorimetric
Rendering intents when u	using Easy-PhotoPhint—		
O Perceptual			
 Relative Colorimetri 	IC		

Default settings of Work color space

You can select from five types of color space (p.123) that is applied as a default setting in RAW images. Color space that has been set is applied as the color space when a RAW image is converted and saved (p.39, p.83) or printed (p.40, p.43, p.46, p.69 to p.72).

- If you have changed the setting, and you restart DPP, the new setting is applied as the default setting color space.
- You can check color space that has been set in an image in the main window (p.107, p.108), the edit window (p.110), and the edit image window (p.115).

Changes are not applied to the edited image

Even if the default setting is changed, the new default setting is not applied to edited (i.e., adjusted using the tool palette, trimmed, dusterased) images. Change each one individually.

You can set a color space that is different from the default settings for each image (p.68).

Display setting (color setting of the monitor)

Where a profile (p.122) is attached to the monitor you are using, you can display an image in more faithful colors by setting the profile.

 If you select [Use the OS settings], the color profile set in Windows will also be applied in DPP.

If you are using multiple monitors, only the profile of the primary monitor is applied to DPP.

 Select the [Monitor profile], click the [Browse] button and in the dialog box that appears, select a profile for your monitor.



F Precise coloring with a third-party monitor color reader

If you use a profile created using a third-party monitor color reader, images can be displayed in even more precise colors.

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



Setting of printing profile (color setting of the printer)

Where a profile (p.122) is attached to the printer you are using to print images, you can print an image and simulate the colors displayed on screen by setting the profile. The profile that has been set is applied to all printing (p.46, p.69, p.70) except for printing using a Canon inkjet printer (p.40, p.43) or linked printing (p.71, p.72).

? The adjustment function of the printer driver should not be used

Even if you set a printer profile, if you use the color adjustment function of the printer driver, the image may print in colors different from those displayed on screen.

Automatic settings for printing using EPP EX, EPP, and linked printing

If you are printing using a Canon inkjet printer (p.40, p.43) or using linked printing (p.71, p.72), a profile is set automatically even when the [Printing profile] setting is not performed. This allows you to print faithful colors easily.

Setting of CMYK simulation profile


You can select the color when printing in the CMYK environment of a printing machine, etc. from four types of profiles (p.123) and perform simulation on screen.

- When CMYK simulation has been set, [CMYK] appears (p.107, p.108, p.110, p.115) in the bottom of the main window, edit window and edit image window, and colors can be checked.
- To temporarily cancel CMYK simulation, press the <Ctrl> + <Y> keys.


Rendering intents when using Easy-PhotoPrint

You can set a rendering intent (matching method) (p.123) for printing using Easy-PhotoPrint (p.43).

- The rendering intent is ordinarily set to [Relative Colorimetric].
- When colors with [Relative Colorimetric] are not satisfactory, set to [Perceptual].



4 Useful Functions for Processing Large Numbers of RAW Images



For users shooting a large amount of RAW images, the convenient function of batch processing large amounts of RAW images is explained here.


Utilizing Adjustment Contents (Recipe) 80 Saving Recipes as a File 81
Loading and Pasting Recipes
Copying a Recipe and Applying to Another Image 81
Batch Apply White Balance to Images (Personal White
Balance)
Registering Personal White Balance
Applying Personal White Balance
Batch Save as JPEG or TIFF Images (Batch
Processing)83
Batch Transfer Images to Image Editing Software 84
Batch Change the File Name of Images
Changing the File Name of Images in the Order in the
Main Window85



Utilizing Adjustment Contents (Recipe)

All the adjustment contents (recipe) made using the tool palette can be saved as an individual recipe file (extension ".vrd") and loaded and applied to another image.

You can edit images efficiently by selecting and adjusting one image from images shot with the same shooting environment and batch applying the adjustment results to a large number of images.



 RAW image data

 Image processing conditions information

Contents adjusted using the tool palette can be handled individually as a recicpe file (extension ".vrd"). Additional information

Recipe data includes tool palette contents

Recipe data includes adjustments made with the tool palette ([RAW], [RGB] and [NR/Lens/ALO]). For this reason, other editing content such as trimming or dust-erasure (copy stamp) is not included in the recipe data.

 Recipes adjusted with the [RAW] tool palette can only be applied to RAW images

Adjustments in the [RAW] tool palette, which can only be made for RAW images, are not applied to a JPEG or TIFF image even if they are pasted. Basic Operation Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images

Introduction

Contents at

a Glance

Editing JPEG/TIFF Images

Reference

Index



The adjustment contents of JPEG or TIFF images (p.87) can be saved as a recipe file (extension ".vrd") and loaded and applied to another image in the same way as with RAW images.

Saving Recipes as a File

- Select an edited image, and then select the [Edit] menu ▶ [Save recipe in file].
- → The [Save recipe in file] dialog box appears.
- Select the destination folder, enter a file name, and then click the [Save] button.

? Check the contents of a recipe file by pasting to an image

When you do not know the contents of a recipe file, paste it to an image and check the settings in the tool palette. When only a few settings are adjusted, we recommend you use a file name that describes the contents or that you separately record the adjustments as text information.

Loading and Pasting Recipes

- Select the image to which a recipe is to be applied, and then select the [Edit] menu ▶ [Read and paste recipe from file].
 - → The [Open] dialog box appears.
- Select a recipe and click the [Open] button.
- \rightarrow The recipe is applied to the image.

Copying a Recipe and Applying to Another Image

You can copy a recipe of an edited image and then apply it to another image.

- Select the image from which a recipe is to be copied and then select the [Edit] menu ▶ [Copy recipe to clipboard].
 - → The recipe is copied.
- Select the image to which the recipe is to be applied and then select the [Edit] menu ▶ [Paste recipe to selected image].
 - → The recipe is applied to the image.



Batch Apply White Balance to Images (Personal White Balance)

The white balance adjustments made to a RAW image shot in a specific shooting environment can be registered as personal white balance. You can then perform efficient white balance adjustment by applying this personal white balance to a large number of RAW images shot in the same shooting environment.

Registering Personal White Balance

- Adjust the white balance (p.25, p.26, p.53).
- To adjust white balance, select a setting other than [Shot settings] from the [White balance adjustment] list box (p.25). You will be unable to register the adjustments if you select [Shot settings].

In the [RAW] tool palette, click the [Register] button.

- → The [Register personal white balance] dialog box appears.
- Select the button number to be registered from the list and click the [OK] button.

Register personal white balance			
Register current setting in personal white balance			
Current setting: Click white balance			
Click white balance			
Import Export OK Cancel			

To use the registered personal white balance on another computer

- 1 In step 3, click the [Export] button to write as a file.
- 2 Copy the file to another computer.
- 3 In DPP on the other computer, display the window of step 3.
- 4 Click the [Import] button and in the window that appears, select the copied file.
- **Applying Personal White Balance** In the main window, select the image to which balance is to be applied. Click the [Tool] button on the toolbar. The tool palette appears. Click the personal white balance number butto is to be applied. RAW RGB NR/Lens/ALO 5 Brightness adjustment 0.00 5 White balance adjustment 1 2 3 Register.. 1 Tune. Daylight Ð Picture Style Browse. Standard v -10.0 -8.0 -6.0 -4.0 -2.0 0.0 2.0 Contrast: (0) Highlight:(0) Shadow:(0) Linear Color tone:(0) Color saturation:(0) Sharpness:(0) Personal white balance is applied to all the selected imag

	Introduction
white	Contents at a Glance
n that	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index
jes.	

Batch Save as JPEG or TIFF Images (Batch Processing)

You can batch convert and save edited RAW images to highly versatile JPEG or TIFF images.

The images are saved as separate images, so the RAW images remain unaffected.

- In the main window, select multiple images to be converted.
- Click the [Batch process] button on the toolbar (p.107). → The [Batch settings] window appears.
- Specify the required settings, and then click the [Execute] button.

Batch settings					
IMG_0001.CR2	Save folder				
IMG_0002.CR2 IMG_0003.CR2	C:\Documents and Settings\Administrator\Desktop Browse				
IMG_0004.CR2 IMG_0005.CR2	- File format				
IMG_0006.CR2 IMG_0007.CR2	Kind of file				
IMG_0008.CR2 IMG_0009.CR2 IMG_0010.CR2 IMG_0011.CR2	Image quality				
IMG_0012.CR2 IMG_0013.CR2 IMG_0014.CR2 IMG_0015.CR2	Output setting Output resolution 350 dpi VEmbed ICC profile				
IMG_0015.CR2	Resize Width Height: Unit Lock aspect ratio File name Current file name String Sequence number DPP				
	Execute				

- → The batch processing dialog box appears and saving begins.
- When all the images are saved, the [Exit] button appears in the batch processing dialog box.

In the processing dialog box, click the [Exit] button.

[Save] cannot be performed

In the [Batch settings] window, you cannot perform [Save] or [Save As] (p.38, p.102) to edited RAW images.

$^{4-}$ To save the developing/editing results for the version you are currently using

DPP's RAW image development processing technology is continually being improved upon so that you can perform the latest image processing more appropriately.

Meaning that, between two differing versions of DPP, processing results may differ very slightly even if with the same RAW image data, or the results of significant editing of RAW image data with an attached recipe may be different.

When you want to save the developing or editing results of the version you are currently using as it is, it is recommended that you convert and save images as JPEG image or TIFF images.

Skillful batch saving

 While saving is being performed, you can continue working in another window

Since the saving function operates independently in the background, you can continue with an operation in another window such as the main window or the edit window during the saving process.

 To convert all images and save, do not select an image in the main window

If you do not perform step 1 and perform step 2 with no image selected in the main window, all the images displayed in the main window will be converted and saved.

- If you have selected [New file name] in [File name], [Sequence number] has to be set.
 - By saving as explained on this page, a trimmed image (p.35, p.95) or dust-erased image (p.64 to p.68, p.98 to p.102) actually becomes a trimmed image or dust-erased image.
 - For a list of [Batch settings] window functions, refer to p.120.

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



Batch Transfer Images to Image Editing Software

You can transfer multiple images to image editing software. Unlike [Transferring a RAW Image to Photoshop] (p.68), you transfer images that have first been converted and saved as a seperate image, so the transferred image will not disappear after exiting the destination software. The software used here as an example is Adobe Photoshop CS.

- In the main window, select multiple images to be transferred.
- Click the [Batch process] button on the toolbar (p.107). → The [Batch settings] window appears.
- Perform settings required for transferring (e.g. file format).

Click the [Browse] button.

Batch settings	
IMG_0001.CR2 IMG_0002.CR2 IMG_0003.CR2 IMG_0005.CR2 IMG_0008.CR2 IMG_0008.CR2 IMG_0008.CR2 IMG_0008.CR2 IMG_0010.CR2 IMG_0011.CR2 IMG_0013.CR2 IMG_0013.CR2 IMG_0015.CR2	Save folder C:\Documents and Settings\:anon\My Documents\ Browse File format Kind of file Exit_JPEG Image quality 10 Output setting Output resolution 350 dpi Embed ICC profile Resize setting Current file name String Output file name String Sequence number DPP_ 0001 Save sequence number Ex: DPP_0001.JPG, DPP_0002.JPG Image transfer settings
	Open image using software Browse
1	Execute Cancel

- Select Photoshop CS.
- In the [Open] dialog box, select a Photoshop CS file or a shortcut and click the [Open] button.
- The [Open] dialog box closes and [Image transfer settings] in the [Batch settings] window is set to Photoshop CS.

Checkmark [Open image using software].

mage	transfer settings
☑	pen image using software
F:\P	rogram Files\Adobe\Photoshop CS\Photoshop.exe Browse
	Execute Cancel

Click the [Execute] button.

- → The processing dialog box appears and batch transfer begins
- When the first image has been transferred, Photoshop CS starts up and transferred images are displayed in transferred order.

	Introduction
ortcut	
in the	Contents at a Glance
	Basic Operation
	Advanced Operation
ins.	Advanced Image Editing and Printing
starts er.	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

→ The [Open] dialog box appears.


Batch Change the File Name of Images

1

In the main window, select multiple images of which the file names are to be changed.

Select the [Tools] menu ▶ [Start Rename tool]. → The rename window appears.

Specify the required settings (p.121) and click the [Execute] button.



→ Processing begins and the file names are changed.

? Changes cannot be made when the file name is duplicated

If a file name in red text has appeared in [Modified File Name], the file name has been duplicated. Changes cannot be made if even one file name has been duplicated. Change the settings so that duplication does not occur.

- You cannot start up the rename tool from the [Collection] window (p.33, p.108).
 - For a list of the rename window functions, refer to p.121.

Changing the File Name of Images in the Order in the Main Window

When you change the order of the images in the main window, you car change in one operation the names of the files for the images, in the order they were rearranged.

- Change the order of the images in the main window (p.19).
- In the main window, select multiple images of which the file names are to be changed.
- Select the [Tools] menu ▶ [Start Rename tool].

Select [Fit to main window].

C:\Documents and Settings\canon\My Do		
File name		
DPP	<	Shooting Date/
Basic Settings Sort Fit to main window File name Shooting Date/Time)	

Specify the required settings (p.121).

To copy an image, checkmark [Copy Rename].


Click the [Execute] button.

The file names are changed and the order in the main window is maintained.

w	
	Contents at a Glance
an	Basic Operation
v	Advanced Operation
h	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index



5 Editing JPEG and TIFF Images



DPP is software mainly aimed for advanced RAW image editing, but it also has JPEG and TIFF image editing functions. Here, the editing and saving of JPEG and TIFF images are explained.

Editing JPEG and TIFF Images
Automatically Adjusting Brightness and Color (Tone
Curve Assist)
Adjusting Brightness and Contrast
Adjusting Color Tone Using Click White Balance 90
Adjusting Hue, Saturation and Sharpness
Tone Curve Adjustment92
Adjusting Dynamic Range
Reducing Noise
Trimming and Adjusting the Angle of an Image 95
Performing Automatic Dust Erasure Processing 98
Compatible Cameras
Automatic Dust Erasure Processing in the Main
Window
Manually Erasing Dust (Repair Function) 100
Erasing Unwanted Parts of an Image (Copy Stamp
Function) 102
Saving Editing Results 102
Saving Editing Content to an Image 102
Saving as a Separate Image 103
Applying Editing Contents to Another Image 103
Printing 103
Re-Editing an Image 103



Editing JPEG and TIFF Images

With DPP, you can adjust JPEG and TIFF images in the same way as RAW images using the [RGB] and [NR/Lens/ALO] tool palettes. Because adjustment made with the tool palette (recipe) only changes the image processing conditions, the "original image data itself" remains unaffected. Therefore, there are no problems with image deterioration that arise with editing and you can readjust your images any number of times.




Image processing conditions information Image processing condition Image processing condition</td

(extension ".vrd") (p.80, p.103).

In DPP all the adjustments (image processing conditions information) made with the tool palette can be saved in the image as data called a "recipe" (p.102), or can be saved, downloaded and applied to other images as a separate recipe file (extension ".vrd") (p.80, p.103).

About the RGB Tool Palette

With the functions in the [RGB] tool palette, you can adjust JPEG and TIFF images with the same functions as ordinary image editing software.

However, because the adjustment width of the adjustment functions in the [RGB] tool palette is wider than the [RAW] tool palette, the image color may be saturated, or the image quality may deteriorate if you adjust too much. Therefore, take care not to adjust your images to an excessive degree.

You can adjust RAW images with the functions in the [RGB] tool palette However, for functions other than tone curve adjustment (p.92) and automatic adjustment (p.88), we recommend adjusting RAW images using the same functions available in the [RAW] tool palette.


d	Contents at a Glance
in	
י ר	Basic Operation
tte.	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index

Automatically Adjusting Brightness and Color (Tone Curve Assist)

In order to make the image a desirable standard image, automatically adjust the image tone curve (p.122). You can select the degree of automatic adjustment from "Standard" and "High".

Click the desired automatic adjustment button.

- **Standard:** Standard automatic adjustment. Suitable for most images.
- **High:** Use when the effect achieved in standard automatic adjustment is not strong enough.



Images not suitable for automatic adjustment (tone curve assist)

The result of automatic adjustment (tone curve assist) may not be as expected with the following images:

- Images which have been shot with the proper exposure
- Images where the brightness is unbalanced
- Images which are too dark
- Images which have extreme backlighting
- If you click the [25] button, the tone curve as well as the [Hue] and [Saturation] revert to the default settings. Take care when adjusting the [Hue] and [Saturation] individually (p.91).


S	Contents at a Glance
	Basic Operation
]	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEC/TIFF Images
	Reference
	Index

Introduction

→ The tone curve changes as adjusted.

Adjusting Brightness and Contrast


The brightness and contrast of an image can be adjusted.



Introduction • **Brightness:** Move the slider to the right to make an image brighter and to the left to make an image darker. Used to adjust modulation and degree of contrast Contrast: Contents at of color. Move the slider to the right to make a Glance contrast of an image stronger and to the left to make contrast weaker. Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editing JPEG/TIFF Images Reference Index

Adjusting Color Tone Using Click White Balance

You can adjust white balance using a selected part of an image as the standard for white to make the image appear natural. Using click white balance is effective when using it in parts of an image where white color tone has changed under the influence of a light source.



Click on a point that is to be the standard for white.



The coordinates of the cursor position and the RGB values (8-bit conversion)

- The color of the image is adjusted with the point you selected as the standard for white.
- If you click on another point in the image, the white balance is adjusted again.
- To finish click white balance, right-click with the mouse or click the [
] button again.

When there are no white areas in your image


When there are no white areas in your image, you can adjust the white balance by clicking on a grey point of the image in step 2. This has the same adjustment result as selecting a white point.

- The image is adjusted based on the average value of 5 x 5 pixel range from the clicked point.
 - The histogram display changes according to adjustment. You can also fix the histogram display to the display before any adjustments (p.76).

	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
S	Editing JPEG/TIFF Images
	Reference
	Index


Adjusting Hue, Saturation and Sharpness

You can adjust hue (tone) and saturation and make the overall atmosphere of an image harder or softer.



Drag the sliders left or right

- Hue: Move the slider to the right to make color tones more yellow, and to the left to make color tones redder.
- Saturation: Move the slider to the right to make the color deeper, and to the left to make the color weaker.
- Sharpness: Move the slider to the right to make an image harder, and to the left to make an image softer.



Sharpness is unnatural

Adjust sharpness with the window view set to [100% view], [50% view] or [200% view]. If the view is set to [Fit to window] (full view), the sharpness will seem unnatural.

The adjustment range is –30 to 30 for hue, 0 to 200 for saturation, and 0 to 500 for sharpness (in 1-stop increments when entering a value).

Tone Curve Adjustment


You can adjust the brightness, contrast and color of a specific area by changing the tone curve (p.122).

Right-click with the


to display the menu

mouse inside the graph

Select the tone curve mode and interpolation method.



Make adjustments.




also fix the histogram display to the display before any adjustments (p.76).
The tone curve mode and interpolation method for a tone curve

can also be changed in [Preferences] (p.76).

Adjusting Dynamic Range

Dynamic range (width of gradation expression) from dark points to bright points in an image can be adjusted.



- The setting range of shadow points is 0 to 247 (in 1-stop increments when entering a value).
- The setting range of highlight points is 8 to 255 (in 1-stop increments when entering a value).

=

 The histogram display changes according to adjustment. You can also fix the histogram display to the display before any adjustments (p.76).



• The horizontal axis shows the input level and the vertical axis shows the output level.

Reducing Noise

You can reduce noise that arises in JPEG and TIFF images that have been shot at night or with a high ISO speed.


Select the [NR/Lens/ALO] tab sheet from the tool palette in the edit window or edit image window.

Click the [NR Preview] button.

Noise reduction	Apply
	NR Preview
RAW	

→ The [NR Preview] window appears.

Adjust an image.




NR check window

- You can set a noise reduction level from within a range of 0 to 20. The larger the setting, the larger the noise reduction effect.
- The noise reduction effect can be checked when an image is displayed at 100% in the NR check window.
- You can change the display position of the NR check window by dragging the enlargement display position in the navigator window.

Click the [Apply] button.

Noise reduction is applied to the image and the image is redisplayed.





To set the same noise reduction level for several images

After selecting multiple images in the main window, you can set the same noise reduction level for the images without displaying the [NR Preview] window, by adjusting the noise reduction level in the [NR/Lens/ALO] tool palette (p.112) using the [Luminance noise reduction] and [Chrominance noise reduction] sliders, and then clicking the [Apply] button.

- If [Luminance noise reduction] has been set, resolution may be reduced along with reduction of noise.
 - If [Chrominance noise reduction] has been set, color bleeding may occur along with reduction of noise.
 - You can set the batch processing settings for noise reduction beforehand, using [Default noise reduction settings] in the [Tool palette] tab sheet in the [Preferences] (p.76). This is particularly useful for applying noise reduction to all the images in a folder at once, such as batch noise reduction for images with high ISO speeds. However, where images have a recipe attached, the noise level recorded in the recipe is applied.
 - For a list of [NR Preview] window functions, refer to p.113.

Introduction

Contents at

a Glance


Trimming and Adjusting the Angle of an Image

You can trim only the part of an image you need, or change the composition of an image where an image shot horizontally becomes vertical. You can also adjust the angle of an image before trimming. When aspect ratio information is attached to an image shot with EOS-1D Mark IV, EOS-1Ds Mark III, EOS-1D Mark III or EOS 7D, the trimming range based on the aspect ratio information is displayed.

Select the image to be trimmed.

- Open the trimming/angle adjustment window.
- Select the [Tools] menu ▶ [Start Trimming/Angle Adjustment tool].
- → The trimming/angle adjustment window appears.
- → Editing can be done once the trimming/angle adjustment window has reached a clear display.

- Adjust the angle of the image as needed.
 - Trimming/angle adjustment window



Contents at a Glance Basic Operation

Introduction

Advanced Operation

Advanced Image Editing and Printing

Processing

Large Numbers

of Images

Editing

JPEG/TIFF Images

Reference


Index

Drag* (0.01-degree increments; adjustment range: -45 to +45 degrees)

Use the mouse (click $\blacktriangle/ \bigtriangledown$) to adjust the angle or directly enter the adjustment angle* (0.01-degree increments; adjustable range: -45 to +45 degrees)

- * You cannot adjust the angle of images that exceed 6666 x 4444 pixels in size.
- If you click [Center on Screen], you can display the trimming range in the center of the window.
- If you click the [OK] button after adjusting only the angle of the image, the image will be trimmed at the largest possible trimming range.






Select a ratio and drag the trimming range.

Click the [OK] button to return to the main window.

- The trimming range frame is displayed in the trimmed image (p.109).
- When the trimmed image is displayed in an edit window or the edit image window, it is displayed in its trimmed form.



Introduction

- The trimming range can be moved by dragging.
- You can enlarge or reduce the size of the trimming range by dragging the four corners of the trimming range.
- List of aspect ratios (width : height)

Free
1:1
3:2
2:3
4:3
3:4
5:4
4:5
A Size Landscape
A Size Portrait
Letter Landscape
Letter Portrait
Custom
[Erool: Vou con trim

[Free]: You can trim an image to any size, regardless of the selectable ratio.

[Custom]: You can trim an image at the specified ratio.

Advanced Operation

Introduction

Contents at

a Glance

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index

About trimmed images

 The trimmed range can be reverted to its original condition at any time

A trimmed image is displayed or printed as a trimmed image. However, since the image is not actually trimmed, you can always revert to the original image by clicking the [Reset] button in the trimming/angle adjustment window or performing the "Re-Editing an Image" procedure (p.103).

Display of the trimmed image in each window

- Main window: The frame showing the trimming range is displayed on the image (p.109).
- Edit window: The image is displayed in its trimmed condition.
- Edit image window: The thumbnail image is the same as the main window display, and the enlarged image is the same as the edit window display.

Printing a trimmed image

You can print as a trimmed image by printing it in DPP.

The image becomes a trimmed image when saved as a separate image

The trimmed JPEG or TIFF image actually becomes a trimmed image when saved as a separate image (p.103).

Images that have aspect ratio set will be displayed as trimmed images

When aspect ratio information is attached to an image shot with EOS-1D Mark IV, EOS-1Ds Mark III, EOS-1D Mark III or EOS 7D, the set trimming range based on the aspect ratio information is displayed. However, since the image is not actually trimmed, you can change the trimming range or revert to the condition before trimming. When reverting to the condition before trimming is performed based on the aspect ratio information at the time of shooting, click the [Reset] button. Also, if you want to cancel all the trimming range, click the [Clear] button (p.117).

- Convenient functions of the trimming/angle adjustment window
- Switch between screens using the keyboard

You can also switch between full screen display/normal screen display by pressing the <Alt> + <Enter> keys or the <F11> key.

Operate using the menu

Each operation can also be performed with the menu which appears when you right-click with the mouse on the image.

Apply the trimmed range to another image

You can apply the trimmed range to another image by clicking the [Copy] button to copy the trimmed range, displaying another image and then clicking the [Paste] button.

To batch apply a copied trimming range to multiple images, select the trimmed image and the multiple images to which you want to apply the trimmed range in the main window, and display the trimming/ angle adjustment window. With the trimmed image displayed, click the [Copy] button and then click the [Apply All] button. This will apply the trimming range to all the images selected when the trimming/ angle adjustment window is displayed.

- For images shot with ISO speed range expansion set, noticeable noise may make it difficult to view image details in the trimming/ angle adjustment window, so using this function is not recommended.
- For a list of the trimming/angle adjustment window functions, refer to p.117.

Performing Automatic Dust Erasure Processing


The Dust Delete Data that is appended to images shot with the camera that can attach this data, can be used to automatically erase dust spots.

Compatible Cameras

EOS-1D Mark IV	EOS-1Ds Mark III	EOS-1D Mark III
EOS 5D Mark II	EOS 7D	EOS 50D
EOS 40D	EOS REBEL T2i/550D	EOS REBEL T1i/500D
EOS DIGITAL REBEL XSi/450D	EOS DIGITAL REBEL XTi/400D DIGITAL	

- In the main window, select an image appended with Dust Delete Data.
- Select the [Tools] menu ▶ [Start Stamp tool]. → The copy stamp window appears.

When the image has redrawn itself, click the [Apply Dust Delete Data] button.



→ Dust spots are erased in a single operation.

Click the [OK] button to return to the main window.

The [] mark (p.109) is displayed on an image from which dus spots have been erased.

ply	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
w.	Processing Large Numbers of Images
dust	Editing JPEC/TIFF Images
	Reference
	Index
	${}^{(2)}$

Contents at a Glance

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

> Editing JPEG/TIFF Images

Reference

Index



Additional Information

The dust-erased image can be reverted to its original condition at any time

A dust-erased image is displayed or printed as a dust-erased image. However, since the dust on the image is not actually erased, you can always revert to the original image by clicking the [Undo] button in the copy stamp window or performing the "Re-Editing an Image" procedure (p.103).

Check dust erasure in the copy stamp window

Check dust erasure in the copy stamp window. Images before dust erasure are displayed in other windows and you will be unable to check them.

Printing dust-erased images

You can print as a dust-erased image by printing it in DPP.

The [Apply Dust Delete Data] button cannot be clicked

Even with an image that has Dust Delete Data attached to it in the camera, if there is no dust to remove by DPP from the image, the [Apply Dust Delete Data] button will be disabled.

• To erase dust spots that cannot be erased with the automatic dust erasure processing

In automatic dust erasure processing, dust spots are erased based on information relating to dust saved in the Dust Delete Data. However, there may be cases where you will not be able to erase dust spots depending on the type of dust. If this occurs, erase those dust spots using the repair function (p.100) or the copy stamp function (p.102).

The image becomes a dust-erased image when saved as a separate image

The dust-erased JPEG or TIFF image actually becomes a dusterased image when saved as a separate image (p.103).

Useful functions of the copy stamp window

Checking the dust erased spots

After step 3, you can display and check in detail the erased dust spots one by one by pressing the <Shift> + <F> keys. (Press the <Shift> + keys to return to the previous dust spot.)

Canceling a specified erased dust spot only After step 3, you can press the <Shift> + <F> keys or the <Shift> + keys to display the erased dust spot, and then press the <Shift> + keys to cancel only the erased dust spot displayed.

Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the <Alt> + <Enter> keys.

Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

For a list of the copy stamp window functions, refer to p.119.

Automatic Dust Erasure Processing in the Main Window

In the main window, you can also automatically erase dust spots in multiple images appended with Dust Delete Data.


Select multiple images appended with Dust Delete Data, and then select the [Adjustment] menu > [Apply Dust Delete Data].

→ Dust spots in all the selected images are erased in a single operation.

Manually Erasing Dust (Repair Function)

You can erase dust spots in an image by selecting them one by one.

- In the main window, select the image you want to erase dust spots.
- Select the [Tools] menu ▶ [Start Stamp tool].
- → The copy stamp window appears.
- When the image has redrawn itself, double-click the point from where dust is to be erased.




- → The display changes to 100% view.
- The display position can be changed by dragging.

Click the button that matches the dust spots to be erased.

- If the dust spot is dark in color, click the [...] button, and if the dust spot is light in color, click the [...] button.
- When you move the cursor over the image, the dust erasure range appears as [O].

Place the dust spot to be erased within the $[\bigcirc]$ an click.



- → The dust spot within the [O] is erased.
- Click on another part of the image to continue erasing dust spots in the image.
- To erase dust in another part of the image, either right-click with the mouse, or click the button clicked in step 4 again to cancel dus erasure processing and perform the operation again from step 3.
- When the dust spot cannot be erased, [S] is displayed.

Click the [OK] button to return to the main window.

→ The [] mark (p.109) is displayed on an image from which dust spots have been erased.

nd	Introduction
	Contents at a Glance
	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
spots	Processing Large Numbers of Images
vith I dust əp 3.	Editing JPEG/TIFF Images
)W. n dust	Reference
	Index

Advanced Image Editing and Printing

Introduction

Contents at

a Glance

Basic

Operation

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



Additional information

- Click several times when dust spots are not erased completely Where unwanted dust spots are not erased even after performing step 5 once, they may be erased completely when you click several times.
- Mainly spots of dust can be erased with the repair function Spots of dust can be erased with the repair function. You may be unable to erase lines of dust. In this case, use the copy stamp function (p.102).
- The dust-erased image can be reverted to its original condition at any time

A dust-erased image is displayed or printed as a dust-erased image. However, since the dust on the image is not actually erased, you can always revert to the original image by clicking the [Undo] button in the copy stamp window or performing the "Re-Editing an Image" procedure (p.103).

Check dust erasure in the copy stamp window

Check dust erasure in the copy stamp window. Images before dust erasure are displayed in other windows and you will be unable to check them.

Printing dust-erased images

You can print as a dust-erased image by printing it in DPP.

 The image becomes a dust-erased image when saved as a separate image

The dust-erased JPEG or TIFF image actually becomes a dusterased image when saved as a separate image (p.103).

Useful functions of the copy stamp window

Checking the dust erased spots

After step 5, you can display and check in detail the erased dust spots one by one by pressing the \langle Shift> + \langle F> keys. (Press the \langle Shift> + \langle B> keys to return to the previous dust spot.)

Canceling a specified erased dust spot only
 After step 5, you can press the <Shift> + <F> keys or the <Shift> +
 keys to display the erased dust spot, and then press the <Shift> +
 + keys to cancel only the erased dust spot displayed.

 Switch between full screen display/normal screen display using shortcut keys

You can also switch between full screen display/normal screen display by pressing the <Alt> + <Enter> keys.

Applying the dust erasure result to another image

You can apply dust erasure to the same place in another image by clicking the [Copy] button to copy the dust erasure results and then displaying the other image to which you want to apply the results and clicking the [Paste] button.

To apply dust erasure to the same place in several other images, you can efficiently erase dust spots by clicking the images while holding down the <Ctrl> key in the main window, or, by selecting multiple images by clicking the first image and then clicking the last image while holding down the <Shift> key, and then displaying the copy stamp window.

For images shot with ISO speed range expansion set, noticeable noise may make it difficult to view dust spots in the copy stamp window, so using this function is not recommended.

a Glance

Contents at

Introduction

Basic Operation

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

Editing JPEG/TIFF Images

Reference

Index



Erasing Unwanted Parts of an Image (Copy Stamp Function)

You can correct an image by pasting a section copied from another part of the image to an unwanted part of the image.

Follow steps 1 to 3 in "Manually Erasing Dust (Repair Function)" (p.100).

Specify the section to be copied.

- Click on the section that is to be the copy source while holding down the <Alt> key.
- To change the section that is to be the copy source, perform the operation above again.
- To fix the position of the copy source, checkmark [Fix Copy Source position].

Correct the image.

- Click or drag on the section you want to correct on the image. [+] in the window indicates the copy source and [O] indicates the copy destination.
- The copied image is pasted in the position to which it was dragged.
- For [Pen type], you can select from [Brush] (the pasted image's borders simulate a brush) and [Pencil] (the pasted image's borders are sharp).

Click the [OK] button to return to the main window.

 \rightarrow The [] mark (p.109) is displayed on a corrected image.

Saving Editing Results

Saving Editing Content to an Image

All the contents (recipe) adjusted with the tool palette (p.87 to p.94) as well as the trimmed range (p.95) and dust-erasure (p.98 to p.102)information can be saved to a JPEG or TIFF image, or to a separate JPEG or TIFF image.

Eile	
Open in Edit window	Ctrl+O
Open in Edit window (enlarged)	
Save	Ctrl+S
Save As	Ctrl+Shift+S
Add thumbnail to image and save	Ctrl+Shift+T
Convert and save	Ctrl+D
Batch process	Ctrl+B
Create new folder	
Print	Ctrl+P
Print with detailed setting	Ctrl+Alt+P
Contact Sheet Prints	Ctrl+Shift+P
Plug-in printing	•
Add to collection	Ctrl+G
Remove from collection	Ctrl+Shift+G
Clear collection	
Delete	Del
Info	Ctrl+I
Exit	Alt+F4

→ Your adjustments are saved to the image.

Select the [File] menu ▶ desired item.

Saving as a Separate Image

If a JPEG or TIFF image is adjusted with the tool palette (p.87 to p.94) and then saved in the same way as a RAW image as described below, the image can be saved as a separate image with the adjustments (recipe) applied to it.

Furthermore, if a trimmed image (p.95) or dust-erased image (p.98 to p.102) is also saved in the same way, it actually becomes a trimmed or dust-erased image.

Saving as a JPEG or TIFF Image (p.39)

Batch save as JPEG or TIFF images (batch processing) (p.83)

By saving as a separate JPEG or TIFF image as explained above, the adjustments made with the tool palette are applied, and some image deterioration that accompanies editing/saving occurs as when editing with ordinary image editing software.

Applying Editing Contents to Another Image

You can copy the adjustment contents (recipe) of JPEG and TIFF images that have been adjusted with the tool palette and apply them to another image with the procedures below, in the same way as with RAW images.

- Applying adjustment contents to another image (p.38)
- Utilizing adjustment contents (recipe) (p.80)

Printing

Edited JPEG and TIFF images can be printed with the procedures below as with RAW images.

- Printing (p.40)
- Printing with shooting information (p.69)
- Printing a thumbnail list (contact sheet printing) (p.70)
- Printing RAW images on a high-end Canon printer (p.71)

Re-Editing an Image

Only the image processing conditions are changed in images adjusted with the tool palette (p.87 to p.94), so the "original image data itself" remains unaffected. Also, the trimming range or dust-erasure information of a trimmed image (p.95) or dust-erased image (p.98 to p.102) is simply saved to the image.

For this reason, you can undo any adjustments saved (p.102) to the image, trimming range and dust-erasure information, and revert to the condition when last saved, or when the image was shot.

Select the image that is to be re-edited.

Select the [Adjustment] menu > desired item.

Adjustment Rotate Left


Rotate Left	Ctrl+L
Rotate Right	Ctrl+R
Add check mark1	Alt+1
Add check mark2	Alt+2
Add check mark3	Alt+3
Remove check mark	Alt+Z
Apply Dust Delete Data	
Work color space	•
Tone Curve Assist - Standard Tone Curve Assist - High	
Revert to last saved settings	Ctrl+Alt+Z
Revert to shot settings	Ctrl+Shift+Z

→ The image reverts to the conditions of the selected item.

ted	Introduction
)	Contents at a Glance
he	Basic Operation
	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index



Reference



This reference section has been provided to enhance your experience using DPP.

It contains various troubleshooting solutions, how to delete DPP from your computer, explanations of the various windows and a glossary. An Index is provided at the end of the chapter for you to easily find information you are looking for.

Troubleshooting 105		
-		
Deleting the Software (Uninstalling) 106		
List of Main Window (Folder Window) Functions 107		
List of Main Window (Collection Window) Functions 108		
Image Frame Information in the Main Window and Edit		
Image Window 109		
List of Edit Window Functions 110		
List of Tool Palette Functions 111		
List of NR Preview Window Functions 113		
List of Quick Check Window Functions 114		
List of Edit Image Window Functions 115		
List of Convert/Save One Image Window Functions 116		
List of Trimming/Angle Adjustment Window Functions 117		
List of Lens Aberration Correction Window Functions 118		
List of Copy Stamp Window Functions 119		
List of Convert/Save Multiple Images Window (Batch		
Processing) Functions 120		
List of Rename Window Functions 121		
Glossary 122		
Index 124		
About This Instruction Manual 128		
Trademark Acknowledgments 128		

Advanced Operation Advanced Image Editing and Printing Processing Large Numbers of Images

Introduction

Contents at a Glance

Basic Operation

Editing JPEG/TIFF Images

Reference

Index

104

Troubleshooting

If DPP is not operating correctly, refer to the items below.

Installation could not be completed correctly

 You cannot install the software if a user setting other than [Computer administrator] privilege or [Administrator] privilege is selected. Select the [Computer administrator] privilege user setting in Windows XP or the [Administrator] privilege user setting in Windows 7/Windows Vista. For detailed information on selecting the user setting, refer to your computer User's Manual.

DPP does not work

- DPP does not operate correctly on a computer if its system requirements does not meet. Use DPP on a computer with compatible system requirements (p.3).
- Even if your computer has the RAM capacity (memory) described in the system requirements (p.3), if other applications are running at the same time as DPP, you may not have sufficient RAM (memory). Exit any applications other than DPP.

The card reader does not detect the SD card.

 Depending on the card reader and computer OS used, SDXC cards might not be correctly detected. In such a case, connect your camera and computer with the provided interface cable, and transfer the images to your computer using EOS Utility (provided software).

Images do not display properly

- Images that are not supported by DPP do not display. There are various types of JPEG and TIFF images, so JPEG images other than Exif 2.2 and 2.21 compatible images and TIFF images other than Exif compatible images may not display properly (p.3).
- When a dust-erased image (p.64 to p.68, p.98 to p.102) is displayed in a window other than the copy stamp window, it is displayed as it was before dust erasure was performed. Check dust-erased images in the copy stamp window.

An image could not be adjusted

- The JPEG and TIFF images cannot be adjusted using the image adjustment function of the [RAW] tool palette. Adjust these images with the [RGB] tool palette (p.111).
- PowerShot Pro1 RAW images cannot be adjusted with the image adjustment function of the [RAW] tool palette. Adjust these images with the [RGB] tool palette (p.111).

A recipe could not be pasted (applied) to another image

- You cannot paste (apply) rotation (p.10, p.23, p.107, p.114, p.115), trimming (p.35, p.95), dust erasure (copy stamp) (p.64 to p.68, p.98 to p.102) of an image to another image as a recipe. Trim the image or erase dust of the image using the copy/paste function in each window and rotate each image individually.
- The adjustment contents (recipe) of RAW images that has been adjusted with the [RAW] tool palette cannot be applied to JPEG or TIFF images (p.111).
- The Auto Lighting Optimizer (p.58) is a function that is only available for RAW images shot with EOS-1D Mark IV, EOS 5D Mark II, EOS 7D, EOS 50D, EOS REBEL T2i/550D and EOS REBEL T1i/500D. You cannot apply the Auto Lighting Optimizer's adjustment contents to RAW images shot with other cameras.

Color appears weak in the image when viewed with other software

A RAW image which has a color space other than sRGB set (p.68, p.77) and is then converted and saved as a JPEG or TIFF image will appear weak in color when viewed in software that is only compatible with sRGB color space. In this case, set the RAW image color space to sRGB, convert again to a JPEG or TIFF image and save, and then view this image.

Introduction

Contents at

a Glance

Basic

Operation

Advanced

Processing Large Numbers

of Images

Image Editing

and Printing

Editing JPEG/TIFF Images

Reference

Index



The colors of the image displayed on screen and the colors of the printed image do not match

- If the color of the monitor that displays an image is not adjusted correctly, or if a profile for a printer that is to print images, has not been set up, the color of the image displayed on screen and the color of the printed photograph may differ greatly. If the color of the monitor that displays images is corrected (p.77) and a profile for a printer is set up correctly (p.77), the color of a printed photograph and the color of an image on screen can be more closely matched. Using a Canon printer (p.40, p.43) or linked printing (p.71, p.72) automatically sets up printer profiles, so you only need to set the color of the monitor to bring the colors closer together.
- When printing using Easy-PhotoPrint and the Easy-PhotoPrint automatic compensation function and the various types of image adjustment functions are operating, colors are not printed correctly. Cancel all Easy-PhotoPrint image adjustment functions (p.44).
- Even if you set a printer profile, if you use the color adjustment function of the printer driver, the image may print in colors different from those displayed on screen. Do not use the color adjustment function of the printer driver.

Printing a large number of images in batches cannot be performed

 If a large number of images are printed in batches, printing may stop in the middle or the images may not be printed. Reduce the number of images to print or increase the memory on your computer.

A file remains in the folder after images are deleted

- Delete [CRW_YYYY.THM] (camera index display image) if it remains in the folder from which images have been deleted (p.46).
 - * Numbers are entered for [YYYY] in the file name.


The image information does not display

• A JPEG image set to Adobe RGB and shot with EOS 10D, EOS DIGITAL REBEL/300D DIGITAL and PowerShot Pro1 may not display image information (p.10, p.21).

Deleting the Software (Uninstalling)

- Exit any applications before uninstalling the software.
- Log in under the Computer administrator/Administrator privileges when uninstalling the software.
- To prevent computer malfunctions, always restart your computer after you have uninstalled the software. Re-installing the software without first restarting your computer is particularly likely to result in computer malfunctions.
- Select the [Start] button ([<a>[]] button in Windows 7/ Windows Vista) ▶ [All Programs] ▶ [Canon Utilities] ▶ [Digital Photo Professional] ▶ [Digital Photo Professional Uninstall].
- Proceed with the uninstallation as directed by the on-screen messages.
 - → The software is uninstalled.






- *1 To switch between show/hide, select the [View] menu ▶ [Toolbar].
- *² The images inside the folders selected here are displayed in a thumbnail list on the right.
- *³ Displays the coordinates of the cursor position and the RGB values (8-bit conversion) when click white balance was performed with the tool palette.
- [Preferences] window is displayed.*5 You can switch between the [Folder] and [Collection] windows.

*4 The item selected in [Viewing and saving RAW images] (p.73) of the


List of Main Window (Collection Window) Functions (p.33)



- *1 The total number of images added to the [Collection] window is displayed in the () in the [Collection] tab sheet. Accordingly, when an image is added that is displayed as a single image (p.20), twice the total number of displayed images is displayed.
- *2 Displays the coordinates of the cursor position and the RGB values (8bit conversion) when click white balance was performed with the tool palette.

Image Frame Information in the Main Window and Edit Image Window (p.10, p.31)

Information displayed when [Large thumbnail] (p.10) is selected





- *1 Does not display with [Small thumbnail].
- *2 Displays in RAW+JPEG images displayed as a single image (p.20). [RAW] is displayed in RAW images.
 - (In [Small thumbnail] (p.10), [R] is displayed.)
 - In PowerShot Pro1 RAW images, [RAW] is not displayed.
- *3 Does not display with [Medium thumbnail] or [Small thumbnail].

- *4 Displays in an image edited with the [RAW] tool palette in the edit window and the edit image window.
- *5 Displays in an image edited with the [RGB] tool palette in the edit window and the edit image window.
- *6 When aspect ratio information is attached to an image shot with EOS-1D Mark IV, EOS-1Ds Mark III, EOS-1D Mark III or EOS 7D, the image is displayed as a trimmed image.

List of Edit Window Functions (p.11, p.23)

Path and file name of image






Introduction Contents at a Glance Basic Operation Advanced Operation Advanced **Image Editing** and Printing Processing Large Numbers of Images Editing JPEG/TIFF Images Reference Index

- *1 To switch between show/hide, select the [View] menu ▶ [Tool palette].
 *2 Displays the coordinates of the cursor position and the RGB values (8bit conversion).
- *³ RAW images are displayed with [RAW].


*4 The item selected in [Viewing and saving RAW images] (p.73) of the [Preferences] window is displayed.

List of Tool Palette Functions

RAW Tool Palette (p.23)




RGB Tool Palette (p.57)



* If an image is displayed enlarged, the enlargement display position can be moved by dragging. The enlargement display position appears when [Docking display] (p.76) has been set and the edit image window (p.115) has been enlarged.

NR/Lens/ALO Tool Palette

(When a RAW image is selected)




Auto Lighting Optimizer (p.58) Apply noise reduction button (p.59) Displays the [NR Preview] window (p.94, p.113) Luminance noise reduction for RAW images (p.59) Chrominance noise reduction for RAW images (p.59)

button (p.62)


Lens aberration correction (p.62)

Enlargement display position*



 If an image is displayed enlarged, the enlargement display position can be moved by dragging. The enlargement display position appears when [Docking display] (p.76) has been set and the edit image window (p.115) has been enlarged.


List of NR Preview Window Functions (p.59, p.94)



* When you select a JPEG or TIFF image and display the [NR Preview] window, [TIFF/JPEG] appears and you can reduce luminance noise and chrominance noise for the JPEG and TIFF images.


Index

List of Quick Check Window Functions (p.16, p.17)




- *1 You can select 50% view/100% view (moiré reduction off) by selecting [Preferences] in the [Tools] menu and using [Quick check tool display] in the [View settings] tab sheet. You can also move the display position in the enlarged display by dragging the image.
- $*^2$ To return to the normal screen, press the <Esc> key.

List of Edit Image Window Functions (p.31, p.33)



- *2 Displays the coordinates of the cursor position and the RGB values (8-bit conversion).
- *3 Displays images selected in the main window. The image selected here is enlarged and displayed on the right.
- *4 You can set the grid spacing with [Grid pitch] in the [Preferences] (p.75).
- *5 The item selected in [Viewing and saving RAW images] (p.73) of the [Preferences] window is displayed.



*2 Color space (p.68, p.77) information that is set in an image is attached to an ICC profile.

Even if you remove the check mark from images that have been set to Apple RGB, ColorMatch RGB or Wide Gamut RGB color space (p.68, p.77), the ICC profiles are embedded automatically.

*3 The setting range is 1 to 10. The higher the numerical value, the higher the image quality becomes.

*4 The larger of the two values set in [Width] and [Height] is applied to the longer edge of an image and change its size.

List of Trimming/Angle Adjustment Window Functions (p.35, p.95) Introduction Cancels all the trimming (aspect ratio) information 1/15 C:¥Documents and Settings¥canon¥My Documents¥My Pictures¥Photo¥xxxx xx xx¥IMG 0001.CR2 Contents at Full screen display/returns to normal screen Full screen a Glance Reverts to the condition when the image was shot Clear Reset Aspect ratio Basic Ratio of trimming range (you can also enter Operation numerical values if you have selected [Custom])*1 Upper left coordinates of trimmed range (you 704 362 can also enter numerical values) Height Advanced 1577 x 1051 Size of trimmed range (you can also enter Operation numerical values)

Angle

Rotate left

CODV

Y Show borders

Opacity

Show Grid

Grid pitch

∩k

it to another image*2

Center on Screen

Cancel

Copies the trimmed range and applies (pastes)

10.10 🔶

Rotate right

*1 If [Free] has been selected in the [Aspect ratio] list box, you can also drag the borders of the trimmed range to change its range.
 Image rotation (90-degree increments)
 *2 Operates when you have select angle adjustment window is displayed by the select of the trimmed range to change its range.

Trimming range

704. $362 \rightarrow (2281, 1413) = (1577 \times 1051) [1.50]$

*² Operates when you have selected multiple images and the trimming/ angle adjustment window is displayed.

Angle of image adjusted

Shows/hides arid lines

images*2

window

numerical values to set angle)

(Drag bar, use the mouse to click \blacktriangle/∇ or enter

Applies the copied trimming range to all other

Switches between displayed images*2

Displays borders around a trimmed range

Level of opacity outside a trimmed range

(Drag bar to set distance between grid lines)

Displays the trimming range in the center of the

Index




Advanced

Image Editing and Printing

Processing

Large Numbers of Images


Editina



*1 The area you clicked on the image (Enlargement display position) is displayed at 200%.
 *2 For RAW images shot with MP-E 65mm f/2.8 1-5x Macro Photo or EF 50mm f/2.5 Compact

Macro with Life Size Converter EF, the slider indicator changes to the zoom magnification.

List of Copy Stamp Window Functions (p.64 to p.68, p.98 to p.102)



Operates when you have selected multiple images and the copy stamp window is displayed.

List of Convert/Save Multiple Images Window (Batch Processing) Functions (p.83)

	Batch settings			
File names of images to be —	IMG_0001.CR2 IMG_0002.CR2	Save folder	—— Save destination	Contents at a Glance
batch saved	IMG_0003.CR2 IMG_0004.CR2	C:\Documents and Settings\canon\My Documents\ Browse		
	IMG_0005.CR2 IMG_0007.CR2	File format	Turner of language	
	IMG_0008.CR2	Kind of file	Types of image	Basic Operation
	IMG_0009.CR2 IMG_0010.CR2	Image quality 0 10	Type of image Extension	operation
Embeds ICC profiles*2 (p.122) -	IMG_0011.CR2 IMG_0012.CR2	Output setting	Exif-JPEG .JPG	
Resolution*1	IMG_0013.CR2 IMG_0014.CR2	Output resolution 350 dpi 🗹 Embed ICC profile	Exif-TIFF 8bit .TIF	Advanced
Resolution	IMG_0015.CR2	Resize setting	TIFF 16bit .TIF	Operation
		☐Resize Width Height Unit	Exif-Tiff 8bit+Exif-JPEG .TIF/.JPG	
Size changing*4		x pixel 🗸	TIFF 16bit+Exif-JPEG .TIF/.JPG	Advanced
				Image Editing
		✓ Lock aspect ratio		and Printing
		File name O Current file name	└───JPEG compression rate* ³	Broossing
		String		Processing Large Numbers of Images
				of Images
		 New file name String Sequence number 	—— File name	
		DPP_ 0001		Editing JPEG/TIFF
		Save sequence number		Images
		Ex.: DPP_0001.JPG, DPP_0002.JPG		
		Image transfer settings Open image using software	Potch transfer to other image editing	Reference
		Browse	 Batch transfer to other image editing software (p.84) 	
		Browse	N /	
Images to be converted are —		Convert RAW images only Execute Cancel	—— Save	Index
limited to RAW images*5				


- *1 The setting range is 1 to 60,000 dpi.
- *2 Color space (p.68, p.77) information that is set in an image is attached to an ICC profile.

Even if you remove the check mark from images that have been set to Apple RGB, ColorMatch RGB or Wide Gamut RGB color space (p.68, p.77), the ICC profiles are embedded automatically.

- *³ The setting range is 1 to 10. The higher the numerical value, the higher the image quality becomes.
- *4 The larger of the two values set in [Width] and [Height] is applied to the longer edge of an image and change its size.
- *5 Appears when you click the [Batch process] button (p.107, p.115) without an image selected in the main window or the edit image window. To convert RAW images only, instead of clicking the [Execute] button, click this button.

5

List of Rename Window Functions (p.85)



Reference

Introduction



Glossary RAW image

EOS DIGITAL camera RAW images are recorded in an uncompressed 14bit or 12bit format.

Because RAW images are special images in an undeveloped status, you need software with development processing functions such as DPP in order to view them. The advantage of the undeveloped RAW images is that you can make a variety of adjustments to RAW images with almost no deterioration of the image.

* "RAW" meaning "in a natural condition" or "not processed or refined".

JPEG image

The most ordinary image in non-reversible compressed 8bit format. The advantage of this is that by saving at a high compression rate, the file size can be small, even for image data that has a high pixel count. Because during saving and compression part of the data is thinned out to make the file size small, every time you edit or save, the image deteriorates.

With DPP, even if you repeat editing/saving, only the recipe data is modified, and no overwriting or compression occurs so the original image data does not deteriorate.

* JPEG is an abbreviation of "Joint Photographic Experts Group".

TIFF image

Bitmap-format image recorded in a 8bit/16bit uncompressed format. Because TIFF images are in uncompressed format, they are suitable for saving an image while maintaining the original high image quality. * TIFF is an abbreviation of "Tagged Image File Format".

Recipe

The "Image processing conditions information" for RAW images that can be edited in DPP is called a "recipe".

Further, in DPP, you can perform image editing on JPEG and TIFF images that use "recipes" as with RAW images.

bit number

Binary unit of information volume in the color of an image. The number shows the number of bits per pixel.

The larger the number of bits, the more the color numbers and the gradation becomes smoother. A one-bit image is a black-and-white image.

Color Management System (Color Matching)

Digital cameras that shoot images, monitors that display images, and printers that print images each have a different way of creating color. For this reason, there may be a difference between the color of an image when viewed on a monitor and when printed.

A color management system is a system for managing color in order to bring these colors closer together. With DPP, you can more closely match color between different devices using ICC profiles between different devices.

ICC profiles

ICC profiles are files containing color information such as color characteristics and color space for various devices, set by the ICC (International Color Consortium). Most devices such as the monitor we use to view images or the printer we use to print images can be managed (color management) using these ICC profiles and the color between different devices can be more closely matched. DPP has color management that uses these ICC profiles.

Tone Curve

A tone curve shows values before adjustment (input) as the horizontal axis on a graph, and the values after adjustment (output) as the vertical axis. Since the values of before adjustment and after adjustment are the same before any adjustment is made, the tone curve displays as a straight line from bottom left to top right, and by changing this tone curve, you can adjust in detail the image's brightness, contrast and color. The more you go right on the horizontal axis, the more the plus value it becomes, and the higher you go on the vertical axis, the more the plus value it becomes. a Glance Basic Operation

Introduction

Contents at

Advanced Operation

Advanced Image Editing and Printing

Processing Large Numbers of Images

> Editing JPEG/TIFF Images

Reference



Color space

0.8

A color space is the reproducible color range (color gamut


characteristics). DPP supports the following five kinds of color space.

- sRGB :Standard color space for Windows. Widely used for
the standard color space of monitors, digital
cameras, and scanners.Adobe RGB :A wider color space than sRGB. Mainly used for
printing for business purposes.
- Apple RGB :Standard color space for Macintosh. A slightly
wider color space than sRGB.
- **ColorMatch RGB** : A slightly wider color space than sRGB. Mainly used for printing for business purposes.

Wide Gamut RGB : A wider color space than Adobe RGB.

Refer to the color chart below for the color area of each color space.

Color chart of color spaces compatible with DPP



CMYK simulation profiles

A profile that simulates colors when printing in a CMYK environment (printing machine, etc.). With DPP, you can simulate color with four types of profile.

Euro Standard :	Profile normally used for book printing in
	Europe, suitable for simulation of standard
	European printing.
JMPA :	Profile normally used for book printing, etc. in
	Japan, suitable for simulation of magazine
	advertising standard color printing.
U.S.Web Coated :	Profile normally used for book printing in
	North America, suitable for simulation of
	North American standard printing.
JapanColor2001 type3	: Profile becoming a standard in the Japanese
	printing industry, suitable for simulation of
	JapanColor standard printing.

Rendering intent

Rendering intents are color conversion methods when printing an image. The conversion method of each rendering intent is shown below.

Perceptual : Before and after conversion, all colors are converted to maintain the relationship between colors. Even where colors slightly change, you can print a natural-looking image which has maintained color harmony. However, depending on the image, the saturation may change overall.

Relative Colorimetric : There will not be much conversion to colors which are similar before and after conversion, but colors which are not similar are converted appropriately. Because there are little changes to similar colors which comprise most of an image, you can print a natural-looking image in which the saturation has not changed greatly. However, depending on the image, there are cases where the overall tone of an image changes somewhat as colors which are not similar and highlights change. Operation Advanced Image Editing and Printing Processing Large Numbers

Introduction

Contents at

a Glance

Basic

Operation

Advanced

Editing JPEG/TIFF Images

of Images

Reference



Index

Α	
Adjust JPEG Images	
Adjust RAW Images	
Adjust TIFF Images	
Adjusting (JPEG or TIFF Image)	
Automatic Adjustment (Tone Curve Assist)	
Brightness	
Click White Balance	
Contrast	
Dynamic Range	
Hue	
RGB Tool Palette 111	
Saturation	
Sharpness	
Tone Curve Adjustment	
Adjusting (RAW image)	
Apply Adjustments	
Automatic Adjustment (Tone Curve Assist)	
Brightness 24	
Brightness of Highlights 54	
Brightness of Shadows 54	
Click White Balance 26	
Color Saturation	
Color Temperature	
Color Tone	
Color Wheel	
Contrast	
Copy Adjustments	
Dynamic Range	
Filter Effect	
Monochrome	
Personal White Balance	
Picture Style	
Picture Style File	
RAW Tool Palette	
Save Adjustments	
Tone Curve Adjustment	
Toning Effect	

Tool Palette	
White Balance Adjustment Contents (Recipe)	
Adobe RGB	123
Apple RGB	123
Arrange Images	
Auto Lighting Optimizer	58
Automatic Adjustment (Tone Curve Assist)	30, 88
Automatic Dust Erasure Processing	64, 65, 98, 99

В

Batch Apply White Balance to Images (Personal White Balance) 82
Batch Change the File Name of Images
Batch Convert/Save Images (Batch Process)
Batch Process (Batch Save JPEG and TIFF Images)
Batch Process of Multiple Images
Change File Name
Convert/Save (Batch Process)
Personal White Balance82
Recipe Data80
Transfer
Batch Settings Window
Batch Transfer Images
Batch Transfer Images to Image Editing Software
Before/After Comparison Display 50
bit Number
Bookmark
Brightness
-

С

Change File Name	
Changing the File Name of Images in the Order in the Ma	ain Window. 85
Check Mark 1	7, 18, 109, 114
Chromatic Aberration Correction	62
Chrominance Noise Reduction (JPEG, TIFF Images)	
Chrominance Noise Reduction (RAW Images)	
Click White Balance	

Basic Operation
Advanced Operation
Advanced Image Editing and Printing
Processing Large Numbers of Images

Introduction

Contents at a Glance

Editing JPEG/TIFF Images

Reference



CMYK Simulation
Collection Window
Color Blur Correction
Color Chart 123
Color Management (Color Matching) 122
Color Setting of the Monitor (Profiles)
Color Setting of the Printer (Profiles)
Color Space
ICC Profiles
Color Management (Preferences)
Color Saturation
Color Setting of the Monitor (Profiles)
Color Setting of the Printer (Profiles)
Color Space
Adobe RGB
Apple RGB 123 Color Space Setting for Each Image 68
ColorMatch RGB
Default Setting of Color Space
sRGB 123
Wide Gamut RGB 123
Color Space Setting for Each Image
Color Temperature
Color Tone 27
Color Wheel 53
ColorMatch RGB 123
Compatible Cameras with the Lens Aberration Correction Function. 60
Compatible Lenses with the Lens Aberration Correction Function 60
Contact Sheet Printing (Printing a Thumbnail List) 70
Contrast 27, 89
Convert to JPEG or TIFF Image and Save 39, 83, 116, 120
Convert/save One Image Window 39, 116
Copy Stamp (Image Correction)
Copy Stamp Window
Copying and Pasting (Applying) Recipes
Correct Images (Copy Stamp Function) 68, 102

Creating a Folder	Introduction
D	
Default Noise Reduction Settings	Contents at
Default Setting of Color Space	a Glance
Delete Images 46	
Deleting	Basic
Delete Images 46	Operation
Delete the Software 106	
Deleting DPP (Uninstalling) 106	
Detailed Setting Printing (Printing with Shooting Information)	Advanced Operation
Display	Operation
Before/After Comparison Display 50	
Enlarged Display (Edit Window)	Advanced
Enlarged Display (Quick Check Window) 16, 114	Image Editing and Printing
Shooting Information Display 10, 21	_
Single Image Display	Processing
Thumbnail Display (Main Window)	Large Numbers
Thumbhail Display and Enlarged Display	of Images
(Edit Image Window)	
Distortion Correction	Editing JPEG/TIFF
Downloading an Image to Your Computer7	Images
Downloading Images from a Camera7	
Downloading Images from a Card Reader9	
Downloading Images7	Reference
Downloading Images from a Camera7	
Downloading Images from a Card Reader9	
Dust Delete Data	Index
Dust Erasure Processing	
Automatic Dust Erasure Processing 64, 98	
Image Correction (Copy Stamp Function) 68, 102	
Manual Dust Erasure (Repair Function)	
Dynamic Range 54, 93	
E	()
Edit Image Window 31, 115	
Edit Window 11, 110	

Editing→Adjusting Enlarged Display (Edit Window)
FFalse Color Reduction73, 74Filter Effect28Folder Window6, 107G
General Settings (Preferences) 73
HCoverHighlight Area Warning Indicator52Hue91
IICC Profiles
Default Noise Reduction Settings
J JPEG Image 122
Ŭ
Lens Aberration Correction
Lens Aberration Correction Window

Luminance Noise Reduction (JPEG, TIFF Images)	
Luminance Noise Reduction (SFLG, THT Images)	
	Contents at a Glance
M	a Glance
Main Window 10, 107	
Manual Dust Erasure (Repair Function) 66, 100	Basic
Monochrome	Operation
Filter Effect	
Toning Effect	Advanced
Move or Copy Folders	Operation
Move or Copy Images 47	
Ν	
Noise Reduction (JPEG or TIFF Image)	Advanced Image Editing
Noise Reduction (RAW Image)59	and Printing
Noise Reduction of a JPEG Image (Luminance, Chrominance)94	
Noise Reduction of a RAW Image (Luminance, Chrominance) 59	Processing
NR Preview Window	Large Numbers of Images
NR/Lens/ALO Tool Palette 112	
0	Editing
Organize Images	JPEG/TIFF
Organizing Images 46	Images
Organizing Images	Images
Create a Folder 47	
Create a Folder	Reference
Create a Folder	
Create a Folder	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48	
Create a Folder	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPeripheral Illumination Correction62	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPPeripheral Illumination Correction62Personal White Balance82	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPeripheral Illumination Correction62Personal White Balance82Picture Style24	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPeripheral Illumination Correction62Personal White Balance82Picture Style24Picture Style File56	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPeripheral Illumination Correction62Personal White Balance82Picture Style24Picture Style File56Preferences73	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPeripheral Illumination Correction62Personal White Balance82Picture Style24Picture Style File56	Reference
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPeripheral Illumination Correction62Personal White Balance82Picture Style24Picture Style File56Preferences73Color Management77	Reference Index
Create a Folder47Delete Images46Move or Copy Folders48Move or Copy Images47Register Folders as Bookmarks48PPeripheral Illumination Correction62Personal White Balance82Picture Style24Picture Style File56Preferences73Color Management77General Settings73	Reference

View Settings	75
Printing	
Printing a Thumbnail List (Contact Sheet Printing)	70
Printing One Sheet of Paper 14,	
Printing Using Easy-PhotoPrint	
Printing Using Easy-PhotoPrint EX	
Printing with a High-End Canon Printer	
Printing with a Large-Format Canon Printer	
Printing with a Printer other than Canon Printers	
Printing with Canon Inkjet Printers 40, Printing with Easy-PhotoPrint Pro	
Printing with Shooting Information (Detailed Setting Printing)	
Rendering Intents when Using Easy-PhotoPrint	
Printing a Thumbnail List (Contact Sheet Printing)	
Printing One Sheet of Paper 14,	
Printing Using Easy-PhotoPrint	
Printing Using Easy-PhotoPrint EX	
Printing with a High-End Canon Printer	
Printing with a Large-Format Canon Printer	
Printing with a Printer other than Canon Printers	
Printing with Canon Inkjet Printers	
Printing with Easy-PhotoPrint Pro	
Printing with Shooting Information (Detailed Setting Printing)	
Q Quick Check Window 16, 1	11
	14
R	
RAW Image 1	
RAW Tool Palette 1	
Re-Adjusting an Image 40, 1	03
Recipe	22
Recipe File	
Re-Editing an Image 40, 1	03
Registering Folders as Bookmarks	48
Rename Window	21
Rendering Intent (Matching Method) 1	23

Rendering Intents when Using Easy-PhotoPrint	, 78
--	------

Rendering Intents when Using Easy-PhotoPrint	Introduction
Repair (Manual Dust Erasure)	
RGB Tool Palette 111	Contents at
Rotate Images 10, 23, 107, 108, 114, 115	a Glance
S	
Saturation	Basic
Save	Operation
Batch Convert/Save Images (Batch Process)	
Convert to JPEG or TIFF Images and Save	
Save	Advanced Operation
Save As	Operation
Save JPEG or TIFF Image as a Separate Image	
View and Save RAW Images	Advanced
Save As	Image Editing and Printing
Salvet Images 81	
Select Images 10, 16, 31	Processing
Shadow Area Warning Indicator	Large Numbers
Sharpness	of Images
Shooting Information Display 10, 21	
Shortcut Keys Cover	Editing JPEG/TIFF
Single Image Display	Images
Single Image Display of RAW and JPEG Image	
Sorting Images (Check Marks) 17, 18	
sRGB	Reference
Starting up DPP	
Supported Images	
Synchronization (Edit Window)	Index
Synchronize Edit Windows	
Synchronize Images	
System Requirements	
т	
Thumbnail Display (Main Window) 10, 107	
Change the Display 10	
Thumbnail Display and Enlarged Display (Edit Image Window) 31	
Thumbnail Display of Images (Main Window) 10	

	10
Change the Display	
TIFF Image	122
Tone Curve	122
Tone Curve Adjustment	55, 92
Tone Curve Assist (Automatic Adjustment)	30, 88
Toning Effect	28
Tool Palette	
NR/Lens/ALO Tool Palette	112
RAW Tool Palette	111
RGB Tool Palette	111
Tool Palette (Preferences)	76
Transfer	
Batch Transfer Images to Image Editing Software	
Transfer an Image to Photoshop	
Trimming and Adjusting the Angle of an Image	
Trimming/Angle Adjustment Window	
	•, • • •
V	
View Settings (Preferences)	75
W	
White Balance	25
Click White Balance	26, 90
Color Temperature	· · · ·

About This Instruction Manual

- It is prohibited to reproduce, in whole or part, the contents of this Instruction Manual without permission.
- Canon may change without notice the software specifications and contents of this Instruction Manual.
- The software screens and displays printed in this Instruction Manual may differ slightly from the actual software.
- The content of this Instruction Manual has been reviewed thoroughly. However, if you should notice any errors or omissions, please contact a Canon Service Center.
- Please note that irrespective of the above-mentioned, Canon does not take responsibility for the outcome of the operation of the software.

Trademark Acknowledgments

- Microsoft and Windows are registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.
- Adobe and Photoshop are registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.
- Other names and products not mentioned above may be registered trademarks or trademarks of their respective companies.

	Introduction
	Contents at a Glance
	Basic Operation
t	Advanced Operation
	Advanced Image Editing and Printing
	Processing Large Numbers of Images
	Editing JPEG/TIFF Images
	Reference
	Index