


GMAP2012 for Windows 7

USER MANUAL AND EXERCISES



Trond Helge Torsvik (PGP, University of Oslo, Norway)


Software Installation:

This preliminary manual can be found at:

<http://www.earthdynamics.org/Bugs/Gmap2012Manual.pdf>

(A) INSTALL SYSTEM (CLICK ON LINK BELOW):

<http://www.earthdynamics.org/Bugs/Gmap2012System.zip>



(1) Click 'Save' in File Download Box (see above)

(2) After the File has been downloaded then click on file to unzip and click 'setup.exe' (see below).

Name	Type	Compressed size
GMAP2012.CAB	Cabinet File	18 804 KB
setup.exe	Application	66 KB
SETUP.LST	MASM Listing	2 KB

(3) During 'setup' the software must be installed to **c:\gmap (VERY IMPORTANT)**


Note also that you must have administrator rights to install the system!

During intallation you should keep system files that are more recent then the one supplied with GMAP (you will be asked). If any problem installing some files just click 'skip'.


(B) INSTALL DATA (CLICK ON LINK BELOW):

<http://www.earthdynamics.org/Bugs/Data.zip>

(1) Click 'Save' in File Download Box (see below)



(2) After the File has been downloaded click 'data.zip' and copy the entire directory /dat with its subdirectories to c:\gmap. **The structure must be c:\gmap\data\'subdirectories'**



1. INTRODUCTION

GMAP for Windows 7 is a state of the art computer program which performs all processing and plotting tasks usually associated with the storage and presentation of palaeomagnetic pole positions, and generation of palaeogeographic reconstructions. GMAP is menu-driven and easy to use; the user is never far removed from the basic data from which palaeogeographic reconstructions are derived, and therefore has a sense of total control over the program's performance.

GMAP can generate reconstructions based on individual palaeomagnetic poles, averaged palaeomagnetic poles, and digitally derived smooth (APW) curves. Palaeogeographic reconstructions can be saved to disk files, and later viewed in chronological order as 'animations'.

GMAP is supplied with a full range of continental outlines. It is also possible to import new continents via simple ASCII files or ARC GIS shape files.

The GMAP software system package was originally developed by Torsvik at the University of Bergen in 1982 and later with contributions from both Lauri Pesonen and M.A. Smethurst (Torsvik & Smethurst 1989). GMAP routines are currently being ported to GPlates (www.gplates.org) and this GMAP version is similar to earlier versions but can run under Windows 7 (older 16/32-bit Editions versions not compatible with Windows 7).

1.1 MAIN PROGRAMS AND FILE-TYPES

Main program

GMAP2012.EXE	Palaeogeographic reconstruction program
--------------	---

Programs run from inside GMAP

APW.EXE	APW Path-fitting routines
VELWIN.EXE	Calculates drift and rotation rates from APWP's

Data file types

GMAPW.SET	GMAPW configuration file
VELW.SET	VELWIN configuration file
.C97	Continent outlines (.CON in very old releases)
*.VGP	Files containing virtual geomagnetic poles (VGP)
.A97	Animation files (.ANI in very old releases)

1.2 ABBREVIATIONS


VGP	VIRTUAL GEOMAGNETIC POLE
APW	APPARENT POLAR WANDER
APWP	APW PATH
CONTINENT	A FILE CONTAINING LATITUDES AND LONGITUDES; THESE CAN W.G. BE COASTLINES OR TERRAIN BOUNDARIES
α_{95}	95 PERCENT CONFIDENCE CIRCLE ON MEAN REMANENCE
A95	95 PERCENT CONFIDENCE CIRCLE ON MEAN POLES

<i>k</i>	FISHER (1953) PRECISION PARAMETER
dp,dm	SEMI-AXES OF THE OVAL OF 95 PERCENT CONFIDENCE ABOUT THE VGP
DEC	MEAN REMANENCE DECLINATION
INC	MEAN REMANENCE INCLINATION
GLAT	LATITUDE OF SAMPLING SITE
GLON	LONGITUDE OF SAMPLING SITE
PLAT	VGP LATITUDE
PLON	VGP LONGITUDE

2. DESCRIPTION OF GMAP for Windows 7


Select GMAP from the Program Manager Window option and double click the GMAP for Windows icon. After start-up the main menu is displayed (Fig. 1). An option in the top menu or the left-hand and right-hand panels (Fig. 2) may be selected through the use of the mouse and executed by clicking the mouse.

FIGURE 1 Main menu GMAP



2.1 MAIN MENU OPTION (SUBOPTIONS)


Organize



OPTION	SUBOPTION
Import	Ascii Import
	ShapeFile Import
Export Continents (Ascii, GMT, Excel, GIS.GEN)	


Export Continents to Shape Files	
Print	
Print setup	
Exit	

Continent




OPTION	EFFECT
Open	LOAD A CONTINENT FILE
Save As	SAVE A CONTINENT FILE
Merge	MERGE CONTINENTS FILES
Library	DISPLAY CONTINENTAL LIBRARY FILES
Draw	SCREEN DISPLAY OF CONTINENT
Rotate	ROTATE CONTINENT ACCORDING TO A PRE-DEFINED EULER-POLE

VGP




OPTION	EFFECT
Open	LOAD A VGP DATA FILE
Save As	SAVE A VGP DATA FILE
Merge	MERGE VGP FILES
Library	
Draw	SCREEN DISPLAY OF VGP DATA
Table	SHOW/EDIT/MANIPULATE VGP IN TABLE FORM
Rotate	ROTATE VGP ACCORDING TO A REDEFINED EULER-POLE
Vgp Reconstruct	MAKE A RECONSTRUCTION BASED ON A VGP
Plot Settings	ADJUST VGP SCREEN SETTINGS

Animation




OPTION	EFFECT
Open	LOAD AN ANIMATION FILE
Save As	SAVE AN ANIMATION FILE TO DISK
Merge	MERGE ANIMATION FILES
Draw	SCREEN DISPLAY OF ANIMATION FILE
Table	SHOW/EDIT ANIMATION FILE IN TABLE FORM
Library	

Euler




Keyboard input	DEFINE A EULER POLE AND ROTATION ANGLE
Euler rotation	PERFORM AN EULER ROTATION
Calculate E.P.	CALCULATE AN EULER POLE
Add Euler poles	CALCULATE AN EULER POLE BASED ON TWO SEPARATE EULER POLES

2.2 LEFT-HAND PANEL




PANEL OPTION	EFFECT
Projection	SET PROJECTION TYPE (SEPARATE FORM WILL APPEAR)
Projection center	SET LATITUDE AND LONGITUDE FOR PROJECTION CENTER (ALSO AVAILABLE IN PROJECTION SUB-OPTION). MUST ENGAGE DRAW CONTINENT/VGP OR ANIMATION TO TAKE EFFECT
Blank	CHANGE BETWEEN BLANK ON AND BLANK OFF. BLANK ON IS DEFAULT, AND TO PRESERVE A PICTURE DURING SUCCESSIVE LOADING OF CONTINENTS ('OPEN CONTINENT') THIS OPTION MUST BE SET TO OFF. CLICK WITH MOUSE FOR THE APPROPRIATE STATE
Grid	SET AUTOMATIC DRAWING OF NET TO ON/OFF CLICK WITH MOUSE FOR THE APPROPRIATE STATE
Scale	SELECT SCALE (MAGNIFICATION) CENTRED AROUND ZOOM-CENTRE CLICK WITH MOUSE AT THE APPROPRIATE SCALE VALUE (50-2000%)
Animation Library	
Apply	TYPE A NUMBER IN MILLION OF YEARS (NEAREST 5 MILL YEAR...0, 5, 10 ETC). MAXIMUM AGE IS 550 MA NOTE THAT ANIMATION FILE CAN BE INSPECTED AND MANIPULATED IN 'ANIMATION TABLE' AND THEN CLICK 'ANIMATION DRAW' THE USER CAN ALSO ADVANCE OR DECREASE AGE IN 5 MA INTERVALS BY CLICKING THE ARROWS BELOW OR PLAY A MOVIE
ANIMATION FILTER	E.G. 7 WILL SHOW ALL CONTINENTS STARING WITH 7 (E.G. SOUTH AFRICA IS 701) OR TYPE 302 TO JUST DISPLAY BALTICA

3.0 ORGANIZE




3.1. IMPORT

3.1.1 ASCII IMPORT




This option allows import of Ascii continental files which are stored as longitude,latitude. A list of CONTINENT (file extension *.*) file-names are displayed in alphabetic order. Select the appropriate directory, drive and file name followed by <OK>. Pen-up command in GMAP continent files are 100 (latitude) and 1000 (longitude).

3.2 SCREEN



When clicking 'Copy to Clipboard' you can later 'Paste' the screen into a drawing package in vector format (e.g. Adobe Illustrator). When saving to WFM file you can also open the vector drawing in a drawing package later. Vlipboard setting should normally be set to 'Metafile'



4.0 Continent/VGP/Animation

4.1 OPEN (CONTINENT, VGP or ANIMATION files)

A list of CONTINENT (file extension .C97), VGP (file extension .VGP) or ANIMATION (file extension .A97) are displayed. Select the appropriate directory, drive and file name followed by <OK>. A range of CONTINENT/VGP/ANIMATION files can be found in c:\gmap\data\continents, c:\gmap\data\VGPs and c:\gmap\data\ANIMATIONS. The CONTINENTS are also found in the ANIMATION directory but all files in this directory are 'Read Only' to avoid overwriting original system files. CONTINENTS starting with a 3-digit number mainly follows GPlates (Plates) conventions

4.2 MERGE (CONTINENT, VGP or ANIMATION)

This option is identical to that described above , but the selected file will be merged with an existing CONTINENT/VGP/ANIMATION file in memory. These combined data can later be saved to a disk-file using option 'SAVE AS' (CONTINENT/VGP or ANIMATION). Note, however, that the maximum

permitted number of co-ordinates in a single continent outline is 30000 and 2000 data-points in a VGP file.

4.3 SAVE AS (CONTINENT, VGP or ANIMATION)

The purpose of this routine is to save modified CONTINENT, VGP or ANIMATION data to disk files. Merged CONTINENT files, EDITED CONTINENTS or rotated CONTINENT data can be saved under a new file name. The latter is useful for constructing ancient terranes or storing palaeogeographic maps. In option 'DRAW CONTINENT' one can also add points/lines to the existing CONTINENT file which can later be saved under this option.

4.4 ROTATE (CONTINENT or VGP)

Define euler-data before selecting this option, either manually using the 'KEYBOARD INPUT' option in the Euler-menu or from a file using the 'OPEN' option. When rotating VGP's one can also rotate the sampling site latitude and longitude, to permit the generation of proper error ovals on data in their rotated positions.


Note that the CONTINENT outline/VGP's in memory are changed during rotation. To later perform a rotation on the original data-set the original continent file must first be re-loaded. Compound rotations can be performed using 'KEYBOARD INPUT' and 'ROTATE CONTINENT/VGP' repeatedly.

Example of compound rotation:

Problem: You wish to rotate the North American craton to its Devonian palaeoposition according to palaeomagnetic data from BALTICA.

- (1) Select option 'OPEN CONTINENT'
- (2) Open North America craton (file = \data\continents\101_North American craton_1100.C97)
(If you now use option 'DRAW CONTINENT', a map like Fig. 3A will appear on the screen)
- (3) Use option 'KEYBOARD INPUT' in the 'Euler Rotations' menu to register the rotation pole and angle which corrects for the Mesozoic/Cenozoic opening of the North Atlantic (e.g. use a classic Bullard et al. (1965) fit: c. 87 (latitude), 27 (longitude) and 37 (euler-angle).
- (4) Select option 'ROTATE CONTINENT'. The continent outline will then be adjusted for the opening of the North Atlantic (If you then use option 'DRAW CONTINENT', a map like Fig. 3B appears on the screen).
- (5) Select option 'OPEN VGP'.
- (6) Open the fitted APW path for BALTICA/Europe (e.g. file data\VGPs\Baltica_Europe_2012.vgp supplied with the GMAP package).

- (7) Select option 'TABLE VGP' in the VGP menu.
- (8) Select reference pole (e.g. pole 41 corresponding to an age of 400 Ma) by clicking the appropriate line at the line-number column.
- (9) Select sub-option 'RECONSTRUCT'.



Select south-pole and click the <OK> option.

Result

Continent data, already corrected for the opening of the North Atlantic is rotated by an amount which brings the selected reference VGP to the South pole. Note that the Euler Rotation Pole required to do this will become the current Euler Pole setting which is displayed below the main menu, and can be used by option 'ROTATE CONTINENT' to position other continents in a Devonian reconstructed position. North American craton will be displayed on the screen in a Devonian (400 Ma) configuration in 'European' co-ordinates.




FIGURE 3 Example of compound rotation. (A) North-American craton displayed in present position. (B) Rotated into a Bullard et al. fit (lat=87, long=27, angle=37) with Europe, taking account of the


opening of the North Atlantic.(C) The 'corrected' NAM positioned according to pole 41 in VGP file
\\data\\VGPs\\Baltica_Europe_2012.

4.5 VGP RECONSTRUCT


This option performs a reconstruction based on a VGP inputted from the keyboard. Enter VGP latitude and longitude and state whether it is a SOUTH (s) or NORTH (n) pole.

Example of how to produce a display for a map of the Permian palaeo-position for Baltica:

1. Load BALTICA (file = \\data\\continents\\302_Baltica_1100.C97) using 'OPEN CONTINENT'
2. Select option 'VGP RECONSTRUCT' and enter -45 (VGP latitude) and 340 (VGP Longitude)
3. Select southpole and click on <OK>.




4. BALTICA will be displayed in 'DRAW CONTINENT' in its PERMIAN position.




4.6 DRAW CONTINENT (or VGP & ANIMATION)

In this option a CONTINENT, VGP or ANIMATION file is displayed on the screen using the pre-defined projection. Use option 'PROJECTION' to alter projection type (see picture below). The plot is centred on a 'zoom-centre', which by default is 0,0 (LAT, LONG). Blanking is ON by default.



5.0 Euler Rotations




5.1 KEYBOARD INPUT (EULER)

This option enables the input of an Euler rotation pole from the keyboard which can subsequently be used by options 'ROTATE CONTINENT (or VGP)' or 'EULER ROTATION'.


5.2 EULER ROTATION

This utility routine performs euler-rotations on VGP's entered interactively from the keyboard. The currently registered Euler Pole (3.13 or 3.14) is used.



5.3 CALC EULER POLE

This option enables calculation of an Euler rotation pole based on manual input of two geographic point (co-ordinates) or poles. Enter Latitude (LAT) and Longitude (LONG) for pole A and B, and the resultant rotation pole (LAT & LONG) and amount of rotation (A.ROT) will be displayed.



Calculate Euler Rotation Pole


	Latitude	Longitude	Angle
POLE A	33	55	
POLE B	12	13	
EULER POLE	-52.59863	86.85920	43.7079

Note that this procedure do not provide a unique answer, i.e. the result is only one of several possible Euler Poles

Calculate Exit

5.4 ADD EULER POLES

This option add/concatenates two Euler poles into a single resultant Euler pole. Enter latitude, longitude and angle for the two Euler poles and click on <Calculate>.




Add Euler Poles

	Latitude	Longitude	Angle
POLE A	34	55	18
POLE B	22	12	13
COMBINED	33.19612	35.07643	29.21585

Right-hand rules - angles must be less than 180 degrees

Calculate Exit

5.5 EULER FIT (4-point)



4-Point Euler Fit

	Latitude	Longitude
Point 1		
Point 2		
Point 3		
Point 4		

Most significant

First Euler Fit: Exact 1 to 2

Latitude	Longitude	Angle

3 Rotated

Iteration for best fit (3 to 4)

Latitude	Longitude	Rotation	Misfit	Deg	km

Best Fit Euler Rotation

Latitude Longitude Angle

Exit Calculate

6. TABLE VGP

This is one of the most frequently used options in GMAP. Upon selecting this option the following table is displayed:

Table VGP for Baltica_Europe_2012


Organize Reconstruct APW Path Calculate Edit Plot Tools





	CLPOL CODE	DEC	INC	a95	GLAT	GLON	PLAT	PLON	Dp (F)	Dm	AGE	
1	4RM: 10 - 10Ma N= 5 (Dp c	187.90	-60.10	5.51	45.83	4.90	-82.51	312.16	5.00	101.00	0.00	
2	4RM: 0 - 20Ma N= 7 (Dp co	186.31	-57.66	5.17	45.05	4.27	-81.77	327.21	7.00	101.00	10.00	
3	4RM: 10 - 30Ma N= 4 (Dp c	187.27	-53.84	7.60	44.30	3.47	-78.61	331.57	4.00	101.00	20.00	
4	4RM: 20 - 40Ma N= 2 (Dp c	187.49	-61.24	21.06	50.55	7.50	-80.30	332.60	2.00	101.00	30.00	
5	4RM WARNING ONLY pole	181.06	-60.19	3.40	50.30	7.00	-80.78	2.00	1.00	101.00	40.00	
6	4RM: 40 - 60Ma N= 8 (Dp c	182.57	-62.17	4.66	55.33	355.22	-78.00	346.20	8.00	101.00	50.00	
7	4RM: 50 - 70Ma N= 13 (Dp c	182.59	-62.13	3.04	56.12	354.64	-77.17	346.13	13.00	101.00	60.00	
8	4RM: 60 - 80Ma N= 7 (Dp c	183.38	-60.30	3.11	55.40	355.84	-75.66	345.52	7.00	101.00	70.00	
9	4RM: 70 - 90Ma N= 4 (Dp c	197.59	-54.48	3.87	46.78	27.74	-72.32	333.17	4.00	101.00	80.00	
10	4RM: 80 - 100Ma N= 4 (Dp c	196.18	-56.47	6.22	48.76	29.23	-73.39	338.13	4.00	101.00	90.00	
11	4RM: 90 - 110Ma N= 2 (Dp c	197.59	-69.26	14.27	58.59	59.50	-78.61	352.04	2.00	101.00	100.00	
12	4RM WARNING ONLY pole	191.74	-66.53	2.50	44.50	102.00	-80.78	338.40	1.00	101.00	110.00	
13	4RM: INTERPOLATED	187.49	-61.24	0.00	50.55	7.50	-78.77	349.77	2.00	101.00	120.00	

Column#	
1- Nr.	Pole number
2- CLPOL	Combined character string of Van der Voo classification/grading (1-7) and palaeomagnetic polarity (n,r,m). This string is important and controls weighting in the fitting of smooth APW paths. For example a pole with 'Q' factor = 7 and normal polarity are entered as '7n'
3- DEC	Remanence Declination
4- INC	Remanence Inclination
5- a95	95 % confidence circle on mean remanence direction
6- GLAT	Latitude of sampling site
7- GLON	Longitude of sampling site
8- PLAT	Latitude of VGP
9- PLON	Longitude of VGP
10- dp	half-angle of the confidence on the VGP in the direction of the palaeo-meridian.
11- dm	half-angle of the confidence on the VGP perpendicular to the palaeo-meridian.
12- AGE	VGP age. All poles must be assigned an age if a smooth path is to be fitted to them. During hard-copying of VGP data the age will be printed next to the pole.

Note that VGP files created with GLOBAL.EXE (The Global Palaeomagnetic Database Query program) substitute column #2 (CLPOL) with RESULT-NUMBER in the Global Palaeomagnetic database. Column #12 (AGE) is a mean of Low and high magnetic age stated in the database.

6.1 MAIN MENU AND SUBOPTIONS

OPTION/SUBOPTION	EFFECT
Organize Open Save Save As GlobalPalmagDatabase New Print Exit 	Open a VGP file Save VGP File Save VGP with a new name Search global palaeomagnetic database Create a new VGP file. Use option 'EDIT' to input data Print table to default printer Return to main menu
Reconstruct	Perform a reconstruction based on a VGP in the table Note - Load a continent prior to this operation • Select reconstruction pole by clicking on numerical row code at the first column • Select North or South pole • Resulting reconstruction will be displayed in mode 'DRAW CONTINENT'
APW Path Spline Fitting"" Moving Average Voo Grading (Q) Timescale (<i>not updated</i>)	Fit a smooth APW path to the data in the Table using splines Fit a smooth APW path to the data in the Table using running means
Calculate Pole Statistics Calculate poles Pole Reference Calculate Dec/Inc Plat Reference Single VGP Calculation Non-dipole field correction	Calculate mean of the listed VGP's (A95) Determine the palaeomagnetic pole-position for all data in the Table. Declination, inclination and sampling position present in data-set. Calculate amount of rotation and flattening. Enter Reference Pole and A95 Calculate declination and inclination Based on VGP latitude & longitude and sampling position Enter latitude & longitude (optional) for which palaeolatitudes are to be determined. Note that latitude & longitude will replace original sampling co/ordinates in the Table. This enables the operator to calculate 'local' declination and inclinations at the selected reference locality. Calculate a pole based on dec, inc and sampling location Type G1 and G2 and inclination and pole will be recalculated

Inclination Error Correction 	Type f (flattening factor) and inc and pole will be recalculated
Edit Delete row(s) Add a row Invert row(s) Invert all rows Sort a column 	Delete one or several entries in the Table. Select pole by clicking on numerical row code at the first column or drag the mouse to include several poles Add a pole to the Table Invert VGP polarity of one or several poles. Invert VGP polarity of all poles Sort data based on any column. Select column by clicking at the first row
Plot Palaeolatitude Stereoplot Histograms APW 	Calculate and display latitudes based on inclination Display dec and inc in a Wulf plot Display data in histogram (select column to display) Calculate APW and display in X-Y plot
Tools Calculate Euler poles for VGPs Check poles Interpolate VGPs Non-dipole Field vs. Latitude Inclination Error vs. Latitude Velocity 	Calculate Euler poles for entire Table. Select North or South pole. Cross-checking type pole and calculated from dec, inc and location Interpolating by typing interval Draw a graph based on G1 and G2 Draw a graph based on f (flattening factor) Engage calculation of velocities from VGPs (<i>very old routine</i>)

Note: All alterations to data in the Table will only affect the dataset in memory, and not on the disk.
To save alterations made in 'TABLE VGP' to disk, use option 'SAVE AS (VGP)' in the main menu.


which has a location and time progression. Path fitting constitutes interpolation; reducing data sets to a simpler, and to some extent interpreted, form.

A number of numerical methods for fitting smooth paths to palaeomagnetic poles have been offered in the literature (Gould, 1969; Parker and Denham, 1979; Thompson and Clark, 1981, 1982; Clark and Thompson, 1984; Jupp and Kent, 1987). In GMAP we have used the method of Jupp and Kent (1987) because it is statistically rigorous, is independent of the co-ordinate system, and is most sympathetic to the concept of APW. The method aims to fit 'spherical smoothed splines' to a given data-set, consisting of pole positions and error parameter.


It is possible to generate a number of paths with different levels of smoothing. This is done by adjusting a smoothing parameter used by the computer program. In GMAP the data can be individually weighted according to their α_{95} , so that the route taken by the smooth path through the data set will depend on both the distribution of the data on the globe and the standard error for each of the palaeopole positions. The lower the reported angular error for a pole position, the closer the curve will pass by it. We have also implemented a weighting procedure based on the Van der Voo's (1988) reliability index 'Q' (grades 1 to 7; least to most reliable).

It is clear that the angular error associated with a particular palaeomagnetic pole position is far from an adequate description of the quality or reliability of that pole. For example, uncertainty in the age of the result has a direct bearing on the angular uncertainty which should be associated with it, since apparent polar wander might be continuing within the time period of uncertainty. Instead of weighting pole positions solely on the basis of criterion (2) in Van der Voo's reliability scheme (α_{95}), it is informative to weight the data in proportion to their 'Quality factors'. This causes the smooth path to pass close to the data which score '7', full-marks, and be only gently guided by those data with lower reliabilities.

GENERATION OF APW PATHS



- (1) Load a VGP file via the main-menu option 'OPEN VGP' (e.g. file \data\VGPs\NorthAmerica2008_ROG.vgp).
- (2) Select option 'TABLE VGP'
- (3) Select sub-option 'SPLINE FITTING'



- (4) Select
- (a) No weighting
 - (b) Weighting according to 'Q' factor
 - (c) Weighting according to alfa95

If option 'b' is selected, the 'Q' factor for every VGP in the table must be encoded in the first character of the VGP 'code' (see section 3.8). If a 'Q' factor is not present included, 'Q' will be set to zero reliability.

If option 'c' is selected, the alfa95 must be included in the table of data.

- (5) Input SMOOTHING PARAMETER (value 10 to 10000)


A high value results in extreme smoothing. Values in the order of 100 to 200 generally result in moderate smoothing (Fig. 11).

- (6) Input VGP FILE-NAME for the output fitted path.

The fitted path, when generated, will be displayed on the graphic screen in option 'DRAW VGP' (3.9) in the main menu.

Note:

The original VGP file is 'shut down' and replaced with the new APW file (spline file).






FIGURE 10 'SPLINE FITTING' option. Left: File \data\VGP's\NorthAmerica2008_ROG.vgp plotted with dp/dm ovals. Right: Spline fitting with smoothing parameter=200 and weighted by alfa95.





FIGURE 10 'MOVING AVERAGE' option on file \data\VGP's\NorthAmerica2008_ROG.vgp and plotted with A95 ovals.

7. TABLE ANIMATION

 Table Animation




File Edit Add Euler poles Vgp Rotate

	Continent	E.Lat.	E.Long.	E.Angle	Age/Comment
1	c:\gmap\Data\Animations\101_North A	60.45	69.53	72.48	250
2	c:\gmap\Data\Animations\102_Greenla	51.36	78.37	64.67	250
3	c:\gmap\Data\Animations\103_North SI	33.13	84.23	58.23	250
4	c:\gmap\Data\Animations\104_Caborce	53.02	80.37	72.3	250
5	c:\gmap\Data\Animations\108_Acadia_	60.45	69.53	72.48	250
6	c:\gmap\Data\Animations\108_Acadia_	60.45	69.53	72.48	250
7	c:\gmap\Data\Animations\108_Acadia_	60.45	69.53	72.48	250
8	c:\gmap\Data\Animations\109_Florida C	60.45	69.53	72.48	250
9	c:\gmap\Data\Animations\109_Florida_	60.45	69.53	72.48	250
10	c:\gmap\Data\Animations\109_Florida_	60.45	69.53	72.48	250
11	c:\gmap\Data\Animations\109_Florida_	60.45	69.53	72.48	250
12	c:\gmap\Data\Animations\109_Florida C	60.45	69.53	72.48	250
13	c:\gmap\Data\Animations\111_Mendeke	57.64	73.4	78.75	250
14	c:\gmap\Data\Animations\113_Northwii	57.64	73.4	78.75	250
15	c:\gmap\Data\Animations\114_Lomono	54.26	74.03	64.39	250
16	c:\gmap\Data\Animations\120_Sverdru	60.45	69.53	72.48	250
17	c:\gmap\Data\Animations\121_Southwii	52.13	78.89	65.1	250
18	c:\gmap\Data\Animations\122_South c	51.9	80.45	63.8	250
19	c:\gmap\Data\Animations\123_Central I	59.81	69.84	73.12	250
20	c:\gmap\Data\Animations\124_North EI	60.45	69.53	72.48	250
21	c:\gmap\Data\Animations\130_Artic Ca	52.13	78.89	65.1	250
22	c:\gmap\Data\Animations\140_Lomono	54.2	73.99	64.3	250
23	c:\gmap\Data\Animations\141_Lomono	53.85	73.69	63.76	250
24	c:\gmap\Data\Animations\142_Lomono	31.07	85.5	42.55	250
25	c:\gmap\Data\Animations\153_Roberts	60.27	69.55	71.76	250
26	c:\gmap\Data\Animations\154_Laurenti	60.27	69.55	71.76	250
27	c:\gmap\Data\Animations\155_Farewel	63.47	84.57	69.64	250
28	c:\gmap\Data\Animations\160_Ruby Tr	33.13	84.23	58.23	250
29	c:\gmap\Data\Animations\161_Eastern	60.27	69.55	71.76	250
30	c:\gmap\Data\Animations\201_Northern	68.74	91.97	44.2	250
31	c:\nman\Data\Animations\202_Parana	70.9	85.24	43.03	250

Double-click a line to insert a continent with file-manager

This option is used to edit (use option 'OPEN ANIMATION') or create animation files. The main menu consists of the following options:

OPTION (SUBOPTION)	EFFECT
File New Export To EXCEL To GMT (all reconstructed) To GPLates rotation format Copy Euler Poles to VGP Exit	Create a new file Copy Euler poles to memory and display with "DRAW VGP"
Edit Edit a row Add a row Delete a row Sort Ages	Edit a single line. Select line by clicking on numerical row code at the first column Add a row to the Table Delete one or several lines. Select line(s) by clicking on numerical row code at the first column or drag the mouse to include several lines





Substitute All Continents with same continent 	
Add Euler Poles Add Euler Rotation of Selected Row to All Rows (negative angle) Add Euler Rotation to all Rows Add Euler Rotation to Selected Rows Move Continents East or Westward 	Example: All supplied animations are palaeomagnetic reconstructions in a South Africa frame (plate 701). If you want to display the data relative a fix North america, then click the row '101North America....' And engage this option. If you have a new pole from North America at this time engage 'VGP rotate' to make animation file absolute based on your new pole. Add the same Euler to all rows As above but rotating about 90 or -90 so only change longitude if animation file is based on palaeomagnetic data (calibrating longitude)
VGP Rotate 	Supplied animation file are 'absolute' but if first rotated to a continent held fix (see 'Add Euler Poles' above) then you can use a VGP from that continent to all rows in the animation file and thus make your own 'absolute' reconstruction.

The input-format in ANIMATION files is as follows:

- | | | |
|---|---------|--|
| 1 | CON | Name of continent ('.CON') file |
| 2 | LAT | Latitude of Euler Pole |
| 3 | LONG | Longitude of Euler Pole |
| 4 | ANGLE | Rotation angle about Euler Pole (+)=clockwise;(-)=counterclockwise |
| 5 | COMMENT | Comment (any text) |

8. VELOCITY

The main purpose of this option is to calculate latitudinal drift-rates and rotational velocities for continents or terranes. This option (*old and not updated yet*) is found in 'VGP Table' and 'Tools' and options are as follows:

OPTION/SUBOPTIONS	EFFECT
Exit	Return to 'VGP Table' menu
VGP Open VGP file Merge VGP file Analysis 1: Velocity and Angular Rates Analysis 2: APW rates HPGL (write to file) 	Open a VGP file from disk Open a VGP file from disk; displayed together with existing VGP data in subsequent graphic actions Calculate and displays palaeolatitude, drift-rates and angular rotation Calculate and displays APW Copy graphics to HPGL plotter or file
Print	
Settings 	Set system parameters that control the program performance (automatically stored during 'Exit')
Timescale Use Gradstein et al. (2004) Build your own 	Gradstein et al. (2004) Modify timescale (auto-saved to a system file)
Polarity Bias 	

3.20.1 DRIFT/ANGULAR RATES

Based on a sequence of ordered (sorted with increasing magnetic ages) VGP poles (either original data or APW spline data) this option provides an analysis and display of palaeo-latitudes for a given reference locality (see 3.20.2) through geological time (top diagram in Fig. 16).

Analysis of APW paths:

If the VGP file contains an APW or 'spline' path (cf. 3.11.3) parameter 'APW path or spline' (see 'SETTINGS'; cf. 3.20.2) and parameter 'Plot declination' should be set to on. This will produce a display as illustrated in Fig. 16 (VGP file B20092; used for Baltica by Torsvik et. al. 1992) where declinations (according to a reference locality: 60oN and 10oE in our example) are plotted along the latitudinal drift-curve (i.e. a natural cubic spline curve). Based on the setting of the 'Time Window' parameter (cf. 3.20.2) this option calculates latitudinal drift-rates (in cm/y) and rotational velocities (in o/Ma). Drift-rates are automatically separated into Northward (UPPER part of diagram) or Southward (LOWER part of diagram) movements (middle diagram in Fig. 16), whereas rotational velocities are separated as clockwise (UPPER part of diagram) or counter-clockwise (LOWER part of diagram) rotations.

Analysis of original data:

If the VGP file contains original data, the parameters 'Original data' and 'Plot latitude error' (cf. 'SETTINGS'; 3.20.2) should be set to on. This produces a display as illustrated in Fig. 17 (VGP file Bal92; used for Baltica by Torsvik et. al. 1992) where palaeo-latitudes (according to the reference locality) are plotted with error bars (based on alfa95).

FIG 16 Example of option 'VELOCITY' (VGP file:B20092) using an APW spline path.

FIG 17 Example of option 'VELOCITY' (VGP file:BAL92) using original data.

3.20.2 SETTINGS

This option permits the adjustment of parameters which control the 'Velocity' option performance. The following parameters can be changed/updated:

PARAMETER	FUNCTION
-----------	----------

Reference latitude (in degrees) Palaeolatitudes, drift-rates and angular velocities Reference longitude (in degrees) are always calculated with respect to the selected reference locality

Start Time (in Ma)	Whenever a VGP file is loaded the program tests for
End Time (in Ma)	minimum (start) and maximum (end) age range, and the horizontal time-axis (see Fig. 16) is set up accordingly. The operator can, however, change the START and
when End	END times after having loaded a VGP file. Useful combining several VGP files with different Start and times (i.e. plot at same scale)
Time window (in Ma)	Drift-rates and rotational velocities are averaged within the setting of this parameter
Invert Latitudes (Yes or No)	Dependent on the choice of VGP polarity the operator may have to invert latitude estimates. E.g. file B20092 is a south-pole file and 'Invert Latitudes' has to be set to
VGP 'Yes' Baltica	in order to display the latitudinal movements of correctly.
Plot Declination or Latitude error	Set 'Plot declination' to ON when analysing APW paths:
original to INC-95).	Use 'Latitude Error' to include latitude error bars for VGP data (calculate error bars from INC+95 to INC-95).
APW path/spline or Original data	Set 'APW path/spline' to ON when analysing APW paths
Expanded Latitude plot (Yes/ No)	Display of latitudinal plot (top diagram) two times normal size when set to YES
Amplitude Latitude Plot (in Deg)	Set maximum amplitude (90<value>0)
Amplitude drift-velocity (in cm/yr)	Set maximum amplitude (Value>0 cm/yr)
Amplitude rotation plot (in o/Ma)	Set amplitude (Value>0 Deg/Ma)
Amplitude CUM APW (in Deg)	Set amplitude (value >0)
(used in option 'APW rates')	
Amplitude APW rate (in cm/year)	Set amplitude (value>0 cm/yr)
(used in option 'APW rates')	