



Central Florida Urology Associates

Michael D. Friedman, M.D., F.A.C.S.
Diplomate American Board of Urology
Charles N. Witten, M.D., F.A.C.S.
Diplomate American Board of Urology


Trimix Injection Instructions

STEP 1: GETTING SET UP

1. Proper hygiene is important. Wash your hands and keep the penis clean.
2. Assemble the following:
 - o Bottle of Trimix
 - o Alcohol pad
 - o Syringe
3. Keep the Trimix cold by returning the bottle to the refrigerator, or by placing the bottle in a cup of ice.

STEP 2: PREPARE THE SYRINGE

1. Wipe the rubber top of the vial with an alcohol pad.
2. After removing the cap of the needle, pull the plunger back to the desired dosage, filling this volume with air. Use a new needle and syringe each time.
3. Insert the needle through the rubber top and inject the air into the vial.
4. Turn the vial with needle and syringe inserted upside down. Pull back on the syringe plunger in a slow and steady motion until the desired dosage is achieved.
5. Tap the side of the syringe (1cc tuberculin syringe with a 29 gauge needle) to allow any air bubbles to float towards the needle. Avoid having these air bubbles in the syringe when self-injecting by first injecting out the collected bubbles that may form.
6. Remove the needle from the bottle and replace the protective cap on the needle.




STEP 3: SELECT AND PREPARE THE SITE FOR INJECTION


210 Rinehart Road, Suite 1000
Lake Mary, Florida 32746
(407) 332-7700
Fax: (407) 332-9749

1027 Town Center Drive
Orange City, Florida 32763
(386) 774-1777
Fax: (386) 456-1206

1. The proper location for injection is at the **9-11 and 1-3 o'clock** positions, between the **base and mid-portion** of the penis. (see diagram) **Avoid** the midline because of potential for injury to the urethra (6 o'clock; for urinary passage) and the penile arteries and nerves (near 12 o'clock). **Avoid** any visible veins or arteries on the surface.



2. Grasp and pull the head of the penis toward the side of your leg with the index finger and thumb (use the left hand, if right handed). While maintaining light tension, select a site for injection.
3. Clean the site with an alcohol pad.



STEP 4: INJECT TRIMIX AND APPLY COMPRESSION

210 Rinehart Road, Suite 1000
Lake Mary, Florida 32746
(407) 332-7700
Fax: (407) 332-9749

1027 Town Center Drive
Orange City, Florida 32763
(386) 774-1777
Fax: (386) 456-1206

1. With a steady and continuous motion, penetrate the skin with the needle at a **90 ° angle**. The needle should then be advanced to the hub. Slight resistance is encountered as the needle passes into the proper position within the erectile tissue (corporeal body).
2. Inject the Trimix over approximately 4 seconds. Withdraw the needle from the penis and apply compression to the injection site for approximately 1 minute. Several minutes of compression may be required to avoid bleeding, especially if you are an aspirin user.
3. Replace the cap on the needle and dispose of properly.

If your erection lasts longer than 3 hours, contact our office at 407-332-7700 so we can instruct you on what needs to be done.

210 Rinehart Road, Suite 1000
Lake Mary, Florida 32746
(407) 332-7700
Fax: (407) 332-9749

1027 Town Center Drive
Orange City, Florida 32763
(386) 774-1777
Fax: (386) 456-1206