

LDIOOPROOF USER MANUAL



DESCRIPTION

Lyrical Distortion is proud to present LDi 100 Proof, a 1994 PRS Custom 22 electric guitar, recorded direct via Countryman Type 85 Active Direct Box, Great River ME-1 NV, Apogee Rosetta and programmed in Kontakt 2.2.4 to be easily played from any MIDI controller (88 keys recommended) or sequencer through an amp or amp simulator.

LDi 100 Proof is produced by Aaron Dirk and Stephanie Pray. Scripting by Günter "The Grey" Hirscher.

LDi 100 Proof represents a unique sounding instrument, sampled with incredible depth and playability. For LDi 100 Proof we sampled four variations of every note for every articulation, utilizing random cycling for authentic swift repetitive lines. The patches include single note picking, single note hammer-on's, performed power-chords (I and V) and more. Also, all patches are available as performed palm-mutes as well as non-muted. The range of possibilities with LDi 100 Proof is like that of no other sampled guitar library currently available.

PLAYING TECHNIQUES

LDi 100 Proof presents single notes and performed power-chords played in the following techniques:

- picked
- palm-muted
- hammer-on

There is no vibrato but the notes are very alive and natural. When picked the notes are not muted and can sustain for some time before naturally decaying.

When palm-muted the single notes are picked while part of your hand is applying pressure to the string. This mutes the sustain of each note and the natural decay happens much quicker. When the palm-mute is applied, the resulting sound is heavier than when not muted.

When hammering the single notes, you pick one note and then move your finger to a new fret. This movement to a new fret creates a unique legato attack. This is called a 'hammer-on' attack. The attacks on these patches are not as hard as they are when picked; this playing technique is often utilized for soloing or performing swift lines.

The best use of the 'hammer-on' patch is in conjunction with the single note sustains. The first note of a legato line should be from the picked patch and the following notes should be from the hammer-on patch.

The above also applies to the performed power-chords (I and V). Keep in mind that four variations of each note were recorded and programmed to replicate a natural performance.

INCLUDED ARTICULATIONS

- · Pick sustain
- Palm mute
- Hammer-on
- Palm Hammer On
- · Powerchord Sustain
- Palm Powerchord
- Powerchord Hammer On's
- Palm Powerchord Hammer On
- Muted Strings Down
- Muted Strings Up
- Release notes of a note de-fretting
- Release notes of finger movement
- Assorted pick scraps, slides and fx of a guitar

SETUP

1994 PRS Custom 22

Black cherry

Quilted maple "10" top

One piece mahogany neck and back

Wide fat neck 1 11/16"

Rosewood fingerboard with bird inlays

25 inch scale with 22 frets

Dragon pickups

GHS Guitar Boomer Strings 010, 013, 017, 026, 036, 046, 053

Countryman Type 85 Active Direct Box

Great River ME-1 NV microphone pre amp

Apogee Rosetta 24bit A/D converter

Direct un-processed 24bit 44.1 samples

Shizit1 for LYRICAL DISTORTION DIRECT 100 proof

About

Combining different playing techniques (articulations) is one of the keys to achieve realistic results with sample libraries. As a trade off, the more articulations, the more difficult the handling will be. LD 100 proof offers several different articulations and comes with a lot of different patches. For more details please read the user manual.

The patches for **LDi 100 Proof** described in this document have been created to make it faster and easier to access the main articulations and combine them by using the script feature of **KONTAKT2 and 3**.

The **basic concept** is that the script does automatically switch between the PICK- and HAMMER-Sounds by the way you play:

- If you play non-legato (non overlapping notes), the script will select PICK-Sounds.
- If you play legato (overlapping notes), the script will select the HAMMER-Sounds.

There are additional features which makes the patches more flexible. Please read the following pages to get the most out of the additional features.

Have fun! Günter Hirscher Vienna, November 2005


Features of the KONTAKT2 script:

- AUTO LEGATO auto switch between PICK- and HAMMER-sounds
- Key switches to override / modify the default LEGATO mode. This allows you to play the following articulations:
 - o PICK
 - o HAMMER
 - o PALM PICK
 - PALM HAMMER

- POWERCHORD
- POWERCHORD HAMMER
- POWERCHORD PALM PICK
- POWERCHORD PALM HAMMER
- SOLO 3 modes: off / Solo 1 / Solo 2
- STACCATO mode repeating the same note on different keys allows you to play fast staccatos.
- RESET to script default values
- Random Cycle with no repeat- this elimanates cycle patterns and syncing both guitars associated with Round Robin cycle
- •TRILL Hold G0 keyswitch and the first key you press now will be memorized and always retriggered if you release a key (sounds best in combination with force hammer). This "base" note will be retriggered as long as you hold the TRILL key
- MOD WHEEL switches between release samples on the lower part of the mod wheel, cross fades from notes to muted strings on the upper mod wheel
 - 0 nothing
 - 1 32 release
 - 33-64 finger noise release
 - 65-127 cross fade from notes to dn/up muted strings

Solo Mode

In my opinion, LD1 sound best when played monophonic. To add flexibility, I have added 3 options you can select in field SoloMode:



1. Solo Mode 0

You can play LD fully polyphonic. If Solo Mode = 0 then the Solo button (see below) is disabled, because there is nothing you can turn on/off.

2. Solo Mode 1

the sustain pedal down is monophonic, a really great feature for repetitive notes and realtime playing

3. Solo Mode 2

: the sustain pedal down works normal, except repetitve notes are monophonic, like a real guitar

Advanced KONTAKT2 patches for LYRICAL DISTORTION 1

THE BUTTONS

There are several buttons to add flexibility and/or change the default behaviour of the script. Except for the "RESET" button, there is a key – switch (actually 2, one low = left hand and one high = right hand) assigned to each button.



Although you can change the state of the buttons with your mouse **I** strongly recommend using the keyboard only, especially if you record your performance with your sequencer. Pressing a button with your mouse will not generate a midi event and will not be recorded in your sequencer.

SOLO on/off Solo

If you have selected Solo Mode 1 or 2 you can switch Solo on/off while you play with F#0 or B5 on your keyboard. By default, SOLO is activated.



You can turn on/off the auto-switch function between PICK and HAMMER sounds with the G#0 or C6 on your keyboard. If LEGATO is off you still can switch between the different sounds (see below), but regardless if you play legato or non-legato, there will be no auto-switch.

PICK / HAMMER / POWER / PALM

This four buttons are the most important because they allow you to quickly change the sounds while you play. In default mode, if none of these keys is pressed (and LEGATO is on), the script will autoswitch between PICK and HAMMER sounds. You can also use combinations of these keys to get i.e. the POWER PALM PICK sound. The table below shows the different possible combinations:



Advanced KONTAKT2 patches for LYRICAL DISTORTION 1

Key-switch low (left hand)	Key-switch high (right hand)	Auto- switch	Non legato	Legato
-	-	Yes	Pick	Hammer
C#0	F#5	Yes	Palm Pick	Palm Hammer
E0	A5	Yes	Power Pick	Power Hammer
C#0+E0	F#5 +A5	Yes	Power Palm Pick	Power Palm Hammer
CO	F5	No	Pick	Pick
D0	G5	No	Hammer	Hammer
C0 + C#0	F5 + F#5	No	Palm Pick	Palm Pick
D0 + C#0	G5 + F#5	No	Palm Hammer	Palm Hammer
C0 + E0	F5 + A5	No	Power Pick	Power Pick
D0 + E0	G5 + A5	No	Power Hammer	Power Hammer
C0 + C#0 + E0	F5 + F#5 + A5	No	Power Palm Pick	Power Palm Pick
D0 + C#0 + E0	G5 + F#5 + A5	No	Power Palm Hammer	Power Palm Hammer

There are 2 different modes for these keys:

In default mode you must hold the keys while you play you i.e. if you press CO or F5 (= PICK) and hold the key all the following notes will be played with the pick sound. If you release the key the script will switch back to the default mode.

Alternatively you can lock these keys (all or individual). Let's assume you want to play with the POWER CHORDS (and its variations) only. Press E0 or A5 and at the same time D#0 or G#5. If you now release the keys the POWER CHORDS will stay active until you press the key again.



If you press D#0 or G#5 without any of the PICK/HAMMER/POWER/PALM keys all keys will be unlocked.



This function allows you to play fast repetitions of the same note using more then one key on your keyboard. Sounds strange? Try the following: Press and hold F0 or A#5 and then press i.e. C1, D1, E1, D1 (play legato!). All the notes will be the C1!

Advanced KONTAKT2 patches for LYRICAL DISTORTION 1



Pressing this button (there is no key assigned to this button) will reset all settings to the default values.

End User License Agreement

Please read this agreement before using this sample library. By downloading and installing this product, you acknowledge and affirm that you have read this license agreement, understand said agreement and agree to the terms and conditions herein. If you do not understand or agree to the terms and conditions of this agreement, do not download, install or otherwise use the content contained in the library. This is the complete agreement between you and Lyrical Distortion, and there are no other representations, warranties, guarantees or prior agreements, whether oral or in writing, express or implied.

It is imperative that you understand that YOU ARE GRANTED A LICENSE FOR YOUR USE ONLY AND THAT YOU DO NOT OWN THE CONTENT CONTAINED IN THE LIBRARY. The sounds, samples and programming contained in the Lyrical Distortion library remains the sole property of Lyrical Distortion, and are licensed (not sold) to you.

Permitted Uses:

- 1) You may use the contents of the Lyrical Distortion library as often as you would like.
- 2) You may use the contents in any of your musical compositions, whether or not the compositions are released commercially. There will be no additional fees or royalties for such use. Whenever possible, credits (film credits, CD inserts, etc.) would be greatly appreciated.
- 3) You may create a data backup of this library for your personal use.

Impermissible Uses:

- 1) You may not duplicate and/or copy said library.
- 2) You may not resell said library.
- 3) You may not share said library.
- 4) You may not upload said library to any form of Peer-to-Peer Internet file sharing service.
- 5) You may not resample said library and/or create any form of sample library product with said samples.
- 6) You may not redistribute said library.

End User License Agreement (Continued)

A right to use the Lyrical Distortion library is granted to the original enduser only, and this license is not transferable without the written consent of Lyrical Distortion. Additional fees for such transfer may apply.

The Lyrical Distortion library is compatible with Kontakt 2.2.4 and higher, and is NOT compatible with any other sampler.

Lyrical Distortion is not responsible if the content of the library is not suitable for your intended purpose. The library is licensed "as is" and is without any warranties of any kind. Lyrical Distortion assumes no liability whatsoever for any loss or damages resulting from the use of this library.

Please be sure that the library will meet your needs and that your system meets the minimum requirements for use before placing your order. There are no refunds on downloaded purchases.

This Agreement is subject to change at any time, with or without notice. This Agreement does not represent a commitment of any kind on the part of Lyrical Distortion.

The terms and conditions contained in this agreement apply to all Lyrical Distortion products.

Your failure to comply with the terms and conditions of this agreement will result in the revocation of this license and may result in litigation to recover loss and damages to Lyrical Distortion caused by your said failure to comply with the terms and conditions contained herein.