


Copyright © 2002-2013 by VeryDOC.com, Inc

User Manual of VeryDOC PDF Stamp

Software Brochure

VeryDOC.COM



Contents

General introduction	3
Operating Systems	3
GUI User guide	3
Download and install	3
Launch GUI interface.....	3
Add PDF files	3
Set text stamp.....	4
How to set text content.....	4
How to edit dynamic text content	4
How to optionally delete added text.....	5
How to set text stamp position	5
How to rotate text stamp	5
How to set display pattern of text stamp	5
How to add action onto text stamp.....	6
How to set text font type	6
How to edit text font color	7
How to edit text alignment.....	8
Set image stamp	8
How to add basic image	8
How to set image stamp position	9
How to set width/height scale of image stamp.....	9
How to rotate image stamp	9
How to set display layer of image stamp	10
How to add action to image stamp.....	10
How to delete edited image stamp	11
Set graphic stamp.....	11
How to add graphic lines.....	11
How to set line length	11
How to set length scale	11
How to edit line width.....	12
How to edit line color.....	12
How to rotate line stamp	13
How to set display layer of graphic lines	13
How to fasten line stamp in specific position	13
How to delete edited graphic line stamp	14
Optionally specify PDF page range to stamp.....	14
How to prepare all pages to stamp	14
How to prepare specific pages to stamp.....	15
Optionally set stamped PDF saving mode	15
How to set targeting folder when starting process to stamp.....	15
How to overwrite source PDF files with stamped ones	15
How to get stamped PDF files and backup files of original PDF files.....	15

How to define targeting folder and filename usually	15
How to preview stamped PDF after process	15
Menu bar on GUI interface	17
File	17
How to monitor directories more professionally	17
Edit	19
Option	20
Help	20
Others	20
CMD User guide	21
Download	21
Usage	21
Template	21
Explanation	21
Parameters/Options	22
Command line examples	22
Contact us	26

General introduction

VeryDOC PDF Stamp enables you to use GUI and command lines to stamp PDF files with text, image and graphics, including lines and rectangles, etc. separately or together on Windows platforms. Generally, **VeryDOC PDF Stamp** provides GUI, CMD and COM versions, and the previous versions could be used by average users, and COM version is specifically applied in application design with supported functions on GUI and CMD. And this manual would like to tell you how to use GUI and CMD to simply stamp PDF files on your own.

Operating Systems

Both 32-bit and 64-bit Windows 98/ME/NT/2000/XP/2003/Vista/7/2008

GUI User guide

Download and install

Firstly, download [installer of VeryDOC PDF Stamp](#), then double-click installer > follow setup wizard to install trial version software in your computer directly.

Launch GUI interface

After installation, double-click software shortcut so that GUI interface is opened on screen for later stamp.

Add PDF files

On opened GUI interface, there are three ways to add PDF files:

- Click **Add PDF Files** on GUI interface > select PDF files in pop dialog box > click **Open**
- Click **Add Directories** on GUI interface > select folder containing numerous PDF files you need to stamp in pop dialog box > click **OK**
- Drag PDF files from one folder, and then, drop them into processing form directly

Finally, selected PDF files in the form of files or folder, can be added as directories in processing form:




Fig1. GUI interface with added PDF files

Set text stamp

If you need to stamp PDF with text, please click tab **Text Stamp** on GUI interface to achieve setting with this way:

How to set text content

- To edit text content, just customize text in edit-box below display table, then, to add it into display table to prepare for text stamp, click **Add**

How to edit dynamic text content

- To add dynamic text content, e.g., local data, page numbers, title, author, etc., please select one of dynamic text content types on pop list **Dynamic Text**




Fig2. Dynamic text content list

How to optionally delete added text

- Optionally, to delete added text, click displayed text in display table > click **Del**

How to set text stamp position

To edit text stamp position, just select one of options on pop list **Position**, e.g., Top-Left of the page (default); to edit translate in X and Y, please input specific values in related edit-boxes




Fig3. Text position list

How to rotate text stamp

- To rotate text stamp, type rotation in edit-box **Rotate**

How to set display pattern of text stamp

- To set text display pattern based on layers, just choose **overlay** or **underlay** in order to stamp text above original PDF content or below original PDF content



Fig4. Text display pattern list

How to add action onto text stamp

- To add action onto text stamp for users' convenience, e.g., hyperlink adding, specific page jump or open targeting file, just select related option on pop list **Action** > type URL in edit-box **www.Link** if selecting **www.Link**, input page number in edit-box **Page No.** suppose click on **gotopage** or select one file in pop dialog box after one click on  to make file path appear in edit-box **Filename** so that this file can be attached




Fig5. Text action list

How to set text font type

- To set text font, just click radio **Adobe Font** > select one font name on dropdown list, e.g., Times-Roman, or Times-Italic, etc., then, text font type could be one of Adobe ones; or click **radio System Font**, then, one of system fonts in your computer can be called directly with the help of  and setting on pop Font panel



Fig6. Text font type based on Adobe Font




Fig7. System font panel

How to set text font size

- To set text font size, type font size in edit-box **Size**, e.g., 16, etc.; optionally, to edit text outline, just click check-box **Outline**

How to edit text font color

- To select text font color, please click to select one color on pop Color panel




Fig8. Pop color panel for select proper color of text stamp

How to edit text alignment

- To edit text alignment, click Left Align/Center Align/Right Align on pop list **Align** directly



Fig9. Text alignment list




Fig10. Set text stamp with options mentioned above

Note: It is possible to set various text stamp one by one following tips in this step, and it is suitable to apply changed settings by click on **Edit** after any setting rectified

Set image stamp

If you need to stamp PDF with images, please click tab **Image Stamp** on GUI interface to fulfill setting with operations below:

How to add basic image

- To add image, please click **Add** > select image file in pop dialog box > click **Open**, then, selected image could be displayed in **Image Stamp List**; to add another image, just repeat previous actions

How to set image stamp position

- To set image position in PDF, just click one of default positions on pop list **Position**, e.g., Top-Center of the page, etc.; besides that, typing integers in edit-boxes **Translate X** and **Translate Y** enables you to fasten image stamp more accurately




Fig11. Image stamp position list

How to set width/height scale of image stamp

- To set image width scale and height scale in order to zoom in/out image display, clicks on one of provided integers on pop list **Width Scale** and **Height Scale** directly lead to proper scale of whole image stamp




Fig12&13. Image stamp list of width scale and height scale

How to rotate image stamp

- To set specific rotation on image stamp, it is easy to type rotation degree in edit-box **Rotate** directly, e.g., 30, etc.

How to set display layer of image stamp

VeryDOC PDF Stamp supports displaying stamp above or below PDF original content, all you need to do is to select **Overlay** to lay image stamp above PDF content, or select **Underlay** to lay image stamp below PDF content on pop list **Layers**



Fig14. Display layer list of image stamp

How to add action to image stamp

- To add action on image stamp, just select one between provided options on pop list **Action**, and the following snapshot is about supported actions:



Fig15. Image stamp action list

Note: to add action to open file on image stamp, just click open file on pop list **Action** > select one image in pop dialog box after click on > click Open in pop dialog box, or just type targeting file path in edit-box **Filename**




Fig16. Set image stamp in mentioned aspects above

Note: It is available to stamp PDF with dozens of images, and it is suitable to apply changed settings by click on **Edit** after any setting rectified

How to delete edited image stamp

- To remove finished image stamp, please click image path in stamp list > click **Del**

Set graphic stamp

- To stamp PDF with graphic lines, please click tab **Line Stamp** on GUI interface to accomplish related operations below:

How to add graphic lines

- To add graphic line, click **Add** directly so that graphic line can be displayed in related table

How to set line length

It is easy to click **Page Width** or **Page Height** on pop list **Line Length=** to set line length directly



Fig17. Line length list

How to set length scale

There are numerous scales program provides, all you need to do is to select one on pop list **Length Scale**




Fig18. Length scale list

How to edit line width

Integer typed in edit-box **Line Width** results in graphic line width directly, and the bigger you set integer, the bigger line width is

How to edit line color

- To edit line width, directly click on results in pop color panel as shown in following snapshot, then, it is easy to select one or customize one color on color panel > click **Ok** to realize color setting




Fig19. Pop color panel for line stamp color

How to rotate line stamp

If inputting integer angle in edit-box **Rotate**, graphic line will rotate around central point of line accurately

How to set display layer of graphic lines

VeryDOC PDF Stamp provides two display modes – overlay and underlay: to make line displayed above PDF content, please click **Overlay**; to make line displayed below content, please click **Underlay**



Fig20. Display layer list of line stamp

How to fasten line stamp in specific position

One way to fasten line is to select one provided mode on pop list **Position** so that it could be easily fastened in popular position, e.g., Bottom-Center of the page, etc.




Fig21. Selected line stamp position list

Another path to fasten line in detail, is, to type integers in edit-boxes **Translate X** and **Translate Y**, thus, line position could be laid more accurately




Fig22. Set graphic stamp as mentioned above

How to delete edited graphic line stamp

- To remove prepared graphic line, just click line path in display form > click **Del** one by one

Optionally specify PDF page range to stamp

Sometimes, it is of need to set special pages of PDF to stamp, for this function, please refer to the followings:

After click on tab **Global** on GUI interface, it is simple to prepare which pages to process with several ways.

How to prepare all pages to stamp

- In **Page Range**, click on radio **All Pages** enables all pages of added PDF to be processed later

How to prepare specific pages to stamp

In **Page Range**, to prepare single page to stamp, please type page number in edit-box **Page** directly after click on radio **Page**

- To set odd pages to stamp, please click radio **Odd Pages**
- To set even pages to stamp, please click radio **Even Pages**
- To set first page to stamp later, click radio **First Page**
- To set last page to stamp later, click radio **Last Page**
- To edit continuous specified pages for stamping, please click radio **From Page** > input page numbers on the both sides of **To** directly, e.g., 1, and 6, etc.

Optionally set stamped PDF saving mode

It is easy to set saving mode under tab **Global**:

How to set targeting folder when starting process to stamp

In **Save Mode**, click radio **Always ask me** helps you realize this setting, then, you need to select destination folder after click on **Stamping** on GUI interface > select folder in pop dialog box with one click on **OK**

How to overwrite source PDF files with stamped ones

To overwrite original PDF, please click radio **Stamp PDF files and overwrite original files**

How to get stamped PDF files and backup files of original PDF files

To get backup original files, please select radio **Stamp PDF files and backup original files(.bak)**

How to define targeting folder and filename usually

To customize targeting folder here, click radio **Save to following directory** > type targeting path in edit-box **Browse** or click **Browse** button to follow it till the end

How to preview stamped PDF after process

Selecting check-box **View after stamp** helps to automatically pop stamped PDF preview after stamping




Fig23. Set specific PDF pages and saving mode with preview check of stamped PDF




Fig24. GUI interface of processing PDF with edited stamps

Menu bar on GUI interface

File

- **Add Files** offers you same function as Add PDF Files button
- **Add Directories** provides same function as set on Add Directories button
- Function of **Stamping** is equal with button Stamping on GUI interface
- **Preview PDF File** helps you open original PDF on screen
- **Exit** helps you exit from GUI interface




Fig25. Pop list of File

- Especially, **Monitor Directories (Stopped)...** provides another essential function of VeryDOC PDF Stamper, so, it is proper for you to check **How to monitor directories more professionally**

How to monitor directories more professionally

After click on **Monitor Directories (Stopped)...**, you can get interface as shown in following snapshot:





Fig26. GUI interface of VeryPDF PDF Stamper Directories Monitor Tool

- To set source folder and targeting folder, please click **Add**, then **Setting** panel pops on screen, where you can do the followings flexibly:
 - Type source directory in edit-box **Input Directory** or click **Browse** to follow steps till the end to add source PDF files in one folder
 - Input targeting directory in edit-box **Output Directory** or click **Browse** to realize setting destination folder
 - To operate original PDF before stamping, and upgrade PDF files to move them into another folder, please click one of displayed measures on pop list **Operation types** > type folder path in edit-box **Move to following directory** or click **Browse** to follow its steps till the end



Do nothing
Upgrade to Acrobat 4, and move new PDF to another folder
Upgrade to Acrobat 5, and move new PDF to another folder
Upgrade to Acrobat 6, and move new PDF to another folder
Upgrade to Acrobat 7, and move new PDF to another folder

Fig27. Operation types for upgrading PDF or not on pop list Operation Types

- To operate original PDF files after stamping, please select one of provided options on pop list **Operation types** as displayed in following snapshot, and of course, it is supported to rename original PDF and backup original PDF if you click related mode on pop list here:



Rename original PDF to .bak file
Delete original PDF file
Move original PDF file to another folder

Fig28. Pop list of Operation types under Operate original PDF file AFTER stamp

- To move original PDF into another folder, please input folder path in edit-box **Move to following directory** under **Operate original PDF file AFTER stamp** or just click **Browse** there to follow steps
- To save setting on this panel, click **Ok**; to cancel setting here, click **Cancel**
- To delete input information shown in display table, please click information there in that form > click **Delete** on interface directly
- To rectify what you set just now, please click **Modify** on interface > reset what you need on Setting panel directly as mentioned above
- To make setting on Setting panel effective, please click **Ok**, and then, based on setting with supported stamps as mentioned before and operations on directories tool, later on, all you expect can be added into destination folders you set just now; to give up on setting here, please click **Cancel** on interface; to close this main interface, please click 




Fig29. Interface of VeryDOC PDF Stamper Directories Monitor Tool

Edit

- Click on **View Original PDF** or click hotkey **Enter** helps you view original PDF, after click on PDF path

View Original PDF	Enter
View Stamped PDF	
Move Up	CTRL+O
Move Down	CTRL+P
Delete Selected Items	Del
Clear All Items	

Fig27. Pop list of Edit

- Click on **View Stamped PDF** on **Edit** list helps you preview stamped PDF, after click on PDF directory
- To adjust display order and processing sequence of added PDF files, just click PDF path > click **Move Up** or **Move Down** on Edit list, or click hotkey **Ctrl + O** or **Ctrl + P** directly after click on PDF path
- Click on **Delete Selected Items** or hotkey **Del** help you delete selected PDF files, after click on PDF directories
- Click on **Clear All Items** enables you to remove all added PDF files one time

Option

- **Save Stamp Profile** helps you save PDF stamp files – SPF with pop dialog box where setting destination folder
- **Load Stamp Profile** helps you open PDF stamp file - SPF




Fig28. Pop list of Option

Help

- **Help** is set for jumping to software help webpage
- **Register** is set to make register window pop out to register software




Fig29. Pop list of Help

- **Buy now** leads to software homepage for you to purchase it
- **Technical Support** helps you open MS Outlook to get support by email
- **On the web** allows you to go to software homepage
- **About** helps you view company info, support email address, as well as design date

Others

- One Click with right button of mouse on added PDF path
- **Add Files** on pop list has the same function as Add PDF Files button
- **Add Directory** on pop list has the same function as Add Directories button
- **Stamping** is the same as button Stamping on GUI interface
- **Preview PDF File** is set to help you preview stamped PDF file
- **View Original PDF** is designed for original PDF preview
- **Move Up/Move Down** is designed to change PDF display sequence, as well as processing order

Add Files	Inter
Add Direcotry	
Stamping	
Preview PDF File	
View Original PDF	Enter
View Stamped PDF	
Move Up	CTRL+O
Move Down	CTRL+P
Delete Selected Items	DEL
Clear All Items	

Fig30. Pop list by click on added PDF path located in file list

- **Delete Selected Items**/hotkey **Del** is set to remove selected PDF file
- **Clear All Items** is set to remove all added PDF files together

CMD User guide

Download

Please download [package of VeryDOC PDF Stamp Command Line](#), then extract its content from package to your computer so that executive file pdfstamp.exe could be called later for your process.

Usage

Open Command Prompt in your computer, then you can refer to the template to get your conversion processed:

Template

```
Pdfstamp.exe -PDF <source PDF> -o <targeting PDF> [options]
```

Explanation

- pdfstamp.exe: executive file to be called to run software
- -PDF <source PDF>: specify input PDF file

Note: if inputting dozens of PDF files for batch process, just use -PDFS <input dir>

- -o <targeting PDF>: specify output PDF file

Note: if outputting dozens of stamped PDF files after batch process, just use -o <output dir>

- [options]: optionally set stamped PDF properties, e.g., stamp PDF with texts, stamp PDF with images, or stamp PDF with graphic lines, etc.

Parameters/Options

In this part, most parameters VeryPDF PDF Stamp Command Line supports, will be shown to you here:

-AT <string>	Create a text Stamp
-FT "font name"	select a system font installed in your system, for example, -FT "Arial"
-FS<int>	Set font size, default is 16 point, e.g.,-FS16
-P1	Stamps on the Top-Left of the page. (default)
-P2	Stamps on the Top-Center of the page.
-P3	Stamps on the Top-Right of the page.
-P4	Stamps on the Right-Center of the page.
-P5	Stamps on the Right-Bottom of the page.
-P6	Stamps on the Bottom-Center of the page.
-P7	Stamps on the Left-Bottom of the page.
-P8	Stamps on the Left-Center of the page.
-P9	Stamps on the Center of the page.
-Opacity	(default is -opacity100), specify the opacity for stamps, range from 0 to 100, this option will apply a transparent watermark into PDF file.
-AI<string>	Stamp image to PDF, e.g., -AI "C:\image.jpg"
-AL	Stamp graphic lines to PDF
-C<int>	(default is -C0), Specify graphic line color, range from 0x000000-0xFFFFFFFF, in decimal system, .e.g -C255
-LineEx (x1,y1,x2,y2)	Draw a line from (x1,y1) to (x2,y2), eg, -LINEEX 100,100,200,200
-LW<int>	(default is -LW1), set graphic line width, e.g ., -LW3
To set text color	Just type hexadecimal to define color, e.g., -C#FF0000, -C#00FF00, -C#0000FF, etc.

Command line examples

If you need to stamp PDF with specific text, image and graphics, just refer to following examples to type command line in Command Prompt as below:

Transparent function

```
pdfstamp.exe -PDF "example.pdf" -o "opacity.pdf" -AT "VeryPDF Opacity" -FT "Arial" -P9 -FS100 -opacity50 -C#FF0000 -AI logo.jpg -opacity80 -P2 -AL -LW30 -opacity30 -LINEEX 100,100,200,200
```

Encryption function

```
pdfstamp.exe -newlayer "VeryPDF New Layer" -PDF "example.pdf" -o "encryption.pdf" -AT  
"VeryPDF New\nLayer Test" -FT "Arial" -P9 -FS100 -opacity50 -R45 -C#0000FF -AI logo.jpg -  
opacity80 -P2 -AL -LW30 -opacity30 -LINEEX 100,100,200,200 -encrypt -openpwd=123  
-ownerpwd=456 -keylen=2 -encryption=3900
```

Bates Number function

```
pdfstamp.exe -PDF "example.pdf" -o "bates-numbers.pdf" -AT "Bates Numbers \B(0000105)" -p3  
-mlr-30 -mtb30 -fs10 -fn300 -c#FF0000
```

New layer function

```
pdfstamp.exe -newlayer "VeryPDF New Layer" -PDF "example.pdf" -o "newlayer.pdf" -AT  
"VeryPDF New\nLayer Test" -FT "Arial" -P9 -FS100 -opacity50 -R45 -C#0000FF -AI logo.jpg -  
opacity80 -P2 -AL -LW30 -opacity30 -LINEEX 100,100,200,200
```

PDFS function, batch stamping

```
pdfstamp.exe -PDFs "C:\*.pdf" -o "C:\out" -AT "An example for '-PDFS' parameter" -p2 -fs32 -  
c2666666 -mtb200
```

Page range function

```
pdfstamp.exe -PDF "example.pdf" -o "18.pdf" -SR -s-2 -e-2 -AT "Set which pages to stamp on by  
selecting a predefined range." -p2 -fs32 -c2666666 -mtb200
```

Link function

```
pdfstamp.exe -PDF "example.pdf" -o "17.pdf" -AT "Supports web links" -p2 -fs32 -c255 -mlr-50 -  
mtb200 -r15 -u "http://www.verypdf.com" -AT "Supports page links" -p4 -fs32 -c255 -mlr-50 -  
mtb200 -go 3 -AI "logo.jpg" -p9 -r15 -l -op "openlink.txt"
```

Line function

```
pdfstamp.exe -PDF "example.pdf" -o "16.pdf" -AT "\d\n\t" -fs10 -p7 -c255 -mlr70 -mtb-50 -AT  
"Page \p of \c " -fs10 -p5 -c255 -mlr-70 -mtb-50 -AT "2003 verypdf.com Inc." -p3 -mlr-60 -mtb60  
-fs10 -fn300 -c255 -AL -p2 -mtb80 -w80 -AL -p6 -mtb-80 -w80
```

Image stamp function

```
pdfstamp.exe -PDF "example.pdf" -o "15.pdf" -AI "logo.jpg" -p2 -r-45 -mlr80 -mtb200 -w300 -h300 -l
```

Text stamp function

```
pdfstamp.exe -PDF "example.pdf" -o "14.pdf" -AT "verypdf.com Inc." -p7 -fs48 -c165296 -r-45 -mtb-100 -AT "verypdf.com Inc." -p7 -fs48 -c1652962 -r-45 -mtb-200 -mlr50 -AT "verypdf.com Inc." -p7 -fs48 -c16529621 -r-45 -mtb-300 -mlr100 -AT "verypdf.com Inc." -p7 -fs48 -c165296210 -r-45 -mtb-400 -mlr150 -AT "verypdf.com Inc." -p7 -fs48 -c165210 -r-45 -mtb-500 -mlr200
```

Image rotation and position

```
pdfstamp.exe -PDF "example.pdf" -o "13.pdf" -AI "logo.jpg" -p9 -r-45 -mlr-70 -mtb-70 -AI "logo.jpg" -p9 -r225 -mlr70 -mtb-70 -AI "logo.jpg" -p9 -r135 -mlr70 -mtb70 -AI "logo.jpg" -p9 -r45 -mlr-70 -mtb70
```

Text rotate and position

```
pdfstamp.exe -PDF "example.pdf" -o "12.pdf" -AT "verypdf.com Inc." -p1 -fs48 -c65296 -r-45 -AT "verypdf.com Inc." -p3 -fs48 -c65296 -r45 -AT "verypdf.com Inc." -p5 -fs48 -c65296 -r-45 -AT "verypdf.com Inc." -p7 -fs48 -c65296 -r45
```

Web links

```
pdfstamp.exe -PDF "example.pdf" -o "11.pdf" -AT "Supports web links" -p2 -fs48 -c255 -mlr-50 -mtb200 -u "http://www.verypdf.com" -AT "Enabling you to easily position the stamp\n in any location on the page" -p4 -fs10 -c255 -mlr-50 -mtb200 -u "http://www.verydoc.com/"
```

Wrap text to a new line if it too long to fit in its margined area

```
pdfstamp.exe -PDF "example.pdf" -o "10.pdf" -AT "Wrap text to a new line if it would otherwise be too long to fit in its margined area." -p9 -fs64 -c2666666
```

Image stamp, vertical center

```
pdfstamp.exe -PDF "example.pdf" -o "9.pdf" -AI "logo.jpg" -p4 -r90 -mlr-10 -AI "logo.jpg" -p8 -r-90 -mlr10
```

Image stamp function

```
pdfstamp.exe -PDF "example.pdf" -o "8.pdf" -AI "logo.jpg" -p7 -mlr30 -mtb-30 -AI "logo.jpg" -p3 -mlr-30 -mtb30
```

Hollow tridimensional effect

```
pdfstamp.exe -PDF "example.pdf" -o "7.pdf" -AT "www.verypdf.com" -p9 -r45 -c2105376 -fs64 -mtb2 -mlr2 -l -h -AT "www.verypdf.com" -p9 -r45 -c255 -fs64 -l -h
```

Tridimensional effect

```
pdfstamp.exe -PDF "example.pdf" -o "6.pdf" -AT "www.verypdf.com" -p9 -r45 -c2105376 -fs64 -mlr1 -mtb1 -AT "www.verypdf.com" -p9 -r45 -c255 -fs64
```

Stamps can be placed in the exact vertical center of a page (or the exact vertical center within an individual stamping space)

```
pdfstamp.exe -PDF "example.pdf" -o "5.pdf" -AT "www.verypdf.com" -p9 -c65535 -fn101 -fs48 -AT "www.verypdf.com" -p8 -r90 -fs48 -c12345678 -AT "www.verypdf.com" -p4 -r-90 -fs48 -c12345678
```

Test Font Style, Font Size, Text Modes (solid, outline), Grayscale and RGB Color (0-255 RGB color values supported)

Place stamp under original PDF page contents

Text and Image can be stamped at any angle, any positive or negative numbers, including decimal numbers may be used to specify an angle in degrees

```
pdfstamp.exe -PDF "example.pdf" -o "4.pdf" -AT "www.verypdf.com" -p9 -r-20 -c13684944 -fs48 -fn201 -h
```

Grayscale Color (0-255 RGB color values supported)

Stamp at topmost or bottommost of the original PDF page contents

```
pdfstamp.exe -PDF "example.pdf" -o "3.pdf" -AT "Page \p of \c " -fs10 -p5 -AT "www.verypdf.com\n Demo" -p9 -r-45 -c13684944 -fs48 -l -fn301
```

Test Font Style, Font Size, Text Modes (solid, outline), Grayscale and RGB Color (0-255 RGB color values supported)

Top, bottom, vertical center, diagonal-top left and diagonal-bottom left

Test multiple line text stamps within one stamp item

```
pdfstamp.exe -PDF "example.pdf" -o "2.pdf" -AT "Sample File\nVeryDOC" -p3 -fn300 -AT  
"Copyright verypdf.com, Inc." -p6 -c255 -AT "www.verydoc.com\n Demo" -p9 -fn200 -r-45 -c255  
-fs48 -h
```

Text stamp page header and page footer

Stamps are placed in the duplicate file, leaving the original copy unchanged

```
pdfstamp.exe -PDF "example.pdf" -o "1.pdf" -AT "\d\n\t - (\f)" -fs10 -p7 -c255 -mlr50 -mtb-30 -  
AT "Page \p of \c " -fs10 -p5 -c255 -mlr-50 -mtb-30 -AT "2003 verypdf.com Inc.\n\F" -p3 -mlr-30  
-mtb30 -fs10 -fn300 -c2666666
```

Register PDFStamp Command Line

```
pdfstamp.exe -REG "Your registration key"
```

Contact us

Official Website: <http://www.verydoc.com/>

Email address: support@verydoc.com