



User Manual
for
ShortcutMe V3.0.0.4

Doc. Version: Preliminary
<http://www.shortcutme.com>

ShortcutMe is a product of Fonware Ltd.
<http://www.fonware.ca>



Table of content

<i>Overview</i>	<i>3</i>
<i>Features:.....</i>	<i>3</i>
<i>Screenshots:</i>	<i>4</i>
<i>Important Setups</i>	<i>6</i>
Convenience Key Setup:	6
License Key Setup (Activating ShortcutMe):.....	6
Multiple-Click Setup:	7
<i>Best ways to use the software.....</i>	<i>10</i>
<i>Add a new shortcut.....</i>	<i>11</i>
<i>Edit a shortcut.....</i>	<i>13</i>
<i>Insert a new shortcut.....</i>	<i>14</i>
<i>Move a shortcut.....</i>	<i>15</i>
<i>Remove a shortcut.....</i>	<i>17</i>
<i>Remove several shortcuts.....</i>	<i>18</i>
<i>Save shortcut settings in a file</i>	<i>20</i>
<i>Load shortcut settings from a file.....</i>	<i>21</i>
<i>More information? Didn't find what you were searching for?.....</i>	<i>22</i>

Overview


ShortcutMe is a must have application for your BlackBerry®. It makes your device extremely handy and user-friendly.

ShortcutMe is a response to what you always felt was missing with your BlackBerry®, ability to assign 6 applications to side keys (i.e. double click to lock your device, triple click to clean memory, double click to turn your blackberry® into a flash light), create your own shortcuts to quickly launch your favorite application from anywhere, or for calling, emailing or sending SMS/PIN to a friend, or even create shortcuts for a new Memo/Task, toggle the Wifi/Radio, open a favorite website.

Features:

- 52 out of the box, yet customizable shortcuts for major BlackBerry® applications.
- Assign 3 applications to each convenience key by double/triple/quadruple clicks.
- Assign 3 applications to ENTER-key (not for touch version).
- Assign single-letter shortcuts to your favorite tasks/applications.
- Shortcuts are active from anywhere, so press the shortcuts and fire an application without closing the current app.
- Create shortcuts for opening your favorite web pages.
- Create shortcuts for directly call/email/PIN/SMS a friend.
- Create shortcuts for opening a new Task or Memo.
- Create shortcuts for turning Radio and Wifi off/on.
- Double click the convenience key (from anywhere) to lock your BlackBerry®.
- Access to other applications while internet browsing without exiting the browser.
- Turn your BlackBerry® quickly to a Flash Light from any application.
- Avoid the annoying "Say a Command" voice because of the accidental convenience key clicks.
- No more worries about losing your shortcuts when upgrading/changing BlackBerry® or its software.
- User-friendly configuration process provided by Copy, Paste, Select, and Multitap in menus. (e.g. Copy a phone number from your AddressBook and paste it in SB to create a Call shortcut).
- Runs on any BlackBerry® that has trackball and runs 4.3+ OS software.
- QWERTY, QWERTZ, and AZERTY keypad support.
- Shortcuts can be created for following popular applications (and many more): Address Book, Alarm, BlackBerry® Messenger, Brick Breaker, Browser, Calculator, Calendar, Call Log, Event Log, Camera, Clock, Face book, Flash Light, Garmin Mobile, Global Search, Google Mobile App, Help, Home Screen, LBS, Lock, Manage Connections, Memo Pad, Memory Cleaner, Messages, My Space, Options, Phone, Profiles, Shazam, Tasks, TeleNav, Twitter Berry, Video Recorder, Voice Dialling, Voice Notes Recorder, and many other popular 3rd party applications.

Screenshots:



MultiClick Config.

Font Size For Config Pages: 7

Left Convenience Key

Double Click runs: CallLog

Parameter:

Tripple Click runs: AppSwitcher

Parameter:

Quadruple Click runs: Calculator

Parameter:

Right Convenience Key

Double Click runs: VoiceDialing

Parameter:

Tripple Click runs: Call

Parameter: 1 800

Quick Config.

-- To disable a shortcut, set it's App. Name to empty field (first item on the application drop-down list).

-- Space is only allowed at the end of the shortcut (i.e 'A1' and 'A 1' are NOT allowed, while 'A ' and 'AB ' are allowed)

-- A text like '&X' can be added to the 'Name in ()' field. That text is set by the program depending on the color you choose for this shortcut.

1: App. Name Alarm

Name in (): &m

Parameter:

Shortcut Char. 1: A

Shortcut Char. 2: L

Shortcut Char. 3:

Color: Magenta

More info on www.shortcutme.com/faq.html

Shortcuts Config.

-- To disable a shortcut, set it's App. Name to empty field (first item on the application drop-down list).

-- Space is only allowed at the end of the shortcut (i.e ' A1' and 'A 1' are NOT allowed, while 'A ' and 'AB ' are allowed)

Font Size For Config Pages:7

1: App. NameAddressBook

Name in ():

Parameter:

Shortcut Char. 1:A

Shortcut Char. 2:B

Shortcut Char. 3:

2: App. NameAlarm

Name in (): &m

Parameter:

Shortcut Char. 1:A

Common Config.

License Key(Valid): odcTFrSo

Vibration Duration (ms): 100

Sorting main page based on:No Sorting

Keypad Type:QWERTY

Font Size For Config Pages:7

Add New Application

If you don't find an application in the drop-down list of applications, add it's name here. Application name is the name that appears in BlackBerry Home Screen when you select an application.

Extra AppName (1)*:

Extra AppName (2)*:

Extra AppName (3)*:

Extra AppName (4)*:

Extra AppName (5)*:

^ -Shortcuts Config.

-- To disable a shortcut, set it's App. Name to empty field (first item on the application drop-down list).

-- Space is only allowed at the end of the shortcut (i.e '^ A1' and '^A 1' are NOT allowed, while '^A ' and '^AB ' are allowed)

Font Size For Config Pages:7

1: App. NameBrowser

Name in (): CBC

Parameter: www.cbc.ca

Shortcut Char. 1 (fixed):ALT-KEY

Shortcut Char. 2:B

Shortcut Char. 3:C

Shortcut Char. 4:

2: App. NameBrowser

Name in (): CBCd


Parameter: www.cbc.ca

Important Setups

Convenience Key Setup:

ShortcutMe works best and more efficiently when you assign both convenience keys (side keys) to it. This will allow you to access your shortcuts from anywhere by just clicking a convenience key, and let you to multiple click side keys from anywhere to launch your Multi-Click Shortcuts.

Assigning of convenience keys can be done as shown in the images below:



Options	
Date/Time	
GPS Extended Ephemeris	
Localisation	
Memory	
MMS	
Mobile Network	
Owner	
Password	
Screen/Keyboard	
Security Options	
SMS	


Screen/Keyboard	
LED Coverage Indicator:	Off
Key Tone:	Off
Key Rate:	Normal
Currency Key:	\$
Right Side Convenience Key Opens:	ShortcutMe
Left Side Convenience Key Opens:	ShortcutMe
Trackball	
Horizontal Sensitivity:	70

Screen/Keyboard	
Key Rate:	Normal
Currency Key:	\$
Right Side Convenience Key Opens:	ShortcutMe
Left Side Convenience Key Opens:	ShortcutMe
Trackball	
Horizontal Sensitivity:	70
Vertical Sensitivity:	70
Audible Roll:	Mute

License Key Setup (Activating ShortcutMe):

(Assuming you already have assigned convenience key to ShortcutMe)

- 1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Press BlackBerry (Menu) key and select 'Common Config.' From the menu:

Common Config.

Font Size For Config Pages:	7
Font Size For Main Page:	21
License Key(Valid):	odcTfrSo
Vibration Duration (ms):	100
Sorting main page based on:	No Sorting
Keypad Type:	QWERTY

Add New Application
 If you don't find an application in the drop-down list of applications, add it's name here. Application name is the name that appears in BlackBerry Home Screen when you select an application.

Extra AppName (1)*:
 Extra AppName (2)*:
 Extra AppName (3)*:

3- Type in your license key (case sensitive) in the License Key field of Common Config. Page.

4- Press the ESC key (The key on the right side of the trackball) to save it and return to the main page.


Multiple-Click Setup:

(Assuming you already have assigned convenience key to ShortcutMe)


1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Press BlackBerry (Menu) key and select 'MultiClick Config.':



3- Set double, triple, and quadruple clicks for each convenience key and ENTER key to launch an application of your choice. Applications can be found from the drop-down application list. This list pops up when you click trackball on any field that shows application name:



4- If the chosen application is one of those that accept input parameter, you may set a parameter for it. Applications that accept input parameter and example of what can be set as parameter are as follows:

Browser, Browser_WAP, Browser_BES, Browser_BIS, Browser_WIFI, Msg_PIN, Msg_SMS, Msg_Email, Call, Maps and MediaFile.

Example:

Browser Parameter: www.google.com

Msg_PIN parameter: 20FFFFFF

Msg_SMS parameter: (1 800) 000 - 0000

Msg_Email parameter: xx@gmail.com

Call parameter: (1 800) 000 - 0000

MediaFile parameter: SDCard/BlackBerry/pictures/sandy.jpg

Maps parameter: 4000000;-8000000;MyLocation

Best ways to use the software

ShortcutMe is most efficient and fast if you run applications in one of the following ways:

1- Multiple click a convenience key to launch your application from anywhere:

For example:

Click the right convenience key twice to launch Address Book

Click the same key 3 times to call your friend

(Up to 6 applications can be run by multiple clicking convenience keys)

2- Press convenience key once and then type a shortcut on the keypad

For example to run Memory Cleaner:

Conv_Key + M + C

(assuming you have set MC to run Memory Cleaner)

3- You may also browse to shortcuts and “click” to launch them but this will be a slow process (not recommended)

Add a new shortcut

(Assuming you already have assigned convenience key to ShortcutMe)

1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Press BlackBerry (Menu) key and select 'Add New Shortcut'

Quick Config.

-- To disable a shortcut, set it's App. Name to empty field (first item on the application drop-down list).

-- Space is only allowed at the end of the shortcut (i.e ' A1' and 'A 1' are NOT allowed, while 'A ' and 'AB ' are allowed)

-- A text like '&X' can be added to the 'Name in ()' field. That text is set by the program depending on the color you choose for this shortcut.

31: App. Name

Name in ():

Parameter:

Shortcut Char. 1:

Shortcut Char. 2:

Shortcut Char. 3:

Color: Default

More info on www.shortcutme.com/faq.html

3- Select an application of your choice. Applications can be found from the drop-down application list. This list pops up when you click on any field that shows application name:

Quick Config.

-- To disable a shortcut, set it's App. Name to empty field (first item on the application drop-down list).

-- Space is only allowed at the end of the shortcut (i.e ' A1' and 'A 1' are NOT allowed, while 'A ' and 'AB ' are allowed)

-- A text like '&X' can be added to the 'Name in ()' field. That text is set by the program depending on the color you choose for this shortcut.

31: App. Name

Name in ():

Parameter:

Shortcut Char. 1:

Shortcut Char. 2:

Shortcut Char. 3:

Color:

More info on www.shortcutme.com/faq.html

Activation

AddressBook

Alarm

AppSwitcher

BlackBerry App World

BlackBerry Game Service

BlackBerryMessenger

BrickBreaker

Browser

Browser_BES

Browser_BIS

Browser_WAP

Calculator

Calendar

Call

- ...

4- If the chosen application is one of those that accept input parameter, you may type in a parameter for it.

Applications that accept input parameter and example of what can be set as parameter are as follows:

Browser, Browser_WAP, Browser_BES, Browser_BIS, Browser_WIFI, Msg_PIN, Msg_SMS, Msg_Email, Call, Maps and MediaFile.

Example:

Browser Parameter: www.google.com

Msg_PIN parameter: 20FFFFFF

Msg_SMS parameter: (1 800) 000 - 0000

Msg_Email parameter: xx@gmail.com

Call parameter: (1 800) 000 - 0000

MediaFile parameter: SDCard/BlackBerry/pictures/sandy.jpg

Maps parameter: 4000000;-8000000;MyLocation

- 5- If the chosen application is one of those that accept input parameter, you may also type in an extra name tag to remember what parameter you have set for that shortcut. That extra name tag should be added to 'Name in ()' field.
- 6- Specify a color for the shortcut. This shortcut will then be shown in the specified color on the main page.
- 7- Press the ESC key (The key on the right side of the trackball) to save and return to the main page.

Edit a shortcut

(Assuming you already have assigned convenience key to ShortcutMe)

1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Use the trackball to browse to the shortcut you want to edit and then press BlackBerry (Menu) key and select 'Edit Selected'



Quick Config.

-- To disable a shortcut, set it's App. Name to empty field (first item on the application drop-down list).

-- Space is only allowed at the end of the shortcut (i.e ' A1' and 'A 1' are NOT allowed, while 'A ' and 'AB ' are allowed)

-- A text like '&X' can be added to the 'Name in ()' field. That text is set by the program depending on the color you choose for this shortcut.

6: App. Name

Name in ():

Parameter:

Shortcut Char. 1:

Shortcut Char. 2:

Shortcut Char. 3:

Color:

Calculator

C

T

Default

More info on www.shortcutme.com/faq.html

3- The rest is the same as step 3 to 7 in **Add a new shortcut** on page 11 of this document

Insert a new shortcut

(This feature only works if No Sorting is selected in Common Config. Page of ShortcutMe)
(Assuming you already have assigned convenience key to ShortcutMe)

1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Use the trackball to browse to where you want the new shortcut to be, press the Menu key and select 'Add Below Selected'

The rest is the same as step 3 to 7 in **Add a new shortcut** on page 11 of this document


Move a shortcut

(This feature only works if No Sorting is selected in Common Config. Page of ShortcutMe)
(Assuming you already have assigned convenience key to ShortcutMe)



1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Use the trackball to browse to the shortcut you want to move, press the Menu key and select 'Move Selected'



3- Use the trackball to browse to the where you want your shortcut to be moved to, then click trackball



Remove a shortcut

(Assuming you already have assigned convenience key to ShortcutMe)

1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Use the trackball to browse to the shortcut you want to remove and then press BlackBerry (Menu) key and select 'Remove Selected'



Remove several shortcuts

(Assuming you already have assigned convenience key to ShortcutMe)



1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Use the trackball to browse to the first shortcut you want to remove and then press BlackBerry (Menu) key and select 'Mark Selected'



3- Use the trackball to the last shortcut you want to remove and then press BlackBerry (Menu) key and select 'Mark RemoveAllFromMarkedToSelected'




4- Click on YES when you are asked if you are sure or not.


Save shortcut settings in a file

(Assuming you already have assigned convenience key to ShortcutMe)

1- Press convenience key. The below screen (Main page of ShortcutMe) will be shown.



2- Press BlackBerry (Menu) key and select 'Configurations->File'



A file called shortcutmeconfig.txt will be created on the root directory of micro SD card (this file can be opened and modified in WordPad on PC).

Load shortcut settings from a file


(Assuming you already have assigned convenience key to ShortcutMe)
(Assuming that you have uSD card in your BlackBerry® and that you have at least once ran 'Configuration->File' menu item)

Please be aware that this will write over your existing shortcut settings.

1- Press convenience key. The below screen(Main page of ShortcutMe) will be shown.



2- Press BlackBerry (Menu) key and select 'File->Configurations'



More information? Didn't find what you were searching for?

Please see <http://www.shortcutme.com/faq.html>