

Uninstalling INTREPID (*Windows version*) (S03)

You can uninstall INTREPID using the *Windows Control Panel* or manually.

The *Windows Control Panel*

Uninstalling INTREPID requires you to open the *Windows Control Panel*.

Under *Windows* you can open the **Control Panel** from the **My Computer** window or from **Settings** in the **Start** menu.

Uninstalling INTREPID with Windows Add/Remove Programs

- 1 Exit from any INTREPID applications that are running.
- 2 Open the **Control Panel** and start **Add/Remove Programs**.



Use Add/Remove Programs to automatically uninstall INTREPID

- 3 Follow the instructions shown in **Add/Remove Programs**. The utility will remove INTREPID files, directories and environment variables and menu entries / icons.

Uninstalling the dongle driver

Uninstall the dongle driver using **Add/Remove Programs** the *Windows Control Panel*. It is listed as *Sentinel Protection Installer*.

Uninstalling INTREPID manually

If you are unable to use Add/Remove Programs to uninstall INTREPID you can uninstall it manually.

Delete INTREPID files


- 1 Delete all of the INTREPID files and directories using the Windows Explorer or File Manager or the command prompt.

Remove any environment variables that you have set

Note: Only do this if you have specially set environment variables.

- 2 Open the Control Panel and start System.
- 3 Choose the Environment tab. Remove any environment variables as listed in the illustration below. Older installations of INTREPID may list the INTREPID variables in the System variables section.

Environment variable settings are rare in more recent versions of INTREPID and would only be present if you had placed them there. See [INTREPID system parameters and install.cfg \(R07\)](#) for details.



Remove INTREPID icons and menu entries

- 4 Remove the INTREPID icons and menu entries.

Under *Windows*, delete the **Intrepid** folder from your user profile.

- 1 Choose Taskbar from Settings in the Start menu.
- 2 Choose the Start Menu Programs tab.
- 3 Choose Remove.
- 4 Select the **Intrepid** folder (in the Programs folder)
- 5 Choose Remove, then close the Taskbar settings dialog box.

If you have an old installation of INTREPID or you cannot find the **Intrepid** folder when you try to perform the steps above, you can locate it and remove it using Windows Explorer. The user profiles are located in **Profiles** in the Windows software directory.

For example, if you find the INTREPID folder in the **All Users** profile, then you need to delete a folder with a path such as:

c:\Winnt\Profiles\All Users\Start Menu\Programs\Intrepid

You can launch the Windows Explorer to immediately show the profiles area by choosing Advanced instead of Remove in step 3 above.


For the skilled user—Entries in the registry

Note: Only do this if you have specially set environment variables.

You can also remove or edit the environment variables by editing the registry. You can edit the registry directly using the program **regedit32.exe** located in the *Windows* directory (e.g., **c:\Winnt**). Be very careful editing the registry directly. Some mistakes can render your computer unusable.

INTREPID environment variables are stored in two registry hives.

HKEY_LOCAL_MACHINE\SOFTWARE\DFA



HKEY_USER\ACURRENT@\ENVIRONMENT

