

Kento Lazy Load



User Manual

Plugin

- Download the plugin from WordPress.Org or from Plugin Directory from your WordPress Site.

1. Login to WordPress Admin Panel
2. On the left menu panel click on **Plugins**
3. Then click on


Upload Plugin

The screenshot shows the WordPress Admin Panel's 'Add Plugins' page. The left sidebar contains a menu with 'Plugins' highlighted. The main content area has a header with 'Add Plugins' and a tab labeled 'Upload Plugin'. Below the tabs are four plugin cards:

- Theme Check**: A simple and easy way to test your theme for all the latest WordPress standards and practices. A great theme development tool! By *Pross, Otto42*. Rating: 5 stars (180). 335,691 downloads. Last Updated: 1 week ago. Compatible with your version of WordPress.
- BuddyPress**: Social network social network school, sports community. By *The Buddha*. Rating: 4.5 stars (665). 2,286,739 downloads.
- Jetpack by WordPress.com**: Supercharge your WordPress site with powerful features previously only available to WordPress.com users. By *Automattic*. Rating: 4.5 stars (1,915).
- WP Super Cache**: A very fast WordPress caching plugin. By *Automattic*. Rating: 4.5 stars (1,915).


Plugin

5. Click Upload File and select the zip file that you have downloaded from CodeCanyon [Filename: lazy-loader.zip]
6. Once you have selected the file, click install now




Once the plugin has been uploaded and installed you will get the following message

4. Click on the link: Activate Plugin to active the plugin



How to use Kento Lazy Load



You will now see Kento Lazy Load plugin setting on your left menu.

Click on Lazy Load setting to edit the appearance of the Loader Icon

Kento Lazy Load Plugin

A screenshot of the 'Kento Lazy Load Settings' page in the WordPress dashboard. The left-hand menu is visible with 'Lazy Load' selected. The settings page has a light gray background and contains the following configuration options:

- Kento Lazy Load Width**: A text input field with the value '5' and the unit 'em'. Below it, a green note says 'select kento lazy loader size. default size:5 em.'
- Kento Lazy Load Height**: A text input field with the value '5' and the unit 'em'. Below it, a green note says 'select kento lazy load height. default height:5 em.'
- Kento Lazy Load Border Radius**: A text input field with the value '5' and the unit '%'. Below it, a green note says 'select kento lazy load border radius. default border radius:50%.'
- Kento Lazy Load Top Color**: A color selection button labeled 'Select Color' with a blue swatch. Below it, a green note says 'select kento lazy loader top color. default top color: #3498DB.'
- Kento Lazy Load Right Color**: A color selection button labeled 'Select Color' with a green swatch. Below it, a green note says 'select kento lazy loader right color. default right color: #3498DB.'
- Kento Lazy Load Bottom Color**: A color selection button labeled 'Select Color' with a green swatch. Below it, a green note says 'select kento lazy loader bottom color. default bottom color: #3498DB.'
- Kento Lazy Load Left Color**: A color selection button labeled 'Select Color' with a red swatch. Below it, a green note says 'select kento lazy loader left color. default left color: #3498DB.'
- Kento Lazy Load Timeout**: A text input field with the value '1500'. Below it, a green note says 'select kento lazy loader timeout. default timeout:1500.'
- Kento Lazy Load Display**: A dropdown menu currently showing 'Enable'. To its right, a green note says 'Use Dropdown Menu to select kento lazy loader enable/disable.'

At the bottom of the settings area is a blue button labeled 'Save Changes'.

Change the width and the height to change the size of the loader



Kento Lazy Load Width

em

select kento lazy loader size. default size:5 em.

Kento Lazy Load Height

em

select kento lazy load height. default height:5 em.

Change the radius to manipulate the shape of the



Kento Lazy Load Border
Radious

%

select kento lazy load border radious. default border radious:50%.

Change the colors to fit your desire



Kento Lazy Load Top Color	<div><div></div>Select Color</div> <div>select kento lazy loader top color. default top color: #3498DB.</div>
Kento Lazy Load Right Color	<div><div></div>Select Color</div> <div>select kento lazy loader right color. default right color: #3498DB.</div>
Kento Lazy Load Bottom Color	<div><div></div>Select Color</div> <div>select kento lazy loader bottom color. default bottom color: #3498DB.</div>
Kento Lazy Load Left Color	<div><div></div>Select Color</div> <div>select kento lazy loader left color. default left color: #3498DB.</div>

You can also input the duration of the loader

Kento Lazy Load Timeout	<div><div>2000</div></div> <div>select kento lazy loader timeout. default timeout:1500.</div>
Kento Lazy Load Display	<div><div>Enable</div>Use Dropdown Menu to select kento lazy loader enable/disable.</div>

Display of the loader will automatically **enable** itself once the plugin is installed

Thank you for downloading Kento Lazy Load!

Please check out our other plugins in

<http://codecanyon.net/user/kentothemes>

<http://kentothemes.com/>

<https://profiles.wordpress.org/kentothemes/>

Source & Credit

<http://www.jqueryscript.net/loading/Creating-A-Loading-Indicator-with-jQuery-CSS3.html>