



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)

## Christmas Photo Fun v 1.0



by SymbianGuru

# User Manual



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)

## Index

Index .....	2
General description.....	3
How to register Christmas Photo Fun .....	4
How to install Christmas Photo Fun.....	4
Working with Christmas Photo Fun .....	4
How to start .....	4
General information.....	4
First application start .....	4
Christmas Photo Fun Options.....	5
<i>Change template</i> .....	6
<i>Night mode /Flash mode</i> .....	6
<i>Settings</i> .....	6
New templates creating .....	7
Templates in MS Paint .....	7
Templates in Adobe PhotoShop .....	8
Sharing Templates .....	8
How to uninstall Christmas Photo Fun v 1.0.....	9
Christmas Photo Fun Support.....	9



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)

## General description

**Christmas Photo Fun Software** allows making funny Christmas photos merging the predefined templates with phone camera. Some templates are shipped with the application.

Version 1.0 Christmas Photo Fun is compatible with **Symbian^3, Symbian Anna, Symbian Bella and Symbian Series 60.3/60.5** smart phones:

Nokia 3250	Nokia N92
Nokia 5500	Nokia N93
Nokia 5700	Nokia N93i
Nokia 6120	Nokia N95
Nokia 6121	Nokia C5-03
Nokia 6110 Navigator	Nokia 5250
Nokia E50	Nokia 5228
Nokia E51	Nokia C6-00
Nokia E61i	Nokia 5230 Nuron
Nokia E62	Nokia 5235 Ovi Music Unlimited
Nokia E65	Nokia N97 mini
Nokia E70	Nokia X6-00
Nokia E90	Nokia 5230
Nokia N71	Nokia 5530 XpressMusic
Nokia N73	Nokia N97
Nokia N73 Music Edition	Nokia 5800 XpressMusic
Nokia N75	Nokia C6-01
Nokia N76	Nokia C7-00
Nokia N77	Nokia E7-00
Nokia N80	Nokia N8-00
Nokia N81	Samsung SGH-i520
Nokia N91	LG JoY
Nokia N91 8GB	



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)

## How to register Christmas Photo Fun

The trial version of the software is limited to 3 days. During 3 days you can test the application with full features. After 3 days you will not be able to launch the application unless registered.

The full version of the software is obtained by a license code provided upon purchase. The license code is based on the unique IMEI provided and the application can be used exclusively on the device it is licensed for. The license cannot be retrieved and applied to other devices.

## How to install Christmas Photo Fun

Please transfer the .SIS file to your mobile phone via Bluetooth, IRDA or Cable. Then follow the installation instructions on the mobile screen. You may install this software either on your phone memory or your MMC.

## Working with Christmas Photo Fun

### *How to start*

Christmas Photo Fun Application can be opened in following ways (depending on the phone):

- Clicking on the Menu button → Christmas Photo Fun
- Clicking on the Menu button → My Own/Applications → Christmas Photo Fun

### *General information*

Christmas Photo Fun application gives you possibility to make photo with different Christmas templates, which you have previously selected. The software has some templates preinstalled, but you also can make your own templates or download more templates from SymbianGuru page [www.symbianguru.com](http://www.symbianguru.com).

### *First application start*

After launching the application you are able to make photos with the default template immediately by pressing button Photo.



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)


[support@symbianguru.com](mailto:support@symbianguru.com)



### ***Christmas Photo Fun Options***

When you press the right soft key Options you have the following possibilities:

- Change template – allows to change the templates
- Night mode – allows to activate or deactivate the night mode
- Flash mode – allows to activate/deactivate the Flash mode or make this mode automatic
- Settings – settings of the software, which you can change
- Register – field for entering Registration Code
- Buy – allows buying the Christmas Photo Fun application online
- Help – short info for user to use the software
- About – short info about company and contacts
- Exit – exit the application






SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)

### ***Change template***

To change the current template you have to click left soft key Options → Change template. You will have to select one from the list of all possible templates by pressing Select item from Options menu.



Also you are able to select such options from Options menu

- Select – select current template
- Preview – preview current template
- Delete – delete current template
- Delete all – delete all templates

### ***Night mode /Flash mode***

You can activate or deactivate the night mode by pressing Options →Night mode→ On/Off

To activate/deactivate the Flash mode or make this mode automatic you should press left soft key Options → Flash mode → On/Off/Automatic.

Note: some mobile phones have no flash, so this option will be unavailable.

### ***Settings***



By pressing right soft key Options→ Settings you will be able to change the following:



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)



1. Image quality (High/Normal/Basic) – This depends on what photo you want to receive and where this photo will be using. If you want to receive a super photo image you should select the high quality option. If not you can select the normal or basic. The optimal option is Basic.
2. Show captured image (On/Off) – if you want to see the captured image, this option should be turned on
3. Default image name (Date/Text) – this option help you to define the name of the photo; it can be saved by date or by the default name, which can be edited (the default name is ‚FunnyImage‘).
4. Memory in use (Phone memory/Memory card) – you should select the memory, where your photos will be saved
5. Image resolution – here you can select the resolution of your photos. Higher resolution means more image details.

## **New templates creating**

To create your own template you have the picture of which you want to create the template. You can create your own template with the help of MS Paint or Adobe Photoshop, or any other graphical redactor that you like.

### ***Templates in MS Paint***

If you want to create your own template with the help of MS Paint you will have to do the following:

1. Launch paint application on your PC and insert your image. Note: The image size should be 320(w)\*240(h) to fit your mobile screen



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)

2. Fill the region which should be transparent with the contrast colour that is not present on your picture.
3. Fill with the same colour the upper left pixel.
4. Save your picture in \*.PNG format. The file extension should be changed from capital letters to the small letters (e.g. name.png, not name.PNG)
5. Upload image to your phone with the help of Bluetooth or datacable to the Christmas Photo Fun - Templates folder on Phone memory or Data - Christmas Photofun - Templates folder.

### ***Templates in Adobe PhotoShop***

If you are going to create your own template with the help of Adobe PhotoShop you will have to do next steps:

1. Launch PhotoShop application
2. Create new file 320\*240 points with resolution 72 dpi
3. Copy the image and resize it to the necessary image size
4. Create new transparent Layer above the image
5. Select Pencil tool and choose the colour different from the present ones
6. Fill the region which should be transparent on your template with this contrast colour
7. Fill with the same colour also upper left pixel of this image
8. Save the image as png file
9. See that the extension of the file is written with small letters
10. Upload image to your phone with the help of Bluetooth or datacable to the Christmas Photo Fun - Templates folder on Phone memory or Data - Christmas Photofun - Templates folder.

After that you will be able to use your own template. You should just launch the application and change the current template to the newly created one, you will be able to change it by pressing Option – Change template and select your template form the list of available templates.

### ***Sharing Templates***

You will find other ready templates ready for download on our website. If you would like to share your templates to the community, please send them to us per e-Mail and we will publish them on our site. We can include your personal author information also.



SymbianGuru.com Your guru in mobile software.

[www.symbianguru.com](http://www.symbianguru.com)

[support@symbianguru.com](mailto:support@symbianguru.com)

### **How to uninstall Christmas Photo Fun v 1.0**

In order to uninstall Christmas Photo Fun, please go to the Menu → System → Applications Manager, choose the Christmas Photo Fun Application from the list and uninstall it in the usual way.

### **Christmas Photo Fun Support**

If you have any questions or concerns regarding the programm, please contact us at [support@symbianguru.com](mailto:support@symbianguru.com). Our experienced support team is always ready to help you. We also encourage you to send us your ready templates if you want to share them, and we will publish them together with your name (if you wish) on our website.