

# Navigating Through



# User Manual



*Cyber Solutions Inc.*

# Contents

<b>1 Getting Started</b> .....	<b>1</b>
<b>1.1 Starting NetSkate Server</b> .....	<b>4</b>
<b>1.2 Starting NetSkate Client</b> .....	<b>5</b>
<b>1.3 Closing NetSkate Client</b> .....	<b>11</b>
<b>1.4 Stopping NetSkate Server</b> .....	<b>12</b>
<b>2 Tutorial</b> .....	<b>1</b>
<b>2.1 Display a map</b> .....	<b>2</b>
<b>2.2 IP Table</b> .....	<b>5</b>
<b>2.3 Online Graph</b> .....	<b>6</b>
<b>2.4 Offline Graph</b> .....	<b>8</b>
<b>2.5 Visualize Disk &amp; Interface Status</b> .....	<b>9</b>
2.5.1 Interface Status .....	9
2.5.2 Disk Status .....	10
<b>2.6 Generate and Display a map</b> .....	<b>12</b>
<b>2.7 Reachability viewer</b> .....	<b>14</b>
2.7.1 HTTP .....	14
2.7.2 SNMP .....	16
<b>3 How-To</b> .....	<b>18</b>
<b>3.1 Network Status</b> .....	<b>18</b>
<b>3.2 Host Status</b> .....	<b>20</b>
<b>3.3 Host-Traffic</b> .....	<b>21</b>
<b>3.4 Network –Connection Status</b> .....	<b>22</b>
<b>3.5 Add New Host</b> .....	<b>24</b>
<b>3.6 Preference</b> .....	<b>25</b>
<b>INDEX</b> .....	<b>27</b>

# 1 Getting Started



Hello, are you busy with something today? I need your help.



Nothing specific to do for now. Tell me what can I do for you.



Yes. I have a NetSkate package. I have heard, you are familiar with NetSkate, I thought you could help me to Navigate through the Package and generate and display Local Network Maps. I understand that we can plot online graphs to monitor network traffic and also visualize interface and resources status. Apart from these, there is a feature called Reachability viewer, which is also explained graphically.




That sounds pretty interesting. Let us start right away.



Here it is. I am told we can run this package on Windows/ MacOSX/and different flavors of Unix and Linux operating Systems. How do I install it? Can you guide me?



NetSkate Installation is very simple. You can refer to NetSkate Installation Guide. Even I learnt from this document. After Installation the NetSkate directory will be created.



OK. How can I start **NetSkate**. Do I need to change the settings and configure the package?



To start NetSkate you need to start the NetSkate Server and NetSkate client. For NetSkate client you need to set the policy.



How can I do that. I have never done it before.



Oh! Its simple. You have to start the policytool.



PolicyTool? Where will I get it from.



Policytool is a standard application which comes along with java Package.



OK. How can I use it.

### Adding Policy



Start the policytool from the commandline by typing  
policytool

- i. Click on the "Add Policy Entry" button
- ii. Enter the following value in the CodeBase field  
http://<server>/<location of OR link to directory in which netskate's index.html file is stored>
- iii. Click on the "Add Permission" button
- iv. In the Permissions dialog, select FilePermission in the Permission drop-down box. Select <<ALL FILES>> from the Target Name drop-down box. From the Actions drop-down box, select read, and then select write. Click on the "Ok" button.
- v. Click on the "Add Permission" button
- vi. In the Permissions dialog, select PropertyPermission in the Permission drop-down box.
- vii. Enter user.home into the Target Name field.  
From the Actions drop-down box, select read.  
Click on the "Ok" button.
- viii. Click on the "Add Permission" button
- ix. In the Permissions dialog, select AWTPermission in the Permission drop-down box. Select accessClipboard from the Target Name drop-down box.  
Click on the "Ok" button.
- x. Click on the "Add Permission" button
- xi. In the Permissions dialog, select Runtime Permission in the Permission drop-down box. In the Target Name field, select "queuePrintJob".  
Click on the "Ok" button.
- xii. Click on Save under the File menu.
- xiii. Save the settings in a file named .java.policy in your home directory.



## 1.1 Starting NetSkate Server

The Server Manager is a UI based tool with which the NetSkate server can be managed. This tool displays the server status and the status of the client(s) connected to the server.



ServerManager  
r

Double clicking on the Server Manager Executable file will start the Server Manager. Alternatively it can be started from the command line also. This will start the Server in UI mode if the UI is accessible otherwise, the server is started in the console mode with no ServerManager UI.



As the client(s) is started, the Client Status is displayed on the UI.

## 1.2 Starting NetSkate Client




Now that you have started the server, we can start the client. I just want to remind you that NetSkate Client can be loaded remotely also. It should be HTTP accessible.

To start the NetSkate Client either double click on the index.html or use appletviewer to start the client.




index.html



Now, click on link with “NetSkate” marked on it. This will start up the NetSkate. Before we proceed, I want to caution you about one thing, be very attentive otherwise; you may not be able to follow. Okay now look; can you see a screen coming up?

Read the messages displayed inside the screen shots.



You should click “Yes” if you want to generate a local network map. An authentication window as shown below is displayed.




Enter the User Name and the Password. Click Ok. The following screen is displayed (Note that if the authentication fails, NetSkate continues without generating the map and takes you back to the main window.)






You may enter a community name and click “Ok” to proceed with the specified value, or click “Cancel” to proceed with the default value.




The progress bar shows the status while the Package is loaded .The generated map will be displayed on the main panel when you select Map display from the view menu. We are going to generate the map in the Tutorial section also, but that will be from the Menu option/Tool bar.



That is a little lengthy procedure, but it is quite interesting. Can you show what the NetSkate Main window looks like?



Here it is. It has the regular Menu bar, Tool bar and Status bar. I am sure you are familiar with these by now.



Before we proceed, let me give a brief description of the Tool bar buttons and show the Full Screen of the NetSkate.

### Tool bar



Invokes Graph dialog



Invokes the Disk Status display.



Toggles Map Display Window



Toggles HTTP Reachability Viewer Window




Toggles SNMP Reachability Viewer Window



Quits the package.

**FULL SCREEN**

- |   |                     |   |                       |   |                       |
|---|---------------------|---|-----------------------|---|-----------------------|
| A | Graph Window        | E | Tool Bar              | I | Status Bar            |
| B | Reachability Viewer | F | IP Table              | J | Map display           |
| C | Logger Display      | G | Interface Status      | K | Disk Status Pie chart |
| D | Menu Bar            | H | Disk Status Bar Graph | L | Preference Dialog     |



Oh Good. That is Netskate displaying all the features .I am looking forward to know more about them.



The following sections will provide an overview of most of the above listed features. Shall we start generating a map and plot the graph?



I am just thrilled to know, that we are going to plot graphs. I have a fascination for graphs. Before starting can you tell me how to close NetSkate.

### 1.3 Closing NetSkate Client



Closing NetSkate Client is simple. On the toolbar




Quits the package.



Hmm... But, then do I need to arrange all my graphs and windows again?




No. NetSkate client asks to save the screen settings and when starting the client again you can get your screen settings again.




## 1.4 Stopping NetSkate Server



After stopping all the client the server can be stopped using the server manager.



The server can be stopped by clicking on Stop Server Button. The server manager stops the Server.



The Exit button on File menu exits the Server Manger application.



OK. Now can you please tell me about NetSkate functions and features?



Lets start.

## 2 Tutorial




Since I had stopped the Server and Client. I restarted the NetSkate again. Server is OK. But, this time client didn't asked for Map Generation.



That's because you already have a map.



But, then this time I have a new window. What should I do?




You can use the screen, which was saved last time, or you can start with a fresh window.



I remember the dialog, which had come while shutting down the client. But, this time I will start afresh.



I got a blank window. What should I do?



You can view your network map.

## 2.1 Display a map



How can I see a map?



You can do this by either using the tool bar or by using the view menu. Let me show you.





**Reload**



The local map, which is loaded as default map, can be reloaded by using Reload button.

**Interface status**



Checks the specified network element for the SNMP access/ICMP reachability and indicates the status using colour codes as,



SNMP accessible: green



SNMP not accessible: red

**Map Statistics display**



The statistics of all the Nodes in the currently loaded map can be viewed by clicking on this button.



What does SNMP accessible and not accessible mean?



If the host is SNMP accessible you can see the Traffic on that host.



Did you said **Traffic**. How can I see the traffic?



You can not only see it using IP Table but, you can plot it also using Grapher. Let me show you how simple this is.

## 2.2 IP Table



On IP Table you can see the traffic statistics for different systems.  
 Not only this you can see the current In / Out Traffic on a logarithmic scale.

IPAddress	Name	MAC	In/Out	Min In...	Max In...	Ave In...
192.168.0.10	EVEREST	00:d0:b7:b2...		0 bps / 0 bps	27 Mbps / 9...	1 Mbps / 38...
192.168.0.11	HEMA	52:29:7b:9e...		0 bps / 0 bps	13 Mbps / 2...	596 Kbps / ...
192.168.0.13	MIYAGI	00:50:ba:3c...		0 bps / 0 bps	3 Mbps / 2 ...	150 Kbps / ...
192.168.0.15	SHOGUN	00:50:ba:3d...		0 bps / 0 bps	2 Mbps / 2 ...	101 Kbps / ...
192.168.0.17	SARAS	00:50:ba:8b...		0 bps / 0 bps	2 Mbps / 1 ...	89 Kbps / 7...
192.168.0.18	SHUBA	00:50:ba:8c...		0 bps / 0 bps	434 Kbps / ...	20 Kbps / 1...
192.168.0.80	SHIRANUI	08:00:46:14...		0 bps / 0 bps	559 Kbps / ...	25 Kbps / 2...



Can you tell me what else is there on this table.



IP Table displays the IP Address of the machine, MAC Address. Min Max and Average Traffic.



You were telling me that we could plot this on Graphs also.




We are going to do that only.


### 2.3 Online Graph



Select Online/Offline graph from the Tools menu.



A graph dialog is displayed. You have to enter the data in the fields. The data can also be selected from the drop down menus. Click 'Show'. The graph is plotted and displayed.





Now that the graph is plotted, we will see how to use the toolbars of the Graph window and the Graph control bar and the side bar.

**Graph Tool Bar**

**Add new graph**



Click this button to add a new graph.

**Change Color**



Provides options to change the colours

**Start button**



Click this button to start plotting the graph. Changes to “Stop button”, when clicked.

**Stop button**



Click this button to stop plotting the graph. Changes to “Start button”, when clicked.

**Graph Control Bar**



These buttons will assist you to scroll the graph to the left, right, Zoom in and Zoom out.

**Graph Side Bar**



All the graphs added have a control button on the Graph Side Bar. The button having the same color of the graph represents them. You can toggle this to display/hide graphs as per need.



Is this data stored somewhere.



Oh yes. This is stored on the server.



Aah! It would be great if I could see this data later also.



NetSkate has taken care of this also. You can see it as Offlien Graph.

## 2.4 Offline Graph



You can plot the offline Graphs using the same Dialog.




So how will I ask for Offline Graphs then?




When we plotted Online Graph, we had placed a check mark on the “From now” Checkbox.(Refer Graph Dialog) Simply uncheck this box. You will notice that ‘From’ and ‘To’ fields are enabled. Insert the dates in the specified format DD/MM/YYYY.

Select ‘Show’ from the Graph Dialog.



If there are no data the following message is displayed.





In the Graph Dialog Interface Name is there. Can I see the Interface Status also.




Oh yes. You can see the Disk Status and Interface Status also.

## 2.5 Visualize Disk & Interface Status


### 2.5.1 Interface Status



This displays all the interfaces associated with the host. Right click on a PC icon on the map. A context menu is displayed. Select Interface Status from this menu.




The interface status is displayed for this host.



### 2.5.2 Disk Status




By Disk Status we mean the resource usage of a host in the network. We are going to display graphically, the status of the Disk-the availability of disk space, used portion of the Disk etc.of a particular host. Select Disk Status from the Tools menu.




Disk Status dialog window is displayed.






Disk Status dialog window is displayed.  
 Enter the Host name and community.  
 You have an option to view the Disk status as Pie chart or Bar graph or both.  
 Select the display type and click 'Show' Bar Graph and pie charts are displayed



Bar Graph



Pie Chart



Hmm. I did not know that map could give me so much of information. But, I have a doubt. What if I add new machines to my network or remove some machines from network.



Oh you can always regenerate map.




Can I regenerate the map also? Tell me how can I do that

## 2.6 Generate and Display a map



Select Generate Local Network map from View menu.




Map Generation Authentication dialog is displayed.




Fill in the Username and Password. Click on OK button.


A dialog window prompting you to enter the community name is displayed



click on 'OK'. The application will take the default value and continue to generate the map. During the generation process 'User Approval' dialog is displayed.



Select the Hosts that should be polled, and click 'Go'. The map generated is displayed below





What else can I do?



You can use Reachability viewer to see how the reachability of your Host and The time taken to reach by the specified URL is represented graphically.




How can I do that?

## 2.7 Reachability viewer


### 2.7.1 HTTP




Select the reachability viewer from the Tools menu.




The bar graphs for URLs present in the file **urls.lst** are displayed. Maximum time is denoted by Red color, Minimum by Yellow, and Average time by Blue color. The current time taken is shown by Cyan.



If you need to edit a URL list, then select the icon from the tool bar of this window and an authentication dialog is displayed. You have to enter the User name and Password and click Ok.



The Reachability Viewer List Edit window is displayed



When you select 'Save' the data is saved. If you want to quit the application you can select 'Save & Exit'. 'Cancel' will quit the window.




How can I see reachability of my host?




You can use SNMP Reachability viewer.

### 2.7.2 SNMP

The time taken by the Snmp queries to the specified host is represented graphically. Select the Snmp reachability viewer from the Tools menu.



The bar graphs for hosts are displayed. Maximum time is denoted by Red color, Minimum by Yellow, and Average time by Blue color. The current time taken is shown by Cyan.



### 3 How-To



#### 3.1 Network Status



How can I know my Network status?



It is very simple, Open Map Display and IP Table. On Map Display you can see the, Status of PCs and other elements. On IP Table you can see the traffic statistics for different systems.









The screenshot shows the NetSkate application window. The 'View' menu is open, showing options like 'ToolBar', 'StatusBar', 'Show In/Out/Error', 'Show IP Table', 'Map Display', 'Generate Local Network map', and 'Logger'. The main window displays a network diagram with a central blue hub and several connected devices. Below the diagram is the 'IP Table' window, which contains the following data:

IPAddress	Name	MAC	In/Out	Min In...	Max In...	Ave In...
192.168.0.10	EVEREST	00:d0:b7:b2...		0 bps / 0 bps	27 Mbps / 9...	1 Mbps / 38...
192.168.0.11	HEMA	52:29:7b:9e...		0 bps / 0 bps	13 Mbps / 2...	596 Kbps / ...
192.168.0.13	MIYAGI	00:50:ba:3c...		0 bps / 0 bps	3 Mbps / 2 ...	150 Kbps / ...
192.168.0.15	SHOGUN	00:50:ba:3d...		0 bps / 0 bps	2 Mbps / 2 ...	101 Kbps / ...
192.168.0.17	SARAS	00:50:ba:8b...		0 bps / 0 bps	2 Mbps / 1 ...	89 Kbps / 7...
192.168.0.18	SHUBA	00:50:ba:8c...		0 bps / 0 bps	434 Kbps / ...	20 Kbps / 1...
192.168.0.80	SHIRANUI	08:00:46:14...		0 bps / 0 bps	559 Kbps / ...	25 Kbps / 2...

### 3.2 Host Status



### 3.3 Host-Traffic

How can I see the traffic of my hosts?






Using the best Grapher tool around. See, NetSkate has it.



Open GraphDialog and specify your host details and click Show. Voila! Grapher will plot the traffic of your hosts.





A screenshot of the NetSkate application window. The title bar reads "NetSkate". The menu bar includes "File", "Edit", "View", "Tools", "Window", and "Help". The main interface is divided into two panes. The left pane is titled "Graph Dialog" and contains a "Data" section with a "Select Data" button. Below this, the "Current Selection" section includes fields for "Domain Name" (LocalNet), "Host Name" (192.168.0.11), "ManagedObject" (In Bytes), "Interface Name" (MAC Bridge Miniport - P...), "Community" (\*\*\*\*\*), "Buffer Size" (1 day), and "Polling Interval" (1 min). There is also a field for "A Title for the Window" (Offline 1 : 1 min) and a "Palette" section. At the bottom, there are "Time (DD/MM/YYYY)" fields for "From Date" (6/6/2002) and "To Date" (7/6/2002), with a "From now" checkbox. "Show", "Cancel", and "Update" buttons are at the bottom of the dialog. The right pane is titled "Offline 3 : 1 min" and displays a line graph. The graph shows two data series: "LocalNet 192.168.0.11 [MAC Bridge Miniport - Packet Scheduler Miniport] : In Bytes / min" and "LocalNet 192.168.0.11 [MAC Bridge Miniport - Packet Scheduler Miniport] : Out Bytes / min". The y-axis is labeled "(x 1,000,000)" and ranges from 0 to 3. The x-axis shows time from 18:58:30 to 21:34:55 on Thursday, June 6, 2002, with a note "(Thu Jun 06 ~ Wed Jun 05)". The graph shows several peaks in traffic, with the highest peak reaching approximately 2.5 million bytes per minute.

### 3.4 Network –Connection Status







### 3.5 Add New Host



After Authentication dialog select some hosts from the User Approval Dialog.





You will see that only three hosts are there in the first map. The second map shows additional hosts.

### 3.6 Preference

Can you tell me something about the menu option Preferences?  
I understand this is a very useful utility in NetSkate.




Go to Edit menu. Select 'Preferences'. There are three options to choose from.


- Themes
- Look& Feel
- Map Display

Screen Settings and other display features Can be altered with this utility.





look ,in the screen shot displayed above, Themes is changed from Steel to Emerald.



In the following screen shots, Look & Feel has been changed from Java to Motif.



**INDEX**

	<b>A</b>	
Add New Host		24
	<b>C</b>	
Closing NetSkate Client		11
	<b>D</b>	
Disk Status		10
	<b>G</b>	
Generate and map		12
	<b>H</b>	
Host Status		20
Host Traffic		21
HTTP Reachability		14
	<b>I</b>	
Interface Status		9
IP Table		5
	<b>M</b>	
Map Display		2
	<b>N</b>	
Network –Connection Status		22
Network Status		18
Network Traffic		4
	<b>O</b>	
Offline Graph		8
Online Graph		6
	<b>P</b>	
Permissions		3
Preference		25
	<b>S</b>	
SNMP Reachability		16
Starting NetSkate Client		5
Starting NetSkate Server		4
Stopping NetSkate Server		12
Cyber Solutions Inc.		27