

AUTO-DEMO

User Manual

Release 5.0 - April 1998



Information in this document is subject to change without notice and should not be construed as a commitment by O₂ Technology.

The software described in this document is delivered under a license or nondisclosure agreement.

The software can only be used or copied in accordance with the terms of the agreement. It is against the law to copy this software to magnetic tape, disk, or any other medium for any purpose other than the purchaser's own use.

Copyright 1992-1998 O₂ Technology.

All rights reserved. No part of this publication can be reproduced, stored in a retrieval system or transmitted in any form or by any means, electronic, mechanical, photocopy without prior written permission of O₂ Technology.

O₂, O₂Engine API, O₂C, O₂DBAccess, O₂Engine, O₂Graph, O₂Kit, O₂Look, O₂Store, O₂Tools, and O₂Web are registered trademarks of O₂ Technology.

SQL and AIX are registered trademarks of International Business Machines Corporation.

Sun, SunOS, and SOLARIS are registered trademarks of Sun Microsystems, Inc.

X Window System is a registered trademark of the Massachusetts Institute of Technology.

Unix is a registered trademark of Unix System Laboratories, Inc.

HPUX is a registered trademark of Hewlett-Packard Company.

BOSX is a registered trademark of Bull S.A.

IRIX is a registered trademark of Siemens Nixdorf, A.G.

NeXTStep is a registered trademark of the NeXT Computer, Inc.

Purify, Quantify are registered trademarks of Pure Software Inc.

Windows is a registered trademark of Microsoft Corporation.

All other company or product names quoted are trademarks or registered trademarks of their respective trademark holders.

Who should read this manual

When O₂ is delivered, you receive a demonstration called **auto** with the installation tape. This demonstration uses O₂C, O₂Look, O₂Kit and O₂Graph.

This document explains how to install and use this demonstration.

See [O2 Documentation set](#).






TABLE OF CONTENTS


This manual is divided into the following chapters:

- 1 - Introduction
- 2 - Installation - explains how to install and run the auto demonstration.
- 3 - Scenario - explains how to install and run the auto demonstration.



TABLE OF CONTENTS

1	Installation	7
	1.1 System Overview.....	8
	1.2 The O2 Auto Demonstration.....	10
2	Installation	11
3	Scenario	17



Installation

AUTO DEMONSTRATION

This chapter introduces the O₂ System through a demonstration.

It contains the following sections:

- [System Overview](#)
- [The O₂ Auto demonstration](#)

1.1 System Overview

The system architecture of O₂ is illustrated in [Figure 1.1](#).




Figure 1.1: O₂ System Architecture

The O₂ system can be viewed as consisting of three components. The Database Engine provides all the features of a Database system and an object-oriented system. This engine is accessed with Development Tools, such as various programming languages, O₂ development tools and any standard development tool. Numerous External Interfaces are provided. All encompassing, O₂ is a versatile, portable, distributed, high-performance dynamic object-oriented database system.

Database Engine:

- O₂Store The database management system provides low level facilities, through O₂Store API, to access and manage a database: disk volumes, files, records, indices and transactions.
- O₂Engine The object database engine provides direct control of schemas, classes, objects and transactions, through O₂Engine API. It provides full text indexing and search capabilities with O₂Search and spatial indexing and retrieval capabilities with O₂Spatial. It includes a Notification manager for informing other clients connected to the same O₂ server that an event has occurred, a Version manager for handling multiple object versions and a Replication API for synchronizing multiple copies of an O₂ system.

System Overview

Programming Languages:

O₂ objects may be created and managed using the following programming languages, utilizing all the features available with O₂ (persistence, collection management, transaction management, OQL queries, etc.)

- C O₂ functions can be invoked by C programs.
- C++ ODMG compliant C++ binding.
- Java ODMG compliant Java binding.
- O₂C A powerful and elegant object-oriented fourth generation language specialized for easy development of object database applications.
- OQL ODMG standard, easy-to-use SQL-like object query language with special features for dealing with complex O₂ objects and methods.

O₂ Development Tools:

- O₂Graph Create, modify and edit any type of object graph.
- O₂Look Design and develop graphical user interfaces, provides interactive manipulation of complex and multimedia objects.
- O₂Kit Library of predefined classes and methods for faster development of user applications.
- O₂Tools Complete graphical programming environment to design and develop O₂ database applications.

Standard Development Tools:

All standard programming languages can be used with standard environments (e.g. Visual C++, Sun Sparcworks).

External Interfaces:

- O₂Corba Create an O₂/Orbix server to access an O₂ database with CORBA.
- O₂DBAccess Connect O₂ applications to relational databases on remote hosts and invoke SQL statements.
- O₂ODBC Connect remote ODBC client applications to O₂ databases.
- O₂Web Create an O₂ World Wide Web server to access an O₂ database through the internet network.

1.2 The O₂ Auto Demonstration





Figure 2: The O₂ Auto demonstration



Installation

This chapter describes all the steps you need to carry out in order to install and use the O₂ demonstration `auto`. In most of the steps given below, the explanation is followed by the actual command.

Unload the O₂ installation Cd-Rom / tape into a directory called O2HOME.

It is assumed that an **O2HOME** environment variable specifying the access path to this directory now exists.

In **O2HOME**, you find different files and directories.

The following directories are important:

- **bin** directory containing the O₂ binary files
- **look** directory containing O₂Look files
- **demo** directory containing demonstrations

Position yourself in **o2HOME**:

```
> cd $O2HOME
```

Add the **o2HOME/bin** directory to the path in each working window:

```
> set path = ($O2HOME/bin $path)
```

In **o2HOME**, create a directory called **o2vol** to contain all the different O₂ catalogues.

```
> mkdir o2vol
```

In **o2HOME**, now create the **systems** file needed to define the different O₂ systems.

You should refer to the *O₂C Reference manual* for more details on this file and the organization of O₂ catalogues.

In the **systems** file, insert a line corresponding to the description of the system **demo**. Use the exact syntax of the following command on a single line:

```
> echo demo:'hostname':$O2HOME/o2vol::$O2HOME/o2vol::$O2HOME/o2vol::>systems
```

Create the symbolic links that position the resource files of the demonstration for O₂Look:

```
> ln -s $O2HOME/demo/auto/resources/english/auto_demo look/english
```

```
> ln -s $O2HOME/demo/auto/resources/french/auto_demo look/french
```

Initialize the system `demo`:

```
> o2init -system demo
```

Launch an O₂server. If you do this in another window, make sure that you add the directory `O2HOME/bin` to the `path`.

```
> o2server -system demo
```

To specify which language you want the demonstration to be in, `english` or `french`, position the environment variable `O2RESOURCE` to one of the following:

```
> setenv O2RESOURCE english
```

or

```
> setenv O2RESOURCE french
```

Position yourself in the directory `demo` and launch an O₂ client:

```
> cd demo/auto
```

```
> o2 -system demo
```

In the client window, load the demonstration `auto`:

```
#"load"
```

```
^D
```

Note

If you are using SunOs, do not worry if you receive the following error message:

```
ERROR 20048: Not available on this platform
```

Now you can launch the demonstration `auto` in the client window:

```
run application demo
```

```
^D
```

How to use the demonstration is described in Chapter 3 : [Scenario](#).

To quit the demonstration, click (with left mouse button) on the "Quit" button of the O₂ application icon shown in Figure 3 below.



Figure 3: Application icon


To now leave O₂, type in the client window:

```
quit
```

```
^D
```

Finally kill the server.

```
o2shutdown -system demo
```

Scenario

This chapter goes through a scenario of the demonstration `auto` step-by-step.

Note

When you read below to click on a particular part of the demonstration, you should always use the **left** mouse button **unless** it is otherwise stated in the text to use the **right** button.

When you launch the demonstration `auto`, as explained in the previous section, an application icon is displayed as shown in Figure 4.




Figure 4: Application icon and menus

Now click on the words **O2 Demo** using the **right** mouse button and a pull down menu appears.

Maintaining the **right** mouse button over the **Demo** item another menu appears. Release the button over the item **Run** of this menu in order to start up this program.

A map of Paris now appears covered with various name tags.

Click using the **right** mouse button on the name tag **John Denver (A)** in the center of the map and select the method **Display**.




Figure 5: Paris map

A login window now appears as shown in the figure below.

Type in the code field the code **7781** and click on **Login**.




Figure 6: Login window

A window now appears containing information about John Denver including name,

code, address, and orders.




Figure 7: Information boxes

If you now click in the address section of this window using the **right** mouse button, as shown in Figure 7 above, you can select **Display** which then gives you details of the address.

Now go back to the John Denver window and select the method `Display` in the menu `Cars`.



A selection box now appears in which you can choose the set of cars you want to look at: `All`, `France`, `Germany`, `USA`. Click on your choice and then on `OK`.



Figure 8: Country selection

Note

All data concerning French cars is in French and all other data is in English.

All the cars corresponding to the country chosen are displayed - in this case Germany.




Figure 9: Display of German cars

Click on one of the cars displayed using the **right** mouse button, and select the method **Display**. The presentation corresponding to the car chosen is now displayed.

Note

Complete information is only available for the Renault, Mercedes and BMW cars. There is no section cut-out for the Corvette, Audi and Venturi.

This presentation contains technical data, text and two color photos and is shown in Figure 10 below.

Click on the **car manufacturer** section and select the method **Display** - you see all the cars produced by that manufacturer in a separate window.

Click on **Quit** to close this window.




Figure 10: Car information

Reposition yourself in the car presentation window and now select the method **Display** in the menu **Schema**.

The section cut-out of the car is displayed. When you click on one of the buttons **Engine**, **Transmission**, or **Body**, the corresponding flags appear on the

diagram.




Figure 11: Car cut-out

Click on the button **Engine**. The various flags are now displayed. Now click on the Air Filter flag using the **right** mouse button and chose the method **schema**.

A diagram of the Air Filter is displayed and if you click on the Button **Air Filter** you see the flags representing the various sub parts of the Filter.




Figure 12: Air filter diagram

If you now click on a subpart flag using the **right** mouse button you see a pull down menu containing the methods **Display**, **Update** or **Price**.

Click on the square on the bottom right hand side using the **right** mouse button and select the method **Display** as in (A) in Figure 12.

The description of the Air Filter intake assembly is displayed.




Figure 13: Air filter intake assembly description

Now go back to the Air Filter illustration and click on the **Information** menu.



From this menu you can select the methods **Description** and **Price** to obtain further information about the Air Filter.

If you have the option O₂Graph, you can select from the Air Filter screen the method **structure** to obtain the graph of the Air Filter components.

This is shown in Figure 14




Figure 14: Graph

Before going on with the demonstration, you should now close all windows, by clicking on quit in each presentation, **except** the windows shown in Figure 15, concerning the map of Paris, **John Denver** chosen at the beginning, the components graph and/ or the intake assembly components window.




Figure 15: Windows you need

If you now return to the John Denver presentation, select the method **Add** in the menu **Orders**.



The presentation of an order is displayed.




Figure 16: Presentation

Click using the right button in the field `parts`, and select the method **Insert**. A new tuple now appears in the `parts` field - you must enlarge the window to see it clearly.

Enter a quantity. To enter a part, simply select, using the middle mouse button, a flag in the Air Filter Structure graph or a part in the intake assembly components and drag and drop on the blackened square in order to copy the value.




Figure 17: Parts window

You can renew this operation and then on the order presentation select the method **Price** from the **Information** menu.

If you have L^AT_EX on your machine click on the method **Letter**. You now see a preview of a letter in L^AT_EX. Type q in this window to exit.



You leave the demonstration by clicking on the **Terminate** button on the map of Paris (A) in Figure 18.




Figure 18: End of demonstration scenario