

---

**Integrated Environmental Control Model**

# **Getting Started**

**Prepared for the National Energy Technology Laboratory  
U. S. Department of Energy**

**By Michael B. Berkenpas**

**John J. Fry**


**Karen Kietzke**

**Edward S. Rubin**

**Center for Energy and Environmental Studies**

**Carnegie Mellon University**

**Pittsburgh, PA 15213**



**Version 3.4 — April 2001**

**(Web and email addresses updated July 2015)**



# Contents

|   |           |
|---|-----------|
| <b>Introduction</b>   | <b>1</b>  |
| The Integrated Environmental Control Model .....            | 1         |
| Purpose.....  | 1         |
| System Requirements.....                                    | 1         |
| Uncertainty Features .....                                  | 2         |
| Software Used in Development.....                           | 2         |
| Disclaimer of Warranties and Limitation of Liabilities..... | 2         |
| Copyright Notices .....                                     | 3         |
| <br>  |           |
| <b>User Documentation and Help</b>                          | <b>4</b>  |
| Getting Started .....                                       | 4         |
| User Manual.....  | 4         |
| Model Tutorial .....  | 4         |
| Technical Manual.....                                       | 4         |
| Online Help.....  | 4         |
| <br>  |           |
| <b>Installing the Model</b>                                 | <b>6</b>  |
| What's Included in the Model Package.....                   | 6         |
| Installation.....   | 6         |
| Installation Steps.....                                     | 7         |
| Canceling the Installation .....                            | 13        |
| Errors During Installation .....                            | 14        |
| Updating the IECM Software.....                             | 14        |
| Removing the IECM Software.....                             | 14        |
| <br>  |           |
| <b>Windows Conventions</b>                                  | <b>15</b> |
| Microsoft® Windows.....                                     | 15        |
| Using the Mouse .....                                       | 15        |
| Cursors .....   | 15        |
| The Arrow.....  | 16        |
| The Cross.....  | 16        |
| The I-Beam .....  | 16        |
| The Hourglass.....  | 16        |
| The Arrow and Hourglass.....                                | 16        |
| Keystroke Commands .....                                    | 16        |
| Alt Commands .....  | 16        |
| Ctrl Commands.....  | 17        |
| <br>  |           |
| <b>IECM Conventions</b>                                     | <b>18</b> |
| The IECM Window.....  | 18        |
| Menu Bar .....  | 18        |
| The File Menu.....  | 19        |

|  |           |
|--|-----------|
| The Edit Menu .....                    | 21        |
| The View Menu .....                    | 21        |
| The Window Menu .....                  | 23        |
| The Help Menu .....                    | 23        |
| The Toolbar .....                      | 24        |
| The Status Bar .....                   | 24        |
| The Session Window .....               | 25        |
| Tabs .....                             | 25        |
| Types of Tabs .....                    | 26        |
| Plant Diagrams .....                   | 27        |
| Parameters and Results Workspace ..... | 28        |
| Selecting Cells .....                  | 29        |
| Highlighting .....                     | 31        |
| Process Type Pull-Down Menus .....     | 32        |
| <b>Running the Model</b> .....         | <b>33</b> |
| Starting the Model .....               | 33        |
| Choosing a Session .....               | 34        |
| Using the Model .....                  | 34        |
| Exiting the Model .....                | 34        |
| <b>Configuring the Plant</b> .....     | <b>35</b> |
| Configure Plant .....                  | 35        |
| Configuration Pull-Down Menus .....    | 36        |
| Invalid Selections .....               | 36        |
| Plant Diagram .....                    | 37        |
| <b>Setting Parameters</b> .....        | <b>38</b> |
| Set Parameters .....                   | 38        |
| Plant Diagram .....                    | 39        |
| Set Parameters Workspace .....         | 40        |
| Title .....                            | 41        |
| Units .....                            | 41        |
| Uncertainty (Unc) .....                | 41        |
| Value .....                            | 41        |
| Calculated (Calc) .....                | 42        |
| Minimum, Maximum, and Default .....    | 42        |
| Entering Inputs .....                  | 43        |
| Input Tools .....                      | 44        |
| Calculated Values .....                | 44        |
| Uncertain Values .....                 | 46        |
| Input Navigation Tabs .....            | 47        |
| Coal Properties Parameters .....       | 48        |
| <b>Getting Results</b> .....           | <b>50</b> |
| Get Results .....                      | 50        |
| Plant Diagram .....                    | 51        |
| Viewing Results .....                  | 51        |
| Results Navigation Tabs .....          | 52        |
| Diagrams .....                         | 52        |
| Capital Cost Summaries .....           | 53        |
| O&M Cost Summaries .....               | 54        |
| Total Cost Summaries .....             | 55        |

|   |           |
|---|-----------|
| Cost Inputs Summaries .....                 | 56        |
| Gas Summaries .....                         | 57        |
| Graphs .....                                | 58        |
| Result Tools .....                          | 59        |
| Uncertainty Areas .....                     | 60        |
| <b>Working with Sessions</b>                | <b>61</b> |
| Sessions .....                              | 61        |
| Creating a New Session .....                | 61        |
| Opening an Existing Session.....            | 62        |
| Saving a Session's Results .....            | 62        |
| Saving a Session with a Different Name..... | 63        |
| Closing a Session .....                     | 63        |
| Deleting a Session .....                    | 64        |
| Unlocking a Session.....                    | 65        |
| <b>Importing and Exporting Data</b>         | <b>66</b> |
| Importing a Session.....                    | 66        |
| Exporting a Session.....                    | 66        |
| Print Screen .....                          | 66        |
| Windows Copy, Cut, and Paste.....           | 66        |
| <b>Printing</b>                             | <b>68</b> |
| Print Dialog Box .....                      | 68        |
| <b>Index</b>                                | <b>69</b> |



# Introduction

---

## The Integrated Environmental Control Model

This Integrated Environmental Control Model (IECM) and Interface were developed for the U. S. Department of Energy's National Energy Technology Laboratory (NETL), formerly known as the Federal Energy Technology Center (FETC), under contract No. DE-AC22-92PC91346 and DE-AC21-92MC29094.

---

## Purpose

The purpose of the model is to calculate the performance, emissions and cost of employing alternative environmental control methods in a coal-fired power plant. The model consists of a base plant and various control technology modules; these modules may be implemented together in any desired combination.

A Graphical User Interface (GUI) facilitates the configuration of the technologies, entry of data, and retrieval of results.

---

## System Requirements

The current model requires the following configuration:

- Intel-based computer running Windows 95 (or better) or Windows NT 4.0 (or better) operating system
- Pentium Processor
- any SVGA (or better) display—at a resolution of 800x600 (or more) pixels<sup>1</sup>
- at least 40 Megabytes of free hard disk space
- at least 32 Megabytes of total memory

---

<sup>1</sup> Smaller screen resolution results in the interface screens being scaled smaller. The taskbar, part of the Windows operating system, reduces the useable resolution of the screen if it is always visible. This may force the IECM interface to be scaled down slightly. To avoid this situation, select the "Auto Hide" option of the Taskbar properties in Windows.

---

## Uncertainty Features

The ability to characterize uncertainties explicitly is a feature unique to this model. As many as one hundred input parameters can be assigned probability distributions. When input parameters are uncertain, an uncertainty distribution of results is returned. Such result distributions give the *likelihood* of a particular value, in contrast to conventional single-value estimates.

The model can run using single deterministic values or uncertainty distributions. The conventional deterministic form using single values for all input parameters and results may be used, or probabilistic analyses may be run—for instance, to analyze advanced technology costs.

---

## Software Used in Development

The underlying engineering models are written in Digital Equipment Corporation's Fortran. Fortran runtime libraries are included with the IECM Interface software. This language provides the flexibility to configure many various power plant designs while also providing the power to conduct probabilistic analyses.

All databases are in Microsoft® Access format and may be viewed in Access, as long as they are not changed. This format is a software industry standard and facilitates sharing and updating of information.

To simplify the use of the model, a Graphical User Interface (GUI) has been added. The interface eliminates the need to master the underlying commands normally required for model operation. The interface is written in Microsoft® Visual C++, a standard software development tool for the Windows environment. Visual C++ runtime libraries are included with the IECM Model software and do not need to be licensed separately.

Wise InstallBuilder was used to generate full and upgrade installer programs. This product was chosen based on its flexibility and its support of Visual Basic runtime libraries and Microsoft Data Access Components (MDAC)<sup>2</sup>. The Visual Basic runtime libraries provide the support needed to run the database file compactor program provided with the IECM. MDAC provides the software support needed to link Microsoft® Access data files to the IECM interface program. Wise InstallBuilder provides the VB and MDAC installation as an option, rather than forcing the user to download it from Microsoft and install it prior to installing the IECM.

---

## Disclaimer of Warranties and Limitation of Liabilities

This report was prepared by the organization(s) named below as an account of work sponsored or cosponsored by the U.S. Department of Energy National Energy Technology Laboratory (NETL). NEITHER NETL, ANY MEMBER OF NETL, ANY COSPONSOR, THE ORGANIZATION(S) NAMED BELOW, NOR ANY PERSON ACTING ON BEHALF OF THEM:

(A) MAKES ANY WARRANTY OR REPRESENTATION WHATSOEVER, EXPRESS OR IMPLIED, (I) WITH RESPECT TO THE USE OF ANY

---

<sup>2</sup> The current version of MDAC is 2.6. This is installed with the full installer for the IECM. Any update installers provided for upgrading the IECM from a previous version to the current version do not upgrade MDAC unless the user updates MDAC separately.



INFORMATION, APPARATUS, METHOD, PROCESS, OR SIMILAR ITEM DISCLOSED IN THIS REPORT, INCLUDING MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, OR (II) THAT SUCH USE DOES NOT INFRINGE ON OR INTERFERE WITH PRIVATELY OWNED RIGHTS, INCLUDING ANY PARTY'S INTELLECTUAL PROPERTY, OR (III) THAT THIS REPORT IS SUITABLE TO ANY PARTICULAR USER'S CIRCUMSTANCE; OR

(B) ASSUMES RESPONSIBILITY FOR ANY DAMAGES OR OTHER LIABILITY WHATSOEVER (INCLUDING ANY CONSEQUENTIAL DAMAGES, EVEN IF DOE OR ANY DOE REPRESENTATIVE HAS BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES) RESULTING FROM YOUR SELECTION OR USE OF THIS REPORT OR ANY INFORMATION, APPARATUS, METHOD, PROCESS, OR SIMILAR ITEM DISCLOSED IN THIS REPORT.

Organization(s) that prepared this report: Carnegie Mellon University

---

## Copyright Notices

DIGITAL Visual Fortran 5.0, Copyright © 1997, Digital Equipment Corporation. All Rights Reserved.

Spread 3.0, Copyright © 1998, FarPoint Technologies, Inc. All Rights Reserved.

Tab Pro 3.1, Copyright © 2000, FarPoint Technologies, Inc. All Rights Reserved.

Graphics Server 4.5, Copyright © 1996, Bits Per Second Ltd. and Pinnacle Publishing, Inc. All Rights Reserved.

Microsoft Visual C++ 5.0, Copyright © 1997, Microsoft Corporation. All Rights Reserved.

InstallBuilder 8.1, Copyright © 2000, Wise Solutions, Inc. All Rights Reserved.

Microsoft Data Access Components 2.6, Copyright © 2000, Microsoft Corporation. All Rights Reserved.

Integrated Environmental Control Model (IECM) Interface 3.4.5, Copyright © 2001, Carnegie Mellon University. All Rights Reserved.

Integrated Environmental Control Model (IECM) 3.4.5, Copyright © 2001, Carnegie Mellon University. All Rights Reserved.

Median Latin Hypercube and Hammersley Sequence Sampling, Copyright © 1997, Urmila Diwekar, Carnegie Mellon University. All Rights Reserved.

Graphics Server is a trademark of Bits Per Second Ltd.

Microsoft is a registered trademark; Windows, Windows 95, Windows 98, Windows NT, and Visual C++ are trademarks of Microsoft Corporation.

Spread™ is a trademark of FarPoint Technologies, Inc.

Tab Pro™ is a trademark of FarPoint Technologies, Inc.

DEC, DEC Fortran, and DIGITAL are trademarks of Digital Equipment Corporation.

# User Documentation and Help

---

## Getting Started

*Getting Started* (this document) gives step-by-step instructions for installing the model software and using the interface. It describes navigating the model, using the main program areas, working with sessions, and printing or exporting results.

---

## User Manual

The *User Manual* gives further information on both the interface and the underlying model. It provides detailed descriptions of plant configurations, parameter settings, and result screens. It also describes technical details behind the model's operation and includes an introduction to uncertainty analysis.

---

## Model Tutorial

The *Model Tutorial* is a pictorial introduction to the IECM. It presents a graphical tour of the interface, a case study to follow using the model, and an appendix which reproduces every screen in the model. These tools help any user to quickly become more familiar with the interface and model.

---

## Technical Manual

The *Technical manual* is a detailed engineering description of the technologies and costing assumptions used in the IECM. This manual is not provided by default with the IECM software; however, it can be downloaded with any web browser from <http://www.iecm-online.com/>.

---

## Online Help

Online help is provided via a Windows Help File containing the text of *Getting Started* and the *User Manual*.

---


## Accessing the IECM Help file:

If you are not running the IECM interface, click the **Help** icon inside the IECM folder on the **Start** menu. This opens the help file to the table of contents.

If you are running the IECM interface, do any one of the following:

- Press the **F1** key. The IECM supports context-sensitive help and will open the help file to the topic associated with the item or screen you are viewing.
- Pull down the **Help** menu at the top of the IECM window. Select **Help Topics**. This opens the help file to the table of contents. (See “The Help Menu” on page 23.)
- Click the **Context-Sensitive Help** icon on the toolbar on the left side of the IECM window. The IECM supports context-sensitive help and will open the help file to the topic associated with the item or screen you are viewing. (See “The Help Menu” on page 24.)
- Click the **Help Topics** icon on the toolbar on the left side of the IECM window. This opens the help file to the table of contents. If this method does not work, try one of the other options above (See “The Toolbar” on page 24.)

The IECM Help File Contents window will display.



*The IECM Help File Topics Window*

# Installing the Model

---

## What's Included in the Model Package

The IECM package should contain the following items:

**Installation Program:** All the software is on one installation program in compressed form. This file is provided either on a compact disk (CD) or from the IECM web site ( <http://www.iecm-online.com/> ). See "Installation" below for instructions on how to install the program.

**Three pieces of documentation:** *Getting Started*, *User Manual*, and *Model Tutorial*, as described in "User Documentation and Help" on page 4.

---

Note: A Technical Manual is not distributed with the model package, but can be downloaded from the IECM web site.

---

---

## Installation

To install the IECM, you must use the installation program, SETUP.EXE, provided on the IECM compact disk (CD). Program files must be decompressed and installed in the appropriate directories to run properly through this program.

Copying the contents of the IECM CD to a local hard drive or a network hard drive can speed the installation process, especially over a network. For more information and instructions, see the *User Manual*.

The IECM can also be installed from one installation program that is available on the worldwide web ( <http://www.iecm-online.com/> ). The installer and update programs on this web site function similarly to the CD originally shipped with the IECM. This method of installation is described in more detail in the *User Manual*.

---

Note: Update or upgrade installers are only provided on the worldwide web site. These are used to enhance or correct the full installation of the IECM on your computer. Send electronic mail to [iecm-team@lists.andrew.cmu.edu](mailto:iecm-team@lists.andrew.cmu.edu) or sign up on our web site if you wish to receive notification of updates.

---

## Installation Steps

### *Running the Setup Program*

1. Place IECM compact Disk (CD) in the CD drive.
2. Click the **Start** button.
3. Choose **R**un... from the Start menu.
4. Type “D : \SETUP” (assuming that the CD drive is D:) and press **Enter**.

The installation program will begin.

### *MDAC Installation*

Before the IECM Interface can be installed, Microsoft Data Access Components (MDAC) must be installed. MDAC is provided by Microsoft as a standard installation package used in conjunction with the IECM installer program. If the appropriate MDAC software components are not detected on your computer, you will be notified that MDAC will be installed this by a warning box as shown below. MDAC is not installed if it the same or a more recent version already exists on your computer.



Click the **OK** button to install MDAC.


Once MDAC has been installed, you will be notified that the computer will reboot by a warning box as shown below.



Click the **OK** button to reboot the computer to continue with the installation. The installation of the IECM will resume automatically after the computer has rebooted.

### *Select Language*

The first screen which displays after MDAC is installed is the “Select Language” screen. Although the IECM itself is written in English, the installer provides several languages during the installation process. The figure below shows the “Select Language” screen.




The “Select Language” installer screen.

After choosing the language, click the **OK** button to continue to the next screen. Click the **Cancel** button at the bottom of the “Choose Language” screen to exit the installer program.

### **Welcome Screen**

The next screen which displays is installed is the “Welcome” screen. It introduces you to the IECM installer and warns you that all Windows programs should be closed before continuing the installation. The figure below shows the “Welcome” screen.




The “Welcome” installer screen.

To quit other programs, you should click the **Cancel** button at the bottom of the “Welcome” screen first and then proceed to quit all other Windows programs. Once other programs are closed, you can restart the installation process.

If there are no other programs running, click the **Next** button to continue to the next screen.

## License Agreement

The next screen to appear displays the license agreement. This screen is shown below. Read the license agreement by scrolling down the window. You cannot install and run the IECM without agreeing to the license agreement. If you do not agree, the installer will quit.




*The License Agreement screen.*

Click the **N**ext button to agree to the license and continue to the next screen.

## Choose Destination Location

The "Choose Destination Location" installation screen asks you to specify the location of the IECM program on your computer. The default location for installation is "C:\Program Files\IECM\_34" as shown in the figure below. This is different than the default used in previous versions; previous versions will co-exist on your computer.




*The "Choose Destination Location" screen.*

For more information on changing the destination location, please refer to the *User Manual*. Click the **N**ext button to continue to the next screen.

## Backup Replaced Files

The “Backup Replaced Files” screen shown below asks if you would like to create backup copies of all files replaced during the installation. This is useful if you are installing a new version of the software over a previous version. You must select **Yes** on this screen to be able to roll back the software to the previous version.




The "Backup Replaced Files" screen

Click the circle next to **Yes** to make backups of replaced files, click the circle next to **No** to skip this step. Click the **Next** button to continue to the next screen.

For more information about backing up replaced files and rolling back installations to a previous version, see the *User Manual*.

## Select Components

The “Select Components” installation screen asks you to specify which portions of the IECM software to install. This screen is shown below.



The "Select Components" screen.



The four components are:

**Microsoft MFC 4.2:** This includes the Microsoft Foundation Class runtime libraries. These are required for using the IECM and are installed by a standard Microsoft installation package as part of the IECM installer.

**Microsoft Visual Basic 4.0 Runtime:** Visual Basic version 4 runtime libraries are required by a database compacting program included with the IECM (compact.exe). These are installed by a standard Microsoft installation package as part of the IECM installer.

**Program Files:** These are the program and support files needed to run the IECM. They are installed into the location specified during the installation process (the default location is C:\Program Files\IECM).

**Documentation:** These are the online help files created from the *Getting Started* and *User Manual* printed documents. These can be omitted from the installation. They are not required for running the IECM software.

Uncheck any of the four options by clicking the checkbox next to its description. Only checked boxes are installed when you continue the installation. Unchecked boxes are NOT installed.

The hard disk space required and available for the selected components is shown at the bottom of the screen. If there is insufficient space to install the software, you will need to cancel the installation and either install the software onto another hard drive or clear space on your hard drive. Click the **N**ext button to continue to the next screen.

---


**WARNING:** If you do not install the Microsoft runtime library packages, you may have difficulty running the IECM. Be sure these library packages are installed by the IECM installer or your computer support group prior to using the IECM.

---

### **Select Program Manager Group**

The IECM interface icon is installed on the desktop by default. Icons for the interface and help file are also provided in a program folder in all versions of Windows (e.g., in the **Programs** folder in the **Start** menu for Windows 95/98). The “Select Program Manager Group” screen asks you to specify the program folder group which will contain the icons to launch the IECM interface program and the online IECM interface help file.


The default Program Manager Group is “IECM Interface 3.4”. You may select another group by clicking on its name in the scroll box to highlight it or create a new group by highlighting the text and typing a new name. Click the **N**ext button to continue to the next screen.



The "Select Program Manager Group" screen

### **Start Installation**

The IECM software is now ready to install. The "Start Installation" screen allows you to go back one last time to check the options you have chosen for installation.




The "Start Installation" screen

Click the **Back** button to return to any of the previous screens to check or change the installation options. Click the **Next** button to continue to install the software.

### **Installation Progress**

The IECM interface setup program now begins copying files onto your hard disk and preparing it for your use. The progress of the activity is shown on the "Installing" screen as shown below.




*The Installation Progress screen*

The top pane of the screen displays the name of the file being copied and its progress. The bottom pane of the screen displays the progress of the entire installation with an estimate of the time remaining.

### ***Installation Complete***

Once the installation program has completed installing the IECM software, the "Installation Complete" screen will display, as shown below.



*The "Installation Complete" screen*

Click the **Finish** button to exit the installation program.

### **Canceling the Installation**

You can stop the installation process at any time by clicking the **Cancel** button which appears on each screen, including the Installation Progress screen. Canceling the process stops all activity and exits the setup program.

## Errors During Installation

If you receive an error message while running Setup, restart the computer and run the installation again. If Setup still returns an error message, contact technical support by electronic mail ( [iecm-team@lists.andrew.cmu.edu](mailto:iecm-team@lists.andrew.cmu.edu) ).

---

## Updating the IECM Software

Updating the IECM software from the original CD, full installation program from the worldwide web site, or update programs downloaded from the worldwide web at some future date can be done in two ways.

1. To replace the existing files: Simply install the software as described under “Installation” on page 6. The software will update the necessary files and allow you to make backup files so that the installation can be rolled back to the previous version. This is the recommended method for updating. User files and data are not effected.
2. To install a second copy of the IECM software on your hard disk: Follow the instructions given under Installation above, but choose a different directory in which to install the files (described in more detail in the *User Manual*).

---

NOTE: Maintaining two copies of the IECM requires more disk space and could lead to confusion. It is not recommended.

---

---

## Removing the IECM Software

To remove the IECM software completely, use the uninstall feature of the Windows 95/98 “Add/Remove Software” control panel.

---

NOTE: Do not just delete the files in the IECM directory, because there are files elsewhere on your system that should also be cleaned up. Deleting the IECM directory could also cause a subsequent attempt to uninstall the software correctly to fail.

---

### ***Running the Uninstall Program***

1. Click the **Start** button.
2. Choose **S**ettings, and then **C**ontrol Panel.
3. Double-click **Add/Remove Programs** in the **Control Panel** folder.
4. Highlight **IECM Interface** on the list of installed software.
5. Click the **Add/Remove...** button.

Follow the instructions on the screen.

Uninstalling the software, as well as rolling back an installation to an earlier version, is described in detail in the *User Manual*.

# Windows Conventions

---

## Microsoft® Windows

The Windows operating environment is based on both graphics and text. Although it is designed to be intuitive, a certain amount of learning is required to use it effectively. Please review the documentation on Microsoft® Windows that came with your personal computer if you are new to the Windows environment.

---

## Using the Mouse

Many commands in Windows 95/98/ME and Windows NT/2000 are executed by moving the mouse cursor (see “Cursors” below) to an item and pressing the left or right button on the mouse.

In this documentation, the following terms will be used for mouse operations:

**Click** - Place the mouse cursor onto a menu, button, field, etc. and press the left button on the mouse.

**Right Click** - Place the mouse cursor onto a menu, button, field, etc. and press the right button on the mouse.

**Double-Click** - Place the mouse cursor onto a menu, button, field, etc. and press the left button on the mouse two times rapidly.

**Click and Drag** - Place the mouse cursor onto a menu, button, field, etc., press the left button on the mouse, and—while holding the button down—move the mouse to another location.

---

## Cursors

The mouse cursor moves on the screen as you move the mouse. The cursor displayed changes as it is placed over different objects, or as the software becomes busy.

## The Arrow



The mouse cursor that is most often displayed is the “arrow” cursor, shown at the left. Use this cursor to pull down menus (see “Menu Bar” on page 18), click buttons on the toolbar (see “The Toolbar” on page 24), or navigate through the model using tabs (see “Tabs” on page 25.)

## The Cross



If the mouse arrow is moved over an input or result spreadsheet table, it becomes the “cross” cursor, shown at the left. Use this cursor to click a cell and enter data, or select a cell or group of cells (see “Parameters and Results Workspace” on page 28).

## The I-Beam



If the mouse cross is placed over an input field and double-clicked, an “I-beam” or editing cursor will display instead of the cross. This cursor is shown at the left. Clicking again places a typing cursor into the field, so that values can be edited instead of replaced (see “Editing values” on page 43).

## The Hourglass



Some software processes take some time to perform. When the software is busy for more than a few seconds, an “hourglass” cursor, shown at the left, will display. Further activity will be delayed until the process is complete.

## The Arrow and Hourglass



Sometimes a process works in the background. Rather than the hourglass, an “arrow and hourglass” cursor, shown at the left, will display. The arrow may still be used, but the command may be delayed because of the process running in the background.

---

# Keystroke Commands

Many operations in Windows can be executed by a combination of keystrokes as well as a mouse click. These keystroke combinations involve the **Alt** key and the **Ctrl** key.

---

NOTE: Once an Alt key combination is active, the Ctrl key combinations will not work. The Ctrl key combinations are meant to bypass menus.

---

## Alt Commands

When the name of an operation appears on the screen with one letter underlined, you may execute that operation by holding down the **Alt** key while pressing the key for the underlined letter at the same time.

Example: **F**ile - hold down the **Alt** key and press the **F** key to activate the **F**ile pull-down menu.

In this documentation, instructions for **Alt** keystrokes are abbreviated in the form “Press **Alt-X**” where X is the letter key. (NOTE: While the capital letter is given in this documentation, do not press the shift key while entering the command.)

Example: “Press **Alt-F** to activate the **File** menu”

## Ctrl Commands

Some operations have been assigned specific keystroke combinations involving the **Ctrl** key. You may execute them by holding down the **Ctrl** key while pressing the key for the appropriate letter. Most are listed on the pull-down menu from which the command is normally selected.

In this documentation, instructions for **Ctrl** keystrokes are abbreviated in the form “Press **Ctrl-X**” where X is the letter key. (NOTE: While the capital letter is given in this documentation, do not press the shift key while entering the command.)

Some of the more common **Ctrl** commands are the following:


|                                |   |                              |
|--------------------------------|---|------------------------------|
| <b>Ctrl-N</b> – New Session    | <b>Ctrl-O</b> – Open Session              | <b>Ctrl-S</b> – Save Results |
| <b>Ctrl-C</b> – Copy           | <b>Ctrl-P</b> – Print                     | <b>Ctrl-V</b> – Paste        |
| <b>Ctrl-F4</b> – Close Session | <b>Ctrl-F6</b> – Switch to another window |                              |

# IECM Conventions

---

## The IECM Window

Once you have started the model , the IECM Window displays. The IECM Window contains all the screens used by the Interface, as well as the tools for control of the software described below.



*The IECM Window*

The IECM Window is initially sized to fill an 800x600 resolution screen. If your display is set to 800x600 pixels, the IECM window will completely fill the screen.

---

## Menu Bar

The menu bar appears at the top of the IECM window. It consists of four pull-down menus: **F**ile, **E**dit, **V**iew, **W**indow, and **H**elp. These pull-down menus issue commands to the IECM software.



## Choosing an Command from a Pull-Down Menu

1. Activate the pull-down menu by doing one of the following:

- Place the mouse arrow on the title of the menu you want to pull down and click.
- Hold down the **Alt** key on the keyboard and press the letter in the menu title which is underlined. Example: To pull down the **F**ile menu, press **Alt-F**.


The menu will remain visible and active until you choose a command or move the mouse cursor outside the window.

2. Choose from the menu by doing one of the following:

- Place the mouse arrow on the action you want to perform and click.
- Hold down the **Alt** key again and press the letter in the action title which is underlined. Example: To **P**rint, press **Alt-P**.

## The File Menu

The **F**ile menu is the left-most pull-down menu on the Menu bar. The **F**ile menu is shown below.



The **F**ile menu

You may choose the following commands from the file menu:

**N**ew Session – Creates a new session from model defaults. (See “Creating a New Session” on page 61.)

**O**pen Session – Opens a previously created session. (See “Opening an Existing Session” on page 62.)

**C**lose Session – Closes the currently active session. (See “Closing a Session” on page 63.)

**D**elete Session – Deletes a session. (See “

Deleting a Session” on page 64.)

**Unlock Session** – Unlocks a session that was not closed normally (e.g. because of a crash or loss of network connectivity. (See “

Unlocking a Session” on page 64.)

**Save Results** – Saves the results from a session in an external file. (See “Saving a Session’s Results” on page 62.)

**Save As** – Saves a session with a different name. (See “Saving a Session with a Different Name” on page 63.)


**Import** – Imports a session from an external database file. (See “Importing a Session” on page 66.)

**Print** – Prints configuration settings, inputs or results. (See “Print Dialog Box” on page 68.)

**Exit** – Closes the current session and exits the interface. (See “Exiting the Model” on page 34.)

## The Edit Menu

The **E**dit menu is the second pull-down menu on the Menu bar. The **E**dit menu is shown below.



*The Edit Menu*

You may choose the following commands from this menu:


**C**ut – Removes text from a workspace. (See “Cut” on page 67)

**C**opy – Copies text from a workspace. (“Copy” on page 67)

**P**aste – Pastes text into a workspace. (See “Paste” on page 67)

## The View Menu

The **V**iew menu is the third pull-down menu on the Menu bar. The **V**iew menu is shown below.



*The View Menu*

You may choose the following commands from this menu:

**T**oolbar – Chooses whether or not the Toolbar displays. (See “The Toolbar” on page 24.)

**S**tatus Bar – Chooses whether or not the Status Bar displays. (See “The Status Bar” on page 24.)

**Uncertainty Tools** – Displays the Uncertainty Tools floating palette. (See “


Uncertainty Areas” on page 60.)

**Input Tools** – Displays the Input Tools floating palette. (See “Input Tools” on page 44.)

**Result Tools** – Displays the Result Tools floating palette. (See “Result Tools” on page 59.)

## The Window Menu

The **Window** menu is the fourth pull-down menu on the Menu bar. The **Window** menu is shown below.



The *Window* Menu

You may choose the following commands from this menu:

**Cascade** – Arranges all open windows in a cascade from the upper left corner of the IECM Window.

**Tile Horizontally** – Arranges all open windows in a tile from the left to the right of the IECM Window.

**Tile Vertically** – Arranges all open windows in a tile from the top to the bottom of the IECM Window.


**Arrange Icons** – Arranges all minimized windows in the lower left corner of the IECM Window.

**Windows...** – Allows you to choose which open window is active.

**1, 2, 3** (etc.) – Allows you to choose which open window is active.

## The Help Menu

The **Help** menu is the fifth pull-down menu on the Menu bar. The **Help** menu is shown below.



The *Help* Menu

You may choose the following commands from this menu:

**Help Topics** – Displays online help. (See “Online Help” on page 4.)

**About IECM Interface** – Displays the Logo Box. (See “Starting the Model” on page 33.)

---

## The Toolbar

The toolbar is a row of buttons which runs down the left side of the IECM Window. Clicking on a button executes a common command. All of the commands can also be executed from pull-down menus. (See “Menu Bar” on page 18.)



*The toolbar buttons: New Session, Open Session, Close Session, Save Results, Print, Cut, Copy, Paste, Import, Help Topics, and Context-Sensitive Help (note that they appear vertical in the model).*

When the mouse arrow is held over a toolbar button momentarily, a description of the button’s command displays.

You may choose whether or not the toolbar displays. Pull down the **V**iew menu and select **T**oolbar. This is a toggle switch which will toggle between displaying the toolbar and not displaying it. When **T**oolbar is checked, the toolbar displays, when it is not checked, it does not display.

---

## The Status Bar

The status bar is displayed at the bottom of the window. Messages about the status of the interface appear at the left side of the status bar . Normally, “Ready” is displayed. When the mouse cursor is moved over a toolbar button or pull-down menu item, the name of the command which is associated with the item is displayed.

At the right of the status bar are three boxes which indicate if the Capital Letters Lock, Number Lock, or Scroll Lock are turned “on”. If the box is empty, the lock is turned off. If CAPS, NUM, or SCRL display, the lock is turned on.




*The status bar: The interface is ready, and the Number Lock is set to on.*

You may choose whether or not the status bar displays: Pull down the **V**iew menu and select **S**tatus Bar. This is a toggle switch which will toggle between displaying the status bar and not displaying it. When **S**tatus Bar is checked, the toolbar displays, when it is not checked, it does not display.

---

## The Session Window

Once you have opened or created a session, a session window displays for the session you are working with. The session window contains all the screens used by the session. (See “Sessions” on page 61.)



*The Session Window*


The session window is initially sized to fill the entire IECM Window at a resolution of 800x600 pixels. If additional windows are open in the IECM Window, they will be behind the session window. You may access these windows through the **Window** menu on the Menu Bar. (See “The Window Menu” on page 23.)

---

## Tabs

Movement within the interface is accomplished primarily by clicking tabs. Tabs extend above or below the session’s workspace. Moving between tabs means moving between program areas, input screens, or result screens.

When a tab is selected, the tab comes forward, its border surrounds the workspace, its color changes, and its text becomes white. Therefore, it is evident which tabs have been selected—or made “active”—and therefore which screen is being displayed. Looking at the tabs above and below the workspace, one can always tell where one is in the model.



The three sets of tabs are all visible: the Program Area Navigation Tabs (Set Parameters is active), the Technology Navigation Tabs (Base Plant is active), and the Input/Results Navigation Tabs (1 Performance) is active.

## Types of Tabs

Three sets of tabs are used in the IECM model:

**Program Area Navigation Tabs:** These three tabs always display at the top of the current session's window. The active tab is red, the others are gray. They allow movement between the model's main program areas: Configure Plant, Set Parameters, and Get Results.

**Technology Navigation Tabs:** These tabs display below the Program Area Navigation Tabs and above the workspace in the Set Parameters and Get Results modules. The active tab is dark red, the others are gray. They allow movement between technology input or results screens.

Technology Navigation Tabs display only currently selected technologies. For example, the combined SO2/NOx input and result tabs are only displayed when a combined technology is selected, replacing the SO2 input and results tabs.

**Input Navigation Tabs/Results Navigation Tabs:** Input Navigation Tabs and Results Navigation Tabs display below the workspace in the Set Parameters and Get Results modules. The active tab is brown, the others are gray. They allow movement between input or results screens within a technology.

## Moving Between Tabs

To move from tab to tab, do one of the following:

- Place the mouse arrow on the tab to which you want to move and click.
- Hold down the **Alt** key on the keyboard and press the letter in the tab title which is underlined. Example: to switch to the Set Parameters tab, press **Alt-S**.




The software remembers which Technology Navigation Tab is active within each Program Area and which Input/Results Navigation Tab is active within each technology. Therefore, when returning to a program area or technology tab, one returns to the same workspace which one left.

---

## Plant Diagrams

In the two program areas where there are Technology Navigation Tabs—**Set Parameters** and **Get Results**—the first tab includes a plant diagram.



*The Plant Diagram*


### ***Using the Plant Diagram***

In the **Set Parameters** and **Get Results** program areas, the Plant Diagram can be used as an alternate way to move among Technology Navigation tabs. Do one of the following:

- Click the button for the technology for which you would like to provide inputs or get results and it will activate the corresponding tab for that technology.
- Move through the Plant Diagram by pressing the **Tab** key—a box will surround the technology selected. Then press the **Space bar** to activate the corresponding tab for that technology.

# Parameters and Results Workspace

In both the **Set Parameters** and **Get Results** program areas, information is displayed in a common workspace. The workspace is made up one or more tables which imitate a spreadsheet and can be used like a spreadsheet is used. The workspace displays between the input and result navigation tabs.



The Base Plant—4. Capital Cost input screen workspace

## Movement in the Workspace

One may move throughout the spreadsheet by doing any one of the following:

- Moving the mouse cursor (it will be the cross cursor): Move the cursor over a cell and click to select a cell.
- Using the **Enter** key on the keyboard: Pressing **Enter** will select the cell beneath the currently selected cell.
- Using the arrow keys on the keyboard: you may move up ( ↑ ), down ( ↓ ), left ( ← ), and right ( → ).

When an individual cell is selected, it is outlined in black.

|   | Title                          | Units | Unc | Value | Calc | Min | Max | Default |
|---|--------------------------------|-------|-----|-------|------|-----|-----|---------|
| 1 | Construction Time              | years |     | 5     |      | 0   | 10  | 5       |
| 2 |                                |       |     |       |      |     |     |         |
| 3 | General Facilities Capital     | %PFC  |     | 10    |      | 0   | 20  | 10      |
| 4 | Engineering & Home Office Fees | %PFC  |     | 6.5   |      | 0   | 20  | 6.5     |
| 5 | Project Contingency Cost       | %PFC  |     | 11.67 |      | 0   | 100 | 11.67   |

The cell selected is in the Value column for the Engineering & Home Office Fees

## Selecting Cells

You may select individual cells (see “

Parameters and Results Workspace” on page 28), multiple cells, or entire rows, columns, or tables. Once selected, the contents of the cells may be copied to the windows clipboard for insertion into another application. (See “Windows Copy, Cut, and Paste” on page 66.)

### Selecting Multiple Cells

To select multiple cells, do one of the following:

- Click and drag the mouse cursor (it will be the cross cursor) over the cells you would like to select.
- Hold down the shift key and use the arrow keys on the keyboard to select a group of cells.

The first cell selected will be outlined in black, all other selected cells will be reverse video.

|   | Title                          | Units | Unc | Value | Calc | Min | Max | Default |
|---|--------------------------------|-------|-----|-------|------|-----|-----|---------|
| 1 | Construction Time              | years |     | 5     |      | 0   | 10  | 5       |
| 2 |                                |       |     |       |      |     |     |         |
| 3 | General Facilities Capital     | %PFC  |     | 10    |      | 0   | 20  | 10      |
| 4 | Engineering & Home Office Fees | %PFC  |     | 6.5   |      | 0   | 20  | 6.5     |
| 5 | Project Contingency Cost       | %PFC  |     | 11.67 |      | 0   | 100 | 11.67   |

*The Values for General Facilities Capital, Engineering & Home Office Fees, and Project Contingency Cost are highlighted*

### Selecting Entire Rows, Columns, or Tables

**To select an entire column:** Click the title button (column heading) above the column.

**To select an entire row:** Click the numbered button (row heading) to the left of the row.

**To select an entire table:** Click the button in the upper left-hand corner of the spreadsheet.

|   | Title                          | Units | Unc | Value | Calc | Min | Max | Default |
|---|--------------------------------|-------|-----|-------|------|-----|-----|---------|
| 1 | Construction Time              | years |     | 5     |      | 0   | 10  | 5       |
| 2 |                                |       |     |       |      |     |     |         |
| 3 | General Facilities Capital     | %PFC  |     | 10    |      | 0   | 20  | 10      |
| 4 | Engineering & Home Office Fees | %PFC  |     | 6.5   |      | 0   | 20  | 6.5     |
| 5 | Project Contingency Cost       | %PFC  |     | 11.67 |      | 0   | 100 | 11.67   |

*The entire row for Engineering & Home Office Fees is selected.*

## Highlighting

On some parameters and results screens, parameters or results are highlighted to indicate their importance. Parameters are highlighted in blue, results are highlighted in yellow.

| Title                                 | Units             | Unc | Value     | Calc | Min    | Max       | Default   |
|---------------------------------------|-------------------|-----|-----------|------|--------|-----------|-----------|
| 1 Gross Electrical Output             | MWg               |     | 500.0     |      | 100.0  | 1500      | 500.0     |
| 2 Steam Cycle Heat Rate               | Btu/kWh           |     | 7880      |      | 6000   | 1.100e+04 | 7880      |
| 3 Boiler Efficiency                   | %                 |     | 89.36     | ☑    | 0.0    | 100.0     | calc      |
| 4 Capacity Factor                     | %                 |     | 75.00     |      | 0.0    | 100.0     | 75.00     |
| 5 Excess Air For Furnace              | % stoich.         |     | 20.00     | ☑    | 0.0    | 40.00     | calc      |
| 6 Leakage Air at Preheater            | % stoich.         |     | 19.00     | ☑    | 0.0    | 60.00     | calc      |
| 7 Gas Temp. Exiting Economizer        | deg F             |     | 700.0     |      | 250.0  | 1200      | 700.0     |
| 8 Gas Temp. Exiting Air Preheater     | deg F             |     | 300.0     |      | 150.0  | 400.0     | 300.0     |
| 9 Ambient Air Temperature             | deg F             |     | 80.00     |      | -50.00 | 130.0     | 80.00     |
| 10 Ambient Air Pressure               | psia              |     | 14.70     |      | 12.00  | 15.00     | 14.70     |
| 11 Ambient Air Humidity               | lb H2O/lb dry air |     | 1.800e-02 |      | 0.0    | 3.000e-02 | 1.800e-02 |
| 12 Percent Water in Bottom Ash Sluice | %                 |     | 39.30     | ☑    | 0.0    | 100.0     | calc      |
| 13 Base Plant Energy Requirements     |                   |     |           |      |        |           |           |
| 14 Coal Pulverizer                    | % MWg             |     | 0.6000    | ☑    | 0.0    | 2.000     | calc      |
| 15 Steam Cycle Pumps                  | % MWg             |     | 0.6500    |      | 0.0    | 2.000     | 0.6500    |
| 16 Forced Draft Fans                  | % MWg             |     | 1.500     |      | 0.0    | 4.000     | 1.500     |
| 17 Cooling System                     | % MWg             |     | 1.800     |      | 0.0    | 2.000     | 1.800     |
| 18 Miscellaneous                      | % MWg             |     | 1.300     |      | 0.0    | 4.000     | 1.300     |


The Base Plant—1. Performance input screen

| Process Area                 | Direct Capital Costs (M\$) | Process Area                       | Indirect Capital Costs (M\$) |
|------------------------------|----------------------------|------------------------------------|------------------------------|
| 1 Steam Generator            | 119.4                      | 1 Process Facilities Capital       | 288.4                        |
| 2 Turbine Island             | 86.50                      | 2 General Facilities Capital       | 28.84                        |
| 3 Coal Handling              | 38.23                      | 3 Eng. & Home Office Fees          | 18.75                        |
| 4 Ash Handling               | 5.259                      | 4 Project Contingency Cost         | 33.66                        |
| 5 Water Treatment            | 7.336                      | 5 Process Contingency Cost         | 0.8652                       |
| 6 Auxiliaries                | 31.73                      | 6 Interest Charges (AFUDC)         | 48.26                        |
| 7 Process Facilities Capital | 288.4                      | 7 Royalty Fees                     | 0.2019                       |
| 8                            |                            | 8 Preproduction (Startup) Cost     | 12.98                        |
| 9                            |                            | 9 Inventory (Working) Capital      | 0.2223                       |
| 10                           |                            | 10 Total Capital Requirement (TCR) | 432.2                        |
| 11                           |                            | 11                                 |                              |
| 12                           |                            | 12                                 |                              |
| 13                           |                            | 13                                 |                              |
| 14                           |                            | 14                                 |                              |
| 15                           |                            | 15                                 |                              |

The Boiler—2. Capital Cost Result Screen

## Process Type Pull-Down Menus

Your power plant may have more than one technology for some processes (especially NO<sub>x</sub> Control). Therefore, at the bottom of most parameters and results screens, there is a pull-down menu which indicates which process is addressed.



*The Process Type Pull-Down Menu from the NO<sub>x</sub> Control—1. Config input screen*

**To change the process for which you are entering inputs or viewing results,** click on the arrow next to the box and choose the appropriate process.

If there is only one technology selected for that process, it will display in gray text and it will not be possible to change it.

# Running the Model


---

## Starting the Model



A program group called **IECM Interface** is created when the model is installed. It will display in the **Programs** group in the Start Menu. The program group contains several icons—one is for the help file, another for the main program file titled **IECM**. The icon for the IECM model is shown to the left. To start the Model, click this program icon in the Start Menu.

The model will launch, and the IECM Interface Window (see “The IECM Window” on page 18) and Logo Box will display.



*The IECM Logo Box*

The Logo Box will disappear in 5 seconds, after which the interface will be ready for use. You may also click the **Close** button (**x**) in the upper right hand corner of the logo box to begin.

---

## Choosing a Session

To begin using the IECM Interface, you must first choose a session. A session is a complete collection of data—configuration, parameters, and results—which describes one power plant. The model uses the configuration settings and parameters in a session to calculate the results.

The first time you use the software, you will have to create a new session. (See “Creating a New Session” on page 61.)

At subsequent startups, you may create a new session or use a previously saved session. (See “Working with Sessions” on page 61.)

---

## Using the Model

There are eight steps involved in running the model:

1. Start the Model. (See “Starting the Model” on page 33.)
2. Open a session (existing or new). (See “Creating a New Session” on page 61.)
3. Configure the Plant. (See “Configuring the Plant” on page 35.)
4. Set Input Parameters. (See “Setting Parameters” on page 38.)
5. View Results. (See “Getting Results” on page 50.)
6. Print or Export Results (if desired). (See “Printing” on page 68 or “Exporting a Session” on page 66.)
7. Save the session results (if desired). (See “Saving a Session’s Results” on page 62.)
8. Exit the model. (See “Exiting the Model” below.)


---

## Exiting the Model

To quit the model, do one of the following:

- Pull down the **F**ile pull down menu and select **E**xit.
- Click the **C**lose button (**x**) in the upper right hand corner of the IECM window.
- Press **Alt-F4**.

A dialog box will ask if you want to save results. (See “Saving a Session’s Results” on page 62.) To save results, click the **Y**es button. To exit without saving results, click the **N**o button. To abandon the procedure, click the **C**ancel button.



*The Save Results at Close dialog box*




# Configuring the Plant

## Configure Plant

**Configure Plant** is the first of the three program areas. When you begin working with a session, the software will display this area. You may also choose this area by clicking on its tab at the top of the screen. You may return to **Configure Plant** and change the configuration settings at any time.

In **Configure Plant** you choose the technologies implemented by the plant and how they will operate. Available options are presented via pull-down menus. Detailed descriptions of each option is given in the *User Manual*.

Once you have selected the options for the session, you may move on to the **Set Parameters** or **Get Results** program areas.




*The Configure Plant Program Area*

---

## Configuration Pull-Down Menus

A series of pull-down menus are displayed on the left side of the screen. Each corresponds to a plant configuration setting or technology.



| Combustion Controls |                     |
|---------------------|---------------------|
| Furnace Type:       | Tangential          |
| NOx Control:        | In-Furnace Controls |


The Combustion Controls Pull-Down Menus allow you to choose Furnace Type and NO<sub>x</sub> Control settings

### Changing Configurations

To change a configuration setting:

Using the Mouse:

1. Click the arrow button to the right of the setting, and the box pulls down to display the options possible for that configuration setting.



|              |                  |
|--------------|------------------|
| SO2 Control: | None             |
|              | None             |
|              | Wet FGD          |
|              | Lime Spray Dryer |

2. Click the option you desire and it will be selected and displayed in the box.

Using the Keyboard:

1. Move between configuration settings by pressing the **Tab** key to move to the next setting, and **Shift-Tab** to move to the previous setting.
2. Change the setting by using the arrow keys: Press the up arrow (↑) key to change the setting to the previous possible option, and the down arrow (↓) key to change the setting to the next possible option.

---

## Invalid Selections

Some combinations of options are not available. Certain settings depend on other configuration settings.

If an option cannot be selected, it will display in gray text and it will not be possible to choose it.




|              |         |
|--------------|---------|
| SO2 Control: | Wet FGD |
| SO2/NOx:     | None    |

If an SO<sub>2</sub> control technology is selected, combined SO<sub>2</sub>/NO<sub>x</sub> controls are not available

---

## Plant Diagram

A plant at the right side of the screen displays icons for the technology options you have selected for the plant configuration.



*The Plant Diagram*


# Setting Parameters

## Set Parameters

The second of the three program areas is **Set Parameters**. Choose this area by clicking its tab at the top of the screen. You may return to **Set Parameters** and change the inputs at any time.

In **Set Parameters**, you modify the input values for the session. Detailed descriptions of all inputs are given in the *User Manual*.

The **Overall Plant** tab is displayed when **Set Parameters** is first selected.




*The Set Parameters Program Area*

---

## Plant Diagram

The first Technology Navigation Tab in the **Set Parameters** program area is for the **Overall Plant**. This screen displays the plant configuration settings on the left side of the page and a diagram of the plant as configured at the right of the page. (See “Configuring the Plant” on page 35.) No inputs are entered on this screen.



*The Plant Diagram*


### **Using the Plant Diagram**

The Plant Diagram can be used as an alternate way to move among input Technology Navigation tabs. Do one of the following:

- Click the button for the technology for which you would like to provide inputs and it will activate the corresponding tab for that technology.
- Move through the Plant Diagram by pressing the **Tab** key. A highlighting box will surround the technology selected. Then press the **Space bar** to activate the corresponding tab for that technology.

# Set Parameters Workspace

Choosing one of the technology area tabs brings up a workspace for the parameters for that area. The workspace imitates a spreadsheet (see “Parameters and Results Workspace” on page 28) with the following columns: Title, Units, Uncertainty, Value, Calculated, Minimum, Maximum, and Default.



The Base Plant—4. Capital Cost input screen workspace

When a new session is created, the default values are loaded for each parameter. You may change any or all of the values for any or all of the technologies.

Because default values exist for every parameter, you do not have to visit every screen, or enter parameters in any particular order.

## Movement in the Workspace

One may move throughout the spreadsheet by doing any one of the following:

- Moving the mouse cursor (it will be the cross cursor): Move the cursor over a cell and click to select a cell.
- Using the **Enter** key on the keyboard: Pressing **Enter** will select the cell beneath the currently selected cell.
- Using the arrow keys on the keyboard: you may move up ( ↑ ), down ( ↓ ), left ( ← ), and right ( → ).

The cell which is selected—and in which the cursor will type—is outlined in black.

|   | Title                          | Units | Unc | Value | Calc | Min | Max | Default |
|---|--------------------------------|-------|-----|-------|------|-----|-----|---------|
| 1 | Construction Time              | years |     | 5     |      | 0   | 10  | 5       |
| 2 |                                |       |     |       |      |     |     |         |
| 3 | General Facilities Capital     | %PFC  |     | 10    |      | 0   | 20  | 10      |
| 4 | Engineering & Home Office Fees | %PFC  |     | 6.5   |      | 0   | 20  | 6.5     |
| 5 | Project Contingency Cost       | %PFC  |     | 11.67 |      | 0   | 100 | 11.67   |

The cell selected is in the Value column for the Engineering & Home Office Fees

## Title

This column displays the name of the parameter to be set in that row. Titles cannot be changed. Each parameter is described in detail in the *User Manual*.

## Units

This column displays the units in which the parameter will be input. Units may be changed for inputs; see “Input Tools” on page 44. (Units may also be changed in results; see “Result Tools” on page 59.)

## Uncertainty (Unc)

This button opens the Uncertainty Editor dialog box so that you may input probabilistic values. Entering uncertainty is described in “Uncertain Values” on page 46.

## Value

This column displays the current value of the parameter. To change the value, see “

Entering Inputs” on page 43.

## Calculated (Calc)

This check-box indicates whether the parameter is entered by the user or calculated by the model using other parameters. If it is checked, the value is calculated, if it is not checked, the value may be changed. Rows with no check box contain static values. See “Calculated Values” on page 44.

## Minimum, Maximum, and Default

These columns provide the minimum, maximum, and default values for the parameter. If a value below the minimum or above the maximum is entered, the interface will display a warning, but the value will be used as entered.

**Minimum** – the lower limit for the value entered in the **Value** column.

**Maximum** – the upper limit for the value entered in the **Value** column.

**Default** – the default value which was shipped with the IECM software, in case the value must be reset to the default. All parameters have a default value.



---

## Entering Inputs

Input values may be entered, or the current values may be edited. In addition, some values are selected from pull-down boxes.

### Entering Values

To enter values:

1. Select the appropriate cell under the **Value** column. The selected cell will be outlined in black.

| Unc | Value | Calc |
|-----|-------|------|
|     | 2500  |      |
|     | 5694  |      |

2. Type the new value. The value entered will replace the current value.

The **Default** column displays the default value which was shipped with the IECM for that parameter, in case the value must be reset to the default.

### Editing values

To change a value rather than replacing it:

1. Use the mouse cursor (the cross cursor) and double-click the cell. The value will display at the left, highlighted in blue and the I-Beam mouse cursor will display.

| Unc | Value | Calc |
|-----|-------|------|
|     | 2500  |      |
|     | 5694  |      |

2. Click again with the cursor next to the number you would like to change. An editing cursor will display. You may now edit the number in the cell.

| Unc | Value | Calc |
|-----|-------|------|
|     | 2500  |      |
|     | 5694  |      |

The **Default** column displays the default value which was shipped with the IECM for that parameter, in case the value must be reset to the default.

### Choices in Pull-Down Boxes

Some cells have fixed choices in the form of pull-down boxes.

|   | Title                   | Units | Unc | Value       |
|---|-------------------------|-------|-----|-------------|
| 1 | Reagent                 |       |     | Limestone ▾ |
| 2 | Flue Gas Bypass Control |       |     | No Bypass ▾ |
| 3 |                         |       |     |             |

*The SO<sub>2</sub> Control—1. Config (Wet FGD) has two values in pull-pull-down boxes*

To change the option in a pull-down box:

1. Click the arrow button to the right of the cell, and the box pulls down to display the options possible for that cell.



2. Click the option you desire and it will be selected and displayed in the box.

The **Default** column displays the default choice which was shipped with the IECM for that parameter, in case it must be reset to the default.

## Input Tools


Inputs may be entered in either English or Metric units. Use the **Input Tools** floating palette to change the unit system in which inputs will be entered. You may move this floating palette to the side of the screen, change units, and watch how the results are altered as a result. To close the palette, click the **Close** button (X) in the upper right hand corner of the palette.

More information on various unit options is provided in the *User Manual*.

### **Changing the Unit System for Inputs**

To change how results are displayed:

1. Pull down the **View** menu and choose **Input Tools**. The **Input Tools** floating palette will display.



*The Input Tools Floating Palette*

2. Choose the unit system desired by clicking the arrow to the right of the pull-down menu and choosing **English** or **Metric**.
3. To close the **Input Tools** floating palette, click the **Close** button (X) in the upper right hand corner of the palette.

## Calculated Values


Values which are calculated by the program are displayed in blue in the Value column and the **Calc** checkbox is checked.

| Value | Calc                                |
|-------|-------------------------------------|
| 75.00 | <input checked="" type="checkbox"/> |

### **Changing Calculated Values**

To change a calculated value:

1. Click the checkbox to remove the check.

| Value | Calc  |
|-------|---|
| 0     |  |

2. The number will be reset to zero and display in black, and you may change the value as described under “

## Uncertain Values


Any input parameter may be assigned a probability distribution. When an input parameter is uncertain, an uncertainty distribution of results is returned. Such result distributions give the *likelihood* of a particular value.

### Entering Uncertainty

To enter or edit an uncertain or probabilistic value:



1. Click the **Unc** button next to the parameter for which you want to enter an uncertain value.
2. The **Uncertainty Editor** dialog box will display.




The Uncertainty Editor Dialog Box

3. Select a Distribution type from the Distribution pull-down box. (See “Distribution Types” on page 47.)
4. Enter values for the Minimum and Maximum, Mean and Deviation, or whatever values are needed for the particular Distribution.
5. Click the **Done** button.



Once you have entered an uncertainty distribution, a question mark displays on the **Unc** button for that parameter on the input screen.



## Distribution Types

**Distribution types:** The distributions are listed in a pull-down box in the uncertainty editor window. **None** is initially selected because the default is for no uncertainty. The following distributions may be used: **Normal, Lognormal, Uniform, Triangular.** Each option is described in more detail in the *User Manual*.

The distribution types **Fractiles, Half Normal, and Negative Half Normal** will be available at a future date.

## Removing Uncertainty

To remove an uncertainty distributions:

1. Click the **Unc** button for which you would like to remove uncertainty. The Uncertainty Editor will display.
2. Select **None** from the list of distributions.
3. Click the **Done** button. This will make the **None** function permanent and close the uncertainty editor window.



The question mark will no longer display on the **Unc** button for that parameter on the input screen.

---

## Input Navigation Tabs

Most technologies have more than one screen of inputs to enter. These are reached via the Input Navigation tabs at the bottom of the screen.




*Input navigation tabs from the Particulate Control input area*

Each tab selects a workspace with a spreadsheet for the appropriate inputs.

# Coal Properties Parameters

The **Coal Properties—1. Coal Prop.** input screen is unique within the **Set Parameters** program area.



The Coal Properties—1. Coal Prop. input screen

There are two panes, one for the properties of the **Current Coal**, the other for those of **Favorite Coals**. The current coal is the coal with which the model will conduct its calculations. Favorite coals are those which you use most.

You may use a favorite coal, use a default model coal, or enter a user-defined coal. Working with coals not provided in the model defaults, entering user-defined coals, editing the ash properties, and other options are described in the *User Manual*.

In a future version of the model it will be possible to load external coal databases created in applications other than the interface.

## Using a Favorite Coal


To use one of the **Favorite Coals**:

1. Select the name of the coal in the box in the **Favorite Coals** pane.
2. Click the **Use This Coal** button.

## Using Model Defaults


To use a coal from the model defaults that is not listed in the **Favorite Coals**:

1. Click the **Browse All Coals** button. The Browse All Coals dialog box will display.



The Browse All Coals dialog box

2. Choose **Model Defaults** in the **Select Source** Pane.
3. Choose a coal from the **Select Coal** Pane:
  - a. Click the arrow button to the right of the **Name:** box, and the box displays a list of coal names.



The Select Coal Name Pull-Down Menu

- b. Click the coal you want to use and it will be selected and displayed in the box.
4. Click the **Use this Coal** button to use the coal and the **Add to Favorites** button to add the coal the list of favorite coals.
5. Click the **Close** button.

### Default Ash Properties

Each of the default coals has a full set of default ash properties associated with it. The properties associated with a coal selected in the **Favorite Coals** pane can be viewed by clicking the **View Ash Properties** button on the lower right corner of the pane.

Ash properties are associated with every coal specified, whether from the default coal list, an external coal list, or a user-specified coal. In cases where the ash properties are not given directly, representative ash properties are selected by the IECM interface. See the *User Manual* for more information on ash properties and how they can be specified.


# Getting Results

## Get Results

The third of the three program areas is **Get Results**. Choose this area by clicking its tab at the top of the screen. You may return to **Get Results** at any time to look at results.

In **Get Results** you view the results for this session. The IECM allows you to view results for any individual plant technology or for the power plant as a whole.

The **1. Diagram** screen of the **Overall Plant** tab is displayed when you first choose **Get Results**.




*The Overall Plant—1. Diagram Result Screen*



---

## Plant Diagram

The first Technology Navigation Tab in the **Get Results** program area is the **Overall Plant**. The **1. Diagram** screen displays the plant configuration settings on the left side of the page and a diagram of the plant as configured at the right of the page. (See “Configuring the Plant” on page 35.) No results are returned on this screen.



*The Plant Diagram*

### **Using the Plant Diagram**

The Plant Diagram can be used as an alternate way to move among result Technology Navigation tabs. Do one of the following:

- Click the button for the technology for which you would like to get results and it will activate the corresponding tab for that technology.
- Move through the Plant Diagram by pressing the **Tab** key—a box will surround the technology selected. Then press the **Space bar** to activate the corresponding tab for that technology.

---

## Viewing Results

Results are displayed in two different kinds of screens: diagrams and spreadsheet screens. Diagrams provide a schematic of and values for the stream flows into and out of that technology. Spreadsheet workspaces operate in the same way as the spreadsheets used in **Set Parameters**. The workspace imitates a spreadsheet (see “

Parameters and Results Workspace” on page 28) with appropriate results for that technology. A detailed description of all results is provided in the *User Manual*.

The table and diagram results are all deterministic values—uncertainties are not taken into consideration. Graphs are probabilistic. This is different from previous versions of the IECM that used Analytica as a calculation engine. Analytica uses the expected value in table and diagram results, which takes into consideration the uncertainties defined.

## Results Navigation Tabs


Many technologies have more than one screen of results. These are reached via the Results Navigation tabs at the bottom of the screen. Each tab selects a screen which displays the appropriate results.



*Result Navigation Tabs*

## Diagrams

Each technology result area has a **Diagram** result screen. This screen provides a schematic of and values for the stream flows into and out of that technology.



*The Air Preheater—1. Diagram result screen*

## Capital Cost Summaries

Some of the technology result areas have a **Capital Cost** result screen. This screen displays spreadsheet workspace tables of the direct and indirect capital costs related to implementation of that technology.

|    | Process Area                | Direct Capital Costs (M\$) |    | Process Area                    | Indirect Capital Costs (M\$) |
|----|-----------------------------|----------------------------|----|---------------------------------|------------------------------|
| 1  | Reactor Housing             | 2.489                      | 1  | Process Facilities Capital      | 11.94                        |
| 2  | Ammonia Injection           | 0.1812                     | 2  | General Facilities Capital      | 1.194                        |
| 3  | Ducts                       | 3.567                      | 3  | Eng. & Home Office Fees         | 1.194                        |
| 4  | Air Preheater Modifications | 0.8525                     | 4  | Project Contingency Cost        | 1.194                        |
| 5  | ID Fan Differential         | 0.1347                     | 5  | Process Contingency Cost        | 0.7377                       |
| 6  | Structural Support          | 1.292                      | 6  | Interest Charges (AFUDC)        | 0.4979                       |
| 7  | Misc. Equipment             | 0.4092                     | 7  | Royalty Fees                    | 0.0                          |
| 8  | Initial Catalyst            | 3.014                      | 8  | Preproduction (Startup) Cost    | 0.4937                       |
| 9  | Process Facilities Capital  | 11.94                      | 9  | Inventory (Working) Capital     | 8.129e-02                    |
| 10 |                             |                            | 10 | Total Capital Requirement (TCR) | 17.33                        |
| 11 |                             |                            | 11 |                                 |                              |
| 12 |                             |                            | 12 |                                 |                              |
| 13 |                             |                            | 13 |                                 |                              |
| 14 |                             |                            | 14 |                                 |                              |
| 15 |                             |                            | 15 |                                 |                              |

Process Type:  Costs are in Constant 1996 dollars.

The NO<sub>x</sub> Control—2. Capital Cost result screen

## O&M Cost Summaries

Some of the technology result areas have a **O&M Cost** result screen. This screen displays spreadsheet workspace tables of the variable and fixed operation and maintenance costs involved in implementation of that technology.

| Variable Cost Component |                             | O&M Cost (M\$/yr) | Fixed Cost Component |                            | O&M Cost (M\$/yr) |
|-------------------------|-----------------------------|-------------------|----------------------|----------------------------|-------------------|
| 1                       | Solid Waste Disposal        | 0.3403            | 1                    | Operating Labor            | 0.2382            |
| 2                       | Power                       | 0.3131            | 2                    | Maintenance Labor          | 1.888e-02         |
| 3                       | <b>Total Variable Costs</b> | <b>0.6534</b>     | 3                    | Maintenance Material       | 2.823e-02         |
| 4                       |                             |                   | 4                    | Admin. & Support Labor     | 7.714e-02         |
| 5                       |                             |                   | 5                    | <b>Total Fixed Costs</b>   | <b>0.3625</b>     |
| 6                       |                             |                   | 6                    |                            |                   |
| 7                       |                             |                   | 7                    |                            |                   |
| 8                       |                             |                   | 8                    |                            |                   |
| 9                       |                             |                   | 9                    |                            |                   |
| 10                      |                             |                   | 10                   |                            |                   |
| 11                      |                             |                   | 11                   |                            |                   |
| 12                      |                             |                   | 12                   |                            |                   |
| 13                      |                             |                   | 13                   |                            |                   |
| 14                      |                             |                   | 14                   |                            |                   |
| 15                      |                             |                   | 15                   | <b>Total O&amp;M Costs</b> | <b>1.016</b>      |

Process Type:  Costs are in Constant 1996 dollars.

1. Diagram   2. Capital Cost   3. O&M Cost   4. Total Cost   5. Cost Inputs   6. Gas Summary

The Particulate Control—3. O&M Cost result screen (ESP)

## Total Cost Summaries

Some of the technology result areas have a **Total Cost** result screen. This screen displays spreadsheet workspace tables of annual variable, fixed, capital, and operation and maintenance costs involved in implementation of that technology.

|    | Cost Component              | M\$/yr | \$/MWh | \$/ton NO2 removed | Percent Total |
|----|-----------------------------|--------|--------|--------------------|---------------|
| 1  | Annual Fixed Cost           | 0.4435 | 0.1486 | 255.3              | 12.01         |
| 2  | Annual Variable Cost        | 1.459  | 0.4887 | 839.8              | 39.50         |
| 3  | Total Annual O&M Cost       | 1.903  | 0.6373 | 1095               | 51.50         |
| 4  | Annualized Capital Cost     | 1.792  | 0.6001 | 1031               | 48.50         |
| 5  | Total Levelized Annual Cost | 3.694  | 1.237  | 2126               | 100.0         |
| 6  |                             |        |        |                    |               |
| 7  |                             |        |        |                    |               |
| 8  |                             |        |        |                    |               |
| 9  |                             |        |        |                    |               |
| 10 |                             |        |        |                    |               |
| 11 |                             |        |        |                    |               |
| 12 |                             |        |        |                    |               |
| 13 |                             |        |        |                    |               |
| 14 |                             |        |        |                    |               |
| 15 |                             |        |        |                    |               |

The  $NO_x$  Control—4. Total Cost result screen

## Cost Inputs Summaries

Some of the technology result areas have a **Cost Inputs** result screen. This screen displays spreadsheet workspace tables of performance and economic inputs used to calculate total cost values.

| Performance Inputs Used for Total Cost Results |                                | Value     | Economic Inputs Used for Total Cost Results |  | Value  |
|--|--------------------------------|-----------|---|--|--------|
| 1  | Net Plant Size (MW)            | 454.1     | 1   | Fixed Charge Factor (fraction)               | 0.1034 |
| 2  | Annual Operating Hours (hours) | 6575      | 2   | Variable Cost Levelization Factor (fraction) | 1.000  |
| 3  | Annual Solids Removed (ton/yr) | 3.024e+04 | 3   | Project Book Life (years)                    | 30.00  |
| 4  |                                |           | 4   | Cost Reporting Year                          | 1996   |
| 5  |                                |           | 5   |  |        |
| 6  |                                |           | 6   |  |        |
| 7  |                                |           | 7   | Total Capital Required (M\$)                 | 1.959  |
| 8  |                                |           | 8   | Total Variable Costs (M\$/yr)                | 0.6534 |
| 9  |                                |           | 9   | Total Fixed Costs (M\$/yr)                   | 0.3625 |
| 10   |                                |           | 10  |  |        |
| 11   |                                |           | 11  |  |        |
| 12   |                                |           | 12  |  |        |
| 13   |                                |           | 13  |  |        |
| 14   |                                |           | 14  |  |        |
| 15   |                                |           | 15  |  |        |

Process Type:  Costs are in Constant 1996 dollars.

The Particulate Control—5. Cost Inputs result screen (ESP)

## Gas Summaries

Some of the technology result areas have a **Gas Summary** result screen. This screen displays spreadsheet workspace tables of major flue gas components before and after passing through the technology.

|    | Major Flue Gas Components      | Flue Gas In (moles/hr) | Flue Gas Out (moles/hr) | Flue Gas In (ton/hr) | Flue Gas Out (ton/hr) |
|----|--------------------------------|------------------------|-------------------------|----------------------|-----------------------|
| 1  | Nitrogen (N2)                  | 1.244e+05              | 1.244e+05               | 1743                 | 1743                  |
| 2  | Oxygen (O2)                    | 9247                   | 9230                    | 148.0                | 147.7                 |
| 3  | Water Vapor (H2O)              | 1.386e+04              | 2.931e+04               | 124.9                | 264.1                 |
| 4  | Carbon Dioxide (CO2)           | 2.027e+04              | 2.031e+04               | 446.0                | 446.8                 |
| 5  | Carbon Monoxide (CO)           | 0.0                    | 0.0                     | 0.0                  | 0.0                   |
| 6  | Hydrochloric Acid (HCl)        | 10.50                  | 1.050                   | 0.1913               | 1.913e-02             |
| 7  | Sulfur Dioxide (SO2)           | 55.81                  | 17.32                   | 1.788                | 0.5547                |
| 8  | Sulfuric Acid (equivalent SO3) | 0.2888                 | 0.1444                  | 1.156e-02            | 5.780e-03             |
| 9  | Nitric Oxide (NO)              | 10.91                  | 10.91                   | 0.1637               | 0.1637                |
| 10 | Nitrogen Dioxide (NO2)         | 0.5744                 | 0.5744                  | 1.321e-02            | 1.321e-02             |
| 11 | <b>Total</b>                   | <b>1.679e+05</b>       | <b>1.833e+05</b>        | <b>2464</b>          | <b>2602</b>           |
| 12 |                                |                        |                         |                      |                       |
| 13 |                                |                        |                         |                      |                       |
| 14 |                                |                        |                         |                      |                       |
| 15 |                                |                        |                         |                      |                       |

Process Type:


1. Diagram / 2. Capital Cost / 3. O&M Cost / 4. Total Cost / 5. Cost Inputs / 6. Gas Summary

The SO<sub>2</sub> Control—6. Gas Summary result screen


# Graphs

Clicking any result value brings up a graph for that value. While all of the values displayed in diagrams and tables are deterministic, some have uncertainty in their calculation. If there is no uncertainty in the value's calculation, the graph will display a vertical line.

If uncertainty is present, the graph will display a curve of all possible values.



*Boiler Flue Gas Solids Flow Graph (Deterministic Result)*



*ESP Flue Gas Out Solids Flow Graph (Uncertain Result)*

The new IECM plots all samples on the CDF graph. The Analytica results in the Macintosh IECM version only displayed every fourth value (a value that could be



adjusted within the model). By eliminating all but every fourth value, the Mac version of the IECM “smoothed” the graph.

When you first bring up a graph, there will be a short delay as all result graphs are drawn. Once all the graphs are drawn, there should be little more than a split second delay when you choose another graph. (However, if you change the plant configuration or input values and then return to **Get Results**, the graphs will have to be redrawn, causing another delay.)

More information on graphs is provided in the *User Manual*.

---

## Result Tools


Results may be displayed according to different rules. Use the **Result Tools** floating palette to change the type of results displayed, the units in which results are displayed, or the type of cost results displayed. You may move this floating palette to the side of the screen, change units, and watch how the results are altered as a result. To close the palette, click the **Close** button (X) in the upper right hand corner of the palette.

More information on various unit options is provided in the *User Manual*.

### ***Changing How Results are Displayed***

To change how results are displayed:

1. Pull down the **View** menu and choose **Result Tools**. The **Result Tools** floating palette will display.



*The Result Tools Floating Palette*

2. Choose the options desired by clicking the appropriate pull-down menus.
3. To close the **Result Tools** floating palette, click the **Close** button (X) in the upper right hand corner of the palette.

---

# Uncertainty Areas

Uncertainty may be entered in any or all input parameters (see “Uncertain Values” on page 46). However, there may be times that you would like to exclude uncertainty from results for a technology.


You may choose the technologies for which uncertain values are displayed in results from the **Uncertainty Tools** floating palette. You may move this floating palette to the side of the screen, change settings, and watch how the results are altered as a result. To close the palette, click the **Close** button (X) in the upper right hand corner of the palette.

More information on running a Probabilistic analysis is provided in the *User Manual*.

## Choosing Uncertainty Areas

To Choose Uncertainty Areas:

1. Pull down the **View** menu and choose **Uncertainty Tools**. The **Uncertainty Tools** floating palette will display.



*The Uncertainty Tools floating palette*

2. Choose the technology or technologies for which you would like results with uncertain values by clicking the check box to the left of each technology.
3. You may select all or none by clicking the buttons at the bottom of the palette.
4. To close the **Uncertainty Tools** floating palette, click the **Close** button (X) in the upper right hand corner of the palette.

# Working with Sessions

---

## Sessions

A session is a complete collection of data—configuration settings, and input parameters—which describes one power plant. The model uses the configuration settings and parameters in a session to calculate the results.

You may run multiple power plant sessions at the same time in order to compare configurations, results, etc.

---

**NOTE:**

A future version of the IECM will enable the user to specify multiple types of sessions. The current version only supports one power plant simulation. Future versions will add optimization (optimizing specified parameters for a given plant flow sheet to optimize an objective such as cost) and synthesis (optimizing a flow sheet with specified parameters to optimize an objective).

---


---

## Creating a New Session

To create a new session, do any one of the following:

- Pull down the **F**ile menu and select **N**ew Session...
- Click the **New Session** button on the toolbar on the left side of the IECM window. (See “The Toolbar” on page 24.)
- Press **Ctrl-N**.

The **New Session** dialog box will display. Type in the name of the new session and click the **Ok** button.



*The New Session dialog box*


---

## Opening an Existing Session

To open an existing session, do any one of the following:

- Pull down the **F**ile menu and select **O**pen Session....
- Click the **O**pen Session button on the toolbar on the left side of the IECM window. (See “The Toolbar” on page 24.)
- Press **Ctrl-O**.

The **O**pen Session dialog box will display.



*The Open Session dialog box*

In the **O**pen Session dialog box:

1. Choose the session you would like to open from the list.
2. Click the **O**k button.

Sessions that are currently open will display in gray and cannot be opened again.

---

## Saving a Session's Results


The information stored in a session—configuration settings and input parameters—is saved as you choose the settings and input data. Results are calculated from that information and initially stored in memory.

Sometimes it is important to save the session's results to disk. At this time it is only necessary if you have multiple sessions open and are comparing results, or if you want to view results outside the interface. If you only ever run one session at a time, you may skip this procedure.

To save a session's results, do any one of the following:

- Pull down the **F**ile menu and select **S**ave session.
- Click the **S**ave results button on the toolbar on the left side of the IECM window.
- Press **Ctrl-S**.

A dialog box will display which informs you that the process is time-consuming and often unnecessary. To save results, click the **Y**es button. To abandon the procedure, click the **N**o button.



*The Save Results dialog box.*

---

## Saving a Session with a Different Name

To save a session you are working on with a different name, pull down the **F**ile menu and select **S**ave **A**s.... The **Save Session As** dialog box will display.

In the **Save Session As** dialog box,

1. Type the name of the session in the box next to **F**ile **n**ame.
2. Click the **S**ave button.

Once you have saved a session with a different name, all subsequent **S**ave commands will save the session with the new name.


---

## Closing a Session

To close a session you are working on, do any one of the following:

- Pull down the **F**ile menu and select **C**lose **S**ession.
- Click the **C**lose **t**his **s**ession button on the toolbar on the left side of the IECM window.
- Click the **C**lose button (**x**) in the upper right hand corner of the session window.
- Press **Ctrl-F4**.

A dialog box will display which asks if you want to save results. It will inform you that saving results is time-consuming and often unnecessary. (See “Saving a Session’s Results” on page 62.) To save results, click the **Y**es button. To close without saving results, click the **N**o button. To abandon the procedure, click the **C**ancel button.



*The Save Results at Close dialog box*


---

## Deleting a Session

To delete an existing session, do one of the following:

- Pull down the **F**ile menu and select **D**elete Session.
- Click the **Delete Session** button on the toolbar on the left side of the IECM window. (See “The Toolbar” on page 24.)

The **Delete Session** dialog box will display.



*The Delete Session dialog box*

In the **Delete Session** dialog box:

1. Choose the session you would like to delete from the list.
2. Click the **Ok** button.

To exit the Delete Session dialog box without deleting a session, click the **Cancel** button or press the **Esc** key.

Sessions that are currently open will display in gray and cannot be deleted until they are closed.

---

**NOTE:** Once you delete a session, it can no longer be accessed. Use caution when deleting sessions.

---

---

## Unlocking a Session

This command allows you to unlock a session that was not closed normally because of a system problem such as a crash, a loss of network connection, or another cause. You cannot open such sessions when you start the IECM again because the software believes that they are already open. Unlocking the session enables you to open the session again.


---

**NOTE:** Choose this command only if you the session was not closed normally the last time you used it. Do not unlock a session that **actually** is in use, as it may cause unpredictable results.

---

To unlock a session, pull down the **F**ile menu and select **Unlock Session**.


A warning box will display.



*The Unlock Session Warning Box*

Click the **Y**es button to proceed.

The **Unlock Session** dialog box will display.



*The Unlock Session dialog box*

In the **Unlock Session** dialog box,

1. Choose the session you would like to unlock.
2. Click the **O**k button.

You may then open the session. See "Opening an Existing Session" on page 62.

To exit the Unlock Session dialog box without unlocking a session, click the **C**ancel button or press the **E**sc key.

Sessions that are not currently open **or** locked by the system will display in gray and cannot be unlocked.

# Importing and Exporting Data

---

## Importing a Session

The **Import** function is not yet available. At a future date, you will be able to import a database of session data into the interface. Thus, you will be able to exchange data with other users, load older archive data, and use data assembled in other ways than by using the interface.

Therefore, the **Import** option on the **File** menu and the **Import** button on the toolbar are not yet active. Watch for updates of the interface for details about importing.

---

## Exporting a Session

The **Export** function is not yet available. At a future date, you will be able to export session data in a standard database format. Thus, you will be able to exchange data with other users, save older data to archives, and use model data in other ways than by using the interface.

An **Export** option will be added to the **File** menu and an **Export** button will be added to the toolbar. Watch for updates of the interface for details about exporting.

---

## Print Screen

Pressing the **Print Screen** key at the top of the keyboard copies a snapshot of the entire IECM Window to the clipboard. This snapshot may then be pasted into any windows application.

---

## Windows Copy, Cut, and Paste

As has been noted, the input and results screens function like spreadsheets (see “



Parameters and Results Workspace” on page 28). Data can be copied from the cells or pasted into them using the Windows **Copy**, **Cut**, and **Paste** commands.

For information about copying graphs, see the *User Manual*.

## **Copy**

To copy data from an input or results screen:

1. Select the cells that you want to copy (see “Selecting Cells” on page 29).
2. Do any one of the following:
  - Pull down the **E**dit menu and select **C**opy.
  - Click the **Copy** button on the toolbar on the left side of the IECM window. (See “The Toolbar” on page 24.)
  - Press **Ctrl-C**.

## **Cut**

The windows **Cut** command will remove data that is not static—i.e. only data on input screens in the Value column which is not calculated. If static data (data in other columns or calculated values) is highlighted and cut, it will be copied—and thus can be pasted—but it will not be removed from the workspace.

To cut data from an input or results screen:

1. Select the cells that you want to copy (see “Selecting Cells” on page 29).
2. Do one of the following:
  - Pull down the Edit menu and select Cut.
  - Click the Cut button on the toolbar on the left side of the IECM window. (See “The Toolbar” on page 24.)
  - Press **Ctrl-X**.

## **Paste**

To paste data from a spreadsheet or database into an input screen:

1. Make sure that the data is in exactly the same format as the input screen accepts. You will only be able to paste data into cells that accept inputs (i.e. cells in the Value column that are not calculated).
2. Select the cells that you want to paste data into (see “Selecting Cells” on page 29).
3. Do any one of the following:
  - Pull down the Edit menu and select Paste.
  - Click the Paste button on the toolbar on the left side of the IECM window. (See “The Toolbar” on page 24.)
  - Press **Ctrl-V**.

# Printing

---


## Print Dialog Box

The IECM has a print option so that you may print the pertinent information from the screen which is currently displayed. If you are in Configure Plant, the IECM will print a summary of the plant configuration options you have selected. If you are in Set Parameters, the IECM will print the input values from the screen which is displayed. If you are in Get Results, the IECM will print the results values from the screen which is displayed.

To print data, do any one of the following:

- Pull down the **F**ile menu and select **P**rint. (See “The File Menu” on page 19.)
- Click the **P**rint button on the toolbar on the left side of the IECM window. (See “The Toolbar” on page 24.)
- Press **Ctrl-P**.

The **P**rint dialog box will display.



*The Print Dialog Box*

To Print, click the **OK** button.

# Index

## A

Alt Commands 16

## C

Calculated Values 40, 60  
Coal Properties 42  
Configure Plant 24, 32  
Copy Data 59  
Ctrl Commands 17  
Cut Data 60

## D

Data  
  copy 59  
  cut 60  
  paste 60  
2

## E

Edit Menu 20, 60  
Editing values 16, 39  
Entering Uncertainty 38, 41  
Entering Values 38  
Exiting the Model 20, 31  
Export 31, 59

## F

File Menu 17, 19, 54, 55, 56, 57, 59, 61

## G

Get Results 25, 45, 46  
Getting Started 4, 6  
Graphs 46, 51, 59

## H

Help Menu 5, 21  
Highlighting 27, 36

## I

IECM Window 18, 22, 23, 30, 59  
Import 20, 22, 59  
Input Navigation Tabs 24, 42  
Installation 6, 13  
  canceling 13  
  destination 9  
  errors 13  
  license agreement 8  
  program folder 11  
  progress 12  
  running setup 7  
  setup type 10  
  9  
  welcome 7

## K

Keystroke Commands 16

## M

Manual  
  technical 6  
  tutorial 6  
  user 6  
Menu Bar 16, 18, 19, 20, 21, 23  
  22  
Model Tutorial 4, 6  
Mouse 15, 19, 22, 24, 26, 27, 33, 37, 39  
Mouse Cursor 15, 16, 19, 39

## O

Online Help 4, 21

## P

Paste Data 60  
Plant Diagram 25, 33, 36, 46  
Print 17, 19, 20, 22, 31, 59, 61  
Print Screen 59  
  24

## R

Removing Uncertainty 41  
Result Tools 21, 38, 52  
  28, 47  
  45, 47

O&M Cost 48  
save 55  
viewing 46  
24, 47

## **S**

Save Results 55  
Selecting Cells 26, 60  
Session 19, 20, 22, 31, 54, 55, 56, 59  
close 56  
delete 19, 56, 57  
export 31, 59  
import 20, 22, 59  
new 17, 19, 22, 31, 37, 54  
open 55  
save as 56  
Set Parameters 25, 35, 36  
Software  
install 6, 13  
uninstall 13  
updating 2, 13  
Status Bar 20, 22  
System Requirements 1

## **T**

Technical Manual 4, 6  
24, 25, 36, 46  
Toolbar 22

## **U**

Uncertain Values 38, 40, 52, 53  
Uncertainty  
areas in results 20, 52, 53  
entering 38, 41  
removing 41  
Uncertainty Distributions 41  
Uncertainty Editor 38, 41, 42  
Uncertainty Tools 20, 53  
Uninstalling Software 13  
User Manual 4, 6

## **V**

Values  
calculated 40, 60  
editing 16, 39  
entering 38  
uncertain 38, 40, 52, 53  
View Menu 20, 22, 52, 53  
Viewing Results 46

## **W**

Window Menu 21, 23  
Workspace 16, 25, 26, 36, 37, 46, 59