



OK-Cam
User Manual

© 2011 Unflustered Software

Table of Contents

Table of Contents	2
Introduction.....	3
Operation	4
Quick Start Guide	5
Installation	6
Application Start and Shutdown	9
Starting the Application	9
Shutting down the Application	9
Tray Icon.....	9
Configuration	10
Control.....	10
Source	12
Capture from Video Device	12
Collect File.....	14
Captions.....	16
FTP.....	18
Email	20
Archive.....	22
Preview	24
Log.....	25
Advanced	26
Registration	28
Appendix A: Time & Date variables.....	29
Appendix B: Text import from external files	30
Appendix C: File types	30

Introduction

OK-Cam captures still images from a video device, or collects them from disk, then processes and uploads the images to a website via FTP, sends them via email, or archives them to disk.

Images can be captured at specified timed intervals, or collected from disk as soon as they are available.

The images can be automatically cropped and resized, and text captions may be added. Text captions can be easily formatted for position, font, colour and size, and may include the current date and time, or data imported from external files.

The application works on all versions of Microsoft Windows from Windows XP onwards.

Operation

In order for the application to operate, a suitable source must be selected. The source may be either a USB video device or a directory on disk where images are saved at intervals by an external application.

The main Control page of the application is used to select the desired processing options, which may be a combination of:

- Adding captions to the captured image.
- Uploading the captured image to an FTP server.
- Sending the captured image via email.
- Archiving the captured image to disk.

Application operation can be summarised as:

Select a source on the Source page.

Select processing options on the Control page.

Enter the settings for the processing options on the respective pages.

Apply the settings.

Click the Start button to start processing.

Start and Stop processing

Processing will begin when the Start button is clicked and will continue until the Stop button is clicked. Any errors will be indicated by the icon in the Windows notification area (commonly called the system tray), and the details will be reported on the Log page.

Applying settings

Any changes to settings will not take effect until the Apply button is clicked. If the Cancel button is pressed unapplied settings will be discarded.

Showing and Hiding the application

Clicking the Cancel button, or the close button at the top right of the window will minimise the application to the Windows notification area, where it will continue to run. To exit the application right-click on the icon and select the Exit option.

Quick Start Guide

The most common form of operation is to use the application to upload images from a video device to an FTP server. It is assumed the video device is installed and is visible in the Windows Device Manager.

To upload images from a video device to an FTP server

Start the application.

On the Source dialog:

 Select 'Capture from Video Device'.

Select the desired video device in the list.

On the FTP dialog:

Enter the details for the desired FTP server.

On the Control dialog:

 Select 'Enable FTP'

 Select 'At Interval'

Enter the desired Process Cycle Time.

Click Apply.

Click Start.

The application will begin to capture images and upload them to the FTP server. The latest captured image can be previewed in the Preview dialog. The Log dialog will report the ongoing progress of the operations.


For more detailed explanation of the available options, consult the relevant section of the manual.

Installation

Double click on the OK-Cam_Setup.msi installation file.




Click 'Next'.



If you would like OK-Cam to install a shortcut Icon on your Windows desktop then select the option.



Specify the desired installation folder.



After a short installation process, OK-Cam will be installed and ready for use.

Application Start and Shutdown

Starting the Application

Click the OK-Cam icon on the Windows Desktop or in the OK-Cam folder accessible from the Start menu.

Shutting down the Application

Right click the application icon in the Windows notification area (system tray) and select 'Exit' from the popup menu.

Tray Icon

An icon in the Windows notification area displays the current state of the application:



Right-clicking the tray icon will display a popup menu, from where the application can be shown or hidden, and processing can be started or stopped.

Double clicking the tray icon will show the application.




Configuration

The application is configured by selecting the relevant tab at the top of the application window, then adjusting the appropriate settings. Changed settings will not take effect until the Apply button is clicked.

Control

This dialog is the main control section, and contains settings for controlling the processing of the image. Here, desired processing options can be enabled, the processing interval can be specified, and processing can be started or stopped.



At Interval

The 'Process cycle time' setting defines the interval between image captures. If the cycle time is a number of seconds that equals a round number of minutes, the 'Process on exact stroke' checkbox will be enabled. If this checkbox is checked the application will process the image capture at the top of the minute. For example if the cycle time is 300 seconds, the image capture will occur at 0, 5, 10, 15 etc minutes past the hour. If this checkbox is unchecked the 300 second count will begin from the moment the Start button is clicked.

On Arrival

This setting is only used, and only selectable, when the image source is set to 'Collect File' (see Source section for details). In this mode the image will be collected as soon as it appears on disk.

Enable Captions

Enables text captions for the image. The captions are configured on the Caption page.

Enable FTP

Enables the FTP transfer. The relevant details for your FTP server must be filled in on the FTP page.

Enable Email

Enables SMTP email transfer. The relevant details for your SMTP mail server must be filled in on the Email page.

Enable Archive

Enables archive of captured images to disk. The location can be specified on the Archive page.

Start on Load

Starts processing as soon as the application is loaded.

Start minimised

The application will start minimised to the Windows notification area.

Current Status

Displays information about the current status of the application.

Start & Stop

Starts or stops the image processing cycle.

Start and Stop can also be accessed by right-clicking the application icon in the Windows notification area.


Source

This dialog is used to specify the source of the processed image. The available settings will change according to whether the source is selected to be 'Capture from Video Device' or 'Collect File'.

This dialog also allows selecting of image crop and resize options. These settings are applicable to both video device and file sources.

Capture from Video Device

Selects the source of the images to be a connected USB webcam or other video device.



Available Devices

Displays devices available for connection. Click the checkbox next to the desired device to connect to that device.

Video Window


The current video stream is shown here. Moving the mouse over the image will cause a window border to appear around the video. The window can then be dragged to another part of the screen and resized.

Current Stream

Shows the current stream image size and frame rate.


Video Properties

Right click the mouse on the video window to cause the video properties menu to appear. From this menu the video and stream properties can be adjusted.



Collect File

Selects the source of the images to be a directory on disk. This option is used when collecting images that are being saved periodically by a digital camera.



Collect Directory

The source directory for the images. The path can be edited manually or browsed to by clicking the icon.

File Mask

The file mask for the images. Only images that match the file mask will be collected. See Appendix C for valid image file types.

Delete on Collect

If this option is selected the image will be deleted from the source directory as soon as it is collected.

Latest File

Shows the details of the latest file to be collected; filename, time of collection and image size.

Thumbnail Window

A thumbnail of the latest file to be collected is shown here. Moving the mouse over the image will cause a window border to appear around the image. The window can then be dragged to another part of the screen and resized.

Crop

If unchecked, the whole image is processed by the application. If checked, only a rectangular portion of the image is processed. The dimensions of the rectangular portion can be specified here.


Alternatively, if the video stream or thumbnail window has been dragged from the application, the crop rectangle can be adjusted with the mouse.

Resize

Resizes the captured image. The resizing occurs after cropping, if cropping is selected.

Captions

In this dialog, text captions can be added to the captured image. Each text caption has its own tab, where the text content, location and appearance are specified. Captions will only be added to the image if 'Enable Captions' is selected on the Control page.



Caption tabs

Each text caption has its own tab. Clicking on the tab brings up the settings for that particular caption.

Font (A)

Selects the caption font. All TrueType or OpenType fonts installed on the computer are available.

Foregnd / Backgnd

Selects the text foreground and background colours.

Alpha

Selects the alpha value (transparency) of the foreground or background colour. The value ranges from 0 to 255, 0 being completely transparent and 255 being completely opaque.

Position

The X & Y coordinates of the caption, and whether these coordinates specify a point on the left, right, or centre of the text.

Text

The caption text to be displayed. Variables can be used to display the current time and date, or to import text from external files. See Appendix A and Appendix B for more information.

Sample


A preview of what the caption will look like, and how it relates to surrounding captions. Click the button to the top right of the sample to expand or contract the image.

Caption Creation and Deletion

Click the 'New' tab to create a new caption. To delete a caption click the close button in the top corner of the caption dialog.

FTP

This dialog contains the settings for the FTP upload of the processed image. FTP upload will only take place if 'Enable FTP' is selected on the Control page.



The screenshot shows the 'OK-Cam' application window with the 'FTP' tab selected. The dialog is organized into several sections:

- Server:** Address: ftp.myftpsite.org, Port: 21
- User:** Username: myuser, Password: [masked], Save
- Main Image:** Destination Directory: /Images/Full/, Destination Filename: Snapshot.jpg
- Thumbnail:** Destination Directory: /Images/Thumbnails/, Destination Filename: Snapshot_small.jpg, Width: 160, Height: 120

At the bottom of the dialog are three buttons: OK, Cancel, and Apply.

Address

The address of the FTP server.

Port

The server port for connection. The default value of 21 will usually be correct.

Username

The username used to log on to the FTP server.

Password

The password used to log on to the FTP server. If the Save checkbox is selected then the password will be saved in the application settings between sessions.

Destination Directory and Filename

The directory to which the processed image is to be uploaded.

Destination Filename


The filename of the uploaded image. See Appendix C for more details regarding valid file types.

Thumbnail

If this is selected a shrunken version of the main image is uploaded in the specified location. The size of this image is specified in the Width and Height boxes. The destination directory and filename can be specified in the same manner as for the main image.

Email

This dialog contains the settings for the email transmission of the processed image. Email transmission will only take place if 'Enable Email' is selected on the Control page.



The screenshot shows the 'OK-Cam' application window with the 'Email' tab selected. The dialog is divided into two sections: 'Server' and 'Message'. The 'Server' section has two input fields: 'Address' with the value 'smtp.myemailserver.org' and 'Port' with the value '25'. The 'Message' section has four input fields: 'From Address' with 'me@myemailaddress.org', 'To Address' with 'recipient@destination1.org, recipient@destination2.org', 'Subject' with 'Latest Image', and 'Filename' with 'OK-Cam Image.jpg'. At the bottom of the dialog are three buttons: 'OK', 'Cancel', and 'Apply'.

Address

The address of the SMTP server.

Port

The server port for connection. The default value of 25 will usually be correct.

From Address

The address from which the email will be sent.

To Address

The address to which the email will be sent. Multiple recipients can be specified, separated by commas.

Subject

The subject of the sent email.


Filename

The filename of the image encoded in the email. See Appendix C for more details regarding valid file types.

Archive

This dialog contains the settings for the archival of the processed image. Archiving will only take place if 'Enable Archive' is selected on the Control page.

If this option is selected any processed image will be saved to disk according to the settings in this dialog.



Root Directory

The root directory of the archive.

Subdirectory and Filename

The subdirectory and filename of the archived file.


Variables can be used to customise the directory and filename of the archived file. See Appendix A for more details of variables. See Appendix C for more details regarding valid file types.

Quick Set

These buttons provide quick access to common archival directory and filename formats.


Preview

This dialog shows the last processed image. Moving the mouse over the image will cause a window border to appear around the image. The window can be dragged to another part of the screen, and will expand to its full size. The image will be updated whenever a new image is processed.



Log

This dialog contains the application's activity log. Error messages are highlighted in red.




Save

The log can be saved as a text file, specified in the accompanying field. The log file is maintained between sessions.

Advanced

This dialog contains the settings for advanced users, and statistics concerning application operation.



Statistics

A collection of statistics to show the current state of the application. Processing cycles and errors are counted. The most recent error is displayed here, which will also be shown on the Log page, in its chronologically ordered place.

JPEG Quality

JPEG format images in the FTP, Email, & Archive dialogs will be saved using the specified quality setting. The higher the quality, the greater the image size.

Enable VMR mixer

On systems with old graphics cards the application may have trouble connecting to the video device. Disabling this option may correct the problem, at the expense of the crop box not being shown on the video stream, if cropping is enabled.

Low CPU

This option is useful on old systems when showing video in a detached window. The video stream is paused every second, which reduces CPU usage at the expense of smooth video.

Registration

The About dialog contains information about the application version, and allows the registration of the application.



To enter a registration key, double-click the OK-Cam banner or press Ctrl-R on the keyboard. A Dialog will appear requesting the location of the registration key. Locate the key and click Open.

Alternatively the key file can be dragged to the OK-Cam banner using the standard drag & drop methods used within Windows Explorer.

Appendix A: Time & Date variables

When specifying filenames or caption text, the following variables can be used within the text:

(assuming the current time is 23:59:00 on Friday 31st December July 2010)

<YYYY> = 2010 - Year in 4 digit format
 <MO> = 12 - Month in 2 digit format
 <DD> = 31 - Day in 2 digit format
 <HH> = 23 - Hour in 2 digit format (24 hour clock)
 <MM> = 59 - Minute in 2 digit format
 <SS> = 00 - Second in 2 digit format

<YY> = 10 - Year in 2 digit format
 <MON> = Dec - Month in 3 digit text format
 <MONTH> = December - Month in full length format
 <DAY> = Friday - Day in full length format
 <DDD> = Fri - Day in 3 digit text format

<SDATE> = 31/12/10 - Short date
 <LDATE> = 31 December 2010 - Long date
 (The above two variables follow the format specified in the Regional Options section of the Windows Control Panel)

Eg 1: In the Archive dialog, if you were to specify an archive filename of
 MyPic-<YYYY><MO><DD>-<HH><MM><SS>.jpg the file would be saved as
 MyPic-20101231-235900.jpg

Eg 2: In the Caption dialog, if you were to specify the caption text
 The Current Time is <HH>:<MM>:<SS> the caption would appear as
 The Current Time is 23:59:00

Appendix B: Text import from external files

Within caption text, the following variable can be used to import data from an external text file:

`<FILELINE=fff|nn>`

Where `fff` is a text file on disk, and `nn` is the line number of the file to display.

Eg: In the Caption dialog, if the caption text is

`The Current Temperature is <FILELINE=Z:\WeatherData.txt|02> degrees`

The second line of the file `Z:\Weatherdata.txt` will be substituted, resulting in a caption of `The Current Temperature is 25 degrees` assuming of course that the appropriate file contains the relevant data on its second line.

The `|nn` is optional, and if omitted the first line of the file is used.

Appendix C: File types

In the Source, FTP, Email, & Archive dialogs, the following image file types can be specified: JPG, BMP, GIF, PNG.

When saving a file, the file will automatically be saved with the correct file type to suit the file extension.

Eg: In the Email dialog, if you specify the Filename to be `MyImage.png` the file will be sent in PNG format.

The quality setting for JPEG images can be specified in the Advanced dialog.