



Polar GoFit

Polar personal teaching

USER GUIDE FOR TEACHER

TABLE OF CONTENTS

Table of Contents	2
Polar GoFit	10
Sign-in	10
Computer requirements	10
Proxy settings	11
About the user guide	11
About the Polar GoFit app	11
About the Lessons for Life book	11
License agreement	11
Getting started	12
Activity monitoring	12
Heart rate monitoring	12
Fitness testing	13
Setting up Polar GoFit	14
Workflows	16
Activity monitoring workflow	16
Heart rate monitoring workflow	17
Fitness testing workflow	19
User accounts	21
Teacher user accounts	21

Student user accounts	21
Products	23
Monitors in Polar GoFit	23
Sensors in Polar GoFit	23
Data transfer	25
Data transfer in activity monitoring	25
Data transfer in heart rate monitoring	27
Evaluation	28
Course evaluation	28
Test evaluation	29
Activarium	31
Activity points	32
Activarium controls	32
Courses	34
Activity courses	34
Creating an activity course	34
Editing an activity course	34
Adding students to an activity course	35
Removing students from an activity course	35
Assigning activity monitors	36
Reassigning activity monitors	38
Transferring activity data	38

Viewing activity courses	40
Viewing "My Courses" on dashboard	40
Viewing activity courses on Courses page	41
Viewing activity data	42
Activating Activarium for a course	45
Opening Activarium	46
On the Dashboard	46
On the Courses page	46
Decorating the Activarium	46
Opening Activarium showcase	47
Showcasing school's all Activariums	47
Showcasing a course's Activarium	47
Removing an activity course	47
Heart rate courses	48
Creating a heart rate course	48
Target zones and badges	48
Target zones	48
Badges	49
Editing a heart rate course	50
Adding students to a heart rate course	51
Removing students from a heart rate course	51

Assigning heart rate sensors	52
Reassigning heart rate sensors	53
Using a personal heart rate sensor	53
Transferring heart rate data	54
Viewing heart rate courses	54
Viewing "My Courses" on dashboard	54
Viewing heart rate courses on Courses page	55
Viewing heart rate data	56
Removing a heart rate course	59
Getting student list	59
Getting password list	59
Reports	61
Getting course evaluation report	61
Reading course evaluation report	61
Getting detailed student report	62
Reading detailed student report	62
Activity courses	62
Heart rate courses	63
Export MET values	63
Reading MET value report	64
Getting school report	64

Activity reports	64
Heart rate reports	65
Reading school report	66
School	68
Students	68
Importing students	68
Creating students	69
Viewing student information	70
Editing students	70
Moving students to another class	71
Generating new password for student	71
Removing students	71
Teachers	72
Creating teachers	72
Viewing teacher information	72
Editing teachers	73
Resetting teacher's password	73
Ordering a new password without signing in	73
Resetting the password	73
Deleting teachers	74
Monitors	74

Registering activity monitors	74
Viewing activity monitors	76
Removing activity monitors	76
Sensors	77
Registering heart rate sensors	77
Viewing heart rate sensors	78
Removing heart rate sensors	78
Evaluation	78
Configuring evaluation types	79
Editing evaluation types	79
Adding evaluation types	79
Deleting evaluation types	79
License status	80
Viewing license status	80
Fitness tests	81
Templates	81
Creating a template	81
Creating a test	81
Students from previous tests	81
Students from student list	82
Editing a template	82

Removing a template	83
Tests	83
Entering results	83
Start entering results	83
Continue entering results	84
Editing a test	85
Removing a test	85
Results	86
Viewing results	86
Editing results	86
Reports	87
Getting student results report	87
Getting test results report	87
Getting school results report	87
Troubleshooting	89
Polar GoFit sign-in page does not load	89
I am unable to sign in to Polar GoFit	89
Important information	90
Medical devices in professional use	90
Precautions	90
Minimizing possible risks	90

Copyright	91
Disclaimer	91

POLAR GOFIT

Welcome to the Polar GoFit web service! Polar GoFit is a part of the Polar Physical Education solution. It supports both activity monitoring and heart rate monitoring. The web service enables teachers and students to track students' daily activity and the time spent in different activity zones. It also enables teachers and students to track students' heart rate data during PE lessons and the time spent in different heart rate zones. In addition, Polar GoFit web service provides a manual fitness testing system.

Teachers can use Polar GoFit for organizing courses and fitness testing. They can also follow and document each student's effort and improvement in and out of the classroom. The web service makes it easy to create reports and track long-term progress. The data can also be shared with parents and administrators.

Students can use Polar GoFit to review their daily activity and heart rate data, and test results. Polar GoFit helps them learn a healthy lifestyle.

 The fitness testing solution is still in beta phase and not yet available for all schools.

SIGN-IN

Sign in to the web service on the Polar GoFit home page (www.polargofit.com). The first teacher user account was created when the licenses were purchased. A link to select a password for the account was provided in the welcome email. More teacher user accounts can be created after signing in. Both teachers and students use the same sign-in page.

COMPUTER REQUIREMENTS

For general Polar GoFit use:

- Internet connection
- Compatible web browser (Microsoft Internet Explorer 8 or newer, Apple Safari 4 or newer, Mozilla Firefox 3 or newer, Google Chrome 12.0.1271.97m or newer)
- 1024 x 768 resolution display or higher

Additional requirement for Activarium:

- [Adobe Flash Player](#)

For data transfer between Polar Active activity monitors and web service with FlowLink and WebSync:

- Operating system: Microsoft Windows XP/Vista/7 or Mac OS X 10.5 or newer (running on Intel platform)
- Internet connection
- Compatible web browser (Microsoft Internet Explorer 8 or newer, Apple Safari 4 or newer, Mozilla Firefox 3 or newer, Google Chrome 12.0.1271.97m or newer)
- Free USB port for the FlowLink
- 1024 x 768 resolution display or higher

PROXY SETTINGS

Make sure your browser's proxy settings are set correctly. Contact your IT administrator if you need help with the browser settings.

ABOUT THE USER GUIDE

The user guide includes instructions for different parts of the web service. You can download the entire user guide in PDF format by clicking 'Download in PDF format' in the navigation panel on the left.

ABOUT THE POLAR GOFIT APP

Teachers use the Polar GoFit iPad app to monitor and share heart rate data during PE lessons. The data transfer between the Polar GoFit app and Polar GoFit web service is automatic.

ABOUT THE *LESSONS FOR LIFE* BOOK

Lessons for Life is a teacher's guidebook to Polar Education Technology. It provides tips on how to use the new technology to motivate students towards an active lifestyle. The book is purchased separately.


LICENSE AGREEMENT

Each teacher must accept the license agreement when signing in to the web service for the first time. The licence agreement can be opened by clicking **Legal Notice** in the Polar GoFit footer.


GETTING STARTED

ACTIVITY MONITORING

Follow the steps below when starting to use the Polar activity monitoring solution. See also [Activity monitoring workflow](#) for more information on the general workflow in activity monitoring.

 Activity data cannot be transferred from the activity monitors to the web service before the monitors have been managed in the Polar GoFit web service.

1. Set up the web service according to the instructions in chapter [Setting up Polar GoFit](#).
2. Create an [activity course](#) in the web service.
3. [Assign the activity monitors](#) to students who participate in the course. The activity monitors are assigned individually for each student.
4. Give the activity monitors to the students. The activity monitors are worn on the wrist.
5. [Transfer the activity data](#) from the activity monitors to the web service regularly with the FlowLink data transfer unit and the WebSync software.

 Polar Active has room for 21 days in the activity diary. When activity data is transferred to the web service, it is removed from the activity monitor. If activity data is not transferred to the web service during the course, the activity monitor stops recording daily activity after 21 days of use. The web service informs on the **Dashboard** how many days it has been since last data transfer. Students can also transfer activity data from Polar Active to the web service with their own user credential.


Daily activity can also be tracked without the web service using the activity progress poster. For more information on the activity monitors, see the Polar Active user manual.

HEART RATE MONITORING

Follow the steps below when starting to use the Polar heart rate monitoring solution. See also [Heart rate monitoring workflow](#) for more information on the general workflow in heart rate monitoring.

1. Set up the web service according to the instructions in chapter [Setting up Polar GoFit](#).
2. Create a [heart rate course](#) in the web service.
3. [Assign the heart rate sensors](#) to students who participate in the course.


4. Students wear the sensors during PE lessons.
5. Monitor heart rate data via the Polar GoFit app during the lesson.

 Data transfer between Polar GoFit and the Polar GoFit app is automatic.

FITNESS TESTING


Follow the steps below when starting to use the Polar fitness testing solution. See also [Fitness testing workflow](#) for more information on the general workflow in fitness testing.

1. Set up the web service according to the instructions in chapter [Setting up Polar GoFit](#).
2. [Create a template](#) by selecting the test items, or use an existing template.
3. [Create a test](#) by choosing the students.
4. Carry out the test and [enter the results](#) into the web service.

 You can use an iPad in the test situation and enter the results into the web service as testing proceeds. Or you can write the results by hand on printed result sheets, and enter them into the web service later.

SETTING UP POLAR GOFIT

We recommend that the following steps are completed when starting to use the Polar GoFit web service in the school. School settings can be modified later with any teacher's user account. See also [Activity monitoring workflow](#), [Heart rate monitoring workflow](#) and [Fitness testing workflow](#) for more information on using Polar GoFit.



i The system must be configured only once. Changes (new teacher accounts, new students, new monitors, new sensors) can be done at any point.

You can return to this list by selecting **Setting up Polar GoFit** from the navigation panel on the left. For further instructions on each step, click on the links below.

1. If you are going to use Polar GoFit for activity monitoring, make sure you have all the necessary components available for [data transfer between an activity monitor and Polar GoFit](#).
2. [Import](#) or [create](#) students in **School > Students**.
3. If you are going to use Polar GoFit for activity and/or heart rate monitoring, [Register the activity monitors](#) into the web service in **School > Monitors**, and/or [register the heart rate sensors](#) into the web service in **School > Sensors**.
4. If you are going to use Polar GoFit for activity and/or heart rate monitoring, [Configure evaluation types](#) in **School > Evaluation**. You can also use the default grades/evaluation types.
5. [Create user accounts](#) for the other teachers in **School > Teacher**. Teacher user accounts are limited based on the number of purchased licenses.

After setting up the web service, you can continue by [creating the first activity course](#) or [creating the first heart rate course](#) in the Courses section, or [creating the first test template](#) in the Fitness tests section.

WORKFLOWS


ACTIVITY MONITORING WORKFLOW

The general activity monitoring workflow in the Polar GoFit web service is described below. Set up the system first. Then proceed to create the first course and continue as shown in the picture below.



You can have several activity courses in the Polar GoFit web service simultaneously. A student can participate in one activity course at a time. An activity monitor can be assigned to one student at a time.

1. [Create an activity course](#). Enter course information, course type, activity course settings and monitor settings.
2. [Add students to the course](#).
3. [Assign activity monitors](#) to the students.
4. Give the activity monitors to the students who wear them on their wrists. Activity measurement starts automatically. For more information on how to use the Polar Active activity monitor, see the Polar Active user manual.
5. [Transfer daily activity data regularly](#) (at least once a week) to the web service. Both teachers and students can transfer activity data from Polar Active to the web service.


 Polar Active has room for 21 days in the activity diary. When activity data is transferred to the web service, it is removed from the activity monitor. If activity data is not transferred to the web service during the course, the activity monitor stops recording daily activity after 21 days of use.

6. [Review the daily activity data](#) during and after course.
7. Collect the activity monitors back from the students after the course ends. The web service evaluates students automatically based on the selected evaluation type. Print out [course evaluation report](#) and [detailed student report](#).

See also [Student user accounts](#).


HEART RATE MONITORING WORKFLOW

The general heart rate monitoring workflow in the Polar GoFit web service is described below. Set up the system first. Then proceed to create the first course and continue as shown in the picture below.




You can have several heart rate courses in the Polar GoFit web service simultaneously. Students can participate in several heart rate courses at a time, and they can have several heart rate sensors assigned to them. Moreover, one heart rate sensor can be assigned to several students at a time provided that the students sharing a heart rate sensor are not participating in the same course.

1. [Create a heart rate course](#). Enter course information, course type and heart rate course settings.
2. [Add students to the course](#).
3. [Assign heart rate sensors](#) to the students.
4. Students wear the heart rate sensors during PE lessons. Teacher monitors and shares heart rate data via the Polar GoFit app. The Polar GoFit app displays each student's heart rate as a percentage of the individual maximum heart rate value. It also shows the reward badges students collect. For instructions on how to wear the heart rate sensor, see the heart rate sensor user manual.

 Students pick up their assigned sensors in the beginning of each PE lesson and return them after the lesson. Alternatively, if each sensor is assigned to only one student, students may keep their assigned sensors at home. It is also possible for individual students to purchase their own sensors and wear them instead of school sensors.


5. [Data transfer](#) between the Polar GoFit app and Polar GoFit is automatic.
6. [Review the heart rate data](#) during and after course in both Polar GoFit and the Polar GoFit app.
7. The course ends. The web service evaluates students automatically based on the selected evaluation type. Print out [course evaluation report](#) and [detailed student report](#).

See also [Student user accounts](#).

 See *Using heart rate monitoring in school* in the *Lessons for Life* book to learn more about the basic structure of a heart-rate-based lesson.

FITNESS TESTING WORKFLOW

The general fitness testing workflow in the Polar GoFit web service is described below. Set up the system first. Then proceed to create a template and continue as shown in the picture below.



1. [Create a template](#) by choosing the test items, or use an existing template.



In addition to the optional test items that you can choose, **Height & Weight** is included in each template by default. This is because students' height and weight influence the evaluation of their performance.

2. [Create a test](#) by choosing the students.
3. Arrange testing and [enter the results](#) into Polar GoFit.
4. [View the test results](#) and [edit them](#) if necessary.
5. [Print out the reports](#).

USER ACCOUNTS

TEACHER USER ACCOUNTS

The number of teacher user accounts is limited based on the purchased licenses. The school receives the first user account to Polar GoFit service when the licenses are purchased. After the sign-in, more user accounts can be created. It is recommended that each teacher has their own user account because created courses are attached to teacher accounts. Separate accounts help to organize courses more efficiently.

The number of available licenses for teacher user accounts is shown at the top of teacher list. To view the teacher list go to **School > Teachers**.

Teachers sign in to the web service to:

- create and manage courses,
- organize and carry out fitness testing,
- review, analyze and follow up students' activity data, heart rate data and test results,
- create reports,
- manage school settings.

Teachers sign in to the web service on Polar GoFit home page (www.polargofit.com) with the email address and password. When a teacher account is created, a link to select a password is sent by email. The password can be reset after sign-in under **School > Teachers**. The same user credentials are also used with WebSync.

See also, [Adding teachers](#), [Editing teachers](#) and [Resetting teacher's password](#).

STUDENT USER ACCOUNTS

The number of student user accounts is not limited in Polar GoFit. Students can sign in to the web service to review their activity and heart rate data, and test results. Students can see only their own data.

Students sign in to the web service on Polar GoFit home page (www.polargofit.com) with a username and password. The username consists of school alias and student ID (school-alias/student-ID), for example *polar-school/johnadams*. The same user credentials are also used to transfer activity data from the activity monitors to the web service with Polar WebSync software.

Passwords are generated automatically when students are added or imported to the web service.

A password list can be printed out on the course page. The list contains course information, student names, usernames, passwords, and the address of the sign-in page. For security reasons, the passwords can only be printed out once. If you print out the list again, the passwords will not show. A *Password assigned previously* text will appear instead. A password can be regenerated with any teacher account under **School > Students**.

See also, [Creating students](#), [Editing students](#), [Getting password list](#) and [Generating new password for student](#).

PRODUCTS


MONITORS IN POLAR GOFIT

Polar GoFit is compatible with the Polar Active activity monitors. It is mandatory to register the activity monitors to Polar GoFit before starting to use them. Activity data cannot be transferred from the activity monitors to the web service before the monitors are registered to the Polar GoFit web service.

Monitors are registered to the web service only once. During each course, the activity monitors will be assigned for students so that the activity data can be transferred to the web service.

There can be up to 1248 Polar Active activity monitors in the web service. The monitor IDs are set to the activity monitors in Polar GoFit when the monitors are registered to the web service. A monitor ID consists of a letter (A-Z) and a number (1-48). The monitor ID tells which case the activity monitor belongs to.

For instructions on registering the products to the web service, see [Registering activity monitors](#). See also [Assigning activity monitors](#).



SENSORS IN POLAR GOFIT

Polar GoFit is compatible with the Polar heart rate sensors that use *Bluetooth®* Smart technology. It is mandatory to register the heart rate sensors to Polar GoFit before starting to use them. Heart rate data cannot be monitored in the Polar GoFit app or transferred to the Polar GoFit web service before the sensors have been registered.

The sensor IDs are inserted into Polar GoFit at registration, and the registered sensors are labeled with stickers. Sensors are registered to the web service only once.

After registration, the sensors can be assigned to students so that their heart rate data can be monitored in the Polar GoFit app and transferred to the web service. One sensor can be assigned to several students at the same time provided that the students are not participating in the same course. Moreover, students can participate in several heart rate courses at a time, which is why they can also have several sensors assigned to them.

For instructions on registering sensors to the web service, see [Registering heart rate sensors](#). See also [Assigning heart rate sensors](#).

i It is possible for individual students to purchase their own heart rate sensors and wear them instead of school sensors. Sensors purchased by students need to be registered to Polar GoFit, too. For more information, see [Using a personal heart rate sensor](#).



DATA TRANSFER

DATA TRANSFER IN ACTIVITY MONITORING


To transfer data between an activity monitor and Polar GoFit, make sure you have the following available:

- Polar GoFit user credentials,
- a Polar FlowLink data transfer unit, and
- the Polar WebSync software (version 2.4 or newer).

 You can download WebSync at www.polar.com/support. To install WebSync, download the installer, run it and follow the instructions on the screen.

To start the data transfer, plug the FlowLink data transfer unit into a free USB port and place an activity monitor on the FlowLink with the display facing down. When the activity monitor is aligned correctly, the Align light is lit on the FlowLink.



When the activity monitor is detected and WebSync is running, WebSync prompts for Polar GoFit user credentials. The WebSync icon  turns green in the task bar (Windows) / menu bar (OS X) simultaneously.

Use data transfer to:

- [register activity monitors to the Polar GoFit web service](#),
- [assign activity monitors to students when creating courses](#), and

- [download activity data from an activity monitor to Polar GoFit.](#)

Depending on what kind of data is transferred, the needed actions vary. See the table below for reference.

I want to...	Location in Polar GoFit	WebSync	FlowLink
register activity monitors to the web service for my school.	School > Monitors	Start the software if it is not already running.	Plug the data transfer unit into the USB port.
assign activity monitors to students for course duration.	Courses > Create course > Assign monitors / Courses > select and open course > Assign monitors	If there is a WebSync icon in the task bar (Windows) / menu bar (OS X), the software is ready to be used.	
download activity data from an activity monitor to the web service.	-		

i Working with several activity monitors: When WebSync confirms with a green tick that the activity monitor is okay, **leave the software running** and place the next activity monitor on the FlowLink. If you accidentally closed WebSync, it prompts for the user credentials again when needed.

For more information on the WebSync software, see the WebSync software help.



DATA TRANSFER IN HEART RATE MONITORING

Heart rate data is transferred from the heart rate sensors to the Polar GoFit app automatically via *Bluetooth®* Smart technology, provided that all the preparations ([setting up the system](#), [creating a heart rate course](#) and [assigning heart rate sensors](#)) have been done as instructed. Teacher just needs to sign in to the Polar GoFit app in the beginning of a PE lesson, select the right course, and start a new lesson. Students wear their assigned heart rate sensors and start exercising as instructed by the teacher.

Also the data transfer between the Polar GoFit app and Polar GoFit is automatic. There is no need for additional data transfer software or equipment. All you need is an Internet connection.


Before PE lesson: Course and student data is synchronized from Polar GoFit to the Polar GoFit app.

Just before PE lesson: Teacher can edit exercise target in the Polar GoFit app. If a sensor is lost or broken, a teacher can assign a new sensor to a student in the Polar GoFit app. The changes are synchronized from the Polar GoFit app to Polar GoFit. Visitors are added to lessons in the Polar GoFit app.

During PE lesson: Heart rate data is transferred from the heart rate sensors to the Polar GoFit app via *Bluetooth®* Smart technology.

Just after PE Lesson: Course and student data is synchronized from the Polar GoFit app to Polar GoFit.

After PE lesson: The Polar GoFit app shows the latest date when data was synchronized to Polar GoFit. The synchronized data is available in both Polar GoFit and the Polar GoFit app.



EVALUATION


COURSE EVALUATION

The most common evaluation types are pre-defined in the web service. However, you can also edit, remove and add new evaluation types. For instructions on adding and editing the evaluation types, see [Configuring evaluation types](#).

Default evaluation types:

Letters fractionalized	Letters	Numbers (1-5)	Numbers (4-10)	Pass/Fail	Basic	Advanced	Olympic medals
A+	A	5	10	Pass	Excellent	Exceeds expectations	Gold
A	B	4	9	Fail	Great	Meets expectations	Silver
A-	C	3	8		Satisfactory	Needs improvement	Bronze
B+	D	2	7		Needs improvement		
B	E	1	6		Fail		
B-	F		5				
C+			4				
C							
C-							
D+							
D							
D-							
E							
F							

Polar solutions for activity monitoring and heart rate monitoring provide teachers with objective evaluation tools. They allow evaluation based on effort, not just skills.

 For more information on how to analyze activity and heart rate data, see *Analyzing activity information* and *Analyzing heart rate information* in the *Lessons for Life* book.

TEST EVALUATION

Teachers organize fitness testing by creating templates. Templates consist of test items, such as One-Mile Run or Shoulder Stretch. Each test item measures one of the following four fitness areas:

1. **Aerobic capacity:**

- **One-Mile Run**,
- **PACER** (Progressive Aerobic Cardiovascular Endurance Run), and
- **Walk Test**.

2. **Flexibility:**


- **Back-Saver Sit and Reach** and
- **Shoulder Stretch**.

3. **Body composition:**

- **BMI** (Body Mass Index),
- **Bioelectrical Impedance Analyzer**, and
- **Skinfold Measurement**.

4. **Muscular strength and endurance:**

- **Curl-Up** (abdominal strength and flexibility),
- **Trunk Lift** (trunk extensor strength and flexibility),
- **Push-Up** (upper body strength and endurance),
- **Modified Pull-Up** (upper body strength and endurance), and
- **Flexed Arm Hang** (upper body strength and endurance).

 In addition to the optional test items that you can choose, **Height & Weight** is included in each template by default. This is because students' height and weight influence the evaluation of their performance.

Each test item is evaluated according to one of the following evaluation scales:

1. **Very Lean - Meets Expectations - Needs Improvement (Some Risk) - Needs Improvement (High Risk):**
 - **BMI** (Body Mass Index),
 - **Bioelectric Impedance Analyzer**, and
 - **Skinfold Measurement**.
2. **Meets Expectations - Needs Improvement (Some Risk) - Needs Improvement (High Risk):**
 - **One-Mile Run**,
 - **PACER** (Progressive Aerobic Cardiovascular Endurance Run), and
 - **Walk Test**.
3. **Meets expectations - Needs improvement:**
 - **Curl-Up**,
 - **Trunk Lift**,
 - **Push-Up**,
 - **Modified Pull-Up**,
 - **Flexed Arm Hang**,
 - **Back-Saver Sit and Reach**, and
 - **Shoulder Stretch**.

ACTIVARIUM



Activarium is a game that students play with the daily activity they gather on their activity monitors: the more daily activity on Polar Active, the more activity points in Activarium!

Each student has their own fish that represents them in the game, and together as a group the students build a structure, such as a castle or a shipwreck, by reaching their daily activity target. The students can see how the building project progresses, and with the collected activity points they can customize their fish. Teacher can also buy decorations for the Activarium with the course's activity points.

Activarium can be activated for any course. There can be several Activariums in use at the same time. The school can showcase either all activated Activariums or a selected one, for example, on a big screen at school. Students can access a course's Activarium after signing in to the web service if Activarium has been activated.

Activarium is not automatically included in the Polar GoFit licenses. It has to be purchased separately for the school.

See also, [Activating Activarium for a course](#), [Opening Activarium](#), [Decorating the Activarium](#) and [Opening Activarium showcase](#).

ACTIVITY POINTS

The daily activity the students gather on their activity monitors is turned into activity points. The fish can be customized and the Activarium can be decorated with activity points.




There are three types of activity points:

- All daily activity a student gathers increases his/her individual activity point score. The students can customize their own fish with these activity points. Customization is buying accessories and changing colors and pattern.
- The daily activity the students gather together gradually builds up the selected structure automatically.
- The gathered daily activity that exceeds the daily activity target increases course's activity point score. The teacher can decorate the Activarium with these activity points.



ACTIVARIUM CONTROLS

Point your mouse to the upper right corner of the Activarium. A menu appears.

In course's Activarium:

	Turn the sound on and off by clicking the first icon.
	View the Activarium in full screen mode by clicking the second icon.
	Buy decorations for the Activarium by clicking the third icon.

In course's or school's Activarium showcase:

	<p>Turn the sound on and off by clicking the first icon.</p>
	<p>View the Activarium in full screen mode by clicking the second icon.</p>


COURSES

ACTIVITY COURSES

CREATING AN ACTIVITY COURSE


1. Go to **Courses**.
2. Click **Create course**.
3. Enter **Course information** (course name, start date, end date, and evaluation type).
4. Select **Activity course** as course type.
5. Select **Target active time**.
6. Select **Monitor settings** (monitor display selection, monitor language and settings lock).
7. Click **Add students**. After adding students, the web service redirects you back to the course page. For more information, see [Adding students to an activity course](#).
8. Click **Assign monitors**. After assigning the activity monitors, the web service redirects you back to the course page. For more information, see [Assigning activity monitors](#).
9. After adding students and assigning activity monitors, click **Save**. The software redirects you back to the **Courses** page.

When you create a course, it is not mandatory to add students or assign monitors right away. You can add (more) students and assign (more) activity monitors at any time.

 You can edit an ongoing or future activity course in Polar GoFit at any time. However, you can only edit course name, evaluation type, students and monitors after you have saved the course. You can also change the teacher. For more information, see [Editing an activity course](#).

EDITING AN ACTIVITY COURSE

You can edit an ongoing or future activity course at any time. Finished courses can only be viewed.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.


5. View the course information and edit the necessary fields. You can edit the following information: course name, teacher, evaluation type, students and monitors.
6. Click **Save**. The software redirects you back to the **Courses** page.

For more information on adding or removing students, see [Adding students to an activity course](#) and [Removing students from an activity course](#).


For more information on assigning and reassigning Polar Active activity monitors, see [Assigning activity monitors](#) and [Reassigning activity monitors](#).

ADDING STUDENTS TO AN ACTIVITY COURSE

Students can be added to the course [when the course is created](#) or afterwards. You can edit an ongoing or future activity course at any time.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Add students**.
6. Select the students you want to add to the course.

School's students are listed on the page, grouped by classes. Expand classes to see the students available for the course. You can also select a whole class to be added. Selected students do not need to be from the same class.


 A student can participate in one activity course at a time. Students who have already been added to another activity course are not shown on the student list on this page. A student can, however, participate in an activity course while participating in one or more heart rate courses.

7. Click **Finish** when you are done. The software redirects you back to the course information page.

REMOVING STUDENTS FROM AN ACTIVITY COURSE

Students can be removed from an activity course any time during the course.


1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.


3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Remove students**.
6. Students who have been marked to participate in the course are listed on the page, grouped by classes. Expand classes to see the students. Select the students you want to remove from the course.
7. Click **Remove students**.
8. Polar GoFit asks for a confirmation. Click **Remove** to confirm or **Cancel** to return to the previous view. After clicking **Remove**, the software redirects you back to the course information page.

ASSIGNING ACTIVITY MONITORS

Activity monitors can be assigned when the course is created or afterwards. An ongoing or future activity course can be edited at any time.

1. Make sure you have Polar FlowLink data transfer unit plugged into a free USB port and Polar WebSync software installed on your computer. For more information, see [Data transfer in activity monitoring](#).



2. Go to **Courses**.
3. Find the course on the **Ongoing courses** list, or use the search.
4. Click the row or the icon  to open the course.
5. Click **Edit course**.
6. Click **Assign monitors**.

7. Place the first free activity monitor on the FlowLink with the display facing down. Make sure the **Align** light is lit on the FlowLink.



8. WebSync prompts for Polar GoFit user credentials.
9. As soon as a green tick appears for the activity monitor in WebSync and the monitor appears in Polar GoFit, place another activity monitor on the FlowLink. Follow the progress in WebSync.




10. Continue until you have assigned activity monitors to all students.
11. Click **Finish** when you are done. The software redirects you back to the course information page.

i Working with several activity monitors: When WebSync confirms with a green tick that the activity monitor is okay, leave the software running and place the next activity monitor on the FlowLink. If you accidentally closed WebSync, it prompts for the user credentials again when needed.

REASSIGNING ACTIVITY MONITORS

Activity monitors can be reassigned to other students or courses after the course has ended. If a monitor is needed for another course before the original course has ended, the reservation can be removed by following the steps below. After that the activity monitor can be reassigned or, for example, removed from the school.

An ongoing or future activity course can be edited at any time. This includes reassigning activity monitors.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Assign monitors**.
6. Remove an activity monitor from a student by clicking **Remove monitor** at the end of the row.
7. Polar GoFit asks for a confirmation. Click **Remove monitor** to confirm or **Cancel** to return to the previous view.
8. Repeat steps 6 to 7 to remove more activity monitors.
9. Click **Finish** when you are done. The software redirects you back to the course information page.


Removed activity monitors can now be assigned to other students or courses. For more information, see [Assigning activity monitors](#).

Removed activity monitors can also be removed from the school. For more information, see [Removing activity monitors](#).

TRANSFERRING ACTIVITY DATA

Activity data can be transferred from the Polar Active activity monitors to the web service with teacher or student user credentials. For more information on user credentials, see [Teacher user accounts](#) and [Student user accounts](#).

1. Make sure you have Polar FlowLink data transfer unit plugged into a free USB port and Polar WebSync software installed on your computer running in the background. For more information see [Data transfer in activity monitoring](#).



2. Place the first activity monitor on the FlowLink with the display facing down. Make sure the **Align** light is lit on the FlowLink.



3. WebSync window opens automatically and prompts for Polar GoFit user credentials.
4. As soon as a green tick appears for the activity monitor in WebSync and the monitor appears in Polar GoFit, place another activity monitor on the FlowLink. Follow the progress in WebSync.



5. Continue until you have transferred activity data from all activity monitors.
6. Close WebSync when you are done. Sign in to the web service to [review the activity data](#).

i Working with several activity monitors: When WebSync confirms with a green tick that the activity monitor is okay, leave the software running and place the next activity monitor on the FlowLink. If you accidentally closed WebSync, it prompts for the user credentials again when needed.



VIEWING ACTIVITY COURSES

There are two ways to list and view activity courses, including your own courses. You can open your latest courses through the **Dashboard** and all the courses at your school through the **Courses** page.

i Your own courses have been created with your teacher account.



VIEWING "MY COURSES" ON DASHBOARD

Your five latest courses are listed on the Polar GoFit dashboard.

1. Click the icon  to go to **Dashboard**.
2. Scroll down to **My Courses**. Activity courses are marked with the activity icon: 
3. View your latest activity courses. The following course information is shown on the **Dashboard**:
 - course name,
 - average active time in minutes compared to target active time (for example, 65/90 min),

- number of students,
 - number of assigned activity monitors,
 - days since the last time activity data was transferred from the activity monitors,
 - start date, and
 - end date.
4. Open a course by clicking **View course**.
 5. View the course information. For more information, see [Viewing activity courses on courses page](#).

VIEWING ACTIVITY COURSES ON COURSES PAGE

1. Go to **Courses**.
2. Find the course on the course lists (Ongoing courses/Finished courses), or use the search. Activity courses are marked with the activity icon:

3. Click the row or the icon  to open the course. Ongoing and future activity courses can be edited, but finished activity courses can only be viewed.
4. Click **Edit course/View course**.
5. The following information is shown:
 - course name,
 - teacher,
 - start date,
 - end date,
 - course duration,
 - evaluation type,
 - course type,
 - target active time in minutes,
 - activity monitor settings, and
 - students added to the course (listed by the class).


Expand a class to see the students. The following information is shown for the students:

- first name,
- last name,
- activity monitor which is assigned to the student, and
- date when activity data was last transferred from the activity monitor.


Return to course list by clicking **Back to Course list**.

VIEWING ACTIVITY DATA

All the activity courses at your school are listed on the **Courses** page. Your latest activity courses are listed also on **Dashboard**. For more information, see [Viewing activity courses](#).

1. Go to **Courses**.
2. Find the course on the course lists (Ongoing courses/Finished courses), or use the search.
3. Click the row or the icon  to open the course.
4. The **Weekly activity** page shows the following **Course information**:
 - number of students,
 - average active time in minutes compared to target active time (for example, 65/90 min),
 - teacher,
 - evaluation type,
 - start date, and
 - end date.
5. Select **All students** on the **Student information** drop-down list to review the daily group averages for the whole course as bar graphs. Up to seven days' activity bars are displayed simultaneously. Browse through the weeks with the arrows above the bar graph area. The bar graph area shows the following information:
 - the bar is the daily activity target, and
 - the colored part of the bar is the group average result for the day.


This information is also shown as a tooltip text when you hover over any of the bars.



6. Select one student on the **Student information** drop-down list to review the daily results for the selected student as bar graphs. Up to seven days' activity bars are displayed simultaneously. Browse through the weeks by using the arrows above the bar graph area. The bar graph area shows the following information:


- the bar is the daily activity target,
- the colored part of the bar is the student's daily activity result, and
- the colored frame on the bar is the group average result for the day.


This information is also shown as a tooltip text when you hover over any of the bars.



7. Click **View daily activity** to review the selected student's daily activity in detail. Each day's activity data is displayed as a curve graph. Alternatively, you can click any of the bars in the weekly bar graph to view the curve graph displaying the selected student's activity data on that particular day. Move between the days with the arrows above the curve graph area. You can change the student from the **Student information** drop-down list. In addition to the daily activity curve, the **Daily activity** page shows the following information:

- active time in minutes compared to target active time (for example, 65/90 min),
- time spent in the different activity zones (the Vigorous+, Vigorous and Moderate zones fill up the daily activity bar),
- time spent in the sleeping zone,
- calories and steps,
- automatic evaluation based on the selected evaluation type and student's total score of daily activity.




 You can print the activity curve by clicking **Print activity curve** above the curve. The curve is printed as a PDF file which can then be saved on the computer or printed on paper.















8. Return to the bar graph page by clicking **Back to weekly activity**.

 You can use, for example, the following questions to discuss the activity data with your students:

- How did you get your activity bar filled?
- How did you get time for each activity zone?
- What could you do to gain more active time?


You can also make a plan for an active day/week, and then discuss the planned and actual hours/minutes.

 For more information on how to analyze activity data, see *Analyzing activity information* in the *Lessons for Life* book.

ZONE	EXAMPLE ACTIVITIES	RECOMMENDATION	BENEFITS
 VIGOROUS+	Fast running 	Be active for more than one hour every day!	<ul style="list-style-type: none"> • Improves maximum performance and cardiovascular fitness • Helps improving speed
 VIGOROUS	Basketball, soccer, rollerblading, rope jumping, dancing 		<ul style="list-style-type: none"> • Improves cardiovascular endurance • Promotes bone health • Helps increasing power
 MODERATE	Playground games, gymnastics 	Being active in Moderate to Vigorous+ zones fills up the Activity bar in your Polar activity monitor.	<ul style="list-style-type: none"> • Helps maintaining a healthy body weight • Helps increasing flexibility
 EASY	Playing catch  Slow walking  Stretching 	It's better to get up and move than sit still!	
 VERY EASY	Playing video games, watching TV 	Avoid sitting for long periods of time!	
SLEEPING		9 hours of sleep every night will keep your mind fresh!	<ul style="list-style-type: none"> • Improves learning ability • Gives your body a rest

ACTIVATING ACTIVARIUM FOR A COURSE


You can activate [Activarium](#) for an ongoing or future course at any time. Activarium cannot be activated for finished courses. The students cannot see Activariums that have not been activated.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Open Activarium**. The Activarium opens into a new window.
6. If Activarium has not been activated for the course, you are asked to select a main building for the course's Activarium.
7. Save the selection by clicking **Save**. The Activarium is now activated for the course.


OPENING ACTIVARIUM

A course's Activarium can be opened on the **Dashboard** or on the **Courses** page.

ON THE DASHBOARD

1. Click the icon  to go to **Dashboard**.
2. Scroll down to **My Courses**.
3. View your latest courses.
4. Open the course's Activarium by clicking **Open Activarium**. The Activarium opens into a new window.


ON THE COURSES PAGE

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Open Activarium**. The Activarium opens into a new window.

The school can also [showcase Activariums](#), for example, on a big screen at school.

DECORATING THE ACTIVARIUM

You can buy decorations for the Activarium's main building with the course's activity points.

1. [Open the Activarium](#).
2. Point your mouse to the upper right corner of the Activarium. A menu appears.
3. Select the decoration icon .
4. The available activity points are shown in the upper left corner. Scroll through the decorations.

Preview a decoration by selecting it and clicking **Preview**. Click the Activarium to return to the decoration store.

5. Select a decoration and click **Buy** if you have enough activity points to buy the decoration. The decoration is added to the Activarium.


 Students can customize (accessorize and modify) their fish with their individual activity points.

Read more about the activity points in [Activarium](#).

OPENING ACTIVARIUM SHOWCASE


The school can showcase activated Activariums, for example, on a big screen at school. You can select to showcase school's all activated Activariums or a course's Activarium.

SHOWCASING SCHOOL'S ALL ACTIVARIUMS

1. Go to **Activarium showcase** on the **Dashboard** .
2. Click **Open showcase with all courses** to launch the Activarium showcase in a new window.
3. Copy the Activarium's URL address to showcase the Activarium on another computer.

All of the school's activated Activariums are shown randomly with anonymous fish.

SHOWCASING A COURSE'S ACTIVARIUM

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Showcase Activarium** to launch the Activarium showcase in a new window.

The course's Activarium is shown with anonymous fish.

REMOVING AN ACTIVITY COURSE

Courses can be removed from the school. Only activity courses that do not have activity monitors assigned to students can be removed.

If the course you wish to remove is not available for removal, make sure there are no activity monitors assigned to the course's students. To remove the monitors from the students, see [Reassigning activity monitors](#).

1. Go to **Courses**.
2. Click **Remove course**. The courses that can be removed from the school are listed.
3. Select the courses you wish to remove from the school. Click **Remove course**.


4. Polar GoFit asks for a confirmation. Click **Remove** to confirm or **Cancel** to return to the previous view.
5. Repeat steps 2 to 4 to remove more courses.


HEART RATE COURSES

CREATING A HEART RATE COURSE

1. Go to **Courses**.
2. Click **Create course**.
3. Enter **Course information** (course name, start date, end date, and evaluation type).
4. Select **Heart rate course** as course type.
5. Enter **Heart rate course settings** (target zone, time in target zone, showing/hiding calories, showing student names/student IDs in the Polar GoFit app). For more information on target zones, see [Target zones and badges](#).
6. Click **Add students**. After adding students, the web service redirects you back to the course page. For more information, see [Adding students to a heart rate course](#).
7. Click **Assign sensors**. After accepting the sensor reservations, the web service redirects you back to the course page. For more information, see [Assigning heart rate sensors](#).
8. After adding students and assigning heart rate sensors, click **Save**. The software redirects you back to the **Courses** page.

When you create a course, it is not mandatory to add students or assign sensors right away. You can add (more) students and assign (more) heart rate sensors at any time.

 You can edit an ongoing or future heart rate course in Polar GoFit at any time. However, start date and course type cannot be changed after you have saved the course. For more information, see [Editing a heart rate course](#).

 It is possible to change the exercise target (target zone and time in target zone) in the Polar GoFit app as well. If you change the exercise target in the Polar GoFit app, the change will be synchronized to Polar GoFit.

TARGET ZONES AND BADGES

TARGET ZONES

When you [create a heart rate course](#), you need to select a **Target zone**. The available target zones are:

- **Performance** (70-100% of maximum heart rate): develops maximum performance and speed,
- **Healthy heart** (70-90% of maximum heart rate): improves aerobic fitness and performance capacity,

- **Active** (60-80% of maximum heart rate): improves basic endurance and muscle tone, and
- **Free** (no zone target).

You also need to select **Time in target zone**, which indicates for how long the students should aim to stay within the target zone in every PE lesson. The system evaluates students automatically based on their achieved percentages of the target time in target zone.

If the target zone is **Free**, there will be no evaluation and no badges.

You can change both the target zone and time in target zone in either Polar GoFit or the Polar GoFit app after the course has been created. For more information, see [Editing a heart rate course](#).



 For more information on heart rate zones in general, see *Using heart rate monitoring in school* in the *Lessons for Life* book.

BADGES

There are two kinds of badges: reward badges and personal best badges.

For every ten minutes spent in the target zone, a student receives a **reward badge**. The reward badges are named after cats:

-  a domestic cat for ten minutes in the target zone,
-  a cougar for twenty minutes in the target zone,
-  a lion for thirty minutes in the target zone,
-  a leopard for forty minutes in the target zone,

-  a tiger for fifty minutes in the target zone, and
-  a cheetah for sixty minutes in the target zone.


Polar GoFit lesson summaries show the reward badges a student has received for each lesson. If a student stays in the target zone for less than ten minutes during a lesson, no reward badge is achieved for that lesson.

In each heart rate course, a student receives a **personal best badge** for the lesson with the best performance in terms of minutes spent in the target zone. The personal best badges are shown in Polar GoFit lesson summaries.




EDITING A HEART RATE COURSE

You can edit an ongoing or future heart rate course at any time. Finished courses can only be viewed.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. View the course information and edit the necessary fields. Start date and course type cannot be edited.
6. Click **Save**. The software redirects you back to the **Courses** page.


For more information on adding or removing students, see [Adding students to a heart rate course](#) and [Removing students from a heart rate course](#).

For more information on assigning and reassigning heart rate sensors, see [Assigning heart rate sensors](#) and [Reassigning heart rate sensors](#).


 It is possible to change the exercise target (target zone and time in target zone) in the Polar GoFit app as well. If you change the exercise target in the Polar GoFit app, the change will be synchronized to Polar GoFit.

ADDING STUDENTS TO A HEART RATE COURSE


Students can be added to the course when the course is created or afterwards. You can edit an ongoing or future heart rate course at any time.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Add students**.
6. Select the students you want to add to the course. The maximum number of students for a heart rate course is 40.

School's students are listed on the page, grouped by classes. Expand classes to see the students available for the course. You can also select a whole class to be added. Selected students do not need to be from the same class.

 A student can participate in several heart rate courses at a time. It is also possible to participate in an activity course while participating in one or more heart rate courses.


7. Click **Finish** when you are done. The software redirects you back to the course information page.

 It is possible for visiting students to participate in individual lessons provided that there are available sensors and the visiting student has been added to Polar GoFit. Visitors are added to lessons in the Polar GoFit app. Visiting students' lesson summaries can be viewed via the students' personal Polar GoFit accounts.

REMOVING STUDENTS FROM A HEART RATE COURSE


Students can be removed from heart rate course any time during the course.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.

3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Remove students**.
6. Students who have been marked to participate in the course are listed on the page, grouped by classes. Expand classes to see the students. Select the students you want to remove from the course.
7. Click **Remove students**.
8. Polar GoFit asks for a confirmation. Click **Remove** to confirm or **Cancel** to return to the previous view. After clicking **Remove**, the software redirects you back to the course information page.


ASSIGNING HEART RATE SENSORS

Heart rate sensors can be assigned when the course is created or afterwards. An ongoing or future heart rate course can be edited at any time.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Assign sensors**.
6. The system assigns a sensor for each student automatically. The number of the assigned sensor is shown for each student. You can use the drop-down list to reassign the heart rate sensors manually.
7. Click **Save** to accept the reservations. The software redirects you back to the course information page.


If a student has purchased their own heart rate sensor to use instead of a school sensor, you need to register the sensor ID to the system. If a student has a personal heart rate sensor in use, the system does not assign a school sensor for that particular student.

Within a course, one sensor can be assigned to one student at a time. Within a school, one sensor can be assigned to several students at a time provided that they are not participating in the same course. Individual students can take several heart rate courses simultaneously, and have several heart rate sensors assigned to them.

 If a sensor is lost or broken, a teacher can assign a new sensor to a student in the Polar GoFit app right before the PE lesson.

REASSIGNING HEART RATE SENSORS

An ongoing or future heart rate course can be edited at any time. This includes reassigning heart rate sensors.


1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Assign sensors**.
6. The number of the assigned sensor is shown for each student. You can use the drop-down list to reassign heart rate sensors manually. Click **Remove reservation** to remove a heart rate sensor from a student.
7. Click **Save** to accept the reservations. The software redirects you back to the course information page.

See also [Assigning heart rate sensors](#).

Removed heart rate sensors can be removed from the school if they have no other reservations. For more information, see [Removing heart rate sensors](#).

USING A PERSONAL HEART RATE SENSOR

It is possible for students to purchase their own heart rate sensors and use them instead of school sensors. Personal sensors need to be registered to the system.

1. Go to **School > Students** tab.
2. Find the student on the student list. Students are listed by the class. Use the search and filtering options above the student list. Expand a class to see the students.
3. Click the icon  to edit the student.
4. Register the sensor by inserting the sensor ID into the **Own sensor's ID** field.
5. Click **Save** to save the changes. The software redirects you back to the student list. To return without saving the changes, click **Back to student list**.

If there is a school sensor assigned to the student, you can [remove the reservation](#).


See also [Assigning heart rate sensors](#).

TRANSFERRING HEART RATE DATA

Heart rate data is transferred from the heart rate sensors to the Polar GoFit app via *Bluetooth®* Smart technology. Also the data transfer between the Polar GoFit app and Polar GoFit is automatic. There is no need for additional data transfer software or equipment. All you need is an Internet connection. For more information, see [Data transfer in heart rate monitoring](#).



VIEWING HEART RATE COURSES

There are two ways to list and view heart rate courses, including your own courses. You can open your latest courses through the **Dashboard** and all the courses at your school through the **Courses** page.



 Your own courses have been created with your teacher account.

VIEWING "MY COURSES" ON DASHBOARD

Your five latest courses are listed on the Polar GoFit dashboard.

1. Click the icon  to go to **Dashboard**.
2. Scroll down to **My Courses**. Heart rate courses are marked with the heart icon:

3. View your latest heart rate courses. The following course information is shown on the **Dashboard**:
 - course name,
 - achieved percentage of target time in target zone (for example 91 /100 %),
 - number of students,
 - number of assigned sensors,
 - number of completed lessons,
 - start date, and
 - end date.
4. Open a course by clicking **View course**.
5. View the course information. For more information, see [Viewing heart rate courses on courses page](#).

VIEWING HEART RATE COURSES ON COURSES PAGE

1. Go to **Courses**.
2. Find the course on the course lists (Ongoing courses/Finished courses), or use the search. Heart rate courses are marked with the heart icon:

3. Click the row or the icon  to open the course. Ongoing and future heart rate courses can be edited, but finished heart rate courses can only be viewed.
4. Click **Edit course/View course**.
5. The following information is shown:
 - course name,
 - teacher,
 - start date,
 - end date,
 - course duration,
 - evaluation type,
 - course type,
 - target zone,
 - time in target zone,
 - visibility of calories (Yes/No)
 - student identifier in the Polar GoFit app (name or student ID), and
 - students added to the course (listed by the class).


Expand a class to see the students. The following information is shown for the students:

- first name,
- last name, and
- heart rate sensor(s) assigned to the student.

Return to course list by clicking **Back to Course list**.

VIEWING HEART RATE DATA

All the heart rate courses at your school are listed on the **Courses** page. Your latest heart rate courses are listed also on **Dashboard**. For more information, see [Viewing heart rate courses](#).

1. Go to **Courses**.
2. Find the course on the course lists (Ongoing courses/Finished courses), or use the search.
3. Click the row or the icon  to open the course.
4. The **Course summary** page shows the following **Course information**:




- number of students,
- number of lessons,
- teacher,
- evaluation type,
- start date, and
- end date.

It also shows:


- achieved percentage of target time in target zone (group average),
- time spent in different heart rate zones (group average), and
- list of lessons.

The list of lessons shows the following information for each lesson:

- date and time,
- target zone,
- time spent in different heart rate zones, and
- lesson duration.

5. Click  /  to open/close all the lessons. Click  to open/close an individual lesson. When you open a lesson, the following information is shown:

- a horizontal bar shows the minutes each student has spent in the target zone,
 - a green vertical line shows the target time in target zone in minutes,
 - a red vertical line shows the group average minutes spent in target zone, and
 - saved data percentage for each student (data can be missing, for example, if the student had to leave the class for a few minutes and the connection between the heart rate sensor and the Polar GoFit app was interrupted)
6. To view the students' lesson summaries with heart rate curves, click **View lesson summaries**. Alternatively, you can click the name of the student whose lesson summaries you wish to view. The **Lesson summary** page shows the following information:
- **Student information** drop-down list where you can select the student whose lesson summaries you wish to view,
 - time spent in different heart rate zones (target zone indicated with a red frame),
 - achieved time in target zone compared to target time (both as a percentage and as minutes),
 - calories spent (optional),
 - evaluation,
 - saved data percentage,
 - lesson number,
 - possible [badges](#),
 - short description of the benefit of the lesson (if the student stayed in the target zone for at least ten minutes),
 - a curve graph displaying the student's heart rate during the lesson, and
 - maximum and average heart rate during the lesson.



Move between the lessons with the arrows above the curve graph area.

 You can print the heart rate curve by clicking **Print HR curve** above the curve. The curve is printed as a PDF file which can then be saved on the computer or printed on paper.

7. Click **View course summary** to return to the course charts.

Heart rate data can be missing for two possible reasons:


- The connection between a heart rate sensor and the Polar GoFit app was interrupted. This could happen, for example, if a student had to leave the class for a few minutes. In this case, the saved data percentage for that student is less than 100 %.
- A heart rate sensor did not detect heart rate. This could happen, for example, if the heart rate sensor was not worn as instructed (the strap must be tight enough and the electrodes must be properly moistened). In this case, the connection between the heart rate sensor and the Polar GoFit app was uninterrupted, and the saved data percentage is 100 %, but the heart rate curve shows that no heart rate was detected.

It is possible for visiting students to participate in individual lessons provided that there are available sensors and the visiting student has been added to Polar GoFit. Visitors are added to lessons in the Polar GoFit app. Visiting students' lesson summaries can be viewed via the students' personal Polar GoFit accounts.

 You can use, for example, the following questions to discuss the heart rate data with your students:

- How did you feel in each heart rate zone?
- What are the benefits of exercise in each heart rate zone?
- Why is it important to have a warm-up and a cool-down phase?
- Compare and discuss your maximum/average heart rate in different lessons. Can you explain the differences between lessons?

You can also make a plan for a heart-rate-based PE lesson together with the students, and then discuss the actual heart rate data after the lesson. Did the class achieve the target?

 For more information on how to analyze heart rate data, see *Analyzing heart rate information* in the *Lessons for Life* book.

REMOVING A HEART RATE COURSE


Courses can be removed from the school. Only heart rate courses that do not have heart rate sensors assigned to students can be removed.

If the course you wish to remove is not available for removal, make sure there are no heart rate sensors assigned to the course's students. To remove the sensors from the students, see [Reassigning heart rate sensors](#).

1. Go to **Courses**.
2. Click **Remove course**. The courses that can be removed from the school are listed.
3. Select the courses you wish to remove from the school. Click **Remove course**.
4. Polar GoFit asks for a confirmation. Click **Remove** to confirm or **Cancel** to return to the previous view.
5. Repeat steps 2 to 4 to remove more courses.

GETTING STUDENT LIST


You can print out a student list for a course and place the printed student list, for example, into the pocket of the case.

1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.
3. Click the row or the icon  to open the course.
4. Click **Edit course**.
5. Click **Print student list** to generate a list of the students added to the course.
6. A PDF file is generated. The PDF file can be saved on the computer and printed on paper.

GETTING PASSWORD LIST

You can print out a password list for a course and share the passwords with students. For security reasons, the passwords are shown on the password list only when they are printed for the first time. For more information on the password list, see [Student user accounts](#).


1. Go to **Courses**.
2. Find the course on the **Ongoing courses** list, or use the search.

3. Click the row or the icon  to open the course.

4. Click **Edit course**.

5. Click **Print password list** to generate a password list for the students added to the course.


6. A PDF file is generated. The PDF file can be saved on the computer and printed on paper. The PDF file includes a student list with passwords. You can cut the student list into strips and give the passwords to students.

 The password list includes only automatically generated passwords. Passwords that have been generated on student information page are not shown in the PDF.

REPORTS

GETTING COURSE EVALUATION REPORT

1. Go to **Reports > Course report**.

2. Click the row or the icon  to select a course. The course list can be filtered with the search form above the list.


3. Select **Course evaluation**.

4. Select either **PDF**, **XLS** or **Data XLS** depending on which format you need.

 **Data XLS** report contains no formatting which makes the data easy to filter, sort and export further.

5. If you wish to exclude days that contain no activity data/times when there is no heart rate data available, tick the box.


6. Click **Create report**. The report is created and opened. The file can be saved on the computer and printed on paper.

 Alternatively, you can proceed to report printing by clicking **Print reports** on the **Course summary** page.

See also [Reading course evaluation report](#).

READING COURSE EVALUATION REPORT

To create a course evaluation report, see [Getting course evaluation report](#). The course evaluation report can be in either XLS, PDF or Data XLS format. All students are printed in the same report.


 **Data XLS** report contains no formatting which makes the data easy to filter, sort and export further.

The report heading shows the following information: teacher's name, school, course name, course start and end dates, report type and course status (not started/ongoing/finished).



The report shows the following information:


- The first column shows the student's name.
- The second column shows the achieved percentage of the maximum score.
- The third column shows the automatic evaluation for the student.

The course averages are shown on the last row.

 For more information on how to analyze activity or heart rate data, see *Analyzing activity information* or *Analyzing heart rate information* in the *Lessons for Life* book.

GETTING DETAILED STUDENT REPORT

1. Go to **Reports > Course report**.
2. Click the row or the icon  to select a course. The course list can be filtered with the search form above the list.
3. Select **Student details**.
4. Select either **PDF**, **XLS** or **Data XLS** depending on which format you need.
 -  **Data XLS** report contains no formatting which makes the data easy to filter, sort and export further.
5. Select the students you want to include in the report. By default all the students who have been added to the course are selected.
6. If you wish to exclude days that contain no activity data/time when there is no heart rate data available, tick the box.
7. Click **Create report**. The report is created and opened. The file can be saved on the computer and printed on paper.

 Alternatively, you can proceed to report printing by clicking **Print reports** on the **Course summary** page.

See also [Reading detailed student report](#).

READING DETAILED STUDENT REPORT

To create a detailed student data report, see [Getting detailed student report](#). The detailed student report can be either in XLS, PDF or Data XLS format. All selected students are printed in the same report and displayed separately.

 **Data XLS** report contains no formatting which makes the data easy to filter, sort and export further.

The report heading shows the following information: teacher's name, school, course name, course start and end dates, and report type.


The report shows the following information in the table header: student's name, course name and date range.

ACTIVITY COURSES

The report shows the following information:

- date,
- daily activity result (of the daily activity target),
- time spent in the different activity zones (5 zones and sleep time),
- steps,
- calories, and
- automatic evaluation.


Student's average results are shown on the last row.

 For more information on how to analyze activity data, see *Analyzing activity information* in the *Lessons for Life* book.


HEART RATE COURSES

The report shows the following information:


- date of each lesson,
- saved data percentage (data can be missing, for example, if the student had to leave the class for a few minutes and the connection between the heart rate sensor and the Polar GoFit app was interrupted),
- time spent in target zone compared to the target time,
- time spent in each heart rate zone (5 zones, target zone highlighted),
- calories (optional), and
- automatic evaluation (if the target zone for a lesson is **Free**, there will be no evaluation for that lesson).

 For more information on how to analyze heart rate data, see *Analyzing heart rate information* in the *Lessons for Life* book.

EXPORT MET VALUES

1. Go to **Reports > Course report**.
2. Click the row or the icon  to select a course. The course list can be filtered with the search form above the list.
3. Select **MET export**.

4. Select the students you want to include to the report. By default all the students who have been added to the course are selected.
5. If you wish to exclude days that contain no activity data, tick the box.
6. Click **Create report**. The report is created and opened. The file can be saved on the computer and printed on paper.


 Alternatively, you can proceed to report printing by clicking **Print reports** on the **Course summary** page.


See also [Reading MET value report](#).

READING MET VALUE REPORT

To create a MET value report, see [Exporting MET values](#). The MET values are printed in CSV (comma separated values) format which can be opened in Microsoft Excel or in similar application. All selected students are printed in the same report.

The first column of the CSV file displays a time stamp for every 30 seconds of the course. All selected students have a separate column after the time stamp column. MET values are shown for each time stamp for all students.

 MET stands for metabolic equivalent and it expresses the intensity and energy expenditure of physical activities.

 For more information on MET values, see *Using activity monitors in school* in the *Lessons for Life* book.

GETTING SCHOOL REPORT

You can create different kinds of school-wide reports for different purposes. Define the students and courses that you want to include in the report by selecting specific values, such as age, gender, course type, date, and activity/exercise target. Define the minimum requirement for the grade **Pass**, and the report shows how many students passed/failed according to these standards.


ACTIVITY REPORTS

1. Go to **Reports > School report**.
2. Define **Students**:
 - Select **Gender**.
 - Enter **Age range**.

- Select whether you want the report to show individual students or not:
 - Select **No** to not show students at all.
 - Select **Yes, with names** to show students identified by their names.
 - Select **Yes, with student IDs** to show students identified by their IDs.

3. Define **Courses**:

- Select **Time range**.
- Select **Activity** as **Course type**.
- Select **Target active time**.
- Select whether you want the report to be based on **Activity** or **Activity and steps**.
- If you selected **Activity and steps**, enter **Number of steps / day**.
- Enter **Minimum requirement** as a number of days.

 This is the minimum number of successive days when **Target active time** needs to be reached for a student to pass.

4. Click **Create report**. The report is created and opened. The file can be saved on the computer and printed on paper.

HEART RATE REPORTS


1. Go to **Reports > School report**.

2. Define **Students**:

- Select **Gender**.
- Enter **Age range**.
- Select whether you want the report to show individual students or not:
 - Select **No** to not show students at all.
 - Select **Yes, with names** to show students identified by their names.
 - Select **Yes, with student IDs** to show students identified by their IDs.

3. Define **Courses**:

- Select **Time range**.
- Select **Heart rate** as **Course type**.
- Select **Target zone**.

- Select **Time in target zone**.
 - Select **Minimum requirement** as a percentage of lessons.
-  This is the minimum percentage of lessons when **Time in target zone** needs to be reached for a student to pass.

4. Click **Create report**. The report is created and opened. The file can be saved on the computer and printed on paper.

See also [Reading school report](#).

READING SCHOOL REPORT

To create a school report, see [Getting school report](#).

The report heading shows the report type and the selected values.

The report shows the following information for each course included:

- course name,
- course duration,
- age range,
- number of students included in the report,
- number of girls and boys included in the report,
- number of students that passed, and
- number of students that failed.

If you chose to show individual students in the report, the following information is shown under each course:

- student names or IDs,
- student ages, and
- pass/fail values for each student.

 This value shows the percentage of lessons/days when a student reached the target.

If you chose not to show individual students in the report, there is a summary row in the end of the report that shows the following information:

- total number of students included in the report,
- total number of girls and boys included in the report,
- total number of students that passed, and
- total number of students that failed.

SCHOOL

STUDENTS

IMPORTING STUDENTS

Each student should have their own user account in Polar GoFit. Both activity and heart rate data is always connected to a student. The student information can be edited afterwards with any teacher user account.

Students can be imported to the web service with an Excel file. It is also possible to [create students one by one](#). It is recommended to import students in larger batches and manually create only individual students.

Content of the Excel file:

- The first row of the file is for field names and it is not processed when the file is imported.
- There should be one line per student in the file. The information must be in the order shown below and each piece of information must be in a separate cell.


For example:

Student ID	Last Name	First Name	Gender (M or F)	Date of birth (mm.dd.yyyy)	Class	Weight	Height	Maximum heart rate
1234	Smith	John	M	05.05.1990	7A	42	145	
1235	Smith	Sandra	F	12.01.1992	5B	35	125	
1236	Taylor	Marcus	M	03.25.1989	8A	65	165	

Contact your IT administrator if you need help in creating the files. You can download sample files from the student import view.

1. Go to **School > Students** tab.
2. Click **Import students**.
3. Download an import file or a sample file. Type in the student information and save the Excel file.
4. Select the Excel file from your computer by using the **Browse** button.
5. Click **Import**.
6. Review the import preview. If the data is correct, click **Import**.
7. Click **Finish** to finalize the student import. The students are imported to the web service.

If the data in the import preview is incorrect, click **Cancel** on the summary page, edit and save the Excel file and repeat steps 4 to 6.


 If you know the students' maximum heart rate values, you can enter the values into the excel file when importing students. If you don't know their maximum heart rate values, you can leave the field empty. If the field is empty, the imported students will have 200 as the maximum heart rate value. You can edit the value later.


CREATING STUDENTS

Each student should have their own user account in Polar GoFit. Both activity and heart rate data is always connected to a student. The student information can be edited afterwards with any teacher user account.

It is also possible to [import students](#) with an Excel file. It is recommended to import students in larger batches and manually create only individual students.

1. Go to **School > Students** tab.
2. Check that the student does not already have an account in the system. Use the search and filtering options above the student list.
3. Click **Create new student**.
4. Fill in the student's information. The mandatory information is marked with an asterisk.

 The default maximum heart rate value is 200. If you know the exact value for a student, insert it here.


 If a student has purchased their own heart rate sensor, register the sensor by inserting the sensor ID here.

For information on student accounts, see [Student user accounts](#).


5. Click **Save** to finalize the student account. The software redirects you back to the student list.
6. Repeat steps 3 to 5 to create more student accounts.


Student ID must be unique within the school. The student ID is part of the student's username.


VIEWING STUDENT INFORMATION

1. Go to **School > Students** tab.
2. Find the student on the student list. Students are listed by the class. Use the search and filtering options above the student list. Expand a class to see the students.
3. The student list includes the following information:
 - student's first name,
 - student's last name, and
 - activity monitor and/or heart rate sensor(s) assigned to the student.
4. Click the icon  to view the detailed student information.
5. The student information is shown and it can be edited.
6. Click **Back to student list** to return to the student list. To save the changes, click **Save** instead.
7. Repeat steps 2 to 6 to view more student accounts.

EDITING STUDENTS

1. Go to **School > Students** tab.
2. Find the student on the student list. Students are listed by the class. Use the search and filtering options above the student list. Expand a class to see the students.
3. Click the icon  to edit the student.
4. Edit the student's information. The mandatory information is marked with an asterisk (*).

 The default maximum heart rate value is 200. If you know the exact value for a student, insert it here.

 If a student has purchased their own heart rate sensor, register the sensor by inserting the sensor ID here.

For information on student accounts, see [Student user accounts](#).


5. Click **Save** to save the changes. The software redirects you back to the student list. To return without saving the changes, click **Back to student list**.
6. Repeat steps 2 to 5 to edit more student accounts.

MOVING STUDENTS TO ANOTHER CLASS

1. Go to **School > Students** tab.
2. Select either individual students or an entire class. Students are listed by the class. Use the search and filtering options above the student list. Expand a class to see the students.
3. Click **Move students**.
4. Insert the new class name (for example, 3B).
5. Click **Move**.
6. If there already are students in the class you wish to move the selected students to, the software asks for your confirmation. If you still wish to move the students to the class, click **Yes, move students**.

For more information on editing students, see [Editing students](#).

GENERATING NEW PASSWORD FOR STUDENT


1. Go to **School > Students** tab.
2. Find the student on the student list. Students are listed by the class. Use the search and filtering options above the student list. Expand a class to see the students.
3. Click the icon .
4. Click **Generate new password**. A new password is generated for the student and it is shown in a new window.
5. Print the password page on paper and give it to the student.
6. Click **Back to student list** to return to the student list.
7. Repeat steps 2 to 6 to generate new passwords for other students.

For information on student accounts, see [Student user accounts](#).

See also [Getting password list](#).

REMOVING STUDENTS

Students can be removed from the school. Only students that do not have activity monitors or heart rate sensors assigned can be removed.

1. Go to **School > Students** tab.
2. Click **Remove students**. The students that cannot be removed from school are marked the red symbol . You cannot select them.

3. Select the students or whole classes you wish to remove from the school. Click **Remove students**.
4. Polar GoFit asks for a confirmation. Click **Remove** to confirm or **Cancel** to return to the previous view.
5. Repeat steps 2 to 4 to remove more students.


If the students you wish to remove are not available for removal, make sure they do not have activity monitors or heart rate sensors assigned. To remove the monitors or sensors from the students, see [Reassigning activity monitors](#) or [Reassigning heart rate sensors](#).

TEACHERS

CREATING TEACHERS


For more information on the teacher accounts in the Polar GoFit web service, see [Teacher user accounts](#).


1. Go to **School > Teachers** tab.
2. Check that the teacher does not already have an account in the system.
3. Click **Create new teacher**.
4. Fill in the teacher's information. All the fields are mandatory.
5. Click **Save** to finalize the teacher account. A link to select a password is sent by email to the teacher.
6. Repeat steps 3 to 5 to create more teacher accounts.


 The new teacher account is not valid until the teacher has generated a password, signed in to the web service, and accepted the terms of use. Until this has been done, the new teacher appears on the teacher list by email address only.

If you are using the free trial, you cannot create new teachers.


VIEWING TEACHER INFORMATION


 Each teacher can only view their own information.

1. Go to **School > Teachers** tab.
2. Find yourself on the teacher list. Teachers are listed alphabetically by the last name.
3. Click the icon  to view the account information.
4. Click **Cancel** to return to the teacher list.

 The number of available licenses for teacher user accounts is shown at the top of teacher list.

EDITING TEACHERS

 Each teacher can only edit their own information.

1. Go to **School > Teachers** tab.
2. Find yourself on the teacher list. Teachers are listed alphabetically by the last name.
3. Click the icon  to view the account information.
4. Edit the information. All the fields are mandatory.
5. Click **Save** to save the changes. The software redirects you back to the teacher list.

RESETTING TEACHER'S PASSWORD


There are two ways to reset a teacher's password. A teacher can order a new password without signing in to the web service, or reset password under **School > Teachers**.

ORDERING A NEW PASSWORD WITHOUT SIGNING IN

1. Go to www.polargoft.com.
2. Click **Forgot your password?**.
3. Type your Polar GoFit username (your email address) into the field and click **Send**. A link to select a new password is sent by email.

Check your spam filter if the email cannot be found in your email inbox.


RESETTING THE PASSWORD


1. Sign in to the web service.
2. Go to **School > Teachers** tab.
3. Find yourself on the teacher list. Teachers are listed alphabetically by the last name.
4. Click the icon  to view the account information.
5. Click **Reset password**.
6. A link to select a new password is sent to your email address.

Check your spam filter if the email cannot be found in the email inbox.

DELETING TEACHERS

If a teacher no longer works at your school, the teacher can be deleted from the web service.

1. Go to **School > Teachers** tab.
2. Find the teacher on the list. Teachers are listed alphabetically by the last name.
3. Click the icon  to delete the teacher.
4. Polar GoFit asks for a confirmation. Click **Delete** to confirm or **Cancel** to return to the previous view.
5. Repeat steps 2 to 4 to delete more teacher accounts.


 The courses created by a deleted teacher can be found in **Courses**. They can be accessed and edited by any teacher.

MONITORS

REGISTERING ACTIVITY MONITORS

It is recommended that the products are registered to the system before they are taken into use. Activity data cannot be transferred from the activity monitors to the web service before the monitors have been managed in the Polar GoFit web service. For information on activity monitors in the web service, see [Monitors in Polar GoFit](#).

1. Make sure you have Polar FlowLink data transfer unit plugged into a free USB port and Polar WebSync software installed on your computer. For more information see [Data transfer in activity monitoring](#).



2. Go to **School > Monitors** tab.
3. Click **Register monitors**.

4. Select a label/case (A-Z) for the activity monitor from the drop down list. The list tells how many activity monitors have already been registered for each label/case.




5. Click **Start**.
6. Place the first activity monitor on the FlowLink with the display facing down. Make sure the **Align** light is lit on the FlowLink.



7. WebSync prompts for Polar GoFit user credentials.
8. As soon as a green tick appears for the activity monitor in WebSync and the monitor appears in Polar GoFit, click **Start** in the web service and place another activity monitor on the FlowLink. Follow the

progress in WebSync.



9. Continue until you have registered all the monitors to the selected case.
10. Click **Finish** when you are done. The software redirects you back to the monitor list.

i Working with several activity monitors: When WebSync confirms with a green tick that the activity monitor is okay, leave the software running and place the next activity monitor on the FlowLink. If you accidentally closed WebSync, it prompts for the user credentials again when needed.


VIEWING ACTIVITY MONITORS


1. Go to **School > Monitors** tab.
2. The activity monitors that have been registered to the school are listed by the case. Expand a case by clicking to see the monitors in it.
3. The monitor list includes the following information:
 - which student the activity monitor is assigned to, and
 - how long the activity monitor is assigned to the student.

See also, [Registering activity monitors](#).

REMOVING ACTIVITY MONITORS

Activity monitors can be removed from the school. Only monitors that are not assigned to any student can be removed.

 Make sure you have transferred all the activity data from the activity monitor to the web service before removing the monitor from the school. See [Transferring activity data](#).

1. Go to **School > Monitors** tab.
2. The activity monitors that have been registered to the school are listed by case. Expand a case to see the monitors in it.
3. Click **Remove monitors**. The monitors that cannot be removed from school are marked with the red symbol . You cannot select them.
4. Select the activity monitors you wish to remove from the school. Click **Remove selected monitors**.
5. Polar GoFit asks for a confirmation. Click **Remove** to confirm or **Cancel** to return to the previous view.
6. Repeat steps 3 to 5 to remove more activity monitors.

If a monitor is assigned to a student, it cannot be removed. The reservation must be removed first. See [Viewing activity monitors](#) and [Reassigning activity monitors](#) for more information.

SENSORS

REGISTERING HEART RATE SENSORS

Heart rate sensors need to be registered to the system before they are taken into use. If the sensors have not been registered, heart rate data cannot be transferred from the sensors to the Polar GoFit app and Polar GoFit. For information on heart rate sensors in the web service, see [Sensors in Polar GoFit](#).

1. Make sure you have the numbered stickers available for numbering the sensors.
2. Go to **School > Sensors** tab.
3. Click **Register sensors**.
4. Type the sensor ID into the field and click **Add sensor**. A green tick appears next to the sensor ID to show that registration was successful.




A screenshot of a web form for registering a sensor. It consists of a text input field containing the sensor ID '000001'. To the left of the input field is the label '11.'. To the right of the input field is a green checkmark icon, indicating successful registration.

5. Label the sensor with the sticker that has the number appearing on the left side of the sensor ID. The registered sensor appears on the sensor list identified by this number.



A screenshot of the same sensor registration form as above. The number '11.' is circled in red, and a red arrow points from the circle to the input field, indicating that the user should use this number to label the sensor.

6. Repeat steps 4-5 to register more sensors.
7. Click **Finish** when you are done.

 If a student has purchased their own heart rate sensor to use instead of a school sensor, you need to [register the sensor ID](#) to the system in **School > Students**.


VIEWING HEART RATE SENSORS

1. Go to **School > Sensors** tab.
2. View the sensor list. The heart rate sensors that have been registered to the school are listed by number. The sensor list also shows how many reservations each sensor has, and which courses and students the sensor is assigned to.

See also [Registering heart rate sensors](#).

REMOVING HEART RATE SENSORS

Heart rate sensors can be removed from the school. Only sensors that are not assigned to any student can be removed.

1. Go to **School > Sensors** tab.
2. The heart rate sensors that have been registered to the school are listed by number. The sensor list also shows how many reservations each sensor has, and which courses and students the sensor is assigned to.
3. Click **Remove sensors**. The sensors that cannot be removed from school are marked with the red symbol . You cannot select them.
4. Select the heart rate sensors you wish to remove from the school. Click **Remove sensor**.
5. Polar GoFit asks for a confirmation. Click **Yes, remove** to confirm or **No** to return to the previous view.
6. Repeat steps 3 to 5 to remove more heart rate sensors.
7. Click **View sensors** to go back to the sensor list.

If a sensor is assigned to a student, it cannot be removed. The reservation must be removed first. See [Reassigning heart rate sensors](#) for instructions.


See also [Viewing heart rate sensors](#).

EVALUATION

CONFIGURING EVALUATION TYPES

For more information on the evaluation types in the Polar GoFit web service, see [Evaluation](#).

EDITING EVALUATION TYPES

1. Go to **School > Evaluation** tab.
2. Find the evaluation type on the list.
3. Click the icon  to edit the evaluation type.
4. Make the necessary changes. You can:
 - edit the grade names,
 - edit the grade limits (minimum and maximum limits), and
 - add new grades.
5. Click **Save** to save the changes. The software redirects you back to the evaluation type list.
6. Repeat steps 2 to 5 to edit more evaluation types.


ADDING EVALUATION TYPES

1. Go to **School > Evaluation** tab.
2. Click **Create new evaluation type**.
3. Give a name to the evaluation type.
4. Fill in and edit the evaluation type settings. You can:
 - edit the grade names,
 - edit the grade limits (minimum and maximum limits), and
 - add new grades.
5. Click **Save** to save the changes. The software redirects you back to the evaluation type list.
6. Repeat steps 2 to 5 to add more evaluation types.

DELETING EVALUATION TYPES

Only evaluation types that are not in use at the moment can be deleted from the web service.

1. Go to **School > Evaluation** tab.
2. Find the evaluation type on the list.

3. Click the icon  to delete the evaluation type.
4. The software asks for a confirmation. Click **Delete** to confirm or **Cancel** to return to the previous view.
5. Repeat steps 2 to 4 to delete more evaluation types.

LICENSE STATUS

VIEWING LICENSE STATUS

1. Go to **School > License status** tab.
2. View license status. The following information is shown:
 - Polar GoFit license information: whether or not license is active, possible license expiration date, number of teacher licenses (total number/number of licenses currently in use)
 - Activarium license information: whether or not license is active, possible license expiration date



FITNESS TESTS

 The fitness testing solution is still in beta phase and not yet available for all schools.

TEMPLATES

CREATING A TEMPLATE

To create a test, you need a template. Templates consist of test items, such as One-Mile Run or Shoulder Stretch. You can create a template yourself or use an existing template.

1. To create a template, go to **Fitness tests > Templates**.
2. Press **Create template**.
3. Type a descriptive name in the **Template name** field.
4. Select the [test items](#) that you want to include in your template. You can press the icon  for more information on a test item. In addition to a written description, you will see a useful video tutorial.
 In addition to the optional test items that you can choose, **Height & Weight** is included in each template by default. This is because students' height and weight influence the evaluation of their performance.
5. You can change the order of test items by dragging and dropping.
6. Press **Save** when you are done.
7. The web service asks you if you want to [create a test](#) right away. Press **Create test** or **Back to templates**.

You can [edit the template](#) later.

CREATING A TEST

When you create a test, you add students to a template. You can select the students either **From previous tests** or **From student list**.

STUDENTS FROM PREVIOUS TESTS

1. Go to **Fitness tests > Templates**.
2. Find the template on the list and press **Create test**.
3. Type a descriptive name for your test in the **Test name** field.
4. Choose a **Planned test date**.



5. Press **Add students**.
6. Press **From previous tests**.
7. Choose either **My tests** or **All tests**.
8. Choose a test from the drop-down list.
9. A list of students that took the test appears. Tick the first box to choose all the students. You can also choose students one by one.
10. Press **Save**.
11. You can still **Remove students** or **Add students**.
12. When your student configuration is ready, press **Save**.
13. The web service asks you if you want to start [entering the results](#) right away. Press **OK** to start entering the results, or press **Back to templates** if you want to enter the results later.

STUDENTS FROM STUDENT LIST


1. Go to **Fitness tests > Templates**.
2. Find the template on the list and press **Create test**.
3. Type a descriptive name for your test in the **Test name** field.
4. Choose a **Planned test date**.
5. Press **Add students**.
6. Press **From student list**.
7. A list of all students appears. Students are listed by class. Expand a class to see the students. Tick the box to choose a student or a class. The chosen students can be from different classes.
8. Press **Save**.
9. You can still **Remove students** or **Add students**.
10. When your student configuration is ready, press **Save**.
11. The web service asks you if you want to start [entering the results](#) right away. Press **OK** to start entering the results, or press **Back to templates** if you want to enter the results later.

EDITING A TEMPLATE

You can add or remove test items, change the order of test items, or rename the template.

1. Go to **Fitness tests > Templates**.
2. Find the template on the list and press the icon .
3. Press a test item to add it to the list of **Selected test items**.
4. Press the icon  to remove a test item from the list of **Selected test items**.
5. You can change the order of test items by dragging and dropping. You can also change **Template name**.
6. Press **Save** when you are done.
7. The web service asks you if you want to create a test right away. Press **Create test** or **Back to templates**.

REMOVING A TEMPLATE

1. Go to **Fitness tests > Templates**.
2. Press **Remove template**.
3. Find the template on the list and press the icon .
4. The web service asks for your confirmation. Press **Remove** or **Cancel**.

TESTS




ENTERING RESULTS

After you have created a test, you can start entering the results. You can use an iPad in the test situation and enter the results into the web service as testing proceeds. Or you can write the results by hand on printed result sheets, and enter them into the web service later.

You don't have to enter all the results into the web service at one go. You can interrupt any time and continue later.



START ENTERING RESULTS


1. Go to **Fitness tests > Tests**.
2. Find your test on the list of **Ready-to-start tests** and press **Enter results**.
3. On the **Preview** page, you can see the following information:
 - test name,
 - teacher,

- creation date,
 - chosen test items, and
 - chosen students.
4. On the **Preview** page, you can:
 - change the order of test items by dragging and dropping,
 - prepare for testing by watching the video tutorials that we've created for each test item (just press the icon  to see a written description and the video tutorial),
 - **Print result sheets.**
 5. If you need to make changes to the test, just press **Edit test** and you'll be able to change **Test name** and **Planned test date**. You can also **Remove students** or **Add students**.
 6. When you are ready to start, press **Enter results**.
 7. You can choose to enter results either by test item or by student. You can browse between the test items/students with the **Next**  and **Previous**  buttons. The results are saved automatically as soon as you enter them. You can watch the video tutorial for a test item at any time. Just press the video thumbnail under the name of the test item.
 8. To stop entering the results, press **Done**.
 9. If there are empty result fields, the web service asks you if you are done with entering the results or if you want to continue later. Press **Continue later**, **Test completed** or **Cancel**.

CONTINUE ENTERING RESULTS


You can continue entering the results any time.

1. Go to **Fitness tests > Tests**.
2. Find your test on the list of **Unfinished tests** and press **Enter results**.
3. You can choose to enter results either by test item or by student. You can browse between the test items/students with the **Next**  and **Previous**  buttons. The results are saved automatically as soon as you enter them. You can watch the video tutorial for a test item at any time. Just press the video thumbnail under the name of the test item.
4. To stop entering the results, press **Done**.
5. If there are empty result fields, the web service asks you if you are done with entering the results or if you want to continue later. Press **Continue later** or **Test completed** or **Cancel**.

 After you have completed the test and entered all the results into the web service, you can [view the results](#). It is also possible to [edit the results](#) if you notice a mistake.


EDITING A TEST

You can only edit **Ready-to-start tests**. If you have already started entering the results, it's no longer possible to edit the test.

1. Go to **Fitness tests > Tests**.
2. Find your test on the list of **Ready-to-start tests** and press **Enter results**.
3. On the **Preview** page, you can see the following information:
 - test name,
 - teacher,
 - creation date,
 - chosen test items, and
 - chosen students.
4. On the **Preview** page, you can:
 - change the order of test items by dragging and dropping,
 - prepare for testing by watching the video tutorials that we've created for each test item (just press the icon  for a written description and the video tutorial),
 - **Print result sheets**.
5. If you need to make changes to the test, just press **Edit test** and you'll be able to change **Test name** and **Planned test date**. You can also **Remove students** and **Add students**.
6. Make your changes and press **Save**.
7. The web service asks you if you want to start [entering the results](#) right away. Press **OK** to start entering the results, or press **Back to templates** if you want to enter the results later.




REMOVING A TEST


You can only remove **Ready-to-start tests**. If you have already started entering the results, it's no longer possible to remove the test from the web service.

1. Go to **Fitness tests > Tests**.
2. Press **Remove tests**.
3. Find your test on the list of **Ready-to-start tests** and press the icon .
4. The web service asks for your confirmation. Press **Remove** or **Cancel**.

RESULTS




VIEWING RESULTS

1. Go to the **Fitness tests > Results**.
2. Find your test on the list of **Completed tests** and press the icon .
3. You can view the results either by test item or by student. You can browse between the test items/students with the **Next**  and **Previous**  buttons.

 After a test has been completed and you have entered all the results into the web service, it is still possible to [edit the results](#) if you notice a mistake.

EDITING RESULTS

After a test has been completed and you have entered all the results into the web service, it is still possible to edit the results if you notice a mistake.

1. Go to the **Fitness tests > Results**.
2. Find your test on the list of **Completed tests** and press the icon .
3. You can view the results either by test item or by student. You can browse between the test items/students with the **Next**  and **Previous**  buttons.
4. Press **Edit results**.
5. Make the changes. The changes are saved automatically as soon as you enter them.
6. Press **Done**.

REPORTS

GETTING STUDENT RESULTS REPORT

1. Go to **Fitness tests > Reports**.
2. Select **Student results**.
3. Select either **PDF** or **XLS**.
4. Use the search and filtering options to find the students whose results you want to include in the report.
5. Select the students whose results you want to include in the report. At least one student must be selected.
6. Press **Create report**.

Unfinished tests can't be included in reports.

GETTING TEST RESULTS REPORT

1. Go to **Fitness tests > Reports**.
2. Select **Test results**.
3. Use the search and filtering options to find the tests and students that you want to include in the report.
4. Select the tests and students that you want to include in the report. At least one student must be selected.
5. Press **Create report**.

Unfinished tests can't be included in reports.

GETTING SCHOOL RESULTS REPORT

You can use the **School results** report to create different kinds of reports for different purposes. You can decide the content of your report by choosing specific values, such as date range, age range, sex, and test items.

1. Go to **Fitness tests > Reports**.
2. Select **School results**.
3. You can narrow down your report by choosing:
 - start date,
 - end date,

- sex, and
- age range.

4. Choose the test items that you want to include in the report. At least one test item must be selected.

5. Press **Create report**.

TROUBLESHOOTING

The following troubleshooting applies for both Windows and Mac OS users.

Always make sure:

- you have installed all the available updates for your operating system,
- you have installed all the available updates for your browser,
- you have installed all the available driver updates for the hardware.

POLAR GOFIT SIGN-IN PAGE DOES NOT LOAD

Make sure:

- you are using the Polar GoFit home page for signing in (www.polargofit.com),
- you are connected to the internet (contact the school's IT administrator for help),
- you are using a compatible internet browser (Microsoft Internet Explorer 8 or newer, Apple Safari 4 or newer, Mozilla Firefox 3 or newer, Google Chrome 12.0.1271.97m or newer), and
- your browser's proxy settings are set correctly (contact the school's IT administrator for help).

I AM UNABLE TO SIGN IN TO POLAR GOFIT

Make sure:

- you are using the Polar GoFit home page for signing in (www.polargofit.com),
- you are using the correct user credentials,
- you are connected to the internet (contact the school's IT administrator for help),
- you are using a compatible internet browser (Microsoft Internet Explorer 8 or newer, Apple Safari 4 or newer, Mozilla Firefox 3 or newer, Google Chrome 12.0.1271.97m or newer), and
- your browser's proxy settings are set correctly (contact the school's IT administrator for help).

IMPORTANT INFORMATION

MEDICAL DEVICES IN PROFESSIONAL USE

Professional use sets high standards for the manufacturer, distributor and user of a medical device. Polar offers user instructions and training for professional users in order to ensure the safe use of Polar devices.

PRECAUTIONS

Polar GoFit web service is designed to enable:

- tracking and documenting students' daily activity and time spent in different activity zones,
- tracking and documenting students' heart rate during PE lessons and the time spent in different heart rate zones,
- fitness testing and documenting test results.

No other use is intended or implied.

MINIMIZING POSSIBLE RISKS

Physical activity and exercising may include some risks. Before beginning a regular exercise program, answer the following questions concerning your health status. If you answer yes to any of these questions, consult a physician before starting any exercise program.

The following questions are for children:

- Have you been physically inactive?
- Do you have symptoms of any disease?
- Are you taking heart or any other medication?
- Do you have a history of breathing problems?
- Are you recovering from a serious illness or medical treatment?
- Do you use a pacemaker or other implanted electronic device?

If you feel unexpected pain or excessive fatigue when exercising, stop the exercise or continue at a lighter intensity.

If you are allergic to any substance that comes into contact with your skin or if you suspect an allergic reaction due to using the product, check the listed materials in the Technical Specifications of the Polar Active activity monitor or the Polar heart rate sensor.

COPYRIGHT

Copyright © 2014 Polar Electro Oy, FIN-90440 KEMPELE. All rights reserved. No part of this manual may be used or reproduced in any form or by any means without prior written permission of Polar Electro Oy.

DISCLAIMER

The material in this manual is for informational purposes only. The products it describes are subject to change without prior notice, due to the manufacturer's continuous development program.

Polar Electro Inc./Polar Electro Oy makes no representations or warranties with respect to this manual or with respect to the products described herein.

Polar Electro Inc./Polar Electro Oy shall not be liable for any damages, losses, costs or expenses, direct, indirect or incidental, consequential or special, arising out of, or related to the use of this material or the products described herein.

The *Bluetooth*® word mark and logos are registered trademarks owned by Bluetooth SIG, Inc. and any use of such marks by Polar Electro Oy is under license.