TV EXPLORER // / // +

REMOTE CONTROL USB COMMANDS



SAFETY NOTES

Read the user's manual before using the equipment, mainly " SAFETY RULES " paragraph.

The symbol on the equipment means "SEE USER'S MANUAL". In this manual may also appear as a Caution or Warning symbol.

Warning and Caution statements may appear in this manual to avoid injury hazard or damage to this product or other property.

TABLE OF CONTENTS

RE	MOTE CONTROL WITH A PC	. 1
1.1	Introduction	. 1
	Protocol for communication between the TV EXPLORER // / //+ and a PC	
	Power on using USB port	
	Remote orders	3



REMOTE CONTROL USB COMMANDS

TV EXPLORER // // +

1 REMOTE CONTROL WITH A PC

1.1 Introduction

The design of **TV EXPLORER !/ !!** +, based on a microprocessor, allows data to be exchanged between the equipment and a remote controller (personal computer) via an USB connector. It is thus possible to obtain data as well as remote control of the **TV EXPLORER !! / !!** + (measurement mode, video format, DATALOGGER status, etc.) for maintenance purposes and monitoring of installations.

1.2 Protocol for communication between the TV EXPLORER // // + and a PC

This protocol is controlled by software and is using a virtual serial port over an USB interface. Data and information are exchanged using messages consisting of ASCII alphanumerical characters. This method ensures easy carrying between different types of personal computers.

To activate the virtual serial port, a special driver must be installed. The driver is included with the purchased instrument.

Connections

The cable between the TV EXPLORER || / || + and the PC must be a standard A to B type USB cable PROMAX reference CC-040 or equivalent.



Figure 1.- USB A-B standard connection cable.

09/2007 Page 1



The **TV EXPLORER** #/ # + accepts remote commands at any time, which the instrument is on, except when in print mode. That is, it is not necessary to put the instrument in special remote control mode; rather, this mode is selected immediately when it detects a complete command during the time necessary for its execution.

The communication protocol is as follows:

- 1.- TV EXPLORER || / || + transmits a XON code (11H) every second. The aim is to indicate to any possible remote device that the equipment is ready to receive data.
- At this moment, data streams can be sent it. Each data stream is composed by:
 - a. Stream beginning: '*' (code 2AH)
 - b. Set of characters that describe data message.
 - c. CR (carriage return, code 0DH)
- Once a data stream has been sent, will be received a XOFF (code 13H) indicating that the transmission is stopped
- 4.- Next, in case of correct message an ACK (acknowledge, code 06H) is expected or a NAK (not acknowledge, code 15H) in the opposite case.
- 5.- If the sent message requires answers it will be sent at this moment.
- 6.- Once completed the data stream transmission, the TV EXPLORER || / || + will send a XON (code 11H) indicating that already it is prepared to receive a new data stream.

A typical communication chronogram would be as follows:

	PC (REMOTE CONTROLL	TV EXPLORER / +	
1)		<	XON
2)	*?TV <cr></cr>	>	
3)		<	XOFF
4)		<	ACK
5)		<	*TV0 <cr></cr>
6)	wait		
7)		<	XON

(all characters are transmitted in ASCII code)

In print mode, as the same port is used as for the data dump to the printer, all data received is rejected and no XON character is transmitted until leaving this mode.

Commands should always be sent in capital letter and cannot be edited online, i.e., once a character is received it is stored in the **TV EXPLORER // // // +** buffer and cannot be rectified by sending an erase code.

Page 2 09/2007

Commands in remote control are divided in to two groups, orders and interrogations. Orders modify a variable or the equipment status. Interrogations respond with information concerning equipment status or the value of a variable. For interrogative command, it is necessary to add the character '?' after the character '*.

1.3 Power on using USB port

The equipment can start up being stopped, by means of the USB port. Following the steps:

- 1.- Send 5 asterisks. '*****'
- 2.- Wait for 1 second.
- 3.- Send '**'

Next, will be described the set of commands that the TV EXPLORER || / || + accepts. All commands are transmitted in ASCII code.

1.4 Remote commands

- **NOTE 1:** The (') character should not be sent; it is only included in the description in order to define the string that makes up the remote command.
- NOTE 2: The values given in small letter are parameters that change in value depending on the function to be executed. These values are always decimal or hexadecimal ASCII characters. For example, to transmit the value '1', we must send the hexadecimal code 31 that corresponds to this character. Consult the text for acceptable value margins. The transmission of erroneous parameters or contradictory information may cause TV EXPLORER || / || + to stop operating correctly. In this case, it is necessary to reset the equipment by shortly switching it off.

IMPORTANT REMARK:

In the case of transmitting to the TV EXPLORER II a command corresponding to some **nonavailable function**, this one will generate a run time error.

09/2007 Page 3



Command: '*' NULL Command. Tests communication.

Syntax:

Interrogation: '*<CR>'

Response: 'ACK'

Command: 'Al' Interrogates if the program is auto-identifying some

signal or not.

Syntax:

Interrogation: '*?AI<CR>'

Response: '*Alx<CR>'

Where:

x =

0: Not carrying out auto-identification.1: Auto-identification in progress.

Command: 'AP' Activates / deactivates the Auto Power Off function. Also, it allows to set the timer for this function.

Syntax:

Selection: '*APsxxxx<CR>'

Where:

s =

'A': Turns on the Auto Power Off function.
'M': Turns off the Auto Power Off function.

'T': Allows to modify the Auto Power Off timer when this

function is activated.

xxxx = Time in minutes to Power Off.

Example:

**APA<CR>'

*APM<CR>'

*APMOI0<CR>'

*APT0010<CR>'

*APT0010<CR>'

*APT0010<CR>

*APT0010<CR>

*APT0010<CR>

*APT0010<CR>

*APT0010<CR>

*APT0010<CR>

*APT0010<CR>

*APT0010<CR>

*APT0010<CR

*APT0010<CR>

*APT0010<CR

*APT0010<CR

*APT0010<CR

*APT0010<CR

*APT0010<CR

*APT0010

*APT0

Page 4 09/2007

Command: 'AT' Selects / interrogates the attenuators

Syntax:

Attenuator selection: '*ATa<CR>'

Interrogation: '*?AT<CR>'

Response: '*ABba<CR>'

Where:

b =

A: Auto
M: Manual

a =

00: 0dB 10: 10dB 20: 20dB 30: 30dB 40: 40dB 50: 50dB 60: 60dB

Example:

'*?AT<CR>'

'***ATM40<CR>**' Manual attenuator value = 40 dB.

'***ATA20**<**CR**>' Automatic attenuator current value = 20 dB.

Note: When the attenuators are set to manual also is operative in the spectrum analyser mode. Therefore, whether the reference level is modified the attenuator remains unchanged.

inglish

09/2007 Page 5



 Command: 'AU'
 Selects the type of signal to be identified in terrestrial and satellite bands when the auto-identification process

is carried out.

Syntax:

Selection: '*AUbs<CR>'

Where:

b =

'T': Terrestrial identification.
'S': Satellite identification.

s =

'C': COFDM signal will be identified.

'Q': Satellite identification.

Example:

'*AUTC<CR>' Sets COFDM as signal to identify.

• Command: 'BW' Selects / interrogates the measurement filter bandwidth.

Syntax:

Interrogation: '*?BW<CR>'

Response: '*BWxxxxx<CR>'

Selection of the bandwidth: '*BWxxxxx<CR>'

Where:

xxxxx = bandwidth in kHz

Page 6 09/2007

Provides the CBER measurement value. If the instrument is not configured to measure CBER, then it will be return

NACK.

'*?CB<CR>' Syntax:

Response: '*CBcsm₂m₁Ese₁e₂<CR>'

Where:

Command: 'CB'

c =

" =": Correct measurement

" >": Overrange " <": Underrange

"!": Measurement can not be carried out.

s =

Positive value measurement. Negative value measurement.

Mantissa decimal value. $m_2 m_1 =$

m₂: High nibble. Low nibble. m_1 :

E = Exponent **e**₁**e**₂ = Exponent value

Example:

'*?CB<CR>'

'*CB=+12E-07<CR>'

Command: 'CN' Provides the C/N measurement value. If the instrument is not configured to measure C/N, then it will be return

NACK.

'*?CN<CR>' Syntax:

Response: '*CNcsl₂l₁l₀<CR>'

Where:

c =

Correct measurement

" >": Overrange " <": Underrange

"!": Measurement cannot be carried out.

s =

" +": Positive value measurement. " –": Negative value measurement.

Measurement in dB decimal notation. $|_{2}|_{1}|_{0}=$

High nibble. l₂: Low nibble.

09/2007 Page 7



• Command: 'CO' Provides / Configures the instrument current constellation.

Syntax:

Interrogates about constellation: '*?CO<CR>'

Response / Configures: '*COxx<CR>'

Where:

xx =

'0': QPSK COFDM

- '1': 16QAM COFDM
- '2': 64QAM COFDM
- '3': 16QAM QAMA
- '4': 32QAM QAMA
- '5': 64QAM QAMA/QAMB
- '6': 128QAM QAMA
- '7': 256QAM QAMA/QAMB
- '8': QPSK DVB-S/DSS/DVB-S2
- '9': 8PSK DVB-S2
- Command: 'CP' Selects a channel plan.

Syntax:

Selection: '*CPTypeName<CR>'

Where:

Type = Two chars

- '00': Terrestrial channel plan as reference. Cannot be removed.
- '01': Read only terrestrial channel plan. Cannot be removed.
- '02': Read/write terrestrial channel plan. Can be modified and
 - removed.
- '03': Satellite channel plan as reference. Cannot be removed.
- '04': Read only satellite channel plan. Cannot be removed.
- '05': Read/write satellite channel plan. Can be modified and
 - removed.

Name = Channel plan name. Max. 12 chars.

Example:

'*CP04EUT13-HH<CR>' Selects EUT13-HH as satellite channel plan.

Page 8 09/2007

• Command: 'CR' Selects / Interrogates the code rate. When the instrument is working in a mode with no sense will return NACK.

Syntax:

Code rate interrogation: '*?CR<CR>'

Response: '*CRxx<CR>'

Code rate selection: '*CRxx<CR>'

Where:

xx =
 '00': 1/2
 '01': 2/3
 '02': 3/4
 '03': 4/5
 '04': 5/6
 '05': 6/7
 '06': 7/8
 '07': 1/4
 '08': 1/3
 '09': 2/5
 '10': 3/5
 '11': 8/9

'**12**': 9/10

Command: 'DS' Sends the DiSEqC program commands.

Syntax:

Selection: '*DSnameprogram<CR>'

Where:

nameprogram = Name of the DiSEqC program to send

Example:

'*DSSAT A<CR>' Sends the "SAT A" program.

nglish

09/2007 Page 9



• Command: 'EM' Selects the equipment operating mode. The equipment can operate in the following modes:

- NULL Stand by to attend remote control commands

- TV TV receiver showing pictures

- SIG. ANALYSER Signal TV analyser
- SPECTRUM Spectrum analyser
- ANTENNA Antenna alignment
- IDENTIFY Signal identification
- CONSTEL. Constellation diagram

Syntax:

Selection: '*EMm<CR>'

Where:

m =

'0': NULL task.

'1': TV.

'2': SIGNAL ANALYSER.

'3': SP.

'4': ANTENNA ALIGNMENT.

'5': IDENTIFY.

'9': MODE CONSTELLATION.

Example:

'*?EM<CR>' Interrogates the current equipment mode.

'***EM1<CR>**' Answer is TV mode.

• Command: 'FM' Provides the FM deviation measurement value.

Syntax: '*?FM<CR>'

Response: '*FMcsl₂l₁l₀<CR>'

Where:

c =

" =": Correct measurement

" >": Overrange " <": Underrange

"!": Measurement cannot be carried out.

s =

" +": Positive value measurement.
" -": Negative value measurement.

 $I_2I_1I_0$ = Measurement in kHz decimal notation.

 I_2 : High nibble. I_0 : Low nibble.

Page 10 09/2007

 Command: 'FR' Selects / interrogates the frequency (with the consequent change).

Syntax:

Frequency selection: '*FRxxxxxxx<CR>'

Frequency interrogation: '*?FR<CR>'

Response: '*FRxxxxxxxCR>'

Where:

xxxxxxx = 7 digits value in kHz decimal notation that represents

the frequency to synthesise.

Example:

'*FR0655250<CR>' Synthesises the 655.25 MHz frequency.

 Command: 'GI' Selects / interrogates the Guard Interval. When the instrument is working in a mode with no sense will return

NACK.

Syntax:

Guard Interval interrogation: '*?GI<CR>'

Response: '*Glx<CR>'

Selection: '*Glx<CR>'

Where:

x =

'0': 1/4 '1': 1/8 '2': 1/16 '3': 1/32

09/2007 Page 11



Command: 'LA' Selects the operating language.

Syntax:

Selection: '*LAxx<CR>'

Where:

xx =

- '1': English
- '2': Spanish
- '3': French
- '4': German
- '5': Italian
- '6': Catalan
- '7': Russian
- '8': Portuguese
- 'FF': Language will be marked as not initialised, and when booting will appear the language selection screen.
- Command: 'LV' Provides the absolute level, filtered and compensated, in dBμV decimal notation (for LEVEL and DIGITAL measurement modes) and in dB decimal notation (for VIDEO / AUDIO and CARRIER / NOISE measurement modes).

Syntax:

Command: '*?LV<CR>'

Response: $^{\prime *}LVcsl_2l_1l_0< CR>^{\prime }$

Where:

c =

- =': Correct measurement
- '>': Overrange
- '<': Underrange
- !': Measurement can not be carried out

s =

- +': Positive measurement
- '-': Negative measurement
- $\textbf{I}_2\textbf{I}_1\textbf{I}_0$: Decimal measurement in $dB\mu V$ decimal notation.

09/2007

I₂: High nibble

 I_0 : Low nibble

Page 12

The command measurement return corresponds to the measurement configuration settings as a result of executing the $\boldsymbol{\mathsf{MC}}$ command. The return value is according the following table:

ANALOGUE TERRESTRIAL				
LEVEL	AUDIO	NOISE	*?LV	
Activated	Activated	Activated	Returns video carrier in dBµV decimal notation.	
Deactivated	Activated	Activated	Returns audio carrier in dBµV decimal notation.	
Deactivated	Deactivated	Activated	Returns noise measurement	
DIGITAL TERRESTRIAL				
LEVEL		NOISE	*?LV	
Activated		Activated	Returns main carrier in dB _µ V decimal notation.	
Deactivated		Activated	Returns noise in dB _µ V decimal notation.	
DIGITAL SATELLITE				
LEVEL		NOISE	*?LV	
Activated		Activated	Returns main carrier in dB _µ V decimal notation.	
Deactivated		Activated	Returns noise in dBµV decimal notation.	
ANALOGUE SATELLITE				
LEVEL		NOISE	*?LV	
Activated		Activated	Returns video carrier in dBµV decimal notation.	
Deactivated		Activated	Returns noise in dB _µ V decimal notation.	

Command: 'LB' Selects the external unit power (LNB).

Syntax:

Voltage selection: '*LBI<CR>'

Where:

I =

0: ΕX 1: 5 V 13 V 2: 3: 15 V 4: 18 V 5: 24 V

13 V + 22 kHz 6: 18 V + 22 kHz

Example: '*LB0<CR>' Selects the external power supply

Page 13 09/2007



Command: 'ME' Provides the MER measurement value. If the instrument

is not configured to measure MER, then it will be return

NACK.

'*?ME<CR>' Syntax:

Response: $'*MEcsl_2I_1I_0<CR>'$

Where:

c =

" =": Correct measurement

" >": " <": Overrange

Underrange

Measurement cannot be carried out.

s =

Positive value measurement.

Negative value measurement. $|_{2}|_{1}|_{0}=$ Measurement in dB decimal notation.

High nibble. l₂: Low nibble.

Selects / interrogates the COFDM carrier number. When Command: 'MO'

the instrument is working in a mode with no sense will

return NACK.

Syntax:

Carrier number interrogation: '*?MO<CR>'

Response: '*MOx<CR>'

Selection: '*MOx<CR>'

Where:

x =

'O': 2k 8k **'2**': 4k

09/2007 Page 14

Command: 'NA' Returns the name of the equipment.

Syntax:

Interrogation : '*?NA<CR>'

Response: '*NA"INSTRUMENT_NAME"<CR>'

Example:

(PC) '*?NA<CR>'

(Instrument) **NA TVEXPLORERII<CR>

Command: 'NI' Interrogates the value of the external unit current (LNB).

Syntax:

Interrogation: '*?NI<CR>'

Response: $"NI I_3I_2I_1I_0 < CR>"$

Where:

I = external unit current in mA, in decimal notation.

 $\mathbf{d_3}$: High nibble $\mathbf{d_0}$: Low nibble

• Command: 'NL' Interrogates the value of the external unit voltage (LNB).

Syntax:

Interrogation: '*?NL<CR>'

Response: $^{\prime *}NL \ l_2 l_1 l_0 < CR > ^{\prime \prime}$

Where:

I = External unit voltage in tens of volts.

I₃: High nibble **I**₀: Low nibble

Command: 'OF' Turns off the unit.

Note: The instrument cannot be turned on remotely.

Syntax:

Selection: '*OF<CR>'

09/2007 Page 15



Command: 'RA' Selects / interrogates the Symbol Rate. When the instrument is working in a mode with no sense will return NACK.

Syntax:

'*?RA<CR>' Interrogation:

Response: '*RAxxxxx<CR>'

Selection: '*RAxxxxx<CR>'

Where:

Symbol Rate in kbps xxxxx =

Command: 'SA' Selects / interrogates the measurement type to analyse

(signal analyser).

Syntax:

Signal analyser interrogation: '*?SA<CR>'

Response: '*SAs<CR>

Selection: '*SAs<CR>'

Where:

'**0**': ANALOGUE

'1': '2': COFDM

QAM-A

'**3**': QPSK **'4**': DSS

'**5**': 8VSB

'**6**': QAM-B

'**7**': DVB-S2

'**8**': FΜ

Page 16 09/2007 Command: 'SC' Selects the SCART operating mode.

Syntax:

Selection: '*SCx<CR>'

Where:

x =

'I': Input mode
'O': Output mode
'A': Automatic mode

Example:

'*SCI<CR>' Selects SCART input mode.

• Command: 'SI' Selects / interrogates the Spectral Inversion.

Syntax:

Spectral Inversion interrogation: '*?SI<CR>'

Response: '*SIx<CR>'

Spectral Inversion selection: '*SIx<CR>'

Where:

x =

'0': OFF

Command: 'SL'
 Selects / interrogates information about a service from service

| Selects / Interrogates information about a service from service
| Selects / Interrogates information about a service from service
| Selects / Interrogates information about a service from service
| Selects / Interrogates information about a service from service
| Selects / Interrogates information about a service from service
| Selects / Interrogates information about a service from service
| Selects / Interrogates information about a service from service
| Selects / Interrogates information about a service from service | Selects / Interrogates | Sel

list. (Digital mode)

Syntax:

Service selection: $^{\prime *}$?SLn₁n₀<CR> $^{\prime *}$

Where:

 N_1N_0 : Last service number in hexadecimal notation.

 n_1n_0 : Number of service sorted from DVBNET service list in

hexadecimal notation. (First service from list is '00')

 n_1 : High nibble. n_0 : Low nibble.

Current service interrogation: '*?SL<CR>'

Response: '*SLn₁n₀<CR>'

09/2007 Page 17



Where:

 $n_1 n_0$: Number of service sorted from DVBNET service list in

hexadecimal notation, currently selected. (First service from

 \mathbf{n}_1 : High nibble. \mathbf{n}_0 : Low nibble.

General service interrogation: $^{\prime*}$?SLn₁n₀<CR> $^{\prime}$

Where:

 $n_1 n_0$: Number of service sorted from DVBNET service list in

hexadecimal notation. (First service from list is '00')

n₁: High nibble.n₀: Low nibble.

Response: ${}^{'*}SLN_1N_0n_1n_0SbL_1L_0$ [service name] L_1L_0 [provider name] <CR> $^{'}$

Where:

 N_1N_0 : Number of services.

Particular case: N_1N_0 ='!!' or '00' indicates that the

adquisition process of service list has not finalized.

 $\mathbf{n_1}\mathbf{n_0}$: Last service number in hexadecimal notation.

(First service from list is '00')

 n_1 : High nibble. n_0 : Low nibble.

 L_1L_0 : Indicates the following field size in hexadecimal notation.

[service name]= ASCII character string with the service

name.

[provider name]= ASCII character string with the provider

name.

S: Service type indication.

b ='**0**': Service without video nor audio contents.

b ='1': Service with video and/or audio contents.

 $\mathbf{b} = \mathbf{2}$: Service with video and/or audio contents but one or all

are encrypted.

b ='!': Video/Audio detection process in progress.

Page 18 09/2007



Command: 'SLC' Returns the percentage of MPEG-2 service list capture.
 Read only command.

Syntax:

Interrogation: '*?SLC<CR>'

Response: '*SLCc₁c₀<CR>'

Where:

 $\mathbf{c_1}\mathbf{c_0} =$ Percentage in hexadecimal notation.

'00': Turns on the Auto Power Off function.
'0x64': Turns off the Auto Power Off function.

If any type of problem occurs during the capture process this indication could back to '00' and begins afresh.

• Command: 'SR' Selects the spectrum reference level.

Syntax:

Selection: '*SRx<CR>'

Where:

x = Reference level value in dB.

Example:

'*SR120<CR>' Selects a reference level of 120 dB.

• Command: 'SS' Selects the span in the spectrum analyser mode.

Syntax:

Selection: '*SRx<CR>'

Where:

x = Span value in MHz.

'X': FULL

Example:

'*SS100<CR>' Selects a 100 MHz span. '*SSFULL<CR>' Selects a FULL span.

09/2007 Page 19



Command: 'ST' Provides the digital demodulator current status.

Syntax:

Interrogation: '*?ST<CR>'
Response: '*STx<CR>'

Where:

x =

'O': No locked **'1**': Locked DVB-T **'2**': Locked DVB-H '**3**' : Locked 8-VSB **'4**': Locked QAMA '**5**' : Locked QAMB '**6**': Locked DVB-S **'7**' : Locked DVB-DSS **'8**' : Locked DVB-S2 **'9**': Locked 8-VSB

• Command: 'SY' Selects / Interrogates the TV system (standard + colour).

Syntax:

Standard selection: '*SYys<CR>'

Note: When the instrument is in digital mode, the standard must be 0x0 (hex.)

Example in digital mode:

'*\$Y00<CR>'
'*\$Y10<CR>'
'*\$Y10<CR>'
'*\$Y20<CR>'
'*SY20<CR>'

'*SY11<CR>' Error due to BG does not exist in DIGITAL.

Example in analogue mode: '*SY11<CR>' Se

'*SY11<CR>'
Selects the SECAM + BG.
'*SY24<CR>'
Selects the NTSC + M.

'*SY10<CR>' Error due to standard is necessary in analogue mode.

Note: When the instrument is in analogue satellite digital mode, cannot be programmed system and standard.

Standard interrogation: '*?SY<CR>'

Response: '* SYys<CR>'

Page 20 09/2007

Where:

ys = (standard in hexadecimal notation)

0x00: (00 dec) PAL WITHOUT TV STANDARD
0x01: (01 dec) PAL_BG
0x02: (02 dec) PAL_DK
0x03: (03 dec) PAL_I
0x04: (04 dec) PAL_M

0x05: (05 dec) PAL_N 0x10: (16 dec) SECAM WITHOUT TV STANDARD

0x11: (17 dec) SECAM_BG 0x16: (22 dec) SECAM_L 0x12: (18 dec) SECAM_DK

0x20: (32 dec) NTSC WITHOUT TV STANDARD

0x24: (36 dec) NTSC_M

Example:

'***SY16<CR>**' Selects the SECAM_L standard.

 Command: 'VB'
 Provides the VBER measurement value. If the instrument is not configured to measure VBER, then it will be return

NACK.

Syntax: '*?VB<CR>'

Response: '*VBcsm₂m₁Ese₁e₂<CR>'

Where:

c =

" =": Correct measurement

" >": Overrange " <": Underrange

"!": Measurement cannot be carried out.

s =

' +": Positive value measurement.
' -": Negative value measurement.

 $m_2m_1 =$ Mantissa decimal value. m_2 : High nibble.

 $\begin{array}{ccc} & & m_1 \colon & \text{Low nibble.} \\ \textbf{E} = & & \text{Exponent} \\ \textbf{e}_1 \textbf{e}_2 = & & \text{Exponent value} \end{array}$

Example:

'*?VB<CR>'

'*VB=+12E-07<CR>'

09/2007 Page 21

'*VFx<CR>'



• Command: 'VE' Returns the version.

Syntax:

Interrogation : '*?VE<CR>'

Response: '*VE"STRING_VERSION"<CR>'

Example:

(PC) '*?VE<CR>' (Instrument) '*VE V1.13<CR>'

Command: 'VF' Selects / interrogates the video format.

Syntax:

Interrogation: '*?VF<CR>'
Response: '*VFx<CR>'

Where:

x =

Selection:

'**0**': 4:3 '**1**': 16:9 '**A**': Automatic

REMARK

The **TV EXPLORER || / ||** + incorporates a system to detect incompatible functions and so it only will accept the functions described in this paragraph if they are compatible with its state. In this case you will obtain as answer a NOT ACKNOWLEDGE' code.

Commands version: v1.05

Page 22 09/2007