



Title: Interfacing Gocator 4.x firmware to Common Vision Blox
Revision: 1.0

Table of Contents

1 Overview 2
2 Verifying the Connection Between the Gocator and CVB 3
3 Verifying the Connection Between Sherlock and CVB 6
4 Profile Mode Operation 8



1 Overview

Common Vision Blox (CVB) is an open architecture, hardware independent toolkit for 3D image processing. Gocator includes a GenTL driver that can be used to stream 3D height map and intensity images into CVB in real-time.

Sherlock is an advanced machine vision software interface that can be applied to a wide variety of automated inspection applications. Sherlock can communicate to the Gocator via the Sherlock CVB driver.

This document assumes that CVB is already installed. If Sherlock is used, the document assumes that the Sherlock CVB driver and Sherlock are installed.

Refer to the *GenTL* chapter in the Gocator's User Manual on how to install and setup the Gocator GenTL driver. This document describes how to verify that CVB and Sherlock are properly connected to the Gocator. Users are assumed to be already familiar with the operation of the Gocator Whole Part mode.


Require Gocator 2 or 3 series, Gocator firmware 4.0.9.136 or later, Common Vision Blox 2011 or later. If interfacing to Sherlock, require Sherlock 7 or later and Sherlock CVB driver.




2 Verifying the Connection Between the Gocator and CVB

Follow the steps below to setup CVB with Gocator for the first time:

1. Connect a Gocator to the PC running CVB.
2. Power up the Gocator and put the Gocator into Surface scan mode and enable Acquire Intensity if intensity data is required.




3. Configure sensors to produce the desired surface data and enable the Ethernet output.



4. Start the CVB Management Console.



5. Click GenICam at the bottom right corner.







6. Select Device Configurator.

Detected Gocators will be listed in the Configured Device table. The Gocator must be running and connected to the PC for this step to be successful.

If no device is detected, select Advanced Config, select the LMI sensor from the list in the left and click ">>" to assign a Gocator to the CVB camera port.




When a Gocator is detected, the device shows up in the Configured Device list.





7. Check Grab box to start data capturing.
8. Trigger the Gocator to output a part object. The method to trigger the Gocator depends on the Gocator setup.
The output will be displayed in the Preview Window.



An acquisition timeout error might display periodically if the Gocator is put into encoder trigger mode and there is no parts scanned for a period of time.


User can configure the acquisition timeout under Settings and Information->General Settings.

3 Verifying the Connection Between Sherlock and CVB

1. Shut down CVB Management Console.
2. The camera port in the file *CVBDrv.ini* (normally under *C:\Program Files\lpd\Sherlock\Drivers*) should point to *GenICam.vin*, as shown below.


```
[Camera0]
Driver = %CVB%\Drivers\GenICam.vin
CameraPort = 0
```

3. Start Sherlock.




It is normal to see an Acquisition Failed error in the Monitor window.

4. Select Image Window -> Options
5. Check the box "On acquisition timeout: Skip execution of this "image window" and continue executing program without a timeout error". Close the dialog box.




This setting prevents Sherlock from executing the program when an acquisition is timed out. Acquisition timeout is normal when no parts are detected.

6. Press the Run Continuously button to begin acquisition.



7. Trigger the Gocator to generate a part height map. The height map should be displayed in the image window.



4 Profile Mode Operation

Gocator 4.x GenTL driver does not yet support scanning with profile mode. The support will be added in future release.