


**ELTEC**

systems

# P3I3 Frame Grabber Family



**p3i\_DIG, p3i\_CL, p3i\_CL/PMC Manual**

**Revision 2B**

---

---

---

Revision Info		
2B	new icons, 64 bit support	dpe
2A	p3i_CL/PMC added	ew, dpe
1A	First edition	ew, dpe

Copyright © 2001-2011 ELTEC Elektronik AG

---

---

# 1. DISCLAIMER

## Copyright

© 2011 ELTEC Elektronik AG. The information, data, and figures in this document including respective references have been verified and found to be legitimate. In particular in the event of error they may, therefore, be changed at any time without prior notice. The complete risk inherent in the utilization of this document or in the results of its utilization shall be with the user; to this end, ELTEC Elektronik AG shall not accept any liability. Regardless of the applicability of respective copyrights, no portion of this document shall be copied, forwarded or stored in a data reception system or entered into such systems without the express prior written consent of ELTEC Elektronik AG, regardless of how such acts are performed and what system is used (electronic, mechanic, photocopying, recording, etc.). All product and company names are registered trademarks of the respective companies.

Our General Business, Delivery, Offer, and Payment Terms and Conditions shall otherwise apply.

## Federal communications commission statement

- This device complies with FCC Rules Part 15. Operation is subject to the following two conditions:
  - This device may not cause harmful interference, and
  - This device must accept any interference received including interference that may cause undesired operation.
  - This equipment has been tested and found to comply with the limits for a Class B digital device, pursuant to Part 15 of the FCC Rules. These limits are designed to provide reasonable protection against harmful interference in a residential installation. This equipment generates, uses and can radiate radio frequency energy and, if not installed and used in accordance with manufacturer's instructions, may cause harmful interference to radio communications. However, there is no guarantee that interference will not occur in a particular installation. If this equipment does cause harmful interference to radio or television reception, which can be determined by turning the equipment off and on, the user is encouraged to try correct the interference by one or more of the following measures:
    - Reorient or relocate the receiving antenna.
    - Increase the separation between the equipment and receiver.
    - Connect the equipment to an outlet on a circuit different from that to which the receiver is connected.
-

- 
- Consult the dealer or an experienced radio/TV technician for help.
  - The use of shielded cables for connection of the monitor to the graphics card is required to assure compliance with FCC regulations. Changes or modifications to this unit not expressly approved by the party responsible for compliance could void the user's authority to operate this equipment.

### **Canadian department of communications statement**

- This digital apparatus does not exceed the Class B limits for radio noise emissions from digital apparatus set out in the Radio Interference Regulations of the Canadian Department of Communications.
- This class B digital apparatus complies with Canadian ICES-003

## **SAFETY INFORMATION**

### **Electrical safety**

- To prevent electrical shock hazard, disconnect the power cable from the electrical outlet before reloading the system.
- When adding or removing devices to or from the system, ensure that the power cables for the devices are unplugged before the signal cables are connected. If possible, disconnect all power cables from the existing system before you add device.
- Before connecting or removing signals cables from motherboard, ensure that all power cables are unplugged.
- Make sure that your power supply is set to the correct voltage in your area. If you are not sure about the voltage of the electrical outlet you are using, contact your local power company.
- If the power supply is broken, do not try to fix it by yourself. Contact a qualified service technician or your retailer.

### **Operation safety**

- Before installing the motherboard and adding devices on it, carefully read the manuals that came with the package.
  - Before using the product, make sure all cables are correctly connected and the power cables are not damaged. If you detect any damage, contact your dealer
-

---

immediately.

- To avoid short circuits, keep paper clips, screws, and staples away from connectors, slots sockets and circuitry.
- Avoid dust, humidity, and temperature extremes. Do not place the product in any area where it may become wet.
- Place the product on a stable surface.
- If you encounter technical problems with the product, contact a qualified service technician or your retailer.

## **EMC Rules**

This unit has to be installed in a shielded housing. If not installed in a properly shielded enclosure, and used in accordance with the instruction manual, this product may cause radio interference in which case the user may be required to take adequate measures at his or her own expense.

## **IMPORTANT INFORMATION**

This product is not an end user product. It was developed and manufactured for further processing by trained personnel.



Please recycle packaging environmentally friendly: Packaging materials are recyclable. Please do not dispose packaging into domestic waste but recycle it.



Please recycle old or redundant devices environmentally friendly: Old devices contain valuable recyclable materials that should be reutilized. Therefore please dispose .... old devices at collection points which are suitable.

---

# Table of Contents

1. Introduction	1
1.1. About this document	1
2. Getting Started	2
2.1. Requirements	2
2.1.1. Requirements for p3i_DIG	2
2.1.2. Requirements for p3i_CL and p3i_CL/PMC	2
2.2. Hardware installation	2
2.3. Connecting the camera	3
2.4. Software installation	3
2.4.1. Windows operating systems	3
2.4.2. Linux operating systems	11
3. Hardware Reference	13
3.1. Introduction	13
3.1.1. General Features of p3i_DIG	13
3.1.2. General Features of p3i_CL and p3i_CL/PMC	13
3.2. p3i_DIG-Hardware	14
3.2.1. Block Diagram p3i_DIG	14
3.2.2. Technical Details of p3i_DIG	14
3.2.3. Connector Pinout of p3i_DIG	19
3.2.4. Hex-Switch (Board-ID-Select)	23
3.2.5. Status-LEDs	23
3.3. p3i_CL-Hardware	24
3.3.1. Block Diagram p3i_CL	24
3.3.2. Technical Details of p3i_CL	24
3.3.3. Connector Pinout of p3i_CL	28
3.3.4. Hex-Switch (Board-ID-Select)	32
3.3.5. Status-LEDs	32
3.4. p3i_CL/PMC-Hardware	33
3.4.1. Block Diagram p3i_CL/PMC	33
3.4.2. Technical Details of p3i_CL/PMC	33
3.4.3. Connector Pinout of p3i_CL/PMC	37
3.4.4. Jumper (Board-ID-Select)	41
3.5. Trigger Modes	42
3.5.1. Softtrigger	42
3.5.2. Exttrigger	42
3.5.3. Autottrigger	42
3.6. Specifications	43
3.6.1. Electrical Specifications	43
3.6.2. Environmental Conditions	45
4. Trouble Shooting - if it does not work	46
5. Programmers Reference	47
5.1. Overview	47
5.1.1. Introduction	47
5.1.2. Main Features	47
5.1.3. Technical Details	47
5.1.4. Software Concept	48
5.1.5. Source code samples	48
5.1.6. Industrial requirements	49
5.1.7. Cameras	49
5.1.8. Developing own applications	49
5.1.9. Allocating Image Memory	49
5.1.10. Multiple Grabbers	49
5.1.11. Error Handling	50

5.1.12. Downloading the software	50
5.1.13. Image Sequences - Program flow	50
5.1.14. Calling the library function from languages other than C/C++	51
5.1.15. Virtual Grabbers	51
5.2. Library Functions	52
5.2.1. Overview of library functions	52
5.2.2. el_Acquire	53
5.2.3. el_AcquireEx	55
5.2.4. el_AssignBuffer	56
5.2.5. el_CloseHW	58
5.2.6. el_CreateMemBuffer	59
5.2.7. el_FreeMemBuffer	59
5.2.8. el_GetBoardIdentifiers	60
5.2.9. el_GetCycleTime	60
5.2.10. el_GetDriverRevision	61
5.2.11. el_GetErrorCode	61
5.2.12. el_GetErrorCodeEx	62
5.2.13. el_GetExposureTime	62
5.2.14. el_GetHWRevision	62
5.2.15. el_GetNumOfBoards	63
5.2.16. el_GetPixelClock	63
5.2.17. el_GetSelectedCamera	64
5.2.18. el_GetSetting	64
5.2.19. el_GetSupportedCamFeaturesEx	65
5.2.20. el_GetSWRevision	65
5.2.21. el_InitContext	66
5.2.22. el_InitHW	66
5.2.23. el_NewMemBuffer	68
5.2.24. el_OpenHW	70
5.2.25. el_OpenHWEx	72
5.2.26. el_ResetOutputs	73
5.2.27. el_SelectCamera	73
5.2.28. el_SetAcqWindow	74
5.2.29. el_SetCycleTime	75
5.2.30. el_SetExposureTime	75
5.2.31. el_SetTriggerModes	76
5.2.32. el_SetExtTriggerInput	76
5.2.33. el_SetOutputs	77
5.2.34. el_SetPixelClock	77
5.2.35. el_TestAcq	78
5.2.36. el_TestFrameCount	79
5.2.37. el_WaitAcqEnd	79
5.2.38. el_WriteSetupFile	81
5.3. Defines	81
5.3.1. EL_ACQUISITIONMODE	81
5.3.2. Error codes	81
5.3.3. EL_FGITEM	85
5.4. Data Structures	86
5.4.1. EL_CAMFEATURES	86
5.4.2. EL_BOARD_IDENTIFIER	86
6. Samples	88
6.1. Programming example	88
A. Cameras	90
A.1. Introduction	90
A.2. Overview of Cameras supported by the software	90
A.3. T Dalsa Spark SP-13-xxx30 / SP-14-xxx30	90
A.4. Hitachi KP-F100	90



A.5. ACC-1xx0 Eagle	90
A.6. Pulnix TM-6710CL	91
A.7. Optisens Colorline-1728	91
A.8. Optisens Colorline-1728 Stereo	92
A.9. JAI CV-M2 Ikegami SKC-145T2 Basler A102k	93
B. FAQs	94
B.1. Common FAQs	94

---

## List of Tables

3.1. Bit Assignments for Appropriate Data Mode of p3i_DIG	15
3.2. Used SODIMM Capacity Dependent on Selected Data Mode	19
3.3. Pinout of 100 pin Mini-Delta-Ribbon Connector(Receptacle)	20
3.4. Pinout of 16-Pin Header X101	22
3.5. frame grabber LED	23
3.6. Used SODIMM Capacity Dependent on Selected Data Mode	27
3.7. Pinout of 26 pin Mini-Delta-Ribbon Connector X1000 (Receptacle)	29
3.8. Pinout of 15 pin high-density female Min-D (X1002)	30
3.9. Pinout of 16-Pin Header X101	31
3.10. frame grabber LED	32
3.11. Used SODIMM Capacity Dependent on Selected Data Mode	36
3.12. Pinout of 26 pin Mini-Delta-Ribbon Connector X100 (Receptacle)	38
3.13. Pinout of 9 pos. Micro-D (X101)	39
3.14. Pinout of 8 pin Header/Jumper X102	40
3.15. Electrical Specifications for Differential Signals p3i_DIG	43
3.16. Electrical Specifications for Differential Signals p3i_CL	43
3.17. Electrical Specifications for TTL Signals	43
3.18. Electrical Specifications for Opto-coupled Input Signals	44
3.19. Power Requirement	44
3.20. Maximum Pixel Clock Frequency	44
3.21. Maximum Pixel Clock Frequency	45
3.22. Environmental Conditions	45
5.1. Initialization	52
5.2. Configuration and Video Input	52
5.3. Acquisition and Buffer Management	52
5.4. Timing/Synchronisation	52
5.5. File I/O	53
5.6. Miscellaneous	53
5.7. Camera Adaptation module functions	53
5.8. Acquisitionmode	81
5.9. Warning codes	81
5.10. Unknown error codes	82
5.11. Error codes	82
5.12. Extended error codes	84
5.13. EL_FGITEM	85
A.1.	90

---

# Chapter 1. Introduction

## 1.1. About this document

The purpose of this documentation is to describe the ELTEC Elektronik AG P3I3 frame grabber family. It contains a description of the hardware and software installation, the list of software APIs and a list of cameras which can be used with this products.

There are three P3I3 family members. p3i\_DIG is a PCI Frame Grabber for Digital Matrix and Line-Scan cameras. p3i\_CL and p3i\_CL/PMC are Frame Grabbers for Camera Link applications with PCI and PMC form factors respectively.

This document contains sections specific for the appropriate P3I3 family member.

The software package is common to all members of the frame grabber family.

---

## Chapter 2. Getting Started

### 2.1. Requirements

#### 2.1.1. Requirements for p3i\_DIG

for the installation and use of the p3i\_DIG frame grabber you need:

- the frame grabber board.
- digital Camera with RS422 or LVDS signaling standard
- Camera Cable
- PC with free PCI slot and Pentium CPU.
- Windows XP, Vista, Windows 7 or a Linux operating system.
- Operating system dependent hardware driver setup and system independent development files

#### 2.1.2. Requirements for p3i\_CL and p3i\_CL/PMC

for the installation and use of the p3i\_CL and p3i\_CL/PMC frame grabber you need:

- the frame grabber board.
- CameraLink camera
- CameraLink cable
- Computer system with free PCI/PMC slot and Pentium CPU.
- Windows XP, Vista, Windows 7 or a Linux operating system.
- Operating system dependent hardware driver setup and system independent development files.

### 2.2. Hardware installation

- Switch off computer
- Prepare site to observe electrostatic discharge (ESD) precautions before opening computer or removing appropriate P3i3 family member from its case: Touch computer steel case during insertion/removal of the frame grabber or take other precautions to ensure the absence of high voltages due to electric charges.
- Open computer case, remove blind back panel
- Insert the board into a free PCI/PMC slot; the board must fit into the slot without use of excessive force, make sure it sits firmly in the slot and the PCI connector conductors sit completely inside the connector.
- Fix the back panel with a screw.
- Close case.

## 2.3. Connecting the camera

Attach camera cable to camera connector.

## 2.4. Software installation

Please download our software from the web site *ELTEC Elektronik AG* [<http://www.eltec.de>] selecting *Downloadcenter* or ask our support( [<support@eltec.de>](mailto:support@eltec.de) ).

### 2.4.1. Windows operating systems

The software package is common to all members of the frame grabber family. For 32 and 64 Bit systems there is only one setup program. The file program on which system it is running and installs the corresponding software.

The software consists of :

- the drivers for Windows XP, Vista, Windows 7 and the DLL that provides the imaging API
- the configuration tools containing the configuration program and import library for the DLL that provides the imaging API

#### 2.4.1.1. Driver installation

The next steps are dependent of your operating system.

This chapter describes how to install the lowlevel drivers. The usermode DLL and test-applications are contained in a different setup.

Please keep the following installation order.

1. Read the documentation.
2. Follow the installation steps described in the next section. Read this section before plugging the grabber into your computer system.
3. Install the software.

The installation procedure is different for the various operating systems.

Please read the appropriate section.

#### 2.4.1.1.1. Windows XP, Vista, Windows 7

Under these operating systems used the setup program provided for Windows.

##### 2.4.1.1.1.1. Installation


Perform the following steps.

For a first time installation perform the following steps:


1. Shut down your computer system, disconnect power.
2. Plug in the grabber and turn on power.
3. Ignore hardware detection dialogue and start setup program. Select your language



4. Select the directory to install the software. Normally you should keep the default path.




5. Select the components to be installed. On a development system you should install all components. On a target "System Drivers" and maybe "Test Programs" are needed.






6. During the installation you have to confirm that you want to install the kernel driver.




7. On a 64 bit system, you will be asked if you want to install the Windows redistributable libraries. You should keep the default setting to install them.




#### 2.4.1.1.1.2. Update

To update an existing installation, the best way is to deinstall the old and the reinstall the new software.


1. Use the deinstallation routine of the setup program



2. Open the device manager and select "deinstall" in the context menu on the grabber.



3. Make sure that the checkbox to remove the driver software is set.



4. If several grabber of a family are shown deinstall all corresponding devices

5. Reboot the system

6. Reinstall the new software

### 2.4.1.2. Samples installation

### 2.4.1.3. Starting the configuration program

The configuration program looks the same under Windows and Linux.

- Start the Configuration Program from the Start-Menu (*/Program Files/P3i3 Configuration Tools/P3i3 Configuration*)
- Select the installed board from the List-Box. Now the camera has to be selected from the camera selection dialog . if your camera does not appear in the list please contact our support ( [<support@eltec.de>](mailto:support@eltec.de) )
- If a Camera is attached, select the Menu *Acquisition/Snap* to get an image.

More details about the Configuration Program can be found in the Configuration Program online help details about the adapted cameras can be found in Appendix A.

### 2.4.1.4. Running the sample `digital_grab`

This sample shows how to use the library functions. The display is done into a window of the display server, so the display server has to be started before.

After successful installation of the samples, Visual C++ 6.0 is required to compile and link the sample. Open the workspace file `digital_grab.dsw` located in the directory */Program Files/eltec/samples/digital\_grab*, compile and link.

After starting the sample a camera can be selected and a new window will be created on the display server.

## 2.4.2. Linux operating systems

The Linux driver distribution consists of a kernel driver, which comes in sourcecode and is compiled during the installation process, a usermode shared library which is only available as binary, the configuration program and some samples.

The Linux drivers are suitable for development under Intel 32 bit Linux operating systems as e.g. SuSE Linux and Red Hat Linux.

All files are contained in a compressed tar file, which is called `p3i3-i386-x.y.z.tgz` (x.y.z denotes a version number).

### 2.4.2.1. Installation

To install the driver, you need the following requirements to be fulfilled.

- The kernel headerfiles must be installed and *match* your kernel. Please refer to your linux distribution manual how to install the kernel sources.
- The current driver can be downloaded from our website.

To install the driver and samples, please perform the following steps.

1. Unpack the compressed tar file to a directory of your choice. This can be done as normal user. Open a shell and use the following commands:

Read the file *readme.htm* to latest installation hints.

```
cd directory_of_your_choice
tar xzvf path_and_name_of_tar_file
```

2. Login as root
3. Start the *INSTALL* script:

```
./INSTALL
```

The installation script compiles and installed the driver, copies the shared library to */usr/lib* and creates a link.

You may need to perform some additional steps - e.g. creating entries in */etc/modules.conf*. Please read the file *readme.htm* for details.

As there are a lot of different linux distributions with many different kernel versions, we can not guarantee that the driver run under all circumstances.

In case of problems please email our support. Attach a copy of the terminal output and error messages.

The subdirectory *bin/i386* contains the configuration program. As this program is the same under Windows and Linux, please have a look at the Windows section of this manual for details.

The subdirectory *samples* contains some simple samples showing how to access the frame grabber in our own programs.

### 2.4.2.2. ELinOS cross development

The Linux drivers are suitable for ELinOS cross development too. Beneath the i386 drivers there exists PowerPC drivers for ELTEC BAB740/750 and BAB911 boards.

In order to install for ELinOS cross compilation perform the following steps:

1. Install ELinOS and create a project for your hardware. This step is beyond the scope of the manual. Please refer to the ELinOS manual and the manuals coming with the ELTEC BAB boards.
2. Source the script *ELINOS.sh* in a shell.
3. Unpack the tar file to a directory of your choice.
4. Change to this directory.
5. Start *INSTALL*. You need not to be root !

The steps above create a subdirectory *src/grabber* in your *ELINOS\_PROJECT* directory. In order to compile the project with *elk*, you may need to edit the *topmost* makefile in your project directory.

Please have a look at the *README* file coming with the driver archive for additional details.

---

## Chapter 3. Hardware Reference

### 3.1. Introduction

The p3i\_DIG is a frame grabber for digital linescan and areascan cameras, which supports EIA-644 (LVDS) as well as RS-422 differential input and output signals. A data bus width of 32-bit together with 7 differential input and 7 differential output signals makes this frame grabber most flexible for use with different data modes and camera specific signals. In addition multiple trigger in- and outputs (Opto-coupled and TTL) can be used to fire or recognize external events. In order to minimize the risk of data loss the onboard SODIMM module buffers high data rates. This is useful especially in cases the PCI bus is busy or data rate exceeds PCI bus bandwidth.

The p3i\_CL and p3i\_CL/PMC is a frame grabber for digital linescan and areascan cameras, which supports the CameraLink standard. The use of the Channel Link technology to transmit multiplexed data and control signals as well as a serial communication protocol and a standardized connector are the main benefits of the CameraLink standard. In addition the p3i\_CL and p3i\_CL/PMC have multiple trigger in- and outputs (Opto-coupled and TTL) which can be used to fire or recognize external events. In order to minimize the risk of data loss the onboard SODIMM module buffers high data rates. This is useful especially in cases the PCI bus is busy or data rate exceeds PCI bus bandwidth.

#### 3.1.1. General Features of p3i\_DIG

- frame grabber for up to four 8-Bit channels of a single camera
- RS422 and LVDS(RS644) signaling standard supported
- Restart cameras supported
- Real-time acquisition of images or image sequences directly into main memory
- PCI 2.2 compliant


#### 3.1.2. General Features of p3i\_CL and p3i\_CL/PMC

- frame grabber supports the CameraLink Base Configuration with up to 3 ports with 8-bit each
- Restart cameras supported
- Real-time acquisition of images or image sequences directly into main memory
- PCI 2.2 compliant

Note that you can use several boards in one computer, in this case the frame grabbers must have different board IDs. Therefore p3i\_DIG and p3i\_CL have one Hex-switch and p3i\_CL/PMC has one jumper onboard.

## 3.2. p3i\_DIG-Hardware

### 3.2.1. Block Diagram p3i\_DIG



### 3.2.2. Technical Details of p3i\_DIG

The frame grabber is capable of handling 11 different data modes. Cameras with 8 bits to 16 bits per pixel and multiple channels are supported.

The pixel clock is taken directly from the camera to satisfy setup and hold timings. Additionally the frame grabber provides a clock output which is programmable in its frequency.

The region of interest, i.e. the part of the video information that is acquired, can be defined on a pixel basis for all 4 channels - not always the whole frame has to be acquired.

The control signals to synchronize the camera on external events and to adjust variable exposure timings are programmable via software.



### 3.2.2.1. Data Modes of p3i\_DIG

There are 11 different modes for handling several combinations of data inputs. The next table shows the bit assignments for the appropriate data modes where the channels are marked with A,B,C and D. A0,B0,C0,D0 are the LSBs of each channel.

**Table 3.1. Bit Assignments for Appropriate Data Mode of p3i\_DIG**

DataBus	Mode0 1x8	Mode1 2x8	Mode2 3x8	Mode3 4x8	Mode4 1x10	Mode5 2x10	Mode6 3x10	Mode7 1x12	Mode8 2x12	Mode9 1x16	Mode10 2x16
VData0	A0	A0	A0	A0	A2	A2	A0	A4	A4	A0	A0
VData1	A1	A1	A1	A1	A3	A3	A1	A5	A5	A1	A1
VData2	A2	A2	A2	A2	A4	A4	A2	A6	A6	A2	A2
VData3	A3	A3	A3	A3	A5	A5	A3	A7	A7	A3	A3
VData4	A4	A4	A4	A4	A6	A6	A4	A8	A8	A4	A4
VData5	A5	A5	A5	A5	A7	A7	A5	A9	A9	A5	A5
VData6	A6	A6	A6	A6	A8	A8	A6	A10	A10	A6	A6
VData7	A7	A7	A7	A7	A9	A9	A7	A11	A11	A7	A7
VData8		B0	B0	B0		B2	A8		B4	A8	A8
VData9		B1	B1	B1		B3	A9		B5	A9	A9
VData10		B2	B2	B2		B4	B0		B6	A10	A10
VData11		B3	B3	B3		B5	B1		B7	A11	A11
VData12		B4	B4	B4		B6	B2		B8	A12	A12
VData13		B5	B5	B5		B7	B3		B9	A13	A13
VData14		B6	B6	B6	A0	B8	B4		B10	A14	A14
VData15		B7	B7	B7	A1	B9	B5		B11	A15	A15
VData16			C0	C0		A0	B6	A2	A2		B0
VData17			C1	C1		A1	B7	A3	A3		B1
VData18			C2	C2		B0	B8		B2		B2
VData19			C3	C3		B1	B9		B3		B3
VData20			C4	C4			C0	A0	A0		B4
VData21			C5	C5			C1	A1	A1		B5
VData22			C6	C6			C2		B0		B6
VData23			C7	C7			C3		B1		B7
VData24				D0			C4				B8
VData25				D1			C5				B9
VData26				D2			C6				B10
VData27				D3			C7				B11
VData28				D4			C8				B12
VData29				D5			C9				B13
VData30				D6							B14
VData31				D7							B15

#### **3.2.2.1.1. Mode0 - 1x8 bit**

Used DMA channels: 1 4 consecutive bytes are packed into one 32-bit word.

#### **3.2.2.1.2. Mode1 - 2x8 bit**

Used DMA channels: 2 4 consecutive bytes of the same channel are packed into one 32-bit word. Each channel is handled separately and the data is written into different memory buffers.

#### **3.2.2.1.3. Mode2 - 3x8 bit**

Used DMA channels: 1 These 24-bits are packed together into one 32-bit word. Unused bits are zero-filled.

#### **3.2.2.1.4. Mode3 - 4x8 bit**

Used DMA channels: 4 4 consecutive bytes of each channel are packed into one 32-bit word. Each channel is handled separately and the data is written into separate memory buffers.

#### **3.2.2.1.5. Mode4 - 1x10 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.2.2.1.6. Mode5 - 2x10 bit**

Used DMA channels: 2 Two consecutive pixels of each channel are packed into one 32-bit word, 16-bit aligned and the data is written into separate memory buffers. Unused bits are zero-filled.

#### **3.2.2.1.7. Mode6 - 3x10 bit**

Used DMA channels: 3 Three separate buffers, one for each channel, are used to write the image into main memory. Two consecutive pixels of each channel are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.2.2.1.8. Mode7 - 1x12 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.2.2.1.9. Mode8 - 2x12 bit**

Used DMA channels: 2 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. The data of each channel is written into separate memory buffers. Unused bits are zero-filled.

#### **3.2.2.1.10. Mode9 - 1x16 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned.

#### **3.2.2.1.11. Mode10 - 2x16 bit**

Used DMA channels: 2 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. The data of each channel is written into separate memory buffers.

#### **3.2.2.2. Frame Grabber Interface of p3i\_DIG**

### **3.2.2.2.1. Digital Video Input**

The data input consists of 32 differential line pairs.

### **3.2.2.2.2. Control Inputs for p3i\_DIG**

Beside a pixel clock, frame enable, line enable, there are resources for 4 additional user signals(DIFFIN0 to DIFFIN3).

### **3.2.2.2.3. Control Outputs of p3i\_DIG**

The p3i\_DIG provides three in timing adjustable outputs. These are EXPOSE , PRIN and a selectable trigger output. The trigger output can be used for instance to fire a strobe light. It is available on the MDR connector(X100) and on the 16 pos. connector(X101). for each signal a start and end time can be defined. These signals are generated with the pixel clock, provided by the camera or a programmable clock. Multiplies of frame enable and line enable signals as timebase are also possible.

EXTCLK is the programmable clock output of p3i\_DIG to synchronize cameras.

DIFF\_OUT0 to DIFF\_OUT3 can be set additionally as static signals.

### **3.2.2.3. 16 pin Header**


The 16-Pin Header is an additional interface for user signals and trigger resources. The user inputs are readable per software to recognize external events. The user outputs can be set statically.

### 3.2.2.4. Trigger Input

There are several trigger inputs on the frame grabber - optocoupled and TTL. The optocoupled trigger inputs have optimum noise immunity and 250 V isolation voltage. TriginOpt0+ (Trigger+ in figure below) for instance is connected to the anode of a LED, TriginOpt0- (Trigger- in figure below) to the cathode of the LED via an internal 220-Ohm resistor. Since the LED needs about 10..20 mA for full drive, a 5 V voltage source or a TTL output is able to drive sufficient current through the circuit. Higher-voltage sources may be used with additional limiting resistors. This trigger input is edge-sensitive. The use of positive or negative edge is possible.

Caution: Do not exceed a maximum of 30 mA LED current!

Opto-coupled Trigger Input Schematic



### 3.2.2.5. Data Transfer of p3i\_DIG

Since the p3i\_DIG is a busmaster card, the video data for a single frame or a whole sequence is moved into memory per DMA-transfer. There is no need for the CPU to support this process. The maximum transfer rate in a system is 105 Mbytes/s typically. In a real application the transfer rate depends on the chipset, graphic card and other active busmaster cards.

### 3.2.2.6. SODIMM for p3i\_DIG

The SODIMM on the p3i\_DIG is used as a large FIFO to buffer data especially in cases the PCI bus is busy or data rate exceeds PCI bus bandwidth.

The SODIMM consists of SDRAM modules and is clocked with 66 MHz. "Non Mixed-Mode" module configurations are used and each SDRAM module has 4 banks.


The used SODIMM capacity is dependent on the selected data mode:

**Table 3.2. Used SODIMM Capacity Dependent on Selected Data Mode**

MODE	Used SODIMM Capacity [%]
Mode0 (1x8bit)	50
Mode1 (2x8bit)	100
Mode2 (3x8bit (RGB))	75
Mode3 (4x8bit)	100
Mode4 (1x10bit)	62.5
Mode5 (2x10bit)	62.5
Mode6 (3x10bit (RGB))	93.75
Mode7 (1x12bit)	75
Mode8 (2x12bit)	75
Mode9 (1x16bit)	100
Mode10 (2x16bit)	100


### 3.2.3. Connector Pinout of p3i\_DIG

Board Overview



### 3.2.3.1. Frame Grabber Interface X100 of p3i\_DIG

Layout of 100 pin Mini-Delta-Ribbon Connector (Receptacle)



This is a 100 pin half pitch Mini Delta Ribbon Connector (MDR) which contains the 32-bit data bus, 7 input signals, 7 camera control signals, 1 TTL trigger input, 1 TTL trigger output and 1 optocoupled input.


**Table 3.3. Pinout of 100 pin Mini-Delta-Ribbon Connector(Receptacle)**

SIGNAL NAME	PIN	SIGNAL NAME	PIN
Ground	A1	Ground	B1
TriginTTL0	A2	TrigoutTTL	B2
TriginOpt0+	A3	TriginOpt0-	B3
EXPOSE(+)	A4	EXPOSE(-)	B4
PRIN(+)	A5	PRIN(-)	B5
DIFFOUT_0(+)	A6	DIFFOUT_0(-)	B6
DIFFOUT_1(+)	A7	DIFFOUT_1(-)	B7
EXTCLK(+)	A8	EXTCLK(-)	B8
DIFFOUT_2(+)	A9	DIFFOUT_2(-)	B9
DIFFOUT_3(+)	A10	DIFFOUT_3(-)	B10
PCLK(+)	A11	PCLK(-)	B11
FR_EN(+)	A12	FR_EN(-)	B12
LN_EN(+)	A13	LN_EN(-)	B13
DIFFIN_0(+)	A14	DIFFIN_0(-)	B14
DIFFIN_1(+)	A15	DIFFIN_1(-)	B15
DIFFIN_2(+)	A16	DIFFIN_2(-)	B16
DIFFIN_3(+)	A17	DIFFIN_3(-)	B17
VDATA0(+)	A18	VDATA0(-)	B18
VDATA1(+)	A19	VDATA1(-)	B19
VDATA2(+)	A20	VDATA2(-)	B20
VDATA3(+)	A21	VDATA3(-)	B21

VDATA4(+)	A22	VDATA4(-)	B22
VDATA5(+)	A23	VDATA5(-)	B23
VDATA6(+)	A24	VDATA6(-)	B24
VDATA7(+)	A25	VDATA7(-)	B25
VDATA8(+)	A26	VDATA8(-)	B26
VDATA9(+)	A27	VDATA9(-)	B27
VDATA10(+)	A28	VDATA10(-)	B28
VDATA11(+)	A29	VDATA11(-)	B29
VDATA12(+)	A30	VDATA12(-)	B30
VDATA13(+)	A31	VDATA13(-)	B31
VDATA14(+)	A32	VDATA14(-)	B32
VDATA15(+)	A33	VDATA15(-)	B33
VDATA16(+)	A34	VDATA16(-)	B34
VDATA17(+)	A35	VDATA17(-)	B35
VDATA18(+)	A36	VDATA18(-)	B36
VDATA19(+)	A37	VDATA19(-)	B37
VDATA20(+)	A38	VDATA20(-)	B38
VDATA21(+)	A39	VDATA21(-)	B39
VDATA22(+)	A40	VDATA22(-)	B40
VDATA23(+)	A41	VDATA23(-)	B41
VDATA24(+)	A42	VDATA24(-)	B42
VDATA25(+)	A43	VDATA25(-)	B43
VDATA26(+)	A44	VDATA26(-)	B44
VDATA27(+)	A45	VDATA27(-)	B45
VDATA28(+)	A46	VDATA28(-)	B46
VDATA29(+)	A47	VDATA29(-)	B47
VDATA30(+)	A48	VDATA30(-)	B48
VDATA31(+)	A49	VDATA31(-)	B49
Ground	A50	Ground	B50

### 3.2.3.2. 16 pin Header X101

Layout of 16 pin Header (male)



The 16-Pin Header is an additional interface for user signals and trigger resources.

**Table 3.4. Pinout of 16-Pin Header X101**

Signal Name	Pin	Signal Name	Pin
USER_OUT0	1	Ground	9
USER_OUT1	2	Ground	10
USER_OUT2	3	TriginOpt1+	11
USER_OUT3	4	TriginOpt1-	12
TRIGOUT_TTL	5	Ground	13
TRIGIN_TTL1/USER_IN0	6	Ground	14
TRIGIN_TTL2/USER_IN1	7	TriginOpt2+	15
Ground	8	TriginOpt2-	16



### 3.2.4. Hex-Switch (Board-ID-Select)


Switch S700 is used to set the board ID. If more than one frame grabber is plugged into the PC, each must have a distinct board ID unequal to "0".



### 3.2.5. Status-LEDs

There are 4 LEDs for status information:

Frame Grabber LEDs




**Table 3.5. frame grabber LED**

LED1:	Board selected - when the frame grabber is initialized, the LED is switched on
LED2:	Capture - Acquisition in progress
LED3:	FiFo overrun - The FiFo has run full
LED4:	FiFo Write Enable - video data is written into the FiFo

These LEDs are not intended to be used in applications but to help in analyzing problems in cooperation with ELTEC Elektronik AG support.

### 3.3. p3i\_CL-Hardware

#### 3.3.1. Block Diagram p3i\_CL



#### 3.3.2. Technical Details of p3i\_CL

The frame grabber is capable of handling 10 different data modes. Cameras with 8 bits to 16 bits per pixel and multiple channels are supported.

The pixel clock is taken directly from the camera to satisfy setup and hold timings. Additionally the frame grabber provides a clock output which is programmable in its frequency.

The region of interest, i.e. the part of the video information that is acquired, can be defined on a pixel basis for all 3 channels - not always the whole frame has to be acquired.

The control signals to synchronize the camera on external events and to adjust variable exposure timings are programmable via software.

### **3.3.2.1. Data Modes of p3i\_CL**

There are 10 different modes for handling several combinations of data inputs.

#### **3.3.2.1.1. Mode0 - 1x8 bit**

Used DMA channels: 1 4 consecutive bytes are packed into one 32-bit word.

#### **3.3.2.1.2. Mode1 - 2x8 bit**

Used DMA channels: 2 4 consecutive bytes of the same channel are packed into one 32-bit word. Each channel is handled separately and the data is written into different memory buffers.

#### **3.3.2.1.3. Mode2 - 3x8 bit**

Used DMA channels: 3 4 consecutive bytes of the same channel are packed into one 32-bit word. The data of each channel is handled separately and written into different memory buffers.

#### **3.3.2.1.4. Mode3 - 3x8(RGB) bit**

Used DMA channels: 1 These 24-bits are packed together into one 32-bit word. Unused bits are zero-filled.

#### **3.3.2.1.5. Mode4 - 1x10 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.3.2.1.6. Mode5 - 2x10 bit**

Used DMA channels: 2 Two consecutive pixels of each channel are packed into one 32-bit word, 16-bit aligned and the data is written into separate memory buffers. Unused bits are zero-filled.

#### **3.3.2.1.7. Mode6 - 1x12 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.3.2.1.8. Mode7 - 2x12 bit**

Used DMA channels: 2 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. The data of each channel is written into separate memory buffers. Unused bits are zero-filled.

#### **3.3.2.1.9. Mode8 - 1x14 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.3.2.1.10. Mode9 - 1x16 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

### 3.3.2.2. Frame Grabber Interface p3i\_CL

#### 3.3.2.2.1. CameraLink Connector of p3i\_CL

The CameraLink standard defines 4 differential inputs with an additional clock to transmit data and control signals from the camera to the frame grabber (X0..X3). Another four LVDS pairs are reserved for general purpose camera control. They are outputs of the p3i\_CL and flexible programmable via software. To each of these outputs you can assign a programmable clock, a static signal(high or low) or one of two signals which have an adjustable hightime and lowtime, for instance for exposure control.

Additionally the CameraLink standard defines an asynchronous serial protocol for a bidirectional communication between camera and frame grabber. The signals used are SerTfg and SerTc.

#### 3.3.2.3. 16 pin Header


The 16-Pin Header is an additional interface for user signals and trigger resources. The user inputs are readable per software to recognize external events. The user outputs can be set statically.

#### 3.3.2.4. Trigger Input

There are several trigger inputs on the frame grabber - optocoupled and TTL. The optocoupled trigger inputs have optimum noise immunity and 250 V isolation voltage. Trigin\_Opt+ (Trigger+ in figure below) for instance is connected to the anode of a LED, Trigin\_Opt- (Trigger- in figure below) to the cathode of the LED via an internal 220-Ohm resistor. Since the LED needs about 10..20 mA for full drive, a 5 V voltage source or a TTL output is able to drive sufficient current through the circuit. Higher-voltage sources may be used with additional limiting resistors. This trigger input is edge-sensitive. The use of positive or negative edge is possible.

Caution: Do not exceed a maximum of 30 mA LED current!

Opto-coupled Trigger Input Schematic



### 3.3.2.5. Data Transfer of p3i\_CL

Since the p3i\_CL is a busmaster card, the video data for a single frame or a whole sequence is moved into memory per DMA-transfer. There is no need for the CPU to support this process. The maximum transfer rate in a system is 105 Mbytes/s typically. In a real application the transfer rate depends on the chipset, graphic card and other active busmaster cards.

### 3.3.2.6. SODIMM for p3i\_CL

The SODIMM on the p3i\_CL is used as a large FIFO to buffer data especially in cases the PCI bus is busy or data rate exceeds PCI bus bandwidth.

The SODIMM consists of SDRAM modules and is clocked with 66 MHz. "Non Mixed-Mode" module configurations are used and each SDRAM module has 4 banks.


The used SODIMM capacity is dependent on the selected data mode:

**Table 3.6. Used SODIMM Capacity Dependent on Selected Data Mode**

MODE	Used SODIMM Capacity [%]
Mode0 (1x8bit)	50
Mode1 (2x8bit)	100
Mode2 (3x8bit)	75
Mode3 (3x8bit (RGB))	75
Mode4 (1x10bit)	62.5
Mode5 (2x10bit)	62.5
Mode6 (1x12bit)	93.75
Mode7 (2x12bit)	75
Mode8 (1x14bit)	87.5
Mode9 (1x16bit)	100


### 3.3.3. Connector Pinout of p3i\_CL

#### Board Overview



#### 3.3.3.1. CameraLink Interface X1000 of p3i\_CL

##### Layout of 26 pin Mini-Delta-Ribbon Connector (Receptacle)




This is a 26 pin half pitch Mini Delta Ribbon Connector (MDR) which contains the data bus, clock, control signals and the serial communication lines.

**Table 3.7. Pinout of 26 pin Mini-Delta-Ribbon Connector X1000 (Receptacle)**

SIGNAL NAME	PIN	SIGNAL NAME	PIN
inner shield	1	inner shield	14
CC4-	2	CC4+	15
CC3+	3	CC3-	16
CC2-	4	CC2+	17
CC1+	5	CC1-	18
SerTfg+	6	SerTfg-	19
SerTc-	7	SerTc+	20
X3+	8	X3-	21
XClk+	9	XClk-	22
X2+	10	X2-	23
X1+	11	X1-	24
X0+	12	X0-	25
inner shield	13	inner shield	26

### 3.3.3.2. Trigger Connector X1002 of p3i\_CL

Layout of 15 pin high-density female Min-D



This is a 15 pin high-density female Min-D connector which contains Trigger In- and Outputs to fire or recognize external events.


**Table 3.8. Pinout of 15 pin high-density female Min-D (X1002)**

PIN	SIGNAL NAME	DESCRIPTION
1	GND	Ground
2	Trigin_TTL	selectable Trigger Input; TTL-Level
3	Trigin_Opt+	selectable Trigger Input; connected to the Anode of the Optocoupler
4	Trigin_Opt-	selectable Trigger Input; connected to the Kathode of the Optocoupler
5	GND	Ground
6	Trigout_TTL	general purpose trigger output; for instance, to fire a strobe light; TTL-Level
7	GND	Ground
8	Contr_Out0+	noninverting part of the Contr_Out0 signal pair; static output; LVDS-Level
9	Contr_Out0-	inverting part of the Contr_Out0 signal pair; static output; LVDS-Level
10	GND	Ground
11	Contr_Out1+	noninverting part of the Contr_Out0 signal pair; static output; LVDS-Level
12	Contr_Out1-	inverting part of the Contr_Out0 signal pair; static output; LVDS-Level
13,14,15	NC	No connect



### 3.3.3.3. 16 pin Header X101

Layout of 16 pin Header (male)



The 16-Pin Header is an additional interface for user signals and trigger resources.

**Table 3.9. Pinout of 16-Pin Header X101**

Signal Name	Pin	Signal Name	Pin
USER_OUT0	1	Ground	9
USER_OUT1	2	Ground	10
USER_OUT2	3	TriginOpt1+	11
USER_OUT3	4	TriginOpt1-	12
TRIGOUT_TTL	5	Ground	13
TRIGIN_TTL1/USER_IN0	6	Ground	14
TRIGIN_TTL2/USER_IN1	7	TriginOpt2+	15
Ground	8	TriginOpt2-	16

### 3.3.4. Hex-Switch (Board-ID-Select)


Switch S700 is used to set the board ID. If more than one frame grabber is plugged into the PC, each must have a distinct board ID unequal to "0".



### 3.3.5. Status-LEDs

There are 4 LEDs for status information:

Frame Grabber LEDs




**Table 3.10. frame grabber LED**

LED1:	Board selected - when the frame grabber is initialized, the LED is switched on
LED2:	Capture - Acquisition in progress
LED3:	FiFo overrun - The FiFo has run full
LED4:	FiFo Write Enable - video data is written into the FiFo

These LEDs are not intended to be used in applications but to help in analyzing problems in cooperation with ELTEC Elektronik AG support.

## 3.4. p3i\_CL/PMC-Hardware

### 3.4.1. Block Diagram p3i\_CL/PMC



### 3.4.2. Technical Details of p3i\_CL/PMC

The frame grabber is capable of handling 10 different data modes. Cameras with 8 bits to 16 bits per pixel and multiple channels are supported.

The pixel clock is taken directly from the camera to satisfy setup and hold timings. Additionally the frame grabber provides a clock output which is programmable in its frequency.

The region of interest, i.e. the part of the video information that is acquired, can be defined on a pixel basis for all 3 channels - not always the whole frame has to be acquired.

The control signals to synchronize the camera on external events and to adjust variable exposure timings are programmable via software.

### **3.4.2.1. Data Modes of p3i\_CL/PMC**

There are 10 different modes for handling several combinations of data inputs.

#### **3.4.2.1.1. Mode0 - 1x8 bit**

Used DMA channels: 1 4 consecutive bytes are packed into one 32-bit word.

#### **3.4.2.1.2. Mode1 - 2x8 bit**

Used DMA channels: 2 4 consecutive bytes of the same channel are packed into one 32-bit word. Each channel is handled separately and the data is written into different memory buffers.

#### **3.4.2.1.3. Mode2 - 3x8 bit**

Used DMA channels: 3 4 consecutive bytes of the same channel are packed into one 32-bit word. The data of each channel is handled separately and written into different memory buffers.

#### **3.4.2.1.4. Mode3 - 3x8(RGB) bit**

Used DMA channels: 1 These 24-bits are packed together into one 32-bit word. Unused bits are zero-filled.

#### **3.4.2.1.5. Mode4 - 1x10 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.4.2.1.6. Mode5 - 2x10 bit**

Used DMA channels: 2 Two consecutive pixels of each channel are packed into one 32-bit word, 16-bit aligned and the data is written into separate memory buffers. Unused bits are zero-filled.

#### **3.4.2.1.7. Mode6 - 1x12 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.4.2.1.8. Mode7 - 2x12 bit**

Used DMA channels: 2 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. The data of each channel is written into separate memory buffers. Unused bits are zero-filled.

#### **3.4.2.1.9. Mode8 - 1x14 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

#### **3.4.2.1.10. Mode9 - 1x16 bit**

Used DMA channels: 1 Two consecutive pixels are packed into one 32-bit word, 16-bit aligned. Unused bits are zero-filled.

### 3.4.2.2. CameraLink Connector of p3i\_CL/PMC

The CameraLink standard defines 4 differential inputs with an additional clock to transmit data and control signals from the camera to the frame grabber (X0..X3). Another four LVDS pairs are reserved for general purpose camera control. They are outputs of the p3i\_CL and flexible programmable via software. To each of these outputs you can assign a programmable clock, a static signal (high or low) or one of two signals which have an adjustable hightime and lowtime, for instance for exposure control.

Additionally the CameraLink standard defines an asynchronous serial protocol for a bidirectional communication between camera and frame grabber. The signals used are SerTfg and SerTc.

### 3.4.2.3. 8 pin Header/Jumper


The 8 pin Header/Jumper is an additional interface for an user input or an trigger input. The user input is readable per software to recognize an external event. Additionally user outputs can be set statically.

### 3.4.2.4. Trigger Input

There are several trigger inputs on the frame grabber - optocoupled and TTL. The optocoupled trigger inputs have optimum noise immunity and 250 V isolation voltage. Trigin\_Opt+ (Trigger+ in figure below) for instance is connected to the anode of a LED, Trigin\_Opt- (Trigger- in figure below) to the cathode of the LED via an internal 220-Ohm resistor. Since the LED needs about 10..20 mA for full drive, a 5 V voltage source or a TTL output is able to drive sufficient current through the circuit. Higher-voltage sources may be used with additional limiting resistors. This trigger input is edge-sensitive. The use of positive or negative edge is possible.

Caution: Do not exceed a maximum of 30 mA LED current!

Opto-coupled Trigger Input Schematic



### 3.4.2.5. Data Transfer of p3i\_CL/PMC

Since the p3i\_CL/PMC is a busmaster card, the video data for a single frame or a whole sequence is moved into memory per DMA-transfer. There is no need for the CPU to support this process. The maximum transfer rate in a system is 105 Mbytes/s typically. In a real application the transfer rate depends on the chipset, graphic card and other active busmaster cards.

### 3.4.2.6. SODIMM for p3i\_CL/PMC

The SODIMM on the p3i\_CL/PMC is used as a large FIFO to buffer data especially in cases the PCI bus is busy or data rate exceeds PCI bus bandwidth.

The SODIMM consists of SDRAM modules and is clocked with 66 MHz. "Non Mixed-Mode" module configurations are used and each SDRAM module has 4 banks.


The used SODIMM capacity is dependent on the selected data mode:

**Table 3.11. Used SODIMM Capacity Dependent on Selected Data Mode**

MODE	Used SODIMM Capacity [%]
Mode0 (1x8bit)	50
Mode1 (2x8bit)	100
Mode2 (3x8bit)	75
Mode3 (3x8bit (RGB))	75
Mode4 (1x10bit)	62.5
Mode5 (2x10bit)	62.5
Mode6 (1x12bit)	93.75
Mode7 (2x12bit)	75
Mode8 (1x14bit)	87.5
Mode9 (1x16bit)	100


### 3.4.3. Connector Pinout of p3i\_CL/PMC

Board Overview



#### 3.4.3.1. CameraLink Interface X100 of p3i\_CL/PMC

Layout of 26 pin Mini-Delta-Ribbon Connector (Receptacle)




This is a 26 pin half pitch Mini Delta Ribbon Connector (MDR) which contains the data bus, clock, control signals and the serial communication lines.

**Table 3.12. Pinout of 26 pin Mini-Delta-Ribbon Connector X100 (Receptacle)**

SIGNAL NAME	PIN	SIGNAL NAME	PIN
inner shield	1	inner shield	14
CC4-	2	CC4+	15
CC3+	3	CC3-	16
CC2-	4	CC2+	17
CC1+	5	CC1-	18
SerTfg+	6	SerTfg-	19
SerTc-	7	SerTc+	20
X3+	8	X3-	21
XClk+	9	XClk-	22
X2+	10	X2-	23
X1+	11	X1-	24
X0+	12	X0-	25
inner shield	13	inner shield	26

**3.4.3.2. Trigger Connector X101 of p3i\_CL/PMC**

Layout of 9 pos. Micro-D (plug)



This is a 9 pos. thumbscrew Micro-D plug connector which contains Trigger In- and Outputs to fire or recognize external events.




**Table 3.13. Pinout of 9 pos. Micro-D (X101)**

PIN	SIGNAL NAME	DESCRIPTION
1	TRIGIN0+	noninverting part of optocoupled trigger input0
2	TRIGIN2+	noninverting part of optocoupled trigger input2
3	ContrDiffOut5+	noninverting part of differential output; LVDS level
4	TrigoutTTL0	TTL Trigger output; programmable by software
5	GND	Ground
6	TRIGIN0-	inverting part of optocoupled trigger input0
7	TRIGIN2-	inverting part of optocoupled trigger input2
8	ContrDiffOut5-	inverting part of differential output; LVDS level
9	TriginTTL1_UserIn0	Trigger input; also readable by software; TTL-Level

### 3.4.3.3. 8 pin Header/Jumper X102

Layout of 8 pin Header/Jumper (male)




The 8 pin Header/Jumper is an additional interface for user signals and trigger resources.

**Table 3.14. Pinout of 8 pin Header/Jumper X102**

PIN	SIGNAL NAME	DESCRIPTION
1	GND	Ground for BoardID Jumper
2	BoardID	Signal for BoardID Jumper
3	GND	Ground
4	TRIGIN_TTL2_USERIN1	TTL Trigger input; also readable by software
5	GND	Ground
6	User_Out0	settable by software; TTL-Level
7	User_Out1	settable by software; TTL-Level
8	User_Out2	settable by software; TTL-Level

### 3.4.4. Jumper (Board-ID-Select)

8 pin Header/Jumper X102 is also used to set different BoardIds. If you want to use two frame grabbers with one computer system, each must have a distinct board ID. If jumper is attached from pin1 to pin2 of 8 pin Header/Jumper X102, the BoardId is 1 (Default). With no jumper the BoardId is 3.



## 3.5. Trigger Modes

The P3I3 family members support various trigger modes to satisfy the requirements of varying applications. There are three main modes of operation to distinguish: Softtrigger, Exttrigger and Autottrigger. For all three modes the necessary timing informations for the camera control signals has to be set by software before operation begins. Refer to the software section for adjustable parameters. Both frame grabbers are capable of handling a frame and a line trigger. The trigger inputs are selectable via software and are located either at the connector(s) at the frontpanel or the 16 pos. connector.

### 3.5.1. Softtrigger

In the "Softtrigger Mode" the software defines the starting point of the generated timing. The grabber repeats this timing until it is stopped again by the software.

### 3.5.2. Exttrigger

In the "Exttrigger Mode" acquisition and timing is started by external events on the falling or rising edge of the selected trigger input. After the programmed timing has expired the grabber waits for the next trigger edge to repeat the control cycle. Working with two triggers, e.g. frame trigger and line trigger, is also possible.

### 3.5.3. Autottrigger

In the "Autottrigger Mode" acquisition and timing is started by external events on the falling or rising edge of the selected trigger input. After the programmed timing has expired the grabber repeats the control cycle immediately. Working with two trigger, e.g. frame trigger and line trigger, is also possible.

## 3.6. Specifications

### 3.6.1. Electrical Specifications

#### 3.6.1.1. Specifications for Differential Signals p3i\_DIG

Every differential input signal pair is terminated with a parallel 100 Ohm resistor.

**Table 3.15. Electrical Specifications for Differential Signals p3i\_DIG**

Parameter	Description	Min	Typ	Max	Unit
High Level Input Voltage VIH	At any differential signal pin			3.8	V
Low Level Input Voltage VIL	At any differential signal pin	-0.5			V
Differential Output Voltage  VOD	when using RS422 signaling standard	2			V
Differential Output Voltage  VOD	when using LVDS signaling standard	240	340	454	mV
Common Mode Output Voltage VCO	when using RS422 signaling standard		1.8		V
Common Mode Output Voltage VCO	when using LVDS signaling standard		1.2		V

#### 3.6.1.2. Specifications for Differential Signals p3i\_CL and p3i\_CL/PMC

**Table 3.16. Electrical Specifications for Differential Signals p3i\_CL**

Parameter	Description	Min	Typ	Max	Unit
High Level Input Voltage VIH	At any differential signal pin			3.8	V
Low Level Input Voltage VIL	At any differential signal pin	-0.5			V
Differential Output Voltage  VOD		240	340	454	mV
Common Mode Output Voltage VCO			1.2		V

#### 3.6.1.3. Specifications for TTL Signals

**Table 3.17. Electrical Specifications for TTL Signals**

Parameter	Description	Min	Typ	Max	Unit
High-Level Output Voltage VOH		2			V
Low-Level Output Voltage VOL				0.7	V

High-Level Output Current  IOH				32	mA
Low-Level Output Current  IOL				64	mA

### 3.6.1.4. Specifications for Opto-coupled Input Signals

**Table 3.18. Electrical Specifications for Opto-coupled Input Signals**

Parameter	Description	Min	Typ	Max	Unit
Input forward current If(on)	to turn output on	6.3	15		mA
Input forward current If(off)	to turn output off	0		250	uA

### 3.6.1.5. Power Requirement

**Table 3.19. Power Requirement**

Parameter	Description	Min	Typ	Max	Unit
Icc(max)	Power supply +5V over PCI-Connector with SODIMM(64MB)		1.2		A

### 3.6.1.6. Pixel Clock Frequency of p3i\_DIG

**Table 3.20. Maximum Pixel Clock Frequency**

Parameter	Description	Min	Typ	Max	Unit
Clock-f	For Mode0(1x8),Mode1(2x8),Mode4(1x10), Mode7(1x12), Mode9(1x16)when using LVDS signaling standard			41	MHz
Clock-f	For all other modes when using LVDS signaling standard			38	MHz
Clock-f	when using RS422 signaling standard			30	MHz

### 3.6.1.7. Pixel Clock Frequency p3i\_CL and p3i\_CL/PMC

**Table 3.21. Maximum Pixel Clock Frequency**

Parameter	Description	Min	Typ	Max	Unit
Clock-f	for Mode0(1x8 bit), Mode1(2x8 bit), Mode4(1x10 bit), Mode6(1x12 bit), Mode8(1x14 bit), Mode9(1x16 bit)			66	MHz
Clock-f	for Mode2(3x8 bit), Mode3(3x8 bit RGB), Mode5(2x10 bit), Mode7(2x12 bit)			38	MHz

### 3.6.2. Environmental Conditions

**Table 3.22. Environmental Conditions**

Storage Temperature:	-20° C - 70° C
Operating Temperature:	0° C - 45°C (2 m/s forced air cooling)
Maximum Operating Humidity:	85 % relative

---

## Chapter 4. Trouble Shooting - if it does not work

Check if the driver and the user mode software are installed properly. See chapter *Getting Started*.

Frame Grabber is not found by software:

Make sure the grabber is correctly plugged into the PCI-connector. If mechanical problems can be excluded refer to the driver installation guide to see if the driver has been installed correctly. Mixing up the recommended installation order of hard and software can be a possible reason for an incorrectly installed driver.

No image at all:

Watch the four Status-LEDs when starting the acquisition. If there is no LED switched on the grabber was not found by software. Refer to the driver installation guide. When only LED1 (Board select) and Led2 (Acquisition in progress) are switched on the grabber may receive no frame enable, no line enable or no pixel clock. Check if MDR connector is plugged properly and camera is running.

Getting support:

Under some circumstances you may not succeed in getting everything running. Then you can contact us - but we need the system configuration as exactly as possible. For that purpose we have prepared a support request form where you can fill in your configuration and submit this form (by fax or E-mail) together with the support request - using this form will help us to help you faster.



---

## Chapter 5. Programmers Reference

### 5.1. Overview

#### 5.1.1. Introduction

Frame Grabber configuration tools is the software foundation for ELTEC Elektronik AG frame grabber family.

It is the unified interface used across all frame grabber products.

Frame Grabber configuration tools is one of the most powerful low-level frame grabber interfaces available on the market.

It combines three essential advantages:

- Fast and optimized access to the frame grabber hardware.
- Relieves the program developer from all hardware dependent stuff.
- Unifies the frame grabber interface to switch between the grabber family members.

Special care has been taken to simplify the use of complex camera features like restart-reset modes or acquisition of image sequences.

Applications ranging from simple single image grabbing, up to programming your frame grabber to become a real image sequence machine, are all easily supported by Frame Grabber configuration tools.

#### 5.1.2. Main Features

- Generic software interface for the grabber product line.
- Real-time image acquisition
- Configuration and setup utility included
- Easy setup file handling to store different configurations.
- Powerful virtual to physical memory management during run-time.
- Makes handling of image sequences as easy as single images.
- DLL with complete frame grabber control.

#### 5.1.3. Technical Details

The heart of each frame grabber is ist PCI DMA controller.

All boards work without the need of a frame buffer on-board. Image data is stored directly in the PC s main memory. ELTEC Elektronik AG is using one of the most sophisticated PCI DMA controllers available. ELTEC Elektronik AG frame grabber DMA means FAST & FLEXIBLE. Flexible DMA schemes (scatter-gather DMA - known from UNIX network drivers) allow the acquisition of complete sequences without CPU intervention and without missing a single frame. So, the main advantage of the PCI bus, fast

data transfer PCI burst transfers is extended by ELTEC Elektronik AG with an intelligent PCI DMA.

The Frame Grabber configuration tools make all these features available at your finger tips. ELTEC Elektronik AG's scatter-gather DMA is used to handle paged addresses, resulting in linear, contiguous images appearing in main memory for easy access. With Frame Grabber configuration tools and your frame grabber you are able to break through all restrictions which exist on other PCI frame grabber solutions:

- Your frame grabber is able to acquire directly into linear memory.
- Frame buffer memory is allocated during run-time, NOT during Windows® startup; Low-level software supplied.
- Drivers for Windows XP, Vista, Windows 7 with acquisition into main memory.
- Windows® -based test/setup program.
- On-line documentation supplied as Windows® Help.
- Reallocation of frame buffer memory is easy

With this flexible memory management of the Frame Grabber configuration tools it is easy to use the whole available main memory of your PC to store numbers of different and long image sequences, filling many megabytes of memory. It is as easy as storing a single frame. Only this flexibility gives you the security that your application is able to adapt to different memory needs during run-time and is able to use the whole memory which is physically available on your PC.

#### **5.1.4. Software Concept**

Frame Grabber configuration tools consists of a device driver and a Dynamic Link Library (DLL). It is only natural that the DLL supports the whole frame grabber hardware.

Setup of ADC, look-up table, offset/gain, camera multiplexer, region of interest (acquisition window dimensions), camera selection and setup file support are part of the DLL. Permanent (live), single shot and sequence acquisition of images can be requested and the various states of the acquisition (active/finished) can be inquired.

A test and setup utility, running also under Windows®, allows to adjust all relevant camera parameters and have them stored by the DLL in a file for further use in user applications. It supplies Video-in-a-Window display by using Windows® functions, thus enabling overlapped acquisition windows. The same utility supports test and configuration of the frame grabber board under Windows®.

#### **5.1.5. Source code samples**

Sample source code for using the driver DLL with custom imaging routines is included as well as sample code to set up the frame grabber board, start single shot acquisition and display the image with Windows® display functions and DirectDraw®.

With Frame Grabber configuration tools you are able to concentrate on the important things of the application and not waste time with the Frame Grabber hardware.

Please have a look at the code example below to see how easy it is to set up a frame grabber board and acquire an image sequence, which could include as many frames as you want (dependent on the available PC main memory).

The samples can be downloaded from *ELTEC Elektronik AG* [<http://www.eltec.de>] selecting

*support/drivers and updates.*

### 5.1.6. Industrial requirements

Frame Grabber configuration tools has an extensive built-in camera support making it extremely easy to use non-standard camera features (e.g. restart/reset).

Further, all signals essential to industrial applications are integrated into the Frame Grabber configuration tools. Signals for pixel synchronous acquisition (external clock) and process control (external trigger) are supported.

### 5.1.7. Cameras

With the default jumpering the board is set up for the use of CCIR/EIA-Cameras with no special features. The software supports this camera types by default.

A list of cameras with special features which are already adapted to the software can be found in Appendix A.

### 5.1.8. Developing own applications

The supplied software includes all the files you need to develop applications. It is required that you include only one header file. This file includes all constant definitions, type definitions and function prototypes. After compiling your application you need to link it with one of the different libraries. if your application is to run under Windows, you need to link it with the import library `eleye516.lib` and run it using the dll `eleye516.dll`. Note that the camera file `eleye516.cam` ( see Appendix A ) has to reside in the same directory as `eleye516.dll`. see *ELTEC Elektronik AG* [<http://www.eltec.de>] selecting *support/drivers and updates* for examples of application development using VC++

### 5.1.9. Allocating Image Memory

The advanced security-technique and virtual address-concepts of modern operation systems makes it more difficult to request image memory which is accessible on fixed addresses or by multiple applications. Additionally, modern video hardware is using flexible and fast DMA data transfers to move the images to memory. But using DMA means that access to physical memory is needed to transfer the image data into on board or system memory.

There are several solutions to provide the video hardware with necessary physical addresses. With ELTEC Elektronik AG's imaging API there are different possibilities to request or to create image memory. Dependent on the operating system used the library function `el_InitHW()` and `el_NewMemBuffer()` are able to work with user defined or internal defined image buffers.

In general the library function mentioned above are allocating image memory and the user needs not to care about requesting access permission and organizing and mapping the physical image memory to the virtual address space of a user program. After the acquisition is finished the application is able to access images in a very transparent way by using the supplied image pointers to walk through the image.

But there are different conditions depending on the operating system used to work with image memory allocated by the application. For example if an application must use fixed memory addresses or more than one application must access the image data to process different areas of the image simultaneous.

For this purposes the functions `el_InitHW()` and `el_NewMemBuffer()` are able to work with user defined image buffers in the same way as they work with buffers defined inside these functions.

### 5.1.10. Multiple Grabbers

The software can handle multiple grabbers using the same library. The grabbers need not to be of the

some kind they must only belong to the same 'family' like , , , and .

Because the grabbers of a family may have different hardware resources the function of a few API calls might differ slightly. Please refer to the software reference.

Using grabbers of different families is more complicated because two libraries have to be used. This leads to a collision of the function names in the libraries. So simple linking of both libraries to an application does not work. Depending on the operation system there are possibilities, like dynamical linking, to overcome this problem.

### 5.1.11. Error Handling

In case of failure of a function call, the function `el_GetErrorCode` can be used to get information of the cause. A list of error codes follows later in this chapter.

### 5.1.12. Downloading the software

Please download our software from the web site *ELTEC Elektronik AG* [<http://www.eltec.de>] selecting *support/drivers and updates* or ask our support ( `<support@eltec.de>` ).

### 5.1.13. Image Sequences - Program flow

Image sequences are a very versatile tool for solving some common problems in imaging:

Functional description:

An image sequence consists of  $n$  frames. Each frame is located at a contiguous memory region, the different frames are not allocated contiguously, however. A single snapshot means that a complete sequence of frames is acquired without any CPU intervention. After the snapshot all frames of the sequence are present in memory. Continuous acquisition (live) means that after the last frame of the sequence is in memory the acquisition starts again with the first frame.

Swing buffers:

Swing buffers are used for continuous acquisition where one image buffer is being acquired into and the other is being evaluated; after one frame time the role of the two buffers is interchanged. The most common method is to implement them with interrupts. However, image sequences can be used here, also. A short sequence of 2..4 frames with continuous acquisition makes a first-class swing (ping-pong) buffer.

How far has the acquisition progressed?

Since the acquisition is done completely in hardware, the CPU has no implicit knowledge about which frame is ready for image processing: It can be inquired by `el_TestFrameCount`. Another method is to write a distinct pattern (0xFF00FF00 e.g.) into frame memory and to test if it has been overwritten by the acquisition process.

SAMPLE:

```
// This sample shows the overall sequence of settings things up and acquiring a sequence.
int SizeX=748;
int SizeY=576;
int NumberOfFrames = 100;          /* This needs more than 40 MB of main memory */

BoardId = el_OpenHW( 0, 0); /* Get board handle */
el_InitContext( BoardId, SetupFileName);
/* Initialize library software structures */
```

```

/* Initialize HW and allocate frame buffer */
framearray=(BYTE**)el_InitHW( BoardId, 0, SizeX, SizeY, NumberOfFrames, 0, 0);
/* optional change of hardware parameters come here */

el_Acquire( BoardId, EL_SNAP); /* real-time acquisition of 100 frames */
el_WaitAcq( BoardId); /* wait until sequence has been acquired */

/* optional display the sequence */
/* image processing comes here */

el_Close(BoardId, 0); /* clean up library structures, close HW */

```

### 5.1.14. Calling the library function from languages other than C/C++

All library functions (e.g. `el_OpenHW`) are exported with `_cdecl` calling conventions. To be able to use the library from other languages (e.g. Visual Basic) all routines are exported as `_stdcall` too. These `_stdcall` version are named the same, but have a second `_`. The `_stdcall` version of `el_OpenHW` is `el__OpenHW`.

Usage under Visual Basic

To use the dll functions under Visual Basic you must declare them. Declare Function `el__OpenHW` Lib "eleyex16" (ByVal HexSwitch As Long, ByVal Mode As Long) As Long

`eleyex16` must be replaced by the name of the DLL.

Usage under Pascal

For Pascal or Delphi you can use the `_cdecl` version as well. Declare the routines in a separate unit.

Example

```

Unit grabber_routines;

interface

{ The "cdecl" Version is used. }

function el_OpenHW(HexSwitch, Mode: longint):longint; cdecl;

...

implementation

const LIBNAME = 'eleyex16.dll';

function el_OpenHW; cdecl; external LIBNAME;

...

begin

end.

```

`eleyex16.dll` denotes the name of the dll.

### 5.1.15. Virtual Grabbers

The use Virtuals Grabbers is a concept to handle several independent units on one piece of hardware. So it is possible to control a colour and a black and white acquisition unit as two grabbers.

Virtual grabbers are opened using `el_OpenHWEx` the hex switch selects the board and the SubId parameter is used to select one of the virtual grabber on the board. `el_OpenHW` can still be used but it

can only open the first virtual grabber.

Because the units on a board might not be totally independent virtual grabbers have to be opened and used within one process. If multitasking is required threads have to be used.

Virtual grabbers can be identified with `el_GetBoardIdentifiers`. If at least one "SubId" element in the list filled with `EL_BOARD_IDENTIFIER` structures is not equal 0 all grabbers with the same HexSwitch element are virtual grabbers.

## 5.2. Library Functions

### 5.2.1. Overview of library functions

**Table 5.1. Initialization**

Initialization
<code>el_OpenHW</code>
<code>el_InitContext</code>
<code>el_InitHW</code>
<code>el_CloseHW</code>

**Table 5.2. Configuration and Video Input**

Configuration and Video Input
<code>el_SelectCamera</code>
<code>el_GetSelectedCamera</code>
<code>el_GetSupportedCamFeaturesEx</code>

**Table 5.3. Acquisition and Buffer Management**

Acquisition and Buffer Management
<code>el_Acquire</code>
<code>el_AcquireEx</code>
<code>el_SetAcqWindow</code>
<code>el_NewMemBuffer</code>
<code>el_FreeMemBuffer</code>
<code>el_AssignBuffer</code>
<code>el_CreateMemBuffer</code>

**Table 5.4. Timing/Synchronisation**

Timing/Synchronisation
<code>el_WaitAcqEnd</code>

<u>el_TestFrameCount</u>
<u>el_TestAcq</u>

**Table 5.5. File I/O**

File I/O
<u>el_WriteSetupFile</u>

**Table 5.6. Miscellaneous**

Miscellaneous
<u>el_SetOutputs</u>
<u>el_ResetOutputs</u>
<u>el_GetSetting</u>
<u>el_GetNumOfBoards</u>
<u>el_GetSWRevision</u>
<u>el_GetHWRevision</u>
<u>el_GetErrorCode</u>
<u>el_GetErrorCodeEx</u>

**Table 5.7. Camera Adaptation module functions**

Camera Adaptation module functions
<u>el_SetTriggerModes</u>
<u>el_SetExtTriggerInput</u>
<u>el_SetPixelClock</u>
<u>el_SetExposureTime</u>
<u>el_SetCycleTime</u>
<u>el_GetPixelClock</u>
<u>el_GetExposureTime</u>
<u>el_GetCycleTime</u>

### 5.2.2. el\_Acquire

long  
**el\_Acquire** (long BoardId, EL\_ACQUISITIONMODE Mode);

Starts acquisition for a single frame/field (snap) or for continuous (live) acquisition

PARAMETERS:

BoardId : board ID returned by el\_OpenHW

Mode:

- live: EL\_LIVE
- snap: EL\_SNAP
- or be aborted: EL\_ABORT

RETURN VALUE:

0 if OK

-1 if ERROR See [el\\_GetErrorCode](#) for details.

DESCRIPTION:

Single buffer acquisition:

EL\_LIVE: switches to live mode. A continuous real-time acquisition takes place.

EL\_SNAP: If acquisition is in live mode the acquisition is terminated after the current image has been acquired. If not in live mode, the acquisition is started for a single frame/field. The acquisition stops automatically after one frame/field has been acquired. Use [el\\_TestAcq](#) to wait for acquisition complete.

Image sequence acquisition:

An image sequence is defined with [el\\_InitHW](#) or [el\\_NewMemBuffer](#) if a FrameCount greater than '1' was supplied. Then the following behavior can be expected with [el\\_Acquire](#) :

EL\_LIVE starts an endless sequence acquisition (ring buffer acquisition). In such a case the number of the current frame can be inquired with [el\\_TestFrameCount](#) .

EL\_SNAP acquires exactly one sequence ( number of frames acquired is equal to FrameCount ). Use [el\\_TestFrameCount](#) to detect the acquisition of a frame inside a sequence or [el\\_TestAcq](#) to wait for the whole sequence to complete. See also: [Sequences](#)

Acquisition and external trigger:

If an external trigger is supplied to control the acquisition, the video hardware should be switched to live mode (call [el\\_Acquire](#) with parameter mode set to EL\_LIVE). In case of single-buffer acquisition each trigger pulse causes the hardware to acquire exactly one frame/field. In case of sequence acquisition each trigger causes the hardware to acquire one frame of the sequence. If you call [el\\_Acquire](#) with mode set to EL\_SNAP, the first following pulse causes an acquisition. Every following pulse has no effect. Therefore, EL\_SNAP can be used to disable external trigger acquisition temporarily. EL\_ABORT can be used to disable image acquisition immediately.

CAVEATS:

[el\\_Acquire](#) returns immediately. Therefore, [el\\_TestAcq](#) has to be used to determine the end of an acquisition. There are several other options to inquire the status of an acquisition. Refer to the descriptions of the different [el\\_Test](#) functions supplied in the on-line help.

If live mode is selected and image processing as well as display is active during acquisition, the PCI bus bandwidth may be exceeded, which can be seen from a rolling picture .

EXAMPLE : see [el\\_OpenHW](#)



SEE ALSO: [EL\\_ACQUISITIONMODE](#), [el\\_OpenHW](#) , [el\\_NewMemBuffer](#)

### 5.2.3. **el\_AcquireEx**

```
long  
el_AcquireEx (long BoardId, EL_ACQUISITIONMODE Mode, long *pChannels, long  
*pStart, long *pLength, long NoOfChan, long Reserved);
```

Starts acquisition for a single frame/field (snap) or for continuous (live) acquisition

#### PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Mode:

- live: EL\_LIVE
- snap: EL\_SNAP
- or be aborted: EL\_ABORT

pChannels: is intended to select specific channels, not used at the moment set to 0

pStart: array with index of start frame, for each channel

pLength: array with length of each sub sequence, for each channel

NoOfChan: length of arrays used before, 4 for most grabbers, 1 for

Reserved: set to 0

#### RETURN VALUE:

0 if OK

-1 if ERROR See [el\\_GetErrorCode](#) for details.

#### DESCRIPTION:

This function is an extended version of [el\\_Acquire](#) . for a general description have a look there.

[el\\_AcquireEx](#) is used to start an acquisition on the given channels filling just a part of the originally allocated sequence(s). The start positions for each channel have to be stored in the pStart array. The length of the sequences in the pLength array.

Future versions of the software might use the pChannels array to select special DMA channels. At the moment a 0 pointer has to be used for pChannels and all channels are set up by the function. So NoOfChan has to be set to 1 for and to 4 for all other grabbers.

It is possible to assign one buffer to more than one channel. If one buffer with the sequence length SEQ\_LEN has been assigned to all DMA channels the example below would fill the first quarter of the buffer with data from the first camera, the second quarter with data from the second camera and so on.

An overlapping of subsequences in one buffer is not allowed and can lead to unpredictable effects.

#### EXAMPLE :

```
#define CHNO 4 // number of channels

long pStart[CHNO];
    pStart[0] = 0;
    pStart[1] = 2 * SEQ_LEN/4;
    pStart[2] = 3 * SEQ_LEN/4;
    pStart[3] = 4 * SEQ_LEN/4;

    long pLength[CHNO];
    pLength[0] = SEQ_LEN/4;
    pLength[1] = SEQ_LEN/4;
    pLength[2] = SEQ_LEN/4;
    pLength[3] = SEQ_LEN/4;

    el_AcquireEx(BoardId, EL_SNAP, 0, pStart, pLength, CHNO, 0);
```

SEE ALSO: [el\\_Acquire](#)

### 5.2.4. **el\_AssignBuffer**

```
void **
el_AssignBuffer ( long BoardId, long ChannelNumber, long BufferNo, double
ScaleX, double ScaleY, long Reserved1, long Reserved2 );
```

Assigns a memory buffer to a DMA channel. The scaling factors are fixed to 1.0 .

#### PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

ChannelNumber : DMA channel (0,1,2,3)

BufferNo : Buffer number returned by [el\\_CreateMemBuffer](#)

ScaleX : Scaling factor X-size 1.0

ScaleY : Scaling factor Y-size 1.0

Reserved1 : reserved for future use

Reserved2 : reserved for future use

#### RETURN VALUE:

Pointer to pointer array if OK

0 if ERROR. See [el\\_GetErrorCode](#) for details.

Description:

SEE ALSO: [el\\_CreateMemBuffer](#)

EXAMPLE:

Allocate four buffers, each one for the channels for

```
//
// in our sample we will suppose only one frame sequence
```

```
//
nSequenceLength = 1;

//
// free all buffer before allocating new
//
long BuffId;
for(int i=0; i<4; i++)
{
    NewBuffIds[i]=0;
}
for( i=0; i<4; i++)
{
    // get buffer ID assigned to channel i
    BuffId=el_GetSetting(nBoardID, EL_BUFFERID, i);
    // delete buffer
    if(BuffId >0) el_FreeMemBuffer(0,BuffId);
}
//
// Allocate four buffers, each one for the channels for
//
ppVideoMemory_0 = el_InitHW( nBoardID, NULL, nSizeX, nSizeY, nSequenceLength ,
    0, &NewBuffIds[0]);
if (ppVideoMemory_0 < 0 )
{
    ReportError( "el_InitHW" );
    return;
}
el_AssignBuffer(nBoardID,0, NewBuffIds[0], 1.0, 1.0, 0, 0);

ppVideoMemory_1 = el_CreateMemBuffer(nBoardID, 0, nSizeX, nSizeY,
    (long *) &nSequenceLength, 0, EL_PACKER_Y, EL_INTERLACE, &NewBuffIds[1]);
if (ppVideoMemory_1 < 0 )
{
    ReportError( "el_CreateMemBuffer" );
    return;
}
el_AssignBuffer(nBoardID,1, NewBuffIds[1], 1.0, 1.0, 0, 0);

ppVideoMemory_2 = el_CreateMemBuffer(nBoardID, 0, nSizeX, nSizeY, (long *) &nSequenceLength, 0,
if (ppVideoMemory_2 < 0 )
{
    ReportError( "el_CreateMemBuffer" );
    return;
}
el_AssignBuffer(nBoardID,2, NewBuffIds[2], 1.0, 1.0, 0, 0);

ppVideoMemory_3 = el_CreateMemBuffer(nBoardID, 0, nSizeX, nSizeY, (long *) &nSequenceLength, 0,
if (ppVideoMemory_3 < 0 )
{
    ReportError( "el_CreateMemBuffer" );
    return;
}
el_AssignBuffer(nBoardID,3, NewBuffIds[3], 1.0, 1.0, 0, 0);
```

for allocate 4 buffers and switch the input channel

```
ppVideoMemory_0 = el_InitHW( nBoardID, NULL, nSizeX, nSizeY, nSequenceLength , 0,
    &NewBuffIds[0]);
if (ppVideoMemory_0 < 0 )
{
    ReportError( "el_InitHW" );
    return;
}

ppVideoMemory_1 = el_CreateMemBuffer(nBoardID, 0, nSizeX, nSizeY,(long *) &nSequenceLength,
```

---

```

                                0, EL_PACKER_Y, EL_INTERLACE, &NewBuffIds[1]);
if (ppVideoMemory_1 < 0 )
{
    ReportError( "el_CreateMemBuffer" );
    return;
}

ppVideoMemory_2 = el_CreateMemBuffer(nBoardID, 0,  nSizeX, nSizeY, (long *) &nSequenceLength,
                                0, EL_PACKER_Y, EL_INTERLACE, &NewBuffIds[2]);
if (ppVideoMemory_1 < 0 )
{
    ReportError( "el_CreateMemBuffer" );
    return;
}

ppVideoMemory_3 = el_CreateMemBuffer(nBoardID, 0,  nSizeX, nSizeY, (long *) &nSequenceLength,
                                0, EL_PACKER_Y, EL_INTERLACE, &NewBuffIds[3]);
if (ppVideoMemory_1 < 0 )
{
    ReportError( "el_CreateMemBuffer" );
    return;
}

el_AssignBuffer(nBoardID,0, NewBuffIds[0], 1.0, 1.0, 0, 0);
nRc = el_SetInputMux(m_nBoardID, EL_INPUT_R_A, EL_ADCBW0, 0);
nRc = SnapAndWait();

el_AssignBuffer(nBoardID,0, NewBuffIds[1], 1.0, 1.0, 0, 0);
nRc = el_SetInputMux(m_nBoardID, EL_INPUT_G_A, EL_ADCBW0, 0);
nRc = SnapAndWait();

el_AssignBuffer(nBoardID,0, NewBuffIds[2], 1.0, 1.0, 0, 0);
nRc = el_SetInputMux(m_nBoardID, EL_INPUT_R_A, EL_ADCBW0, 0);
nRc = SnapAndWait();

el_AssignBuffer(nBoardID,0, NewBuffIds[3], 1.0, 1.0, 0, 0);
nRc = el_SetInputMux(m_nBoardID, EL_INPUT_G_A, EL_ADCBW0, 0);
nRc = SnapAndWait();

```

### 5.2.5. el\_CloseHW

```

long
el_CloseHW ( long BoardId, long Mode );

```

Switches hardware back to idle state: Acquisition and DMA stopped. Releases allocated memory. Context becomes invalid. Parameter 'Mode' not implemented.

#### PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

long Mode : not implemented

#### RETURN VALUE:

0 if OK

-1 if ERROR See [el\\_GetErrorCode](#) for details.

SEE ALSO: [el\\_InitHW](#)

## 5.2.6. **el\_CreateMemBuffer**

```
void **  
el_CreateMemBuffer ( long BoardId, void** ppMemStart, long SizeX, long SizeY,  
long *pFrameCount, long Pitch, long PackingMode, long MemForm, long* pBufferNo  
);
```

Similar to [el\\_NewMemBuffer](#) the routine allocates image memory.

Use [el\\_AssignBuffer](#) to assign the buffer to a DMA channel.

### PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

ppMemStart : Pointer to array of pointers to picture buffers. NULL pointer terminates array. Only used if user allocated memory should be locked. On 64 bit systems not available for all grabbers.

SizeX: hor. size of frame buffers

SizeY: vert. size of frame buffers

pFrameCount: pointer to a long variable holding the number of frames allocated. If there is not enough memory to allocate all frames, the number of frames that could be allocated is returned

Pitch: hor. pixel offset between subsequent video lines

PackingMode: Packing mode not used for P3I3. Mode is determined by camera.

MemForm: The memory format (EL\_INTERLACE or EL\_NONINTERLACE)

pBuffNo: Pointer to frame buffer identifier

### RETURN VALUE:

pointer to memory array if OK

0 if ERROR See [el\\_GetErrorCode](#) for details.

SEE ALSO: [el\\_NewMemBuffer](#) , [el\\_FreeMemBuffer](#) , [el\\_AssignBuffer](#)

EXAMPLE: see [el\\_AssignBuffer](#)

## 5.2.7. **el\_FreeMemBuffer**

```
long  
el_FreeMemBuffer ( void** MemStart, long BufferNo );
```

This function releases the previously allocated buffers so that the memory is available for the system again.

### PARAMETERS:

MemStart: set to NULL or Pointer to array of pointers to picture buffers. NULL pointer terminates array.

BufferNo : identifier of buffer to be freed

### RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

CAVEATS: 'BufferNo' specifies the buffer or sequence to be released. If user allocated memory has been used set MemStart to the array used for the allocation of the memory.

### 5.2.8. [el\\_GetBoardIdentifiers](#)

```
long  
el_GetBoardIdentifiers ( EL_BOARD_IDENTIFIER *pArray, long StructSize, long  
ArrayLength, long *pNumOfBoards );
```

Fills the EL\_BOARD\_IDENTIFIER with informations about the installed grabber boards. At the moment a name the hex switch setting and a sub id is returned. For sub IDs > 0 [el\\_OpenHWEx](#) has to be used to open the [virtual grabber](#) .

PARAMETERS:

pArray : user array of EL\_BOARD\_IDENTIFIER stuctures

StructSize : size of a single array element

ArrayLength : number of array elements

\*pNumOfBoards : long pointer to return number of grabbers

RETURN VALUE:

number of bytes copied in each array element if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

CAVEATS: If the number of bytes is less than the actual structure size of [EL\\_BOARD\\_IDENTIFIER](#) an older Dll has been used, in which the structure had less elements. In this case the unknown structure elements remain uninitialised.

SEE ALSO: [EL\\_BOARD\\_IDENTIFIER](#)

```
long BoardCount;  
EL_BOARD_IDENTIFIER IdList[16];  
  
long ByCount=el_GetBoardIdentifiers(IdList,  
                                     sizeof(EL_BOARD_IDENTIFIER),  
                                     16,  
                                     &BoardCount);  
  
if(ByCount > 0)  
    printf("%ld boards found",BoardCount);  
if( sizeof(EL_BOARD_IDENTIFIER) > ByCount)  
    printf("old Dll, only first %ld bytes of structure were set up",ByCount);
```

### 5.2.9. [el\\_GetCycleTime](#)

```
long  
el_GetCycleTime ( long BoardId, long ValSelect, long Reserved2 );
```

BoardId : board ID returned by [el\\_OpenHW](#)

ValSelect : 0: reads the realised value, 1: reads the desired value

DESCRIPTION: Retrieves the current cycle time (for details look at `el_SetCycleTime`). With ValSelect=0 the actually realized value is returned. With ValSelect=1 the desired value is returned. Nearly all cameras have a minimum value due to the time needed for data read out.

if the difference between the desired and the realized value is significant, the minimum or the maximum cycle time of the camera has been exceeded.

RETURN VALUE:

the cycle time if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO:

[el\\_SetExposureTime](#)

[el\\_SetCycleTime](#)

### 5.2.10. `el_GetDriverRevision`

```
char *  
el_GetDriverRevision ( long *Release, long *Revision );
```

Inquires revision of the grabbers hardware driver.

Release : Pointer to long with release

Revision : Pointer to long with revision

RETURN VALUE:

pointer to revision string if OK or NULL if error. See [el\\_GetErrorCode](#) for details.

EXAMPLE:

```
long hwrevlo, hwrevhi, swrevhi, swrevlo, drrevhi, drrevlo;
```

```
el_GetHWRevision( BoardId, &hwrevhi, &hwrevlo );  
el_GetSWRevision( &swrevhi, &swrevlo );  
el_GetDriverRevision( &drrevhi, &drrevlo );
```

### 5.2.11. `el_GetErrorCode`

```
long  
el_GetErrorCode ( void );
```

DESCRIPTION: Inquire error.

RETURN VALUE:

The Error Number

SEE ALSO: [Error Codes](#)

### 5.2.12. **el\_GetErrorCodeEx**

```
long  
el_GetErrorCodeEx ( char *pszBuffer, long lnLen, long nLanguage );
```

DESCRIPTION: Inquire error description string.

pszBuffer: Buffer to be filled with error description string.

lnLen: Length of the buffer that should be filled.

nLanguage: Language of description. Not used yet, set to 0.

RETURN VALUE:

The Error Number

Fills the buffer with a string that gives a short error description and informs where in the library the error occurred .

SEE ALSO: [Error Codes](#)

### 5.2.13. **el\_GetExposureTime**

```
long  
el_GetExposureTime ( long BoardId, long ValSelect, long Reserved2 );
```

BoardId : board ID returned by [el\\_OpenHW](#)

ValSelect :0: reads the realized value, 1: reads the desired value

DESCRIPTION: Retrieves the current exposure time. With ValSelect=0 the actually realised value is returned. With ValSelect=1 the desired value is returned. Due to camera limitations not all values can be realized.

if the difference between the desired and the realized value is significant, the minimum or the maximum cycle time of the camera has been exceeded.

RETURN VALUE:

the exposure time if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO:

[el\\_SetExposureTime](#)

[el\\_GetCycleTime](#)

### 5.2.14. **el\_GetHWRevision**

```
char *  
el_GetHWRevision ( long BoardId, long *High, long *Low );
```



Inquires hardware revision of the video hardware.

**PARAMETERS:**

BoardId : board ID returned by [el\\_OpenHW](#)

High : Pointer to long with high part of revision

Low : Pointer to long with low part of revision

**RETURN VALUE:**

pointer to revision string if OK or NULL if error. See [el\\_GetErrorCode](#) for details.

**EXAMPLE:**

```
long hwrevlo, hwrevhi, swrevhi, swrevlo, drrevhi, drrevlo;

el_GetHWRevision( BoardId, &hwrevhi, &hwrevlo );
el_GetSWRevision( &swrevhi, &swrevlo );
el_GetDriverRevision( &drrevhi, &drrevlo );
```

## 5.2.15. **el\_GetNumOfBoards**

```
long
el_GetNumOfBoards ( void, );
```

Inquires number of installed boards that can be accessed with the software used. This function can be called prior to any other API function to indicate the number of boards available.

**RETURN VALUE:**

Number of boards

number of boards found or '-1' if ERROR. See [el\\_GetErrorCode](#) for details.

**CAVEATS:**

Be sure to use different board selects for each frame grabber board available in the computer. Otherwise [el\\_GetNumOfBoards](#) returns an error. Please refer to the hardware help how to set the board select.

SEE ALSO: [el\\_OpenHW](#)

## 5.2.16. **el\_GetPixelClock**

```
long
el_GetPixelClock ( long BoardId, long ValSelect, long Reserved2 );
```

BoardId : board ID returned by [el\\_OpenHW](#)

ValSelect :0: reads the realized value, 1: reads the desired value

DESCRIPTION: Retrieves the current pixel clock. With ValSelect=0 the actually realized value is returned. With ValSelect=1 the desired value is returned. Because the resolution of the clock generator is very high only small differences should occur.

RETURN VALUE:

the pixel clock if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO:

[el\\_SetPixelClock](#)

## 5.2.17. [el\\_GetSelectedCamera](#)

```
long  
el_GetSelectedCamera ( long BoardId, char *Buffer, long BufferLen );
```

DESCRIPTION: Gets the current camera name.

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Buffer : Buffer for the camera name

BufferLen : length of the buffer

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO: [el\\_SelectCamera](#)

## 5.2.18. [el\\_GetSetting](#)

```
long  
el_GetSetting ( long BoardId, EL_FGITEM Item, long Select );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Item : Constant selecting item to get

Select : if the 'Item' is used for several (hardware) units, 'Select' distinguishes between them. Otherwise 0.

DESCRIPTION: Returns the context value selected with *Item*. Virtually all context settings can be inquired with this function - also minimum and maximum values, such as for acquisition size. Possible values for *Item* see [EL\\_FGITEM](#) and the [el\\_...](#) defines. If the values of independent hardware units (e.g. ADCs) should be inquired the parameter 'Select' determines which value is read. Typical values for 'Select' are 0..4 or the defines used to setup the hardware unit (e.g. [EL\\_ADCBW1](#) for the second ADC).

RETURN VALUE:

value of item selected if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO: [EL\\_FGITEM](#)

EXAMPLE:

```
maxxwid = el_GetSetting (BoardId, EL_MAXACQSIZE, 0);  
if( maxxwid == -1 ) {  
    bErrorOnGetSetting = TRUE;  
}
```

### 5.2.19. [el\\_GetSupportedCamFeaturesEx](#)

```
long  
el_GetSupportedCamFeaturesEx ( long BoardId, long Cam, EL_CAMFEATURES  
*Feature, long StructSize );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Cam : formerly used Camera identifier, now used for mode selection

Feature : Camfeature Structure

StructSize : Size of Camfeature Structure

DESCRIPTION: Fills camera feature structure 'Feature' for selected camera. The feature list contains all features of the selected camera supported with the current software release of the ELTEC Elektronik AG API. Retrieves only cameras supported by the hardware used.

Because in the new software releases the camera is only selected by name, the parameter has changed its meaning:

Value GETFIRSTCAMFEATURE: retrieves the first camera in the list.

Value GETNEXTCAMFEATURE: retrieves the next camera in the list.

GETFEATURESBYNAME: searches for a camera which name was placed in the 'info' parameter of the 'Feature' structure

RETURN VALUE:

0 at the moment, further releases return the number of bytes copied into the structure if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

### 5.2.20. [el\\_GetSWRevision](#)

```
char *  
el_GetSWRevision ( long *Release, long *Release );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Release : Pointer to long with release

Revision : Pointer to long with revision

DESCRIPTION: Inquires software revision of the API library.

RETURN VALUE:

pointer to revision string if OK

NULL if ERROR. See [el\\_GetErrorCode](#) for details.

EXAMPLE:

```
long hwrevlo, hwrevhi, swrevhi, swrevlo, drrevhi, drrevlo;  
el_GetHWRevision( BoardId, &hwrevhi, &hwrevlo ); el_GetSWRevision( &swrevhi, &swrevlo );  
el_GetDriverRevision( &drrevhi, &drrevlo );-->
```

### 5.2.21. **el\_InitContext**

```
long  
el_InitContext ( long BoardId, char *Filename );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Filename : name of parameter file with path name

DESCRIPTION: Initializes internal software structures with data read from a setup file. This data will be used to initialize the video hardware by [el\\_InitHW\(\)](#) later.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

DESCRIPTION:

If *Filename* is NULL, the following default data will be prepared for initialization:

CCIR camera timing, interlace

If the file specified with *Filename* is not found or can't be opened a error is returned.

CAVEATS: No setup of hardware is done. This function sets up the software parameter structure only.

SEE ALSO: [el\\_InitHW](#)

### 5.2.22. **el\_InitHW**

```
void**  
el_InitHW ( long BoardId, void** MemStart, long SizeX, long SizeY, long  
FrameCount, long Pitch, long *BuffNo );
```

## PARAMETERS:

BoardId : board ID returned by el\_OpenHW

MemStart : Pointer to array of pointers to picture buffers, NULL pointer terminates array.

SizeX : hor. size of frame buffers

SizeY : vert. size of frame buffers

FrameCount : number of frames allocated

Pitch : hor. pixel offset in pixel between subsequent video lines

BuffNo : Pointer to frame buffer identifier

DESCRIPTION: Initializes the video hardware with parameters prepared with el\_InitContext().

## RETURN VALUE:

Pointer to image pointer array if OK

0 if ERROR. See el\_GetErrorCode for details.

## Library defined Image Memory Buffers:

If *MemStart* is NULL el\_InitHW allocates the necessary memory for the requested picture (frame) buffers.

*FrameCount* specifies the number of buffers in a sequence. If *FrameCount* is 0, the value for the frame count is determined by the setupfile used with el\_InitContext. el\_InitHW allocates as much frame buffers as specified with *FrameCount*. The pointers to these frame buffers are stored in an array allocated by el\_InitHW. A pointer to this array is returned if enough memory for frame buffers is available. See also: Sequences

It is not allowed to modify the values in this array, because it is used every time the buffer is reselected. Please make a copy of this array and use the entries of the copy to access the image. Each pointer of the array points to a contiguous image frame buffer. This ensures that you can read and write image data from any location in the image just by modifying the supplied pointers (or the copies).

*Pitch* specifies the offset in pixel between the start locations of two following lines in an image. If *Pitch* is set to 0, the width of the image is used as pitch (on HiPerCam1 *Pitch* is always equal to *SizeX*). Every change of the image width (e.g. by calling el\_SetAcqWindow) will change the pitch too, if the buffer was created with the *Pitch* parameter set to 0. Otherwise it is fixed to the specified value.

## User defined Image Memory Buffers:

User defined image memory buffers can be used by the library for image acquisition under the following conditions:

*On 64 bit systems user defined memory can only be used with the PCEYE 600/610 grabbers.*

If *MemStart* is not NULL it is expected that *MemStart* points to an array of valid image buffer pointers. The supplied pointer array must be NULL terminated. Furthermore it is expected that *SizeX* and *SizeY* are not 0 and specify the X/Y dimension of each image buffer allocated by the user.

In this case el\_InitHW does not allocate image memory it uses the supplied image buffers. The size of the current acquisition window is adapted to the supplied *SizeX/SizeY* values to make the image data fit into

the supplied memory buffers.

*FrameCount* specifies the number of buffers in a sequence. If *FrameCount* is 0/1 only a single buffer is used for image acquisition.

*Pitch* specifies the offset in pixel between the start locations of two following lines of an image. *Pitch* must supply the value (horizontal X dimension) used to allocate the image memory buffer. With user defined image buffers the *Pitch* is fixed to the specified value, e.g. a call to el\_SetAcqWindow will not change the *Pitch*.

The image buffer pointers supplied with *MemStart* are returned by el\_InitHW() for compatibility reasons.

Identification of Image Memory Buffers:

If more than one sequence is defined the returned value in *\*BuffNo* can be used by el\_NewMemBuffer to switch between sequences already allocated. If only one sequence is used, *BuffNo* can be set to NULL (**WARNING** NULL can not be used with current software release). In this case no identifier is assigned for the buffer.

CAVEATS: When the function is called, all frame buffers created before are invalid, and a new buffer or sequence is created depending on the parameters of the function. Single buffers and sequences can be freed by the function el\_FreeMemBuffer.

User defined image memory:

To use user defined image memory together with el\_InitHW some conditions have to mentioned:

If image memory is allocated with malloc() or with user specific allocation routines the start address of each image buffer passed to el\_InitHW must be page (on HiPerCam1 0x20000) aligned otherwise el\_InitHW will return with error.

To request page aligned memory, please use one of the following methods:

The function VirtualAlloc() reserves or commits a region of memory in the virtual address space of your application. Memory allocated with VirtualAlloc() can not be exported to other applications.

To use memory mapped files as shared memory for multiple applications use the functions CreateFileMapping() and MapViewOfFile(). For detailed information, please refer to the function description within the Windows SDK. Allocating Image Memory

SEE ALSO: el\_NewMemBuffer, el\_FreeMemBuffer

EXAMPLE:

```
// Initialize buffers with default sizes.
if((vidbufpoi = el_InitHW (BoardId, NULL, 0, 0, 0, 0, 0))
    == NULL){
    sprintf( str, "Initializing video hardware. (err-no: %d)",
        el_GetErrorCode() );
    MessageBox( NULL, str, "Error", MB_OK ); /* Windows only */
    bErrorOnHardwareInit = TRUE;
}
```

### 5.2.23. el\_NewMemBuffer

```
void**
el_NewMemBuffer ( long BoardId, void** MemStart, long SizeX, long SizeY, long
FrameCount, long Pitch, long *BuffNo );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

MemStart : Pointer to array of pointers to picture buffers. NULL pointer terminates array.

SizeX : hor. size of frame buffers

SizeY : vert. size of frame buffers

FrameCount : number of frames allocated

Pitch : hor. pixel offset between subsequent video lines

BuffNo : Pointer to frame buffer identifier

DESCRIPTION: Activates and/or allocates memory buffer for acquisition.

#### RETURN VALUE:

Pointer to pointer array if OK

.

0 if ERROR. See [el\\_GetErrorCode](#) for details.

Library defined Image Memory Buffers:

If *MemStart* is NULL [el\\_NewMemBuffer\(\)](#) allocates the necessary memory for the requested picture (frame) buffers.

The size of the frame buffers allocated and the size of the images acquired is specified with *SizeX* and *SizeY*.

*FrameCount* specifies the number of buffers in a sequence. If *FrameCount* is 0, the value for the frame count is determined by the setup file used with [el\\_InitContext](#) . [el\\_NewMemBuffer](#) allocates as much frame buffers as specified with *FrameCount*. The pointers to these frame buffers are stored in an array allocated by [el\\_NewMemBuffer](#) . A pointer to this array is returned if enough memory for frame buffers is available. See also: Sequences

It is not allowed to modify the values in this array, because it is used constantly, the buffer is reselected. Please make a copy of this array (if auto-incrementing pointers are needed) and use the entries of the copy to access the image. Each pointer of the array points to a contiguous image frame buffer. This ensures that you can read and write image data from any location in the image just by modifying the pointers supplied.

*Pitch* specifies the pixel offset between the start locations of two following lines in an image. If *Pitch* is set to 0, the width of the image is used as pitch (on HiPerCam1 *Pitch* is always equal to *SizeX*). Every change of the image width (e.g. by calling [el\\_SetAcqWindow](#) ) will change the pitch too, if the buffer was created with the *Pitch* parameter set to 0. Otherwise it is fixed to the specified value.

User defined Image Memory Buffers:

User defined image memory buffers can be used by the library for image acquisition under the following conditions:

*On 64 bit systems user defined memory can only be used with the PCEYE 600/610 grabbers.*

If *MemStart* is not NULL it is expected that *MemStart* points to an array of valid image buffer pointers. The supplied pointer array must be NULL terminated. Furthermore it is expected that *SizeX* and *SizeY* are not

0 and specify the X/Y dimension of each image buffer allocated by the user.

Then `el_NewMemBuffer` does not allocate image memory it uses the supplied image buffers. The size of the current acquisition window is adapted to the supplied SizeX/SizeY values to make the image data fit into the supplied memory buffers.

*FrameCount* specifies the number of buffers in a sequence. If *FrameCount* is 0/1 only a single buffer is used for image acquisition.

*Pitch* specifies the offset between the start locations of two following lines in an image. *Pitch* must supply the value (horizontal X dimension) used to allocate the image memory buffer. With user defined image buffers the *Pitch* is fixed to the specified value, e.g. a call to `el_SetAcqWindow` will not change the *Pitch*.

The image buffer pointers supplied with *MemStart* are returned by `el_InitHW` for compatibility reasons.

Identification of Image Memory Buffers:

If new memory buffers should be created by `el_NewMemBuffer` or if new user defined memory buffers are passed to `el_NewMemBuffer` the pointer used as parameter 'BuffNo' has to point to a long value initialised with 0. Then a new buffer or sequence is added and the identifier of the new buffer is placed in *\*BuffNo*. If the pointer used for 'BuffNo' points not to a 0 value the value is interpreted as a buffer handle and the function tries to switch to the specified buffer sequence. In this case no new buffer sequence is created. For a discussion of sequences used as swing buffers see [Sequences](#)

CAVEATS: When the function is called a new buffer or sequence is created depending on the parameters of the function. Single buffers and sequences can be freed by the function `el_FreeMemBuffer`.

User defined image memory

To use user defined image memory together with `el_NewMemBuffer()` some conditions have to mentioned:

If image memory is allocated with `malloc()` or with user specific allocation routines (on HiPerCam1 0x20000) the start address of each image buffer passed to `el_NewMemBuffer` must be page aligned otherwise `el_NewMemBuffer` will return with error.

Windows only:

To request page aligned memory, please use one of the following methods:

The function `VirtualAlloc()` reserves or commits a region of memory in the virtual address space of your application. Memory allocated with `VirtualAlloc()` can not be exported to other applications.

To use memory mapped files as shared memory for multiple applications use the functions `CreateFileMapping()` and `MapViewOfFile()`. For detailed information please refer to the function description within the Windows SDK. Allocating Image Memory

SEE ALSO: `el_InitHW`

## 5.2.24. `el_OpenHW`

```
long  
el_OpenHW ( long BoardSelect, long Mode );
```

Basic setup of selected video hardware - no initialization of video frontend. `el_OpenHW` returns an unique board ID for each video hardware. The board ID returned by this function will be needed for all subsequent calls of the library to access the corresponding video hardware.

PARAMETERS:



BoardSelect: board number

Mode: force basic setup yes/no

#### RETURN VALUE:

Board ID of board initialized successfully

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

#### DESCRIPTION:

If the board specified with *BoardSelect* is not initialized yet, `el_OpenHW()` does the basic setup of the video hardware and returns an unique board ID. If the board specified with *BoardSelect* is already initialized, an error is returned.

To force a basic setup of the video hardware, if it is initialized or not, the parameter *Mode* must be set to 1. *Mode* = 1 must only be used when it is made sure that no other application is using the same video hardware.

#### CAVEATS:

If a single board is used *BoardSelect* can be set to 0. With 0 the first board found on the bus is initialised. If you use multiple boards in one PC the *BoardSelect* supplied must be higher than 0 and correspond to the value set with the on-board hex switch of the grabber board. Otherwise you will get no board ID for the grabber hardware. For example: If the hex switch on the board is set to '8' *BoardSelect* must be equal '8' to get the board ID.

Errors may occur if an invalid *BoardSelect* parameter or a software revision incompatible with the hardware revision is used. Other reasons are that '`el_OpenHW`' was called for the second time with *Mode* = 0 or that two or more grabber boards have the same hex switch value.

SEE ALSO: [el\\_CloseHW](#) , [el\\_GetNumOfBoards](#)

#### EXAMPLE:

```
// Open the hardware
nBoardID = el_OpenHW( nHexSwitch, 0 );
if ( nBoardID < 0 ) {
    ReportError( "el_OpenHW" );
    return FALSE;
}

//
// Init context
//
char *pName = (szContextFile && szContextFile[0]) ? szContextFile : NULL;
int nRc = el_InitContext( nBoardID, pName );
if ( 0 != nRc ) {
    int nError = el_GetErrorCode();
    return FALSE;
}

//
// Allocate Frame-Buffers
//
long nDummy = 0;
ppVideoMemory = el_InitHW( nBoardID, NULL, 0, 0, nSequenceLength, 0, &nDummy );
if ( !ppVideoMemory )
```

```
{
    nError = el_GetErrorCode();
    return FALSE;
}
nRc = el_Acquire( nBoardID, EL_SNAP );
if ( 0 != nRc ) {
    nError = el_GetErrorCode();
    return FALSE;
}
else {
    // Wait for Acquisition end
    nRc = el_WaitAcqEnd( nBoardID );

    if ( 1 != nRc ) {
        nError = el_GetErrorCode();
        return FALSE;
    }
}
//
// Get settings
//
nSizeX = el_GetSetting(nBoardID, EL_ACQSIZEEX, 0);
nSizeY = el_GetSetting(nBoardID, EL_ACQSIZEY, 0);
```

### 5.2.25. el\_OpenHWEx

long  
**el\_OpenHWEx** ( long BoardSelect, long Mode, char \*pFirmWare, long SubId, long Reserved );

Extended version of el\_OpenHW, which allows the selection of a special firmware version (not implemented yet). If a board with virtual grabber s is used these virtual grabber s can be opened using the SubId parameter.

For the basic functionality please refer to el\_OpenHW

#### PARAMETERS:

BoardSelect: board number

Mode: force basic setup yes/no

pFirmWare: not used yet, should allow to load a special firmware version

SubId: only used on grabber with virtual grabber s to open them.

Reserved: reserved for further use. Set to 0.

#### RETURN VALUE:

Board ID of board initialized successfully

-1 if ERROR. See el\_GetErrorCode for details.

SEE ALSO: el\_GetBoardIdentifiers

#### EXAMPLE:

```
long BoardId[16];
long LastHex=-1;

int i;
long BoardCount;
EL_BOARD_IDENTIFIER IdList[16];

// get list of all installed boards
long ByCount=el_GetBoardIdentifiers(IdList,
                                     sizeof(EL_BOARD_IDENTIFIER),
                                     16,
                                     &BoardCount);

// open all boards installed in the computer
for(i=0; i< BoardCount; i++)
{
    BoardId[i] = el_OpenHWEx( IdList[i].HexSwitch, 0,"",IdList[i].SubId,0 );
    if(LastHex == IdList[i].HexSwitch)
    {
        if(LastHex == IdList[i-1].HexSwitch)
        {
            printf(" %s is a virtual sub grabber",IdList[i-1].Name);
        }
        printf(" %s is a virtual sub grabber",IdList[i].Name);
    }
    LastHex = IdList[i].HexSwitch;
}
```

### 5.2.26. **el\_ResetOutputs**

```
long
el_ResetOutputs ( long BoardId, long Value );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Value : Output value

DESCRIPTION: This function is used to reset available output lines on the hardware. Each bit of *Value* refers to an output line. Therefore, all bits set in *Value* reset the correspondent output line.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

### 5.2.27. **el\_SelectCamera**

```
long
el_SelectCamera ( long BoardId, char *CameraName );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

CameraName : The camera name

DESCRIPTION: Sets a camera defined in the camera file.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO: [el\\_GetSelectedCamera](#)

EXAMPLE:

```
//  
// Get camera name  
//  
szCameraName = new char [50];  
nRc = el_GetSelectedCamera(nBoardID, szCameraName, 50);  
if (0 != nRc) {  
    ReportError( "el_GetSelectedCamera" );  
    return;  
}
```

## 5.2.28. **el\_SetAcqWindow**

```
long  
el_SetAcqWindow ( long BoardId, long StartX, long StartY, long SizeX, long  
SizeY );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

StartX : hor. start of image

StartY : vert. start of image

SizeX : hor. size of image

SizeY : vert. size of image

DESCRIPTION: Sets acquisition window relative to camera image (video-timing) in units of pixels. The absolute start position within video timing is calculated internally by the DLL and depends on the camera type selected with [el\\_SelectCamera](#) . Therefore, the DLL makes the necessary post-settings for each camera to adjust the upper and the left margin. If *StartX* and *StartY* are set to '0', the acquisition window starts with the first valid upper left pixel of the camera. Therefore, the caller does not have to care about invalid pixels (black front porch) in the camera timing.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

*SizeX* and *SizeY* specify the amount of pixels that should be acquired and transferred to the frame buffers allocated. If the allocated frame buffers are smaller than *SizeX* \* *SizeY*, an error is returned. *StartX* + *SizeX* resp. *StartY* + *SizeY* must not be smaller than the limits imposed by the camera. The maximum values for *SizeX/SizeY* can be inquired with [el\\_GetSetting](#) .

If the acquisition memory format is set to interlace acquisition, all acquisition window parameters must be specified as frame-related values. If the acquisition memory format is set to non-interlace, the window parameters must be specified as field-related values.

The hardware does not allow to set the window parameter in units of one pixel. Therefore, the values programmed can be inquired with [el\\_GetSetting](#) (EL\_ACQSTARTX, EL\_ACQSTARTY, EL\_ACQSIZEX, EL\_ACQSIZEY).

EXAMPLE:

```
el_SetAcqWindow( BoardId, StartX, StartY, SizeX, SizeY );
```

### 5.2.29. [el\\_SetCycleTime](#)

```
long  
el_SetCycleTime ( long BoardId, long CycleTime, long Reserved1, long Reserved2  
);
```

BoardId : board ID returned by [el\\_OpenHW](#)

CycleTime : time in us after which an new trigger pulse is detected

DESCRIPTION: Sets the desired cycle time (in micro seconds) after which the camera can be retrigged. In auto trigger mode this value determines the line frequency for line cameras and the frame frequency for frame cameras. Nearly all cameras have a minimum value, determined by the data readout time and in some cases also by the exposure time . If a values below this limit is set the value is automatically increased to the minimum value. The realized and the desired values can be obtained with [el\\_GetCycleTime](#).

If external trigger is used the desired value should be set to 0.

For cameras which do not use the clock generated on the board the use of [el\\_SetPixelClock](#) is still necessary because the values set there are used for the necessary timing calculations. For some cameras it is possible, that the parameters set by [el\\_SetScriptPara](#) influence the timing too. In these (rare) cases the meaning of the parameters is described in the "camera.htm" file.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO:

[el\\_SetExposureTime](#)

[el\\_GetCycleTime](#)

### 5.2.30. [el\\_SetExposureTime](#)

```
long  
el_SetExposureTime ( long BoardId, long ExpTime, long Reserved1, long  
Reserved2 );
```

BoardId : board ID returned by [el\\_OpenHW](#)

ExpTime :desired exposure time in microseconds

DESCRIPTION: Sets the desired exposure time in micro seconds. For some cameras not all values can be realised. In these cases the function sets the exposure time to the next possible value. The realized and the desired values can be obtained with `el_GetExposureTime`. For cameras which do not use the clock, generated on the board, the use of `el_SetPixelClock` is still necessary because the values set there are used for the timing calculations.

RETURN VALUE:

0 if OK

-1 if ERROR. See `el_GetErrorCode` for details.

SEE ALSO:

`el_GetExposureTime`

`el_SetCycleTime`

### 5.2.31. `el_SetTriggerModes`

```
long  
el_SetTriggerModes ( long BoardId, long FrameTrigger, long LineTrigger, long  
Reserved );
```

PARAMETERS:

BoardId : board ID returned by `el_OpenHW`

FrameTrigger : mode of frame trigger, see below for list

LineTrigger : mode of line trigger, see below for list

DESCRIPTION: Sets the line and the frame trigger to one of the following modes:

RETURN VALUE:

0 if OK

-1 if ERROR. See `el_GetErrorCode` for details.

*AUTOTRIGGER:*

grabber waits for no signal at the end of a line/frame.

*EXTERNALTRIGGER:*

Grabber waits at the end of a line/frame for an external signal. If frame and line trigger are set to EXTERNALTRIGGER the line trigger event is taken from the OPTO\_2 input and the frame trigger can be selected by `el_SetExtTriggerInput`. If for one of the triggers ( frame or line) AUTOTRIGGER is selected the other trigger can be selected without restriction. E.g. if the frame trigger runs in AUTOTRIGGER mode the line trigger is no longer restricted to OPTO\_2.

### 5.2.32. `el_SetExtTriggerInput`

```
long
```

```
el_SetExtTriggerInput ( long BoardId, long CamSel, long TriggerInput );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

CamSel : Selects camera; set to 0

TriggerInput : Selects the external trigger input

DESCRIPTION: Selects one of six possible types of external trigger inputs:

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

*EL\_TRIG\_OPTO\_0*: optical decoupled input 0, uses pins Trigin0 + and Trigin0 - on 100 pin MDR connector

*EL\_TRIG\_OPTO\_1*: optical decoupled input 1, uses pins Trigin1 + and Trigin1 - on 16 pin connector

*EL\_TRIG\_TTL\_0*: TTL input 0, located on 100 pin MDR connector

*EL\_TRIG\_TTL\_1*: TTL input 1, located on 16 pin connector

*EL\_TRIG\_TTL\_2*: TTL input 2, located on 16 pin connector

*EL\_TRIG\_OPTO\_2*: optical decoupled input 1, uses pins Trigin2 + and Trigin2 - on 16 pin connector. Used as line trigger input if external frame and external line trigger are used together.

### 5.2.33. **el\_SetOutputs**

```
long  
el_SetOutputs ( long BoardId, long Value );
```

PARAMETERS:

BoardId : board ID returned by [el\\_OpenHW](#)

Value : Output value

DESCRIPTION: This function is used to set output lines, if available on the hardware. Each bit of *Value* refers to an output line. Therefore, all bits set in *Value* set the correspondent output line.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

### 5.2.34. **el\_SetPixelClock**

```
long  
el_SetPixelClock ( long BoardId, long Frequency, long Reserved1, long
```

Reserved2 );

BoardId : board ID returned by [el\\_OpenHW](#)

Frequency : Frequency in Hz

Reserved1 :

DESCRIPTION: Sets the pixel clock generated on the board. The value has to be specified in Hz. If a camera uses its own clock, the value has to be set to the frequency of the camera clock, because it is used for timing calculations. The realized and the desired frequency can be obtained with [el\\_GetPixelClock](#).

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

SEE ALSO:

[el\\_GetPixelClock](#)

### 5.2.35. [el\\_TestAcq](#)

```
long  
el_TestAcq ( long BoardId );
```

DESCRIPTION: Test if acquisition is active (on). This function can be used as a replacement for [el\\_WaitAcqEnd](#) if the programmer wants to check different other conditions or works on the image while he is waiting for the end of a acquisition e.g. useful in a multitasking environment.

RETURN VALUE:

1 if acquisition is running

0 if acquisition is not running

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

Single buffer acquisition

A single snap was triggered with acquisition mode `EL_SNAP`. Then `el_TestAcq()` returns '0' after the frame was transferred into memory. During acquisition '1' is returned.

Image sequence acquisition:

A single sequence acquisition was triggered with acquisition mode `EL_SNAP`. Then `el_TestAcq()` returns '0' after the last frame of the sequence was transferred to memory. During sequence acquisition '1' is returned.

CAVEATS: This function looks at the DMA transfer of data into data memory and not directly to the camera's frame timing.

EXAMPLE



```
// Acquire one frame
el_Acquire (BoardId, EL_SNAP);

do {
    ...;
} while( el_TestAcq( BoardId ) || Timeout-- );
```

## 5.2.36. el\_TestFrameCount

```
long
el_TestFrameCount ( long BoardId );
```

DESCRIPTION: Returns contents of the frame-counter. [el\\_TestFrameCount](#) is used to determine the currently used acquisition buffer during a running sequence acquisition. It is ensured that the frame count returned specifies the frame which is present in memory. Consequently, [el\\_TestFrameCount](#) can be used to pick a single frame out of a big image sequence during acquisition easily.

RETURN VALUE:

modulo 255 of the number of the last completely acquired frame if OK

-1 if Error. See [el\\_GetErrorCode](#) for details.

CAVEATS: The counter is incremented by every transfered frame.

After an [el\\_Acquire](#) command this 8 bit counter is set to 0. Immediately after the completion of the first image the counter value is increased to 1 and for every following image the value is increased until 255 has been reached. With the end of the following image the counter is reset to 0. Due to this behavior a sequence length equal to a power-of-two is recommended because then the actual image number can be obtained by a simple modulo operation.

## 5.2.37. el\_WaitAcqEnd

```
long
el_WaitAcqEnd ( long BoardId );
```

DESCRIPTION: Wait until acquisition is finished.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

Single buffer acquisition

A single snap was triggered with acquisition mode EL\_SNAP. Then [el\\_WaitAcqEnd](#) returns after the frame was transferred into memory.

Image sequence acquisition:

A single sequence acquisition was triggered with acquisition mode EL\_SNAP. Then [el\\_WaitAcqEnd](#) returns after the last frame of the sequence was transferred to memory. See also: Sequences

CAVEATS: This function looks at the end of the DMA transfer of data into data memory and not directly to the camera's frame timing. It returns only when the DMA transfer of frames is finished and the acquisition

is stopped, or a time-out is reached. Therefore, this function can be used to determine the end of an acquisition triggered with [el\\_Acquire](#) .

SEE ALSO: [el\\_TestAcq](#)

EXAMPLE:

```
// Acquire one frame/sequence
el_Acquire (BoardId, EL_SNAP);

// wait until frames are present in memory
if( el_WaitAcqEnd( BoardId ) == -1 ) {
    if( el_GetErrorCode() == EL_E_ACQTIMEOUT ) {
        MessageBox (NULL, "No video input.", "Error", MB_OK);
    }
}
```

## 5.2.38. el\_WriteSetupFile

```
long  
el_WriteSetupFile ( long BoardId, char* Filename, long Overwrite );
```

Filename : pointer to string with name of setup file and path

Overwrite : '1' if file should be overwritten, '0' otherwise

DESCRIPTION: Saves all current settings into a file. If the file specified with '*Filename*' exists, it is not updated. Only if *Overwrite* is set to '1' the function can be forced to overwrite an existing file. If *Overwrite* is set to '0' and the file exists the function will return '-1' and the error code is set to EL\_E\_FILEEXIST.

RETURN VALUE:

0 if OK

-1 if ERROR. See [el\\_GetErrorCode](#) for details.

The setupfile are not compatible for the different grabbers.

Must be used before [el\\_CloseHW](#) .

EXAMPLE:

```
if ( el_WriteSetupFile(BoardId, Filename, 0 ) == -1) {  
    if( el_GetErrorCode() == EL_E_FILEEXIST){  
        el_WriteSetupFile(BoardId, Filename, 1 )  
    }  
    else {  
        // e.g. wrong path specified or other I/O error  
    }  
}
```

## 5.3. Defines

### 5.3.1. EL\_ACQUISITIONMODE

UDSED IN: [el\\_Acquire](#)

**Table 5.8. Acquisitionmode**

EL_SNAP	stop acquisition or acquisition of one frame
EL_LIVE	live acquisition
EL_ABORT	abort ongoing acquisition immediately

### 5.3.2. Error codes

Error and warning codes returned by [el\\_GetErrorCode](#) and [el\\_GetErrorCodeEx](#)

**Table 5.9. Warning codes**

EL_W_WRONGREVISIONCRC	4	Wrong CRC in hardware revision EEPROM
EL_W_ACQWINDOWTOOBIG	3	Acquisition window too big for the camera selected; will be made smaller automatically
EL_W_INLUTINDEXTOOBIG	2	The requested entry of the input look-up table does not exist. Valid values are 0..255.
EL_W_HWALREADYOPENED	1	The hardware has been opened without subsequent close. This may indicate that another task uses the DLL already, which will lead to errors. The cause may also be, that the DLL was not closed properly by an aborted task which can be tolerated.

**Table 5.10. Unknown error codes**

EL_UNKNOWNERROR	0	Unknown error
-----------------	---	---------------

**Table 5.11. Error codes**

EL_E_WRONGBOARDSELECT	-1	Board select parameter in function el_OpenHW invalid.
EL_E_HWNOPENED	-2	Hardware has not been opened - call 'el_OpenHW' prior to the offending call.
EL_E_BIOSNOTCORRECT	-3	PCI Bios may not be present. The BIOS call 'Find PCI Bios' did not return correct values. This call verifies no hardware access yet, it checks only that the BIOS can handle PCI functions and that it complies with PCI rev. 2.0.
EL_E_NOPCEYEFOUND	-4	No grabber board could not be found on PCI. This indicates that the PCI Bios of the computer is not capable of finding the grabber. Grabbers can be identified by the driver in a unique way ('Find PCI device' and software-readable signature string)
EL_E_PCEYESYSTEMMEMORY	-5	
EL_E_FRAMEBUFALLOC	-6	Memory for the frame buffer in the requested size could not be allocated. Closing other applications may help.
EL_E_CONTEXTNOTINIT	-7	The driver-internal context structure must be initialized first by calling el_InitContext.
EL_E_HWNOPENED	-8	Call el_InitHW before using other functions.
EL_E_PITCHTOOSMALL	-9	The acquisition pitch is smaller than the horizontal image size.
EL_E_MEMORYALLOC	-10	Internal memory allocation failed. Closing other applications may help.
EL_E_WRONGCAMERASELECT	-11	An invalid camera input number (0..3) is given.
EL_E_ACQWINDOWTOOBIG	-12	The acquisition window is too big for the camera selected. May indicate not enough memory. See

		description of 'el_NewMemBuffer'.
EL_E_WRONGBOARDID	-13	No board with this ID is open.
EL_E_ADCREFLEVELS	-14	Invalid reference values for analog-to-digital converter given.
EL_E_FILEOPEN	-15	File not existing or otherwise not accessible.
EL_E_FILEIO	-16	Read or write error during file I/O.
EL_E_FILECHECKSUM	-17	Wrong checksum for setup parameter file. Parameter file corrupted. Write new file or restore backup file.
EL_E_UNKNOWNSETUPVERSION	-18	Version code in setup file wrong. Setup file may have been written with newer driver version. Write or use new setup file.
EL_E_FRAMEBUFFFREE	-19	Attempt to free frame buffer failed.
EL_E_FILEEXIST	-20	Attempted to write existing file.
EL_E_UNKNOWNACQMODE	-21	A number for a non-existing acquisition mode is given.
EL_E_FUNCNOTAVAILABLE	-22	Not implemented yet or wrong function code.
EL_E_ACQTIMEOUT	-23	The driver waits a certain time (about 5 frame times) for the acquisition to finish. Normally, this error occurs when the camera is not connected or powered down.
EL_E_INVALIDPARAMETER	-24	Invalid function parameter supplied.
EL_E_INVALIDPOINTER	-25	Invalid pointer supplied.
EL_E_WRONGPCEYE386REV	-26	The driver DLL needs another program, a so-called VxD, to function properly. This program was found but has a revision not fitting with the current DLL.
EL_E_UNKNOWNACQFORMAT	-27	A number for a non-existing acquisition format is given.
EL_E_READREVISIONINFO	-28	The hardware revision info PROM on the grabber cannot be read.
EL_E_WRONGBUFFERNO	-29	A number for a non-existing buffer is given.
EL_E_EXTCLKNOTSUPPORTED	-30	This message is sent when hardware revision 0.x (1.A) is used with external camera clock. The external clock input is not supported for this hardware revision. Or this software does not support external clock for the current camera.
EL_E_RESTARTNOTSUPPORTED	-31	This message is sent when hardware revision 0.x (1.A) is used in restart mode. The external trigger input is not supported for this hardware revision. Or this software does not support restart for the current camera.
EL_E_SHUTTERNOTSUPPORTED	-32	This message is sent when hardware revision 0.x (1.A) is used with shutter control. Or this software does not support shutter control for the current camera.
EL_E_INIPCIBASE1NOTSET	-33	The grabbers I/O-mapped hardware address could not be set by the BIOS.
EL_E_INIPCIEXP1NOTSET	-34	The grabbers memory-mapped hardware address is set to a value equal 0.

EL_E_BIOSFUNCTIONCALL	-35	The Bios did not execute one of the following PCI Bios calls properly (returned an error): 'Find PCI device', 'Write configuration word', 'Read configuration word'. The Bios call did finish without an error, but the address cannot be read back. May indicate that the boards does not sit firmly in its connector.
EL_E_NOHARDWARESUPPORT	-36	This special feature is not supported by the used hardware revision.
EL_E_FRAMECOUNTTOOBIG	-37	The value for framecount is greater than the max. possible value.
EL_E_DATAFIFOOVERFLOW	-38	The transfer of image data is corrupted. The last image transferred is not correct.
EL_E_DEVICENOTPCEYE	-39	The selected device is no supported framegrabber.
EL_E_WRONGSELECT	-40	The select is out of range.
EL_E_VXD_NOT_PRESENT	-41	The driver is not installed. Check installation.
EL_E_BUFFER_TOO_LARGE	-42	No longer valid
EL_E_DEVICENOTPCEYE2	-43	The device is not a PCEYE2.
EL_E_NO_MEMORY	-44	Error allocating memory.
EL_E_MULTIPLEBOARDID	-45	Same hex switch setting for multiple identical grabbers.
EL_E_WRONG_PIXEL_CLOCK	-46	Wrong pixel clock.
EL_E_UNSUPPORTEDCAMERA	-47	Unsupported camera.
EL_E_UNKNOWNCAMERA	-48	Unknown camera.
EL_E_WRONGADCSELECT	-49	Wrong selection.
EL_E_NOCELUT	-50	No color encoding LUT installed.

**Table 5.12. Extended error codes**

EL_E_INVALIDSCALEFACTOR	-97	scaling factor not supported
EL_E_NOCAMERAFILE	-98	camerfile "xxx.cam" not found in the directory of the dll.
EL_E_IOTIMEOUT	-99	a timeout during the internal grabber communication has occured.
EL_E_CANTMAPPOINTER	-100	can not map an internal hardware address to a pointer.
EL_E_IRQNOTIMPLEMENTED	-300	IRQs are not implemented on this platform.
EL_E_IRQISENABLED	-301	IRQ is enabled.
EL_E_IRQNOTENABLED	-302	IRQ is not enabled.
EL_E_IRQNOTAVAILABLE	-303	IRQs are not available, check correct driver load order.
EL_E_IRQINVALIDEVENT	-304	Invalid IRQ-event type, use one of 'EL_IRQ_...!.
EL_E_IRQINVALIDBOOST	-305	Invalid priority boost.
EL_E_IRQOPENEVENT	-306	Error opening event.
EL_E_IRQINTERNALERROR	-307	Internal error setting up IRQs.

EL_E_WRONGTASKID	-500	Internal errorcode
EL_E_BUFFERNULLPTR	-501	User defined buffer pointer is NULL.
EL_E_WRONGBUFFERALIGN	-502	User defined buffer has wrong DMA alignment.
EL_E_WRONGPITCH	-503	Pitch is wrong
EL_E_WRONGFRAMESIZE	-504	Framesize not supported by the sensor.
EL_E_WRONGACQFORMAT	-505	Acquisition format not supported by the sensor.
EL_E_WRONGINTERRUPTMODE	-506	selected interrupt mode unknown.

SEE ALSO [el\\_GetErrorCode](#) , [el\\_GetErrorCodeEx](#)

### 5.3.3. EL\_FGITEM

Virtually all context settings can be inquired with these arguments - also minimum and maximum values, such as for acquisition size. This struct can be used for inquiring the actual parameters of the video hardware.

SEE ALSO: [el\\_GetSetting](#)

**Table 5.13. EL\_FGITEM**

EL_ACQSIZE X	size x of acquisition window
EL_ACQSIZE Y	size y of acquisition window
EL_ACQSTART X	start x of acquisition window relative to camera
EL_ACQSTART Y	start y of acquisition window relative to camera
EL_MAXACQSIZE X	max. acquisition size x of currently used camera
EL_MAXACQSIZE Y	max. acquisition size y of currently used camera
EL_VIDEOINPUTPORT	maximum number of video inputs
EL_MAXVIDEOINPUTPORTS	
EL_SYNCINPUTPORT	currently used sync input
EL_MAXSYNCINPUTPORTS	maximum numbers of sync inputs
EL_ADCREFBOTTOM	minimum ADC bottom reference level
EL_ADCREFTOP	
EL_MINADCREFBOTTOM	
EL_MAXADCREFBOTTOM	
EL_MINADCREFTOP	minimum ADC top reference level
EL_MAXADCREFTOP	maximum ADC top reference level
EL_LIVEMODE	HW in Live mode? (EL_ACQUISITIONMODE)
EL_CAMERAFORMAT	Camera is interlace/non-interlace - for enquiry only
EL_EXTCLOCK	External clock currently used
EL_EXTTRIGGER	External trigger currently used
EL_MEMACQFORMAT	Size of one pixel in bits; e.g. 8 bits for b/w images
EL_PIXELSIZE	

EL_MEMPIXELSIZE	
EL_PACKINGMODE	
EL_FRAMECOUNT	
EL_FRAMEBUFITCH	
EL_BUFFERID	

## 5.4. Data Structures

### 5.4.1. EL\_CAMFEATURES

An entry of the camera feature list

This structure can be used for inquiring the (maximum) parameters the grabbers supports for the specific camera. The actual settings can be inquired with [el\\_GetSetting](#) (...).

[el\\_GetCamFeatures\(\)](#) will initialize this structure, if the first entry (SpecialFeature.StructureSize) is set to sizeof (EL\_CAMEXTENSIONS). If not, [el\\_GetSupportedCamFeaturesEx](#) will return the standard features.

```
typedef struct
{
    EL_CAMERATYPE Cam; /* Camera manufacture code */
    char info[32]; /* Additional camera info */
    long Interlace; /* Interlace(1)/Noninterlace(0) */
    long ExtClock; /* External clock in use = 1,internal = 0*/
    double PixelClk; /* if ExtClock -> Pixel clock in MHz */
    long Restart; /* use restart feature of camera */
    double Rtime; /* specify min. time of restart pulse in us */
    long Shutter; /* programmable camera shutter = 1 */
    double Stime; /* specify min. shutter time in units of line durations, if possible */
    long IntStartX, IntStartY, IntSizeX, IntSizeY; /* Acq. Window parameters for internal pixel clock */
    long ExtStartX, ExtStartY, ExtSizeX, ExtSizeY; /* Acq. Window parameters for external pixel clock */
    long ColourSystem; /* Color encoding Systems supported by Camera (only colour grabber) */
    long OutputSignals; /* Color output signals delivered by Camera (only colour grabber) */
    long AlignmentX; /* Pixel alignment X direction */
    long AlignmentY; /* Pixel alignment Y direction */
    long Reserved5; /* Reserved for further extensions */
    long Reserved6; /* Reserved for further extensions */
}
EL_CAMFEATURES;
```

### 5.4.2. EL\_BOARD\_IDENTIFIER



USED IN: el\_GetBoardIdentifiers

used to retrieve informations about the installed boards

```
typedef struct
{
    char Name[32]; // name of the board
    long HexSwitch; // hex switch setting of the board
    long SubId; // used to select sub grabbers if several virtual grabbers are hosted on one board
} EL_BOARD_IDENTIFIER;
```

---

## Chapter 6. Samples

### 6.1. Programming example

This small programming example shows how to use the basic API functions to setup the grabber hardware for getting a snap shot from the camera into memory.

The import library `eleye716.lib` (compiler dependent) has to be specified in your development tool.

```
#include "elpceye7.h"

#define IMAGE_WIDTH 560
#define IMAGE_HEIGHT 480

int main(int argc, char* argv[])
{
    long Err, nRet = 0;

    long wBoardID;
    long wBufID;
    void ** ppVideoMemory;

    // open the grabber
    wBoardID = el_OpenHW(0, 1);
    if( wBoardID < 0)
    {
        printf( "Errorcode:%d\n", el_GetErrorCode() );
        return false;
    }
    // initialize with default values
    nRet = el_InitContext(wBoardID, NULL);
    if( nRet != 0)
    {
        printf( "Errorcode:%d\n", el_GetErrorCode() );
        return false;
    }
    wBufID = 0;
    // initialize HW and allocate memory for the image
    ppVideoMemory = el_InitHW(wBoardID, NULL, IMAGE_WIDTH, IMAGE_HEIGHT, 1, 0,
                              &wBufID);

    if ( !ppVideoMemory )
    {
        printf( "Errorcode:%d\n", el_GetErrorCode() );
        return false;
    }
    .
    .
    . setup the display
    .
    .

    // aquire one snap shot
    nRet = el_Acquire(wBoardID, EL_SNAP);
    if( nRet != 0)
    {
        printf( "Errorcode:%d\n", el_GetErrorCode() );
        return false;
    }
}
```

```
    }
    nRet = el_WaitAcqEnd(wBoardID);
    if(nRet < 0){
        printf("Failed!!");
    }
    else
    {
        printf("Snap!!");
    }

    .
    .
    . call the display server
    .
    // close the grabber
    el_CloseHW(wBoardID, NULL);

    return(true);
}
```

**6**

- 1** Open the hardware. The routine returns -1 or a board identifier, which is used in subsequent function calls.
- 2** Initializes internal software structures with data read from a setup file. This data will be used to initialize the video hardware by `el_InitHW()` later.
- 3** Initializes the video hardware with parameters prepared with `el_InitContext()`. Returns pointer to image pointer array if OK or 0 if ERROR.
- 4** Starts acquisition for a single frame/field (snap) or for continuous (live) acquisition
- 5** Wait until acquisition is finished.
- 6** Close the hardware. Use the board id returned by `el_OpenHW`.

---

## Appendix A. Cameras

### A.1. Introduction

The software adaptation for each camera is done by ELTEC Elektronik AG and included in the camera file eleye716.cam which has to reside in the same directory as eleye716.dll.

if you don't find your camera in the list below ask the ELTEC Elektronik AG support ( <support@eltec.de> ) to check if an adaptation is possible.

### A.2. Overview of Cameras supported by the software

**Table A.1.**

Cameras	p3i_DIG	p3i_CL
1. <u>Dalsa Spark</u>	X	
2. <u>Hitachi KP-F100</u>	X	
3. <u>ACC-1xx0 Eagle</u>	X	
4. <u>Pulnix TM-6710CL</u>	X	
5. <u>JAI CV-M2 Ikegami SKC-145T2 Basler A102k</u>	X	
6. <u>Optisens Colorline-1728</u>	X	
7. <u>Optisens Colorline-1728 Srereo</u>	X	

### A.3. T Dalsa Spark SP-13-xxx30 / SP-14-xxx30

The camera has been adapted with a default frequency of 30 MHz.

In the default cable the clock lines have been connected to the camera, so that the frequency can be lowered down to 4 MHz.

The cameras has also be adapted with three line sizes (512,1024, and 2048 pixel). The only difference between these cameras is the minimun time after which the cameras can be retriggeded. In the software this value is called cycle time. The software ignores all values of the cycle time below the minimum times needed for data readout and latency times of the specific sensor.

### A.4. Hitachi KP-F100

The cameras uses its internal clock. So the value for the clock generated on the board is fixed to a value of 20 MHz.

From the different modes of the camera the "single trigger mode has been selected". Due to limitations of the camera the minimum exposure time has been limited to 161 us. The maximim time after which a new frame can be retriggeded, called cycle time in the software is limited by the exposre time plus the time needed for data readout. So long exposure time leads to low frame frequeuncies.

### A.5. ACC-1xx0 Eagle

All cameras use internal clock. Because the software needs the clock value to calculate exposure and cycle times the (unused) clock generator has to be set to the frequence of the camera.

For the cameras "ACC-11x0 Eagle 2048 pix." and "ACC-1100 Eagle 2592 pix." a range of 4-17 MHz is accepted. For the cameras "ACC-1120 Eagle 5000 pix." and "ACC-1120 Eagle 7926 pix." the clock is fixed to 12.5 MHz

For all these cameras 4 pixel are not usable due to technical reasons.

The minimum time after which the cameras can be retriggered depends on the length of the sensor and the used pixel clock. In the software this minimum time is called cycle time.

The software ignores all values of the cycle time below the minimum times needed for data readout and latency times of the specific sensor.

If external trigger sources are used, the rising slope starts the grabber generated timing.

The following commands were used to set up the camera with the serial interface. It sets the pixel clock to 10 MHz what is not supported by all camera types. The default value of 5MHz used by the software is also different and should be set to the real camera clock.

```
@02 0001
@01 0122
@01 0102
@01 0304
@03 0000
@04 002C
@05 0040
@02 0002
@06 0800
@03 0005
@00 0000
```

## A.6. Pulnix TM-6710CL

Be aware that "One Shot" asynchronous output has to be used for all triggered modes.

The Pulnix TM-6710CL has been adapted in free running and external trigger mode. The free running mode can also be used in combination with the partial scan mode. In these cases the values for StartY and SizeY have to be adapted. For external trigger there is a separate camera entry for each partial scan mode to reach the maximum frame rate without illegal retriggering.

For the triggered partial scan mode the initial window size of the configuration program is too big. To change this use the size dialogue of the program.

Pulse width mode is used as default. If this is not desired set the exposure time to 0 which generates the minimum trigger pulse width, necessary to trigger the camera.

## A.7. Optisens Colorline-1728

For the use of this camera a special firmware "p3i3.frw" file is needed. It has to be placed in the directory of the used eleye716.dll file. If the dll is placed in the correct directory the Optisens cameras are selectable with the configuration program. If something goes wrong only the default cameras are selectable.

The camera is used with MCLK provided by the grabber. The default clock is 24 MHz which generates a pixel clock of 9 MHz. MCLK can be decreased to a value of 4 MHz which also decreases the maximum line frequency.

The camera is controlled by the grabber using the EXSYNC signal. In Mode 1 the integration time and the cycle time are controlled independently using `el_SetExposureTime` and `el_SetExposureTime`. In Mode 2

the cycle time, which is the time after which the cameras can be retriggered, is also controlled by `el_SetExposureTime`.

If the desired values of `el_SetExposureTime` and `el_SetExposureTime` are below the values required by the camera the real values are set to the lowest possible values and the realised values can be inquired using the corresponding `el_Get...` function.

If the incremental decoder of the camera is used the software settings are not used and the user has to insure that the trigger timing is correct.

The "Frame Start Initiator Input" of the camera can be used if `el_SetExtTriggerInput( )` is called with the parameter `EL_TRIG_LVDS` and external frame triggering is enabled using `el_SetTriggerModes`.

If external trigger sources are used, the falling slope starts the grabber generated timing.

## A.8. Optisens Colorline-1728 Stereo

In the stereo mode two simultaneously running cameras are serviced. For this a special cable and a slightly modified hardware are needed.

For the use of this camera a special firmware "p3i3.frw" file is needed. It has to be placed in the directory of the used `eleye716.dll` file. If the dll is placed in the correct directory the Optisens cameras are selectable with the configuration program. If something goes wrong only the default cameras are selectable.

To do the necessary changes a path is available to does the modifications for you if the main installation was done to the default paths.

The camera is used with MCLK provided by the grabber. The default clock is 24 MHz which generates a pixel clock of 9 MHz . MCLK can be decreased to a value of 4 MHz which also decreases the maximum line frequency.

The camera is controlled by the grabber using the EXSYNC signal. In Mode 1 the integration time and the cycle time are controlled independently using `el_SetExposureTime` and `el_SetExposureTime`. In Mode 2 the cycle time, which is the time after which the cameras can be retriggered, is also controlled by `el_SetExposureTime`.

If the desired values of `el_SetExposureTime` and `el_SetExposureTime` are below the values required by the camera the real values are set to the lowest possible values and the realised values can be inquired using the corresponding `el_Get...` function.

The incremental decoder of the cameras are not usable, because this would break the synchronous behaviour of the cameras.

The "Frame Start Initiator Input" of the camera can be used if `el_SetExtTriggerInput( )` is called with the parameter `EL_TRIG_LVDS` and external frame triggering is enabled using `el_SetTriggerModes`.

If external trigger sources are used, the falling slope starts the grabber generated timing.

if you have a modified hardware the gain settings of the camera can modified. For this the function `el_SetRegister` has to be used. Each bit can be set and reset individually. An example is given below.

```
// The last parameter has to be always 1
el_SetRegister(wBoardId,"Gain0", 1, 1); // set Gain0 to 1
el_SetRegister(wBoardId,"Gain0", 0, 1); // set Gain0 to 0
```

```
el_SetRegister(wBoardId,"Gain1", 1, 1); // set Gain1 to 1  
el_SetRegister(wBoardId,"Gain1", 0, 1); // set Gain1 to 0
```

## **A.9. JAI CV-M2 Ikegami SKC-145T2 Basler A102k**

These cameras have been adapted in a free running and an triggered mode. The triggered mode is intended to be used with pulse width mode controlled exposure. Exposure time determined by the camera is also possible, but `el_SetExposureTime()` has still to be used, because the valued is needed to calculate allowed valued for the cycle time.

An exception are the partial modes where no limit for the cycle time is enforced because it depends on the setting of the camera. These modes are only intended for the experienced user because wrong cycle times can lead to unpredictable results. For this reason no support for these modes can be given.

---

## Appendix B. FAQs

### B.1. Common FAQs

#### B.1.1. What is synchronous acquisition?

Synchronous acquisition means that all cameras run synchronously to each other. This is done by applying a horizontal and a vertical sync signal to each camera. For the frame grabber family these signals have to be taken from the on-board sync generator. Using sync signals from an extra camera is not possible.

In restart mode synchronous operation is achieved by using the h-sync signal for the horizontal synchronisation. The vertical synchronisation is done by the trigger signal. One signal is used for all cameras. The preferred trigger mode in synchronous operation is grabber trigger, where the trigger signal is sent to the grabber which sends a trigger signal to the cameras that is synchronised to the camera timing.

The synchronisation makes sure that the trigger signal is not applied to the cameras in critical timing phases, where one camera might react immediately to the signal whereas another camera starts its restart timing one h-sync period later.

#### B.1.2. What is asynchronous acquisition?

Asynchronous acquisition is only possible with the frame grabbers. The data of all cameras can only be stored as 8 bit per pixels b/w images. Up to four cameras of the same type can be used and do not have to be (and can not be) synchronised to each other. To control the progress of the acquisition of the four channels the function of some `el_Test...` and `el_Wait...` functions have been changed. Please refer to the API documentation for details, because some of these functions do not work at all and some have a slightly different function.

In the restart mode a trigger signal for each camera has to be provided. Please refer to the hardware documentation to see which jumpers have to be set and at which inputs the signals have to be applied.

#### B.1.3. What are DMA channels?

A DMA channel moves data from a source on the grabber to a buffer in the memory. Data sources on the grabber are fed by one or more ADCs which digitise the input signals. Before the transmission the data source packs the ADC values into long words according to the packing mode (e.g. red, green and blue in one word for RGB transmission, 4 b/w pixel for monochrome transmission or 2 b/w pixels each blown up to 16 bit RGB pixel with identical blue red and green values for pseudo RGB mode)

The connection of a DMA channel to a buffer is done with `el_AssignBuffer`. The packing mode of the buffer determines the way the image data is packed at the source. If the packing mode of the target buffer is not supported by the data source or the buffer is not large enough for the acquired image an error is generated.

It is possible to connect several DMA channels to one buffer (but not vice versa). Normally this does not make sense because the data of the two buffers overwrite each other. It happens sometimes by accident if the buffer is connected to a new channel without switching off the previously used



channel (calling `el_AssignBuffer` with channel ID 0).

There is one exception if the memory acquisition format is set to `el_DUAL`. In this case the data is written to different lines within the buffer (if the camera adaptation supports this). For a camera like the JAI CV-M10 which provides even and odd field at the same time at two different outputs this can be used to transfer the even lines over one DMA-channel and the odd lines over another channel.

#### B.1.4.

What methods to allocate buffers do exist?

The software can handle two different memory management methods. The first one is to apply a 0 pointer to the `MemStart` parameter of `el_InitHW`, `el_NewMemBuffer`, `el_NewMemBufferEx` or `el_CreateMemBuffer`. These functions return all a pointer to pointer list. The elements of the list then point to the memory buffers.

Another method is to build a list like the one return by the functions mentioned above with self allocated memory. The pointer list must be one element longer than the number of frames in the sequence ( a single buffer can be seen as a sequence with the length 1) because the last element of the list has to be 0. For some software versions the addresses of the buffers have to lie on a page boundary (modulo 4096 = 0). Please refer to the software documentation for details.

If the self generated list is used as the `MemStart` parameter of the functions mentioned above, the supplied memory areas are locked at their current physical position in the memory. This means that they are protected against being transferred into the swap file. The list returned by the function is identical to the supplied list.

#### B.1.5.

What is the Dual Mode?

Special cameras deliver the even and the odd image on separate video channels simultaneously. The grabber can combine these channel to one image with twice of the normal frame rate.

```
ppVidPtr = el_InitHW(.....,&nBufNo);
:
el_SetAcqMemFormat (nBoardId, EL_DUAL); ❶

el_SetVideoInPort(nBoardId, EL_CAMPARALLEL); ❷

ppVidPtr = el_AssignBuffer(nBoardId,1,nBufNo,1.0, 1.0,0,0); ❸
:
```

- ❶ set acquisition format of the buffer assigned to channel 0 to `EL_DUAL`.
- ❷ connect video data stream of input channel 1 to DMA channel 1.
- ❸ assign buffer also to channel 1. Data coming through this channel is sorted between the lines of channel 0.

#### B.1.6.

What is the Stereo Mode ?

In the stereo mode the images of two cameras are stored in two different buffers. The two cameras have to be synchronized externally. The jumpers which have to be set are described in the

documentation of the camera file. if no setup file is used, el\_InitSyncGenerator has to be called to chose the correct synchronization signals and with el\_EnableSyncGenerator the generator has to be switched on.

```
ppVidPtr = el_InitHW(.....,&nBufNo); ❶
:
el_SetVideoInPort(nBoardId, EL_CAMPARALLEL); ❷

ppVidPtr2=el_NewMemBuffer(BoardId, 0, 0, 0, 1, 0, &nBufNo2) ❸;

ppVidPtr = el_AssignBuffer(nBoardId,1,nBufNo,1.0, 1.0,0,0); ❹
```

- ❶ first buffer is created with el\_InitHW
- ❷ connect video data stream of input channel 1 to DMA channel 1
- ❸ Get a second buffer. el\_CreateMemBuffer could have also be used, but then packing mode and memory format must be set explicitly and the buffer is not connected to a channel. In this case the modes are inherited form the first buffer. The first buffer is disconnected and the second buffer is connected to channel 0
- ❹ The unconnected first buffer is now assigned to channel 1

#### B.1.7. How do I get camera names for el\_SelectCamera?

It is extremly important to write the camera names used in el\_SelectCamera exactly like they are displayed in the configuration program. If you integrate the sourcecode below in a console application and provide the BoardId obtained by el\_OpenHW to it you can get the camera names easily.

```
EL_CAMFEATURES Feature;
el_GetSupportedCamFeaturesEx(BoardId, GETFIRSTCAMFEATURE, &Feature,
                             sizeof(EL_CAMFEATURES));
printf("%s\n",Feature.info);
while(el_GetSupportedCamFeaturesEx(BoardId, GETNEXTCAMFEATURE, &Feature,
                             sizeof(EL_CAMFEATURES)) >0)
{
    printf("\n%s\n",Feature.info);
}
```

You get an output like:

```
"Generic CCIR625"
"Generic EIA"
"JAI CV-M50"
"Jai CV-M50 edge sel. cam. trg."
"JAI CV-M50 edge sel. grab trg."
"Jai CV-M50 long exp."
"Jai M70 camera trig."
"Jai M70 fullframe"
"Jai M70 grabber trig."
"Jai M70 interlaced"
"Jai M70 long exp."
"CV-M77"
"CV-M77 camera trg."
```

"CV-M77 grabber trg."  
 "Sony XC-55 E-DONPISHA II"  
 "Sony XC 55 continous DONPISHA"  
 "Sony XC-55 fullframe"  
 "Sony XC-55 interlaced"  
 "Sony XC-55 Long Time Exp"  
 "Sony XC-55 Rest. Res."  
 "Teli CS3910 Fixed Mode"  
 "Teli CS3910 fullframe"  
 "Teli CS3910 RTS Pulse Mode"  
 "XC-003P"  
 "XC-003P donp. camera trg."  
 "XC-003P donp. grabber trg."  
 "XC-003P R.R. 4"  
 "XC-003P longtime exposure"  
 "Jai A11"  
 "Jai A-11 camera trigger"  
 "Jai A-11 edge mode partial"  
 "Jai A-11 edge mode"  
 "Jai A-11 longtime exposure"  
 "Jai A-11 pulse width"  
 "Jai A-11 pulse width partial"  
 "Jai A-60"  
 "Jai A-60 camera trigger"  
 "Jai A-60 edge mode"  
 "Jai A-60 pulse width"  
 "Sony XC8500 2I norm. gr. trg."  
 "Sony XC8500CE noninterl."  
 "Sony XC8500 interl./dual"  
 "Jai CV-M10 cam. trg. non intl."  
 "Jai CV-M10 cam.trg. dual"  
 "Jai CV-M10 grab.trg. dual"  
 "Jai CV-M10 grab.trg. non intl."  
 "Jai CV M10 interlaced"  
 "Jai CV M10 dual"  
 "Jai CV-M10 non intl."  
 "JAI-CV-M1 noninterlaced"  
 "DMP 60H13 dbl. rest."  
 "DMP 60H13 intl."  
 "DMP 60H13 non intl."  
 "DMP 60H13 non intl. dbl."  
 "DMP 60H13 rest."  
 "CV-M77"  
 "CV-M77 camera trg."  
 "CV-M77 grabber trg."  
 "Sony XC-HR50"  
 "Sony XC-HR50 ext. sync"  
 "Sony XC-HR50 rest."  
 "Ikegami SKC-151"  
 "DMP 70H13 dbl. rest."  
 "DMP 70H13 intl."  
 "DMP 70H13 non intl."  
 "DMP 70H13 non intl. dbl."  
 "DMP 70H13 rest."  
 "JAI CV-M50 mode 2"  
 "JAI CV-M50 mode 2 ext. sync"  
 "Jai CV M10 dual EIA"  
 "Jai CV-M10 non intl. EIA"  
 "Jai CV-M10 cam. trg. n. i. EIA"  
 "Jai CV-M10 grab.trg. n. i. EIA"  
 "Jai CV-M10 cam.trg. dual EIA"  
 "Jai CV-M10 grab.trg. dual EIA"  
 "Sony XC-HR50"  
 "Sony XC-HR50 Mode 1"  
 "Sony XC-HR50 Mode 1 partial"  
 "Sony XC-HR70"  
 "Sony XC-HR70 Model"  
 "Sony XC-HR70 Model partial"



---

# Index

## G

### Grabber functions

- el\_Acquire, 53
- el\_AcquireEx, 55
- el\_AssignBuffer, 56
- el\_CloseHW, 58
- el\_CreateMemBuffer, 59
- el\_FreeMemBuffer, 59
- el\_GetBoardIdentifiers, 60
- el\_GetCycleTime, 60
- el\_GetDriverRevision, 61
- el\_GetErrorCode, 61
- el\_GetErrorCodeEx, 62
- el\_GetExposureTime, 62
- el\_GetHWRevision, 62
- el\_GetNumOfBoards, 63
- el\_GetPixelClock, 63
- el\_GetSelectedCamera, 64
- el\_GetSetting, 64
- el\_GetSupportedCamFeaturesEx, 65
- el\_GetSWRevision, 65
- el\_InitContext, 66
- el\_InitHW, 66
- el\_NewMemBuffer, 68
- el\_OpenHW, 70
- el\_OpenHWEx, 72
- el\_ResetOutputs, 73
- el\_SelectCamera, 73
- el\_SetAcqWindow, 74
- el\_SetCycleTime, 75
- el\_SetExposureTime, 75
- el\_SetExtTriggerInput, 76
- el\_SetOutputs, 77
- el\_SetPixelClock, 77
- el\_SetTriggerModes, 76
- el\_TestAcq, 78
- el\_TestFrameCount, 79
- el\_WaitAcqEnd, 79
- el\_WriteSetupFile, 81