

## ThermalVision<sup>™</sup> PRO PC Software Instruction Manual







© 2011 IDEAL INDUSTRIES, INC. No part of this publication may be reproduced without prior permission in writing from IDEAL. While IDEAL will endeavor to ensure that any data contained in this product information is correct, IDEAL does not warrant its accuracy or accept liability for any reliance on it. IDEAL reserves the right to change the specification of the products and descriptions in this publication without notice. Prior to ordering products please check with IDEAL for current specification details. All brands and product names are acknowledged and may be trademarks or registered trademarks of their respective holders.



## Contents

1. Installing the ThermalVision™ PRO series software onto a PC	3
2. Transferring saved images from the camera to the PC	3
2.1. Direct from Camera	3
2.2. From Micro-SD Card 4	ł
3. Using the ThermalVision™ PRO series software	1
3.1. Starting the Software 4	ł
3.2. Opening an image 4	ł
3.3. Analysis Tools	5
3.4. Menus and Toolbars 11	
4. Report Writer	7
4.1. Title Page 17	,
4.2. Image tab 18	}
4.3. Inspection data tab 20	)



#### 1. Installing the ThermalVision<sup>™</sup> PRO series software onto a PC.

To install the ThermalVision<sup>™</sup> PRO software onto a PC:

- 1. Insert the CD into the PC.
- 2. Use Windows Explorer to view the files on the CD.
- 3. Open and run the file "ThermalVision PRO PC setup.exe".
- 4. This will install the software on to the PC.



Once the software has successfully been installed an

icon appears on the PC Desktop.

# 2. Transferring saved images from the 61-846 or 61-848 camera to the PC.

In the camera the images are saved on a micro-SD card and are in folders. A new folder is created every time the camera is switched on. The folder also contains the voice message file if it is recorded. Each saved image will therefore consist of two or three files.

- a. A BMP file containing the thermal and visual image.
- b. An IR5 file containing the temperature data.
- c. A WAV file if a voice recording was made when the image was saved.

#### Note: Do not use the Microsoft Scanner and Camera Wizard to download images. Use Windows Explorer.

There are two ways to transfer images to the PC.

#### 2.1. Direct from Camera

- a) Connect the camera to the PC via the USB cable.
- b) Use Windows Explorer and filing system to locate the micro-SD card in the camera. This will normally be shown as a removable disk.
- c) Copy the complete folders from the micro-SD card on to the PC. Note that there are at least two files for each image, which must be kept together.





#### 2.2. From Micro-SD Card

- a) Take the micro-SD card out of the camera and insert into a suitable card reader.
- b) Connect the card reader to the PC.
- c) Use Windows Explorer to locate the files with the images on the micro-SD card and copy the complete folders on to the PC. Note that there are at least two files for each image, which must be kept together.

#### 3. Using the ThermalVision<sup>™</sup> PRO series software.

The PC software has two main parts.

1. Analysis Mode – Allows the user to analyse the image and also alter the settings for how the image is displayed.

2. Report Writer Mode - Allows the user to create a report of the thermal images for records and administration and operational use.

#### 3.1. Starting the Software.

Double Click on the ThermalVision<sup>™</sup> PRO series icon to start the software

The following window will appear.

Note it may be necessary to maximise the window.

10 20 2	inte Elife				
	中午日 あませ	19. Y		 	
Darley Corete	Setterp				
Teni-Berti	607 W 107				
	Address				
Color Faller	The first	-			
Yabic Built	1.4	-			
menterer	040min0				
Don Father	54	•			
Area Salaci	Peaks				
-far Land -	Calification of the second sec				
	 cc				
	ec test is				
	ec test is				
	ec test is				
nışı Ayrım	ec test is				

#### 3.2. Opening an image.

Click on the drop down File menu and click on "Open".

	DEAL	Then	nal∀is	ion
File	Edit	⊻iew	Tools	Help
0	pen		1	+1
5	ave		-	
S	ave <u>A</u> s		eti	tings
R	evert.			
E	Excel Output			0.0 °F
P	roperti		_	
E <u>x</u> it				Ironbo
۷	isible B	lend:		0 %

Use the Windows Explorer to locate the folder where the images are saved. If viewing images directly from the camera this will be shown as a removable disk.



Once the folder is located, double click on the image to be loaded.



#### Opening Screen shot.

The window format shown below should be displayed. It may be necessary to maximise the window in order to see all the features.



#### Image Description

The thermal image is seen on the right hand side of the screen. A temperature scale relating to the colours is displayed to the right of the image. An adjustable span, also showing a histogram of temperatures in the image is shown at the bottom of the screen. There is a drop down menu bar and an icon toolbar. A set of Tabs is on the left hand side of the image. On start up the display tab is shown.



#### 3.3. Analysis Tools

To analyse an image and change its presentation the tools available are:

- 1. Drop down menus.
  - <u>File E</u>dit <u>V</u>iew <u>T</u>ools <u>H</u>elp
- 2. Icon Toolbar.



3. Tabs.

Display	Cursors	Settings	
Temp	Snan:	lot and	

#### TABS

Display Tab

Display Cursors Se	Display Cursors Settings					
Temp. Span:	31.3 °C to 39.4 °C					
	Auto Span					
Colour Palette:	Ironbow	-				
Visible Blend:	0 %	•				
Interpolation:	x2 (640x480)	•				
Zoom Factor:	×1	•				
Area Select:	Medium	•				
Pan Control						
Image Alignment:	Α					
<<	Reset >>					
	V					



1. Temperature span allows the image display span values to be altered manually by clicking on the Figures in the boxes and changing them. Auto span sets the temperature span values based on the temperature values in the image.



The temperature span can also be adjusted using a mouse in the level and span adjustment bar (see below). To adjust span click on the dark grey and light grey border and drag. To adjust level click in the middle of the light grey area and move.



adjustment bar.

2. Colour palette. To change the colour palette, click on the arrow button.



- 1. White Hot Mono.
- 2. Ironbow.
- 3. Rainbow.
- 4. Isotherm Style.

- 5. Hot Metal.
- 6. High Contrast.
- 7. 16 step Rainbow.
- 8. Black Hot Mono.
- 3. Visible blend. To change the visible/infrared ratio click on the arrow button.



0% Thermal.







100% Visible.



Picture in picture



4. Interpolation. To change the interpolation click on the arrow button.



x 1 (320X240)



x 2 (640 x 480)

5. Zoom factor. To change the zoom setting click on the arrow button. The following four settings are available X1, X2, X3, X4 (examples of X1, X2 and X4 shown below).



When zoomed to  $x^2$  or more, the part of the image diplayed can be selected by means of the mouse in the Pan Control box.

- 6. Area Select. Use the arrow button to select a small, medium, or large area for measurement (see page 14).
- 7. Image alignment. This allows the vertical and horizontal alignment of the thermal and visible images. Clicking on the navigation arrows will move the visible image while the infrared image remains stationary. It is easiest to adjust with a 50% thermal and 50% visible image.



Note: Clicking on the reset button returns the alignment to the setting when the file was opened.





Cursors tab



Up to 10 cursors can be added to the display.

- 8. To add a cursor to the image, double click on the image on the screen. The cursor can be moved by the drag and drop method.
- 9. To remove cursors either double click on it or highlight the cursor in the box and click remove.

The list of cursors within the box shows: -

- 1. The temperature of the cursors.
- 2. The position of those cursors.
- 3. The emissivity value. This can be set individually.
  - a. Select the cursor by clicking on its name in the table.
  - b. Then either click on the double arrow on the side to call up the emissvity look up table.
  - c. Or use the emissivity value box adjustment box and then click on the set button.





#### Settings tab

Units:	∘⊂	-	
Reflected Temp:	20.0 °C	÷	
Global Emissivity:	0.99	÷	>>
Capture Time:	07:14:03		
Capture Date:	30/08/2010	•	
Comments:	1	<u>~</u>	
	3	×	
Caption:		<u>^</u>	
		~	
	<	>	

- 1. Units:
- 2. Reflected Temp.:
- 3. Global Emissivity:
- 4. Capture Time:
- 5. Capture Date:
- 6. Comments:
- 7. Caption
- 8. Voice annotation

- °C, °F, K. Change using the arrow button.
- Change using the arrow buttons.
- 0.01 to 1.00. Change using the arrow buttons or
- >> button. Access the emissivity look up table
- Change if required using the arrow buttons.
- Change if required using the arrow buttons.
- Type in any comments in the box.
  - Any text caption typed when saving the image will appear here.
  - Voice notes recorded when saving the image can be replayed via the play button. These can be heard from the PC's speakers.



File

#### 3.4. Menus and Toolbars

Use either the drop down menus or the icons on the toolbar to carry out various operations.

<u>File Edit View I</u>	ools <u>H</u> elp						
	Drop down menus						
	} -+- <mark>-</mark> + [	🗆 🤖 👪 🤼 🗊	8				
	Icons toolbar.						
File Edit View Tool	s <u>H</u> elp						
Open Save	+ + + <b>+</b> □ 🛍 🖬 🕅	t 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1					
	ettings						
Excel Output	31.1 °C to 39.4 °C						
Properties	Auto Span						
Exit Visible Blend:	0 %	• •					
Interpolation:	×2 (640×480)						
Zoom Factor:	x1	v v					
Area Select:	Medium	•					
Pan Control							
Image Alignment:							
	V						

Items 1 and 2 below are also available via the icons on the toolbar.

- 1. Open. Use Windows Explorer to open an image.
- 2. Save. To save changes to the image.
- 3. Save As. To save the image with a different file name.
- 4. Revert. To discard all changes since the last save.
- 5. Excel output. Selecting this provides the temperature values of all pixels in a CSV format allowing it to be saved as a file. This can then be read as an Excel spreadsheet. Note that the file must be opened from within the Excel application (not by "double-clicking" on the file) and selecting comma delimiters.

this is correct, choose Next, or choose th Driginal data type choose the file type that best describes y Delimited		rate each field.			ο <u></u> Se	ed in the pre				cucivo delin	niters as on
Start income at row: 1	all the Sugar.	437 : OEM United States	~	Data previ	iew				_	/	
23.550, 23.450, 23.350, 23.	.350, 23.550, 23	.550, 23.650, 23. .650, 23.650, 23.	650,	23.550 23.550	23.450 23.450 23.350	23.350	23.450	23.550	23.550 23.650 23.550	23.650 23.650 23.550	23.650 23.650 23.650
23.550, 23.450, 23.350, 23. 23.450, 23.350, 23.350, 23. 23.350, 23.350, 23.350, 23. 23.450, 23.450, 23.350, 23.	.350, 23.450, 23 .350, 23.350, 23	.350, 23.450, 23.	\$50,	23.450 23.350 23.450	23.350	23.350	23.350	23.350	23.350	23.450 23.350	23.550 23.450



#### Edit

- 1. Copy...
- 2. Copy To Bitmap...



This offers the option to copy the image to the clipboard or to save as a bitmap. Both of these options will allow three choices - Full window, Snapshot or Snapshot+.

Copy To Bitmap		
Full Window	Snapshot	Snapshot +



**Full window.** Full window saves the complete window.

**Snapshot.** Snapshot saves the image only.

**Snapshot +.** Snapshot + saves the image and the colour temperature scale.



View

it	⊻iew	<u>T</u> ools <u>H</u> elp
1	✓ Io	olbar
	<b>√</b> <u>S</u> ta	atus Bar
'	Me	asurement Cursor Lisl
. 9	🖌 Me	asurement <u>C</u> ursors
	🗸 C <u>u</u>	rsor Temperature
	Ho	t & Cold Cursors
ır F	Are	ea Select
	Blu	e Isotherm
εB	Re	d Isotherm
20	Pro	ofiles
F	✓ Op	tions
Se	Re	port <u>W</u> riter

Items 3 onwards are also available via the icons on the toolbar.

- 1. Toolbar. Turns on/off the icon toolbar.
- 2. Status Bar. Turns on/off the status bar at the bottom of the screen.
- 3. Measurement Cursors List. Toggles to show the temperature value and position of the selected cursors. The value of the hottest and coldest points in the image (see item 5 below) and the area box values (item 6 below).

Measurement Cursors					
ID	Temp.	Position			
Cursor 1	40.0 °C	(62,140)			
Cursor 2	42.5 °C	(223,143)			
Cursor 3	38.6 °C	(142,140)			
Cursor 4	37.8 °C	(282,148)			
Cursor 5	35.2 °C	(51,21)			
Cursor 6	42.6 °C	(160,25)			
Cursor 7	35.1 °C	(263,28)			
Cursor 8	0.0 °C	(0,0)			
Cursor 9	0.0 °C	(0,0)			
Cursor 10	0.0 °C	(0,0)			
Temp Diff	-2.5 °C	(C1-C2)			
1	mage Info				
Hot	39.2 °C	(2,208)			
Cold	14.5 °C	(2,237)			
Temp Diff	24.7 °C	(H-C)			
Average	34.4 °C				
Average	34.4 °C				

4. Measurement Cursors. Toggles between displaying or removing the cursor/s on the image.





## #ThermalVision<sup>™</sup> PRO SW

5. Cursor Temperature. Toggles between displaying cursor/s with temperature values besides them or the cursor number.



6. Hot & Cold Cursors. Allows the display of the hottest and coldest point of the whole image.



 Area Select. Selects an area in the middle of the image. The maximum, minimum and average temperatures of the area box are displayed in the cursor list (item 3 above). Three different area sizes are available (see page 8).



Small Area



Medium Area



Large Area



- 8. Blue Isotherm.
- 9. Red Isotherm.

Isotherms are regions within the scene of the same temperature range and are shown in the same colour. This is best seen using either the white hot or Black hot colour schemes.



**Red Isotherm** 

Blue isotherm



5 명 수 # 수 다 **한 명** 년 38 동 9 명 수 # 수 다 한 명 년 38 동

The red and blue isotherms can be set by adjusting the red and blue blocks in the level and span adjustment bar. This can be done using a mouse.

To adjust the isotherm width, click on the colour block edge and drag. To adjust level click in the colour block and move.

The temperature difference between the centre of the two isotherms is displayed at the bottom.

10. Profiles. A temperature profile is a histogram showing the temperature values through a cross-section of the scene. The profiles are displayed as shown below. The cross-section lines can be moved by the user.





## **#ThermalVision™ PRO SW**

11. Options. Toggles to display the Tabs panel.



Options on - Tabs displayed

Option off

12. Report Writer. This will toggle between the Analysis Mode and Report Writer Mode.

#### Tools



- 1. Reset Isotherms. Reset the isotherms to the default values.
- 2. Language. The following languages can be selected. Once a language is selected exit the IR series software and re-start it to activate the selection.



#### Help



About. Shows the software version.





#### 4. Report Writer

It is possible to toggle between the ThermalVision<sup>™</sup> 160 Analysis Mode and the Report Writer Mode from the drop down view menu or the toolbar.

There are three steps to create a report. There is a separate tab for each function.

- 1. Title page.
- Enter details that should appear in the title page of the report.
- Image select.
   Inspection Data.
   Information and additional data about each image can be added
- and then the report can be generated.

### 4.1. Title Page tab

🖬 Untitled.rw2* - IDEAL ThermallYision	E 6 X	
Die Die Diese Innie Diefe		
○日 20日→2014日1日 1日		
Title Page [Image Select   Inspection Data		
	Se Inage Ore Inage	
Green Autor Doe © 2020/2011 _ * No Dee General Converts		Title Page Image Select Inspection Data

- 1. When the Report Writer Mode is opened the title page appears as shown above. There is an empty space where a logo or other image can be placed to appear on the front page of the final report.
- 2. Press the select image button.



- **3.** Windows Explorer can now be used to find an image.
- 4. Click on the open button to select and place an image or logo in the title page.

		-
	-F	
*		
TIT		
• <del>تن</del> م	Let trap	
		Respection Date Respection Date Respective Date Respec

Enter the rest of the details required for the front page of the report.



#### 4.2. I mage select tab.

Title Page	Image Select	Inspection Data
5napshot F	older	
	se	Refresh

1. The screen shown below appears.

	1000 00000		Interface I			
AN R SS	AN M System 2000	Bronse Robust.	Peperer	Particul simplified	Trend was seed	000 749
		A10 A1 >>				till trage

2. Click on the browse button to open Windows Explorer.

sect   Inspection Data
Refresh

3. Highlight an image and click on the open button, or simply double click on a IR series image.

🖻 🖬 🖆 🖷 🕂 +'	4 🗆 🖬 🖬	<u> </u> 桂  1월  <b>?</b>			
Title Page Image Select	nspection Data				
Snapshot Folder		Tocoactione: 0	Thormal	Sapadat	Thormal a
1	Open				
Browse	Look jn:	imodify images		- 🗕 🖻 🖛	
	My Recent Documents Desktop		img0010	189 snapshot.bmp	
	My Documents				
	My Computer	img_0188.bmp	img_0189.bmp	img_0193.bmp	~
	My Network Places	-	9 snapshot.bmp	•	<u>O</u> pen
		Files of type: IR	Series (*.bmp)	<b>_</b>	Cancel

-	
Cancel	L



4. All the Images in that folder will now appear in the browser selection on the left of the window.



5. Click on a selected image in the browser section and it appears in the image preview section on the right of the window.



6. The add/add all remove/remove all buttons allow the selection and removal of images as required.



7. Selected Image/s will appear in the inspection section in the centre of the window.





## #ThermalVision<sup>™</sup> PRO SW

8. Each image, when selected, may be edited by means of the "Edit Image" button. This switches to the Analysis Mode. When editing is complete, switch back to the Report Writer Mode by means of the "Toggle Report Writer" button.

#### 4.3. Inspection Data Tab

t	Inspection Data	

1. The inspection Data window will appear.

pedian Name No Date No Date Initials Inspected C 10001/2011 - C Repared C 10001/2011 - C Reinpected C 10001/2011 -		<pre></pre>	of 9 Next >> Visible Image			e PDF Report eport Project	
spection lane Foo Date Initials spection lane Foo Date Initials Regard C [20001/2011 = C Reinyacted C [50001/2011 = C Fask/Recomminded Action	apedian Name			Global Emissivity: Reflected Temp: Measured Load	0.99		
perstor	Solitation	C (Documents and Settings)sat.sendhu)Desitop(mod/y images)mod-mg_0189.htmp Impection Name	Edit Image	Date Inspected (* Repaired (*	09/01/2011	* (* *	Initials
		ocation quipment	Fauk / Pr		09/01/2011	-	
Curson 1         •         (342.90)           Curson 2         •         (362.90)           Ofference         0.4 %		tepär Priority Lew ta 5 High none 💌					

- 1. Complete and enter data as required for the report. The image can be edited if required by clicking on the edit image button.
- 2. Once data is entered press the Save Project Report button to save the full report. This allows the report to be edited later if required.



- 3. Press the Generate PDF Report button when ready to create the report.
- 4. A report is now generated and can be saved where required.



## #ThermalVision<sup>™</sup> PRO SW

#### Warranty Statement:

Any implied warranties arising out of the sale of an IDEAL product, including but not limited warranties of merchantability and fitness for a particular purpose, are limited to the above. The manufacturer shall not be liable for loss or damage to computer equipment, peripheral equipment or other incidental or consequential damages, expenses, or economic loss, or for any claim or claims for such damage, expenses or economic loss.

Country laws vary, so the above limitations or exclusions may not apply to you. This warranty gives you specific legal rights, and you may also have other rights which vary from country to country.

IDEAL INDUSTRIES Unit 3, Europa Court Europa Boulevard Westbrook, Warrington, WA5 7TN Cheshire, UK Tel.: +44 (0)1925 44 44 46 Fax: +44 (0)1925 44 55 01

UKsales@idealnwd.com

www.idealindustries.co.uk

www.europe.idealindustries.de