Drive Application Software Application Set

Description:

Limitations:

Options &

Inputs

Notes:

Application Set Title Position Profile - Encoder Incremental **Drive Product** PowerFlex® 700 Vector Control (Series B)

File Name for (AS) AS PF700 Position Profile Encoder Incremental.doc

Date / Revision 01 8/11/05

Attention: This document and related file(s) are designed to

> supplement configuration of the listed drive product. The information provided does not replace the drive products user manual and is intended for qualified personnel only.

The Position Profile is used to move incrementally to the desired position. The position is determined by the step being used as the starting step. For this example, two selector switches

(Pos Sel 1 & Pos Sel 2) are used to choose step 1, 2 or 3 as the starting position.

If both selector switches (Pos Sel 1 & 2) are off (false) when a start command is issued, the profile will not operate because this is an invalid state. To recover from this the drive must be stopped and profiling must be disabled via P88 or power must be cycled.

The starting step of the indexer can be controlled via digital inputs or by manipulation of the Pos/Spd Prof Cmd word. This example uses digital inputs.

After downloading *.dno file, the Motor Data and Motor Tests portions of the Basic Startup should be performed through the LCD HIM. Then tune the Speed Regulator Bandwidth and Position Regulator Filter and Gain for desired performance.

Description

Drive Input & Output Connections:

Function

DI 1	4 – Stop CF	P361
DI 2	5 - Start	P362
DI 3	0 - Not Used	P363
DI 4	52 – Pos Sel 1	P364
DI 5	53 – Pos Sel 2	P365
DI 6	0 – Not Used	P366
AI 1		Not Used
AI 2		Not Used
Outputs	Function	Description
DO 1		Not Used
DO 2		Not Used
DO 3		Not Used
AO 1		Not Used
AO 2		Not Used





Drive Application Software Application Set

Parameter Configurations Changes from Default Parameter Settings (Any listed defaults are in gray.)

Par	Name	Value	Link	Description
41- 45	Motor NP	per nameplate		(Data entered per motor nameplate)
53	Motor Cntl Sel	4 - "FVC Vector"		
80	Feedback Select	3 - "Encoder"		Must use quadrature and differential encoder
88	Speed/Torque Mod	7 – "Pos/Spd Prof"		Enables position/speed profiling.
153	Regen Power Lim	-200.0		This must be set high enough (negative) to not limit deceleration into position otherwise overshoot will occur.
161	Bus Reg Mode A	Dynamic Brak		All regenerative energy dissipated into braking resistor.
163	DB Resistor Type	Internal Res		An External resistor may be required for high duty cycle or low friction applications. Sizing of resistor is determined by the loads and speeds of application.
190	Direction Mode	1 – "Bipolar"		Allows position loop to control direction.
259	Alarm Config 1	Bit 17 = 0		Disables alarm condition to defeat requirement to run a homing routine. The User must determine if this is necessary for the application.
449	Speed Desired BW	40 Rad/Sec.		Typical range will be 20-40 rad/sec. Adjusting this will automatically change Parameters 445 and 446
445	Ki Speed Loop	(475.8)		For Reference Only. Automatically adjusted when Parameters 449 is changed.
446	Kp Speed Loop	(47.6)		For Reference Only. Automatically adjusted when Parameters 449 is changed.
450	Total Inertia	(1.19 Sec)		For Reference Only. Automatically determined during inertia autotune. (Note: Kp = BW x Inertia)
***	Position Indexer			
705	Pos/Spd Prof Cmd	Bit 0 = Bit 1 = Bit 2 = Bit 3 = Bit 4 = Bit 5-7 = na Bit 8 = 0 Bit 9 = 0 Bit 10 = 0 Bit 11 = 0 Bit 12-15 = na		Bits 0 – 4 Control what step the profile will start at. The digital inputs are used in this setup as noted on page 1. (binary value determines step number) Bits 8 Hold Step, not used Bit 9 Redefine Pos, not used Bit 10 Find Home, not used Bit 11 Vel Override, not used
707	Encoder Pos Tol	10		Defines the tolerance window of "at position".
708	Counts per Unit	4096		This defines the number of encoder pulses equal to 1 unit. It can be scaled to a rotational or linear motion as desired by the User. (4096 = 1 rev of 1024PPR quadrature encoder)
713	Find Home Speed	10% of max		Default is 1/10 of maximum speed. Set to the lowest possible value to reduce overshoot.
714	Find Home Ramp	10.0		This value will typically be less than the default value of 10 seconds.

Drive Application Software Application Set

Times the gain value set in P719. Pos Reg Gain 12 This gain adjusts the responsiveness of the position regulator. Increase the value for better response. **** **** **** *** *** *** **		1		This is a law maps filter whose value should be 5.0
regulator. Increase the value for better response. **** **** **** *** **** *** *	718	Pos Reg Filter	75	This is a low pass filter whose value should be 5-6 times the gain value set in P719.
Step Data Type	740	D D O :	40	This gain adjusts the responsiveness of the position
Step 1 Type	719	Pos Reg Gain	12	regulator. Increase the value for better response.
721 Step 1 Velocity 500.0 Speed and direction for step 1 722 Step 1 AccelTime 1.00 Acceleration time for step 1 723 Step 1 DecelTime 1.00 Deceleration time for step 1 724 Step 1 Value 10.00 Number of units to travel for step 1 725 Step 1 Dwell 1.00 Seconds to hold at position when step value is reached. 726 Step 1 Batch 1 Number of times to do this step consecutively. 727 Step 1 Next 16 The step to go to after this step is complete. 730 Step 2 Type 4 Selects an encoder incremental move. 731 Step 2 Velocity 1000.0 Speed and direction for step 2 732 Step 2 DecelTime 1.00 Acceleration time for step 2 733 Step 2 DecelTime 1.00 Deceleration time for step 2 734 Step 2 Walue 15.00 Number of units to travel for step 2 735 Step 2 Batch 1 Number of times to do this step consecutively. 737 Step 3 Batch 1 Number of times to do this step comp	***	Step Data		
721 Step 1 Velocity 500.0 Speed and direction for step 1 722 Step 1 AccelTime 1.00 Acceleration time for step 1 723 Step 1 DecelTime 1.00 Deceleration time for step 1 724 Step 1 Value 10.00 Number of units to travel for step 1 725 Step 1 Dwell 1.00 Seconds to hold at position when step value is reached. 726 Step 1 Batch 1 Number of times to do this step consecutively. 727 Step 1 Next 16 The step to go to after this step is complete. 730 Step 2 Type 4 Selects an encoder incremental move. 731 Step 2 Velocity 1000.0 Speed and direction for step 2 732 Step 2 DecelTime 1.00 Acceleration time for step 2 733 Step 2 DecelTime 1.00 Deceleration time for step 2 734 Step 2 Walue 15.00 Number of units to travel for step 2 735 Step 2 Batch 1 Number of times to do this step consecutively. 737 Step 3 Batch 1 Number of times to do this step comp	720	Step 1 Type	4	Selects an encoder incremental move.
722 Step 1 AccelTime 1.00 Acceleration time for step 1 723 Step 1 DecelTime 1.00 Deceleration time for step 1 724 Step 1 Value 10.00 Number of units to travel for step 1 725 Step 1 Dwell 1.00 Seconds to hold at position when step value is reached. 726 Step 1 Batch 1 Number of times to do this step consecutively. 727 Step 1 Next 16 The step to go to after this step is complete. 730 Step 2 Type 4 Selects an encoder incremental move. 731 Step 2 Velocity 1000.0 Speed and direction for step 2 732 Step 2 AccelTime 1.00 Acceleration time for step 2 733 Step 2 DecelTime 1.00 Deceleration time for step 2 734 Step 2 Dwell 1.00 Number of units to travel for step 2 735 Step 2 Next 16 Number of units to travel for step 2 736 Step 3 Batch 1 Number of times to do this step consecutively. 737 Step 3 Velocity 1500.0 Speed and direction for step 3	721	Step 1 Velocity	500.0	Speed and direction for step 1
723 Step 1 Value 1.00 Deceleration time for step 1 724 Step 1 Value 10.00 Number of units to travel for step 1 725 Step 1 Dwell 1.00 Seconds to hold at position when step value is reached. 726 Step 1 Batch 1 Number of times to do this step consecutively. 727 Step 1 Next 16 The step to go to after this step is complete. 730 Step 2 Velocity 1000.0 Speed and direction for step 2 731 Step 2 Velocity 1000.0 Speed and direction for step 2 732 Step 2 DecelTime 1.00 Acceleration time for step 2 733 Step 2 DecelTime 1.00 Number of units to travel for step 2 734 Step 2 Devell 1.00 Number of units to travel for step 2 735 Step 2 Dwell 1.00 Seconds to hold at position when step value is reached. 736 Step 2 Batch 1 Number of times to do this step consecutively. 737 Step 3 Type 4 Selects an encoder incremental move. 740 Step 3 Type 4 Selects a	722		1.00	
724 Step 1 Value 10.00 Number of units to travel for step 1 725 Step 1 Dwell 1.00 Seconds to hold at position when step value is reached. 726 Step 1 Batch 1 Number of times to do this step consecutively. 727 Step 1 Next 16 The step to go to after this step is complete. 730 Step 2 Type 4 Selects an encoder incremental move. 731 Step 2 Velocity 1000.0 Speed and direction for step 2 732 Step 2 AccelTime 1.00 Acceleration time for step 2 733 Step 2 DecelTime 1.00 Deceleration time for step 2 734 Step 2 Dwell 1.00 Number of units to travel for step 2 735 Step 2 Dwell 1.00 Seconds to hold at position when step value is reached. 736 Step 2 Batch 1 Number of times to do this step consecutively. 737 Step 2 Next 16 The step to go to after this step is complete. 740 Step 3 Type 4 Selects an encoder incremental move. 741 Step 3 Velocity 1500.0 <	723		1.00	
726 Step 1 Batch 1 Number of times to do this step consecutively. 727 Step 1 Next 16 The step to go to after this step is complete. 730 Step 2 Type 4 Selects an encoder incremental move. 731 Step 2 Velocity 1000.0 Speed and direction for step 2 732 Step 2 AccelTime 1.00 Acceleration time for step 2 733 Step 2 DecelTime 1.00 Deceleration time for step 2 734 Step 2 Dwell 1.00 Number of units to travel for step 2 735 Step 2 Dwell 1.00 Seconds to hold at position when step value is reached. 736 Step 2 Batch 1 Number of times to do this step consecutively. 737 Step 2 Next 16 The step to go to after this step is complete. 740 Step 3 Type 4 Selects an encoder incremental move. 741 Step 3 Velocity 1500.0 Speed and direction for step 3 742 Step 3 AccelTime 1.00 Acceleration time for step 3 743 Step 3 Dwell 1.00 Mumber of times to do this	724		10.00	
727Step 1 Next16The step to go to after this step is complete.730Step 2 Type4Selects an encoder incremental move.731Step 2 Velocity1000.0Speed and direction for step 2732Step 2 AccelTime1.00Acceleration time for step 2733Step 2 DecelTime1.00Deceleration time for step 2734Step 2 Value15.00Number of units to travel for step 2735Step 2 Dwell1.00Seconds to hold at position when step value is reached.736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Dwell1.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 DecelTime1.00Acceleration time for step 16<	725	Step 1 Dwell	1.00	
727Step 1 Next16The step to go to after this step is complete.730Step 2 Type4Selects an encoder incremental move.731Step 2 Velocity1000.0Speed and direction for step 2732Step 2 AccelTime1.00Acceleration time for step 2733Step 2 DecelTime1.00Deceleration time for step 2734Step 2 Value15.00Number of units to travel for step 2735Step 2 Dwell1.00Seconds to hold at position when step value is reached.736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 DecelTime1.00Acceleration time for step 16	726	Step 1 Batch	1	Number of times to do this step consecutively.
731Step 2 Velocity1000.0Speed and direction for step 2732Step 2 AccelTime1.00Acceleration time for step 2733Step 2 DecelTime1.00Deceleration time for step 2734Step 2 Value15.00Number of units to travel for step 2735Step 2 Dwell1.00Seconds to hold at position when step value is reached.736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 DecelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Dwell0.50Seconds to hold at position.875<	727	Step 1 Next	16	
732Step 2 AccelTime1.00Acceleration time for step 2733Step 2 DecelTime1.00Deceleration time for step 2734Step 2 Value15.00Number of units to travel for step 2735Step 2 Dwell1.00Seconds to hold at position when step value is reached.736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively. <td>730</td> <td>Step 2 Type</td> <td>4</td> <td>Selects an encoder incremental move.</td>	730	Step 2 Type	4	Selects an encoder incremental move.
733Step 2 DecelTime1.00Deceleration time for step 2734Step 2 Value15.00Number of units to travel for step 2735Step 2 Dwell1.00Seconds to hold at position when step value is reached.736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Dwell0.50Seconds to hold at position.875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively. <td>731</td> <td>Step 2 Velocity</td> <td>1000.0</td> <td>Speed and direction for step 2</td>	731	Step 2 Velocity	1000.0	Speed and direction for step 2
734Step 2 Value15.00Number of units to travel for step 2735Step 2 Dwell1.00Seconds to hold at position when step value is reached.736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.	732	Step 2 AccelTime	1.00	Acceleration time for step 2
735Step 2 Dwell1.00Seconds to hold at position when step value is reached.736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 DecelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.	733	Step 2 DecelTime	1.00	Deceleration time for step 2
reached. 736 Step 2 Batch 1 Number of times to do this step consecutively. 737 Step 2 Next 16 The step to go to after this step is complete. 740 Step 3 Type 4 Selects an encoder incremental move. 741 Step 3 Velocity 1500.0 Speed and direction for step 3 742 Step 3 AccelTime 1.00 Acceleration time for step 3 743 Step 3 DecelTime 1.00 Deceleration time for step 3 744 Step 3 Value 20.00 Number of units to travel for step 3 745 Step 3 Dwell 1.00 Seconds to hold at position when step value is reached. 746 Step 3 Batch 1 Number of times to do this step consecutively. 747 Step 3 Next 16 The step to go to after this step is complete. 870 Step 16 Type 7 Selects "End and Hold Position" 871 Step 16 Velocity 0.00 Speed and direction for step 16 872 Step 16 DecelTime 1.00 Acceleration time for step 16 873 Step 16 DecelTime 1.00 Deceleration time for step 16 874 Step 16 Value n/a Number of units to travel for step 16 875 Step 16 Dwell 0.50 Seconds to hold at position. 876 Step 16 Batch 1 Number of times to do this step consecutively.	734	Step 2 Value	15.00	Number of units to travel for step 2
736Step 2 Batch1Number of times to do this step consecutively.737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.	735	Step 2 Dwell	1.00	
737Step 2 Next16The step to go to after this step is complete.740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.	736	Step 2 Batch	1	
740Step 3 Type4Selects an encoder incremental move.741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
741Step 3 Velocity1500.0Speed and direction for step 3742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
742Step 3 AccelTime1.00Acceleration time for step 3743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
743Step 3 DecelTime1.00Deceleration time for step 3744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
744Step 3 Value20.00Number of units to travel for step 3745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
745Step 3 Dwell1.00Seconds to hold at position when step value is reached.746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
746Step 3 Batch1Number of times to do this step consecutively.747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				Seconds to hold at position when step value is
747Step 3 Next16The step to go to after this step is complete.870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.	746	Step 3 Batch	1	
870Step 16 Type7Selects "End and Hold Position"871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
871Step 16 Velocity0.00Speed and direction for step 16872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
872Step 16 AccelTime1.00Acceleration time for step 16873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.			0.00	
873Step 16 DecelTime1.00Deceleration time for step 16874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
874Step 16 Valuen/aNumber of units to travel for step 16875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
875Step 16 Dwell0.50Seconds to hold at position.876Step 16 Batch1Number of times to do this step consecutively.				
876 Step 16 Batch 1 Number of times to do this step consecutively.				
or potential to probabilities to probabilities at the step to go to after this step is complete.	877	Step 16 Next	16	The step to go to after this step is complete.

Tuning Tips:

1. After downloading the *.dno file, the *Motor Data* and *Motor Tests* portions of the Basic Startup should be performed through the LCD HIM.

2. Speed Regulator Settings

P449 [Speed Desired BW] should be set to a point below where instability occurs.


3. Position Regulator Settings

P719 [Pos Reg Gain] should be increased to a value that is just below the point where overshoot occurs. P718 [Pos Reg Filter] must be adjusted at a rate that is 5-6 times the value of P719.

Drive Application Software Application Set

The plot below shows how the profile will operate when a different starting step is used. The sequence was as follows:

- 1. Pos Sel 1 = on, Pos Sel 2 = off. A start command issued. Step 1 moves incrementally 10 units. Once at position, a one second dwell at position occurs. The step completes and jumps to step 16 which is programmed to end the profile.
- 2. Pos Sel 1 = off, Pos Sel 2 = on. A start command issued. Step 2 moves incrementally 15 units (total of 25). Once at position, a one second dwell at position occurs. The step completes and jumps to step 16 which is programmed to end the profile.
- 3. Pos Sel 1 = on, Pos Sel 2 = on. A start command issued. Step 3 moves incrementally 20 units (total of 45). Once at position, a one second dwell at position occurs. The step completes and jumps to step 16 which is programmed to end the profile.



Drive Application Software Application Set Wiring Diagram

